

Upgrading From PDI 4.2.1 to 4.3



This document is copyright © 2011 Pentaho Corporation. No part may be reprinted without written permission from Pentaho Corporation. All trademarks are the property of their respective owners.

Help and Support Resources

If you have questions that are not covered in this guide, or if you would like to report errors in the documentation, please contact your Pentaho technical support representative.

Support-related questions should be submitted through the Pentaho Customer Support Portal at http://support.pentaho.com.

For information about how to purchase support or enable an additional named support contact, please contact your sales representative, or send an email to sales@pentaho.com.

For information about instructor-led training on the topics covered in this guide, visit http://www.pentaho.com/training.

Limits of Liability and Disclaimer of Warranty

The author(s) of this document have used their best efforts in preparing the content and the programs contained in it. These efforts include the development, research, and testing of the theories and programs to determine their effectiveness. The author and publisher make no warranty of any kind, express or implied, with regard to these programs or the documentation contained in this book.

The author(s) and Pentaho shall not be liable in the event of incidental or consequential damages in connection with, or arising out of, the furnishing, performance, or use of the programs, associated instructions, and/or claims.

Trademarks

Pentaho (TM) and the Pentaho logo are registered trademarks of Pentaho Corporation. All other trademarks are the property of their respective owners. Trademarked names may appear throughout this document. Rather than list the names and entities that own the trademarks or insert a trademark symbol with each mention of the trademarked name, Pentaho states that it is using the names for editorial purposes only and to the benefit of the trademark owner, with no intention of infringing upon that trademark.

Company Information

Pentaho Corporation Citadel International, Suite 340 5950 Hazeltine National Drive Orlando, FL 32822

Phone: +1 407 812-OPEN (6736) Fax: +1 407 517-4575

http://www.pentaho.com

E-mail: communityconnection@pentaho.com

Sales Inquiries: sales@pentaho.com

Documentation Suggestions: documentation@pentaho.com

Sign-up for our newsletter: http://community.pentaho.com/newsletter/

Contents

ntroduction	4
What's new in 4.3?	5
Jpgrade Best Practices	
Jpgrade Checklist	
Obtaining the Archive Packages	
Creating Backups	
Backing Up Content Files	9
Backing Up a Database Repository	g
Backing Up a Database Repository How to Back Up the Enterprise Repository	🤅
Backing Up the .kettle Directory	9
Backing Up the data-integration Directory	10
Jpgrading a Data Integration Server	.11
Upgrading the Pentaho Enterprise Console	
Jpgrading a Data Integration Workstation	.13
Calculator Step Bug Fix	
Testing and Cleanup.	

Introduction

This guide shows current Pentaho Data Integration Enterprise Edition customers how to upgrade from PDI 4.2.1 to 4.3. If you are upgrading from a version of PDI older than 4.2.1, refer instead to PDI Upgrade Guide documents from previous PDI releases.



Note: This guide is only for Enterprise Edition upgrades. You cannot upgrade a PDI 4.2.1 Community Edition deployment to PDI 4.3 Enterprise Edition through this process.

What's new in 4.3?

Below is a list of major changes between Pentaho Data Integration 4.2.x and 4.3:

Exasol database support

The Exasol Database support is integrated since PDI Version 4.3 RC. Contact Exasol directly to get the latest version and the JDBC driver suitable to your server version. To install, simply copy the JDBC driver jar(s) into your PDI distribution folder data-integration/libext/JDBC. After restarting PDI, the connection with Exasol can be established.



Note: You may define the default schema in the Connection/Advanced/Preferred Schema name.



Note: As with any column store database, it is best to use steps that are optimal from a performance standpoint in this regard (e.g. the Dimension Lookup/Step).

Removal of JDBC drivers

Due to licensing concerns, PDI no longer ships with the following drivers:

- ExtenDB
- IBM UniVerse
- Ingres
- Kingbase
- MySql Connector/J
- Oracle

You will have to retrieve these driver JARs from the manufacturer, vendor, or developer; or you can copy them from your previous PDI insance.

Expanded support for Big Data technologies

- More recent Hadoop distributions are supported
- There is no longer a need for a separate Hadoop node installation package or procedure; this is now done
 automatically when connecting to the Hadoop service from PDI
- Added support: Cassandra, MapR, MongoDb
- Renamed "Hadoop Transformation Job Executor" to "Pentaho MapReduce"
- The Using Hadoop With Pentaho Data Integration document has been renamed to The Pentaho Big Data Guide to better reflect its broader array of content

Upgrade Best Practices

All production software upgrades, including Pentaho Data Integration, should be performed during off-peak hours and with enough time to restore from a backup before off-peak ends if something should go wrong. Ideally you would perform the upgrade on a test machine that mirrors the production environment, take notes along the way, and perform the same procedure on the production server when you know how long the entire process will take and are sure that there will be no unexpected problems.

This guide contains instructions for performing the safest possible upgrade. There may be quicker ways, but the software's architects recommend the path outlined in this guide for the safest and most predictable transition to PDI 4.3.



Danger: Always back up your production data, and test the backup before proceeding with an upgrade.

Upgrade Checklist

The Upgrade Checklist is a concise list of instructions intended to show a high-level overview of the upgrade process. It also serves as a method of verifying that each task is performed in the correct order. You may find it useful to print the checklist out and physically mark each step in the Done column as you complete it. **The checklist is not the complete instruction set**; consult the verbose instructions throughout this guide for more details on each step.

Step	Procedure	Done
Step 1	Download the PDI 4.3 client and server packages and the Pentaho Enterprise Console package from the Pentaho Customer Support Portal.	
Step 2	Stop your DI Server and Pentaho Enterprise Console server. Ensure that the DI Server	
	process is stopped; if it is not, file copy and delete commands could silently fail later on.	
Step 3	Back up your content files, database repository or enterprise repository; your ~/.kettle	
	directory; your PDI client tool directory, and your /pentaho/server/data-	
	integration-server/pentaho-solutions/ directory. Modify this and all future	
	paths to match your PDI deployment.	
Step 4	On your PDI server, rename the /pentaho/server/data-integration-server/directory to data-integration-server-old.	
Step 5	Create a new, empty /pentaho/server/data-integration-server/directory.	
Step 6	Rename the /pentaho/server/enterprise-console/ directory to enterprise-	
•	console-old.	
Step 7	Create a new, empty /pentaho/server/enterprise-console/ directory.	
Step 8	Unpack the new pdi-ee-server-4.3.0-GA archive to /pentaho/server/data-	
·	integration-server/.	
Step 9	Copy all of the applicationContext files from /pentaho/server/data-	
	integration-server-old/pentaho-solutions/system/ (the old solutions	
	directory) to the new one.	
Step 10	Copy the pentaho-spring-beans.xml file from /pentaho/server/data-	
'	integration-server-old/pentaho-solutions/system/ (the old solutions	
	directory) to the new one.	
Step 11	Transfer the admin role information and merge any custom changes from your old	
	pentaho.xml and repository.spring.xml files to the new ones.	
Step 12	Copy the entire quartz directory from /data-integration-server-old/pentaho-	
	solutions/ to the new one.	
Step 13	Copy the entire repository directory from /data-integration-server-old/	
Cich 10	pentaho-solutions/system/jackrabbit/ to the new one.	
Step 14	Copy repository.xml from the old jackrabbit directory to the new one.	
Step 15	Copy the entire jre directory from /data-integration-server-old/ to the new one.	
Step 16	Merge any custom changes from your old DI Server configuration files to the new ones.	
	Copy the following files from the old Pentaho Enterprise Console to the new one:	
Step 17	console.xml, console.properties, login.properties, login.conf, log4j.xml.	
Stop 19	Unpack the pec-4.5.0-GA archive to the /pentaho/server/ directory.	
Step 18		
Step 19	Copy the following files from the old Pentaho Enterprise Console to the new one: console.xml, console.properties, login.properties, login.conf, log4j.xml; and the entire /	
Cton 20	resource/config/hsqldb/ directory.	
Step 20	Start the DI Server and Pentaho Enterprise Console and test their functionality and	
Otan 04	availability.	
Step 21	On your PDI workstations, delete the /pentaho/design-tools/data-	
	integration/ directory after you have ensured that there are no KJB or KTR content	
Cton 22	files stored there.	
Step 22	Unpack the pdi-ee-client-4.3.0-GA archive to the /pentaho/design-tools/directory.	
Step 23	Start the Data Integration client tools that you normally use, and ensure that they work	
	properly, can access existing content, create and share new content, run existing	
	schedules, create new schedules, and have a connection to the DI Server (if you are	
	using it).	
Step 24	Perform any other necessary testing, then delete any installation artifacts and the data-	
	integration-server-old directory, and inform users that the upgrade is complete.	

Obtaining the Archive Packages

Log into the Pentaho Customer Support Portal and download individual archive packages for the DI Server and Data Integration client tools. If you don't know your login information, consult the Welcome Kit email that was sent to you after completing the sales process, or contact your Pentaho sales or support representative.

Here are the packages you need for each platform and distribution:

- DI Server for Windows: pdi-ee-server-4.3.0-GA.zip
- DI Server for Linux/Solaris/OS X: pdi-ee-server-4.3.0-GA.tar.gz
- Data Integration client tool Windows package: pdi-ee-client-4.3.0-GA.zip
- Data Integration client tool Linux/Solaris/OS X package: pdi-ee-client-4.3.0-GA.tar.gz

If you download the pdi-ee-server package, you must also download the Pentaho Enterprise Console package:

- Pentaho Enterprise Console for Linux/Solaris/OS X: pec-4.5.0-GA.tar.gz
- Pentaho Enterprise Console for Windows: pec-4.5.0-GA.zip

Creating Backups

You should back up your content files or repository and your Kettle settings in case something goes wrong with the upgrade. Refer to the sections below that apply to your situation.

Backing Up Content Files

If you do not use a database or enterprise repository for storing PDI content, then you are saving individual KJB and KTR files on a local or network drive. Hopefully you have created a sensible directory structure and naming convention for them. If not, this may be a good time to organize them properly.

Once you have all of your content in one directory, simply create a Zip or tar archive of it and copy the archive to a safe location outside of your local machine, such as a network drive or removable media.

This should be part of your normal production backup routine outside of this upgrade process.

Backing Up a Database Repository

Backing up your PDI database repository is as simple as using the **Export complete repository to XML** functionality in Spoon's **Repository Explorer** dialogue, which is accessible from the **File** menu. Then copy the resulting file to a safe location outside of the machine you are upgrading.

This should be part of your normal production backup routine outside of this upgrade process.

How to Back Up the Enterprise Repository

Follow the instructions below to create a backup of your PDI enterprise repository.



Note: If you've made any changes to the Pentaho Enterprise Console or DI Server Web application configuration, such as changing the port number or base URL, you will have to modify this procedure to include the entire /pentaho/server/ directory.

1. Stop the DI Server.

/pentaho/server/data-integration-server/stop-pentaho.sh

2. Create a backup archive or package of the /pentaho/server/data-integration-server/pentaho-solutions/ directory.

tar -cf pdi_backup.tar /pentaho/server/data-integration-server/pentaho-solutions/

- 3. Copy the backup archive to removable media or an online backup server.
- 4. Start the DI Server.

/pentaho/server/data-integration-server/start-pentaho.sh

Your DI Server's stored content, settings, schedules, and user/role information is now backed up.

To restore from this backup, simply unpack it to the same location, overwriting all files that already exist there.

Backing Up the .kettle Directory

The .kettle directory stores all of your client tool configuration settings and preferences. It is located in ~/.kettle on Linux, Solaris, and OS X; and C:\Documents and Settings\username\.kettle on Windows, where username refers to the user account that the PDI client tools are installed to.

Create a Zip or tar archive of this directory and copy the archive to a safe location before upgrading.

Backing Up the data-integration Directory

The **/design-tools/data-integration/** directory contains the PDI client tool, JDBC drivers, and the command line tools (Pan, Kitchen, and Carte). While there are no configuration files stored here, you may need to back up this directory so that you can restore from a failed upgrade, or to copy over your previous driver JARs.

Create a Zip or tar archive of this directory and copy the archive to a safe location before upgrading.

Upgrading a Data Integration Server

Ensure that the DI Server and Pentaho Enterprise Console are stopped before continuing. You must have a PDI 4.2.1 DI Server installed in order to follow this procedure; if you do not use the DI Server, this upgrade task is unnecessary.



Note: For a smoother post-upgrade test experience, you should perform this procedure before upgrading your PDI workstations.

Follow the instructions below to upgrade your Data Integration Server to version 4.3.

1. Rename the /data-integration-server/ directory to data-integration-server-old.



Note: If you are coming from a BI Server upgrade, you already have a **server_old** directory. If this is the case, use /server_old/data-integration-server/ in place of /data-integration-server-old/.

mv /home/pentaho/pentaho/server/data-integration-server/ /home/pentaho/pentaho/server/
data-integration-server-old/

2. Unpack the pdi-ee-server-4.3.0-GA package to the parent of the directory you just renamed.

```
tar zxvf ~/downloads/pdi-ee-server-4.3.0-GA.tar.gz -C /home/pentaho/pentaho/server/
```

3. Copy all of the applicationContext files from the /data-integration-server-old/pentaho-solutions/system/ directory to the new one, overwriting the equivalent files that are already there.

```
cp applicationContext-* ~/pentaho/server/data-integration-server/pentaho-solutions/
system/
```

4. Edit the applicationContext-spring-security-hibernate.xml file in /data-integration-server/pentaho-solutions/system/ and add a PentahoUserRoleMapping.hbm.xml value to the mappingResources property, as shown in this example:

5. Copy the **pentaho-spring-beans.xml** file from the /data-integration-server-old/pentaho-solutions/system/ directory to the new one, overwriting the equivalent file that is already there.

```
cp pentaho-spring-beans.xml ~/pentaho/server/data-integration-server/pentaho-
solutions/system/
```

6. Transfer the information about the admin role from the following two old files to the new ones: /pentaho-solutions/system/pentaho.xml and /pentaho-solutions/system/repository.spring.xml

Copy the entire old quartz directory from /data-integration-server-old/pentaho-solutions/ to the new one.

```
cp -r ./quartz ~/pentaho/server/data-integration-server/pentaho-solutions/
```

8. Copy the entire old repository directory from /data-integration-server-old/pentaho-solutions/system/jackrabbit/ to the new one.

```
cp -r ./jackrabbit/repository/ ~/pentaho/server/data-integration-server/pentaho-
solutions/system/jackrabbit/
```

9. Copy the old /pentaho-solutions/system/jackrabbit/repository.xml file to the new jackrabbit directory.

cp ./jackrabbit/repository.xml ~/pentaho/server/data-integration-server/pentahosolutions/system/jackrabbit/

10.Copy the **scripts** directory from /data-integration-server-old/ directory to the new data-integration-server directory.



Note: The scripts directory will only exist if you installed PDI from a graphical installation utility. If you installed via archive packages, it won't be there. If you do not see a scripts directory, then skip this step.

11.If you plan to connect to Hadoop, ensure that the **hadoop-core** JAR in your Hadoop cluster is the same version as the one Pentaho ships with PDI (in /data-integration/libext/bigdata/).

If these JARs are different versions, strange and unusual problems can occur.

12.Copy the entire **ire** directory from /data-integration-server-old/ to the new one.

```
cp -r jre ~/pentaho/server/data-integration-server/
```

This step is optional. If you already have a supported JRE or JDK installed on your system, you can skip copying this directory and simply ensure that you have a JAVA_HOME or PENTAHO_JAVA_HOME system variable that points to your Java instance.

13.If you have not already done so, merge any custom changes you have made to DI Server configuration files from the old ones to the new ones.

Your DI Server is now upgraded to version 4.3. Continue on to the next subsection to upgrade the Pentaho Enterprise Console.

Upgrading the Pentaho Enterprise Console

The upgraded DI Server will not work properly without upgrading the Pentaho Enterprise Console. To upgrade, follow the below process.

1. Rename the /pentaho/server/enterprise-console/ directory to enterprise-console-old.

```
mv enterprise-console enterprise-console-old
```

2. Unpack the pec-4.5.0-GA zip or tar.gz file to /pentaho/server/.

```
tar zxvf ~/downloads/pec-4.5.0-GA.tar.gz -C /home/pentaho/pentaho/server/
```

- **3.** Copy the following files from your old /pentaho/server/enterprise-console-old/resource/config/directory into the new one:
 - console.xml
 - · console.properties
 - · login.properties
 - login.conf
 - log4j.xml

cp /home/pentaho/pentaho/server/enterprise-console-old/resource/config/console.* /
home/pentaho/pentaho/server/enterprise-console/resource/config/ && cp /pentaho/server/
enterprise-console-old/resource/config/log* /home/pentaho/pentaho/server/enterpriseconsole/resource/config/

4. Copy the your old /enterprise-console/resource/config/hsqldb/ directory to the new Enterprise Console instance, overwriting the files that are there.

This directory contains PDI-specific settings.

cp -r /home/pentaho/pentaho/server/enterprise-console-old/resource/config/hsqldb/ /
home/pentaho/pentaho/server/enterprise-console/resource/config/

The Pentaho Enterprise Console has been upgraded to version 4.5.0.

Upgrading a Data Integration Workstation

Ensure that the Data Integration client tools (Spoon, Pan, Kitchen) are not running on the machine before proceeding.



Note: If you use an enterprise repository to store your jobs and transformations, you should perform the DI Server upgrade process before this in order to properly test DI Server connectivity from your upgraded workstations.

Follow the directions below to upgrade your PDI workstations to version 4.3. Adjust the installation paths to match your scenario.

- 1. Remove your existing /data-integration/ directory.
 - rm -rf /home/rwilco/pentaho/design-tools/data-integration/
- 2. Unpack the pdi-ee-client-4.3.0-GA package to the same location that you just deleted.
 - cd /home/rwilco/pentaho/design-tools/ && tar zxvf \sim /downloads/pdi-ee-client-4.3.0-GA.tar.gz
- 3. Start Data Integration and ensure that you can still connect to the DI Server (if you have an enterprise repository connection) and access all of your old content.

This workstation is now upgraded to PDI 4.3.0-GA. Repeat this procedure for other workstations that you have support entitlements for.

Calculator Step Bug Fix

In previous versions, the "Date A - Date B (working days)" function of the Calculator reversed the calculation and it was necessary to perform a workaround to address the incorrect values returned (link to previous workaround: http:// jira.pentaho.com/browse/PDI-6811). Specifically, with the calculation "Date A - Date B (working days)" users were advised to reverse the calculation to get the correct values.

This bug was addressed and corrected in version 4.3.



Note: After upgrading to version 4.3, the calculation used to perform the workaround will now return incorrect values. Any instance where the calculation "Date A - Date B (working days)" was used should be verified.

Testing and Cleanup

You should now have a complete PDI 4.3 environment, from the DI Server to individual client workstations. Before you go back into production, you should perform the following tests:

- Open old jobs and transformations and ensure that they execute properly.
- If you are using an enterprise repository, ensure that each PDI workstation can connect to it.
- Create a new job, transformation, and/or Agile BI analysis schema and save it as you normally would.
- Schedule a job or transformation and ensure that the schedule executes properly.
- Ensure that existing schedules are still valid.
- If you are using an enterprise repository, share a job or transformation between PDI users and verify that both can access it.
- Physically restart the server and ensure that the DI Server and Enterprise Console are automatically started as services, if you have them configured as such.

Once you're certain that your PDI environment is ready for production, you can remove any installation artifacts, such as ZIP or tar.gz archives and installers. You can also remove your data-integration-server-old directory.