


# **Chapter 3: Processes**






#### **Outline**

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- IPC in Shared-Memory Systems
- IPC in Message-Passing Systems
- Examples of IPC Systems
- Communication in Client-Server Systems





### **Objectives**

- Identify the separate components of a process and illustrate how they are represented and scheduled in an operating system.
- Describe how processes are created and terminated in an operating system using system calls.
- Describe and contrast interprocess communication using shared memory and message passing.
- Design programs that uses pipes and POSIX shared memory to perform interprocess communication.
- Describe client-server communication using sockets and remote procedure calls.
- Design kernel modules that interact with the Linux operating system.






### **Process Concept**


- An operating system executes a variety of programs that run as a process.
- Multiple processes can execute concurrently, with the CPU (or CPUs) multiplexed among them.
- Process a program in execution; process execution must progress in sequential fashion. No parallel execution of instructions of a single process
- Multiple parts
  - The executable code, also called text section
  - Current activity including program counter, processor registers
  - Stack containing temporary data
    - Function parameters, return addresses, local variables
  - Data section containing global variables
  - Heap containing memory dynamically allocated during run time






### **Process Concept (Cont.)**


- Program is passive entity stored on disk (executable file); process is active
  - Program becomes process when an executable file is loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc.
- One program can be associated with several processes
  - Consider multiple users executing the same program






### **Process in Memory**


- Sizes of the text and data sections are fixed (Why??)
- Operating system must ensure they do not overlap one another







### **Memory Layout of a C Program**









#### **Process State**

- As a process executes, it changes state
  - New: The process is being created
  - Running: Instructions are being executed
    - only one process can be running on any processor core at any instant
  - Waiting: The process is waiting for some event to occur
  - Ready: The process is waiting to be assigned to a processor
  - Terminated: The process has finished execution






### **Diagram of Process State**








### **Process Control Block (PCB)**

Information associated with each process(also called task control block)

- Process state running, waiting, etc.
- Program counter location of instruction to next execute
- CPU registers contents of all process-centric registers e.g., accumulators, stack pointers, etc
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information memory allocated to the process
- Accounting information CPU used, clock time elapsed since start, time limits
- I/O status information I/O devices allocated to process, list of open files


process state
process number
program counter
registers
memory limits
list of open files






#### **Threads**

- So far, process has a single thread of execution
- Consider having multiple program counters per process
  - Multiple locations can execute at once
    - Multiple threads of control -> threads
- PCB must have storage for thread details, multiple program counters
- Example:
  - A multithreaded word processor could, for example, assign one thread to manage user input while another thread runs the spell checker.
  - Video players could use multiple threads for decoding videos, synchronizing sound, and reading a network stream.






### **Process Representation in Linux**

#### Represented by the C structure task struct in <include/linux/sched.h>

```
/* process identifier */
pid t pid;
                                   /* state of the process */
   long state;
   unsigned int time slice /* scheduling information */
   struct task struct *parent; /* this process's parent */
   struct list head children; /* this process's children */
   struct files struct *files;/* list of open files */
   struct mm struct *mm; /* address space of this
   process */
                struct task struct
                              struct task struct
                                                struct task struct
               process information
                              process information
                                               process information
```

 Within the Linux kernel, all active processes are represented using a doubly linked list of task struct

current (currently executing process)




### **Process Scheduling**


- For a system with a single CPU core, there will never be more than one process running at a time.
- In case more processes than cores, excess processes will have to wait until a core is free.
- The number of processes currently in memory is known as the degree of multiprogramming.
- Process scheduler selects among available processes for next execution on CPU core
- Goal -- Maximize CPU use, quickly switch processes onto CPU core
- Maintains scheduling queues of processes
  - Ready queue set of all processes residing in main memory, ready and waiting to execute
  - Wait queues set of processes waiting for an event (i.e., I/O)
  - Processes migrate among the various queues (state diagram!!)





### **Ready and Wait Queues**












## Representation of Process Scheduling







#### **Context Switch**


- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is pure overhead; the system does no useful work while switching
  - The more complex the OS and the PCB → the longer the context switch
- Time dependent on hardware support
  - Some hardware provides multiple sets of registers per CPU → A
    context switch here simply requires changing the pointer to the
    current register set.






# **CPU Switch From Process to Process**


A **context switch** occurs when the CPU switches from one process to another.





### Multitasking in Mobile Systems

- Some mobile systems (e.g., early version of iOS) allow only one process to run, others suspended
- Due to limited screen size, user interface limits iOS provides for a
  - Single foreground process- controlled via user interface
  - Multiple background processes— in memory, running, but not on the display, and with limits
  - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
  - Background process uses a service to perform tasks
  - Service can keep running even if background process is suspended
  - Service has no user interface, small memory use





### **Operations on Processes**

- System must provide mechanisms for:
  - Process creation
  - Process termination





#### **Process Creation**

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- pstree command displays a tree of all processes in Linux
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing options
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution options
  - Parent and children execute concurrently
  - Parent waits until children terminate






### **Process Creation (Cont.)**

- Address space
  - Child duplicate of parent
  - Child has a program loaded into it
- UNIX examples
  - fork() system call creates new process
  - exec() system call used after a fork() to replace the process' memory space with a new program
  - Parent process calls wait () waiting for the child to terminate






### A Tree of Processes in Linux









### **Process Creation (Cont.)**

- After fork(), one of the two processes typically uses the exec() to replace the process's memory space with a new program.
- execlp() is a version of the exec() through which child process overlays its address space with the UNIX command /bin/ls
- The parent waits for the child process to complete with the wait()
  - When the child process completes, by either implicitly or explicitly, invoking exit() the parent process resumes from the call to wait()







### **C Program Forking Separate Process**

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid_t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
   else if (pid == 0) { /* child process */
      execlp("/bin/ls", "ls", NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait(NULL);
      printf("Child Complete");
   return 0;
```



# **Creating a Separate Process via Windows API**

Read by yourself






#### **Process Termination**

- Process executes last statement and then asks the operating system to delete it using the exit() system call.
  - Returns status data from child to parent (via wait())
  - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the abort () system call. Some reasons for doing so:
  - Child has exceeded allocated resources.
    - the parent must have a mechanism to inspect the state of its children.
  - Task assigned to child is no longer required
  - The parent is exiting, and the operating systems does not allow a child to continue if its parent terminates (cascading termination)
    - Normally initiated by the operating system






### **Process Termination**

The parent process may wait for termination of a child process by using the wait() system call. The call returns status information and the pid of the terminated process

```
pid = wait(&status);
```

- When a process terminates, its resources are deallocated
  - However, its entry in the process table must remain there until the parent calls wait(), because it contains the process's exit status
  - All processes transition to this state when they terminate
- If no parent waiting (did not invoke wait()) process is a zombie
- If parent terminated without invoking wait(), process is an orphan






### **Interprocess Communication**

- Processes within a system may be independent or cooperating
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing (allow concurrent access to such information)
  - Computation speedup (we must break it into subtasks)
  - Modularity
- Cooperating processes need interprocess communication (IPC)






### **Interprocess Communication**

- Two models of IPC
  - Shared memory
    - Processes can then exchange information by reading and writing data to the shared region
    - Shared memory can be faster than message passing (Why??)
  - Message passing
    - communication takes place by means of messages exchanged between the cooperating processes
    - Useful for exchanging smaller amounts of data, because no conflicts need be avoided
    - easier to implement in a distributed system






### **Communications Models**

(a) Shared memory.

(b) Message passing.






### **IPC in Shared-Memory Systems**

- Requires communicating processes to establish a region of shared memory
- Shared-memory region resides in the address space of the process creating the shared-memory segment.
  - OS tries to prevent one process from accessing another process's memory. Thus, processes agree to remove this restriction
- Exchange information by reading and writing data in the shared areas.
  - The form of the data and the location are determined by these processes and are not under the OS's control.






#### **Producer-Consumer Problem**

- Paradigm for cooperating processes:
  - producer process produces information that is consumed by a consumer process
    - e.g., a compiler may produce assembly code that is consumed by an assembler.
- Two variations:
  - unbounded-buffer places no practical limit on the size of the buffer:
    - Producer never waits
    - Consumer waits if there is no buffer to consume
  - bounded-buffer assumes that there is a fixed buffer size
    - Producer must wait if all buffers are full
    - Consumer waits if there is no buffer to consume





### **Bounded-Buffer – Shared-Memory Solution**


Shared data


```
#define BUFFER_SIZE 10
typedef struct {
    . . .
} item;
item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```





# **Producer Process – Shared Memory**






# **Consumer Process – Shared Memory**


Solution is correct, but can only use **BUFFER\_SIZE-1** elements





### What about Filling all the Buffers?

- Suppose that we wanted to provide a solution to the consumerproducer problem that fills all the buffers.
- We can do so by having an integer counter that keeps track of the number of full buffers.
- Initially, counter is set to 0.
- The integer counter is incremented by the producer after it produces a new buffer.
- The integer counter is and is decremented by the consumer after it consumes a buffer.






#### **Producer**

```
while (true) {
    /* produce an item in next produced */

    while (counter == BUFFER_SIZE)
        ; /* do nothing */

    buffer[in] = next_produced;
    in = (in + 1) % BUFFER_SIZE;
    counter++;
}
```






#### Consumer

```
while (true) {
    while (counter == 0)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;
    counter--;
    /* consume the item in next consumed */
}
```





#### **Race Condition**

counter++ could be implemented as

```
register1 = counter
register1 = register1 + 1
counter = register1
```

counter-- could be implemented as

```
register2 = counter
register2 = register2 - 1
counter = register2
```

Consider this execution interleaving with "count = 5" initially:

```
S0: producer execute register1 = counter {register1 = 5}

S1: producer execute register1 = register1 + 1 {register1 = 6}

S2: consumer execute register2 = counter {register2 = 5}

S3: consumer execute register2 = register2 - 1 {register2 = 4}

S4: producer execute counter = register1 {counter = 6}

S5: consumer execute counter = register2 {counter = 4}
```






#### **Race Condition (Cont.)**

Question - why was there no race condition in the first solution (where at most N - 1) buffers can be filled?





### **IPC – Message Passing**


- Processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - send(message)
  - receive(message)
- The message size is either fixed or variable





### Message Passing (Cont.)

- If processes P and Q wish to communicate, they need to:
  - Establish a communication link between them
  - Exchange messages via send/receive
- Implementation issues:
  - How are links established?
  - Can a link be associated with more than two processes?
  - How many links can there be between every pair of communicating processes?
  - What is the capacity of a link?
  - Is the size of a message that the link can accommodate fixed or variable?






## **Implementation of Communication Link**


- Physical Implementation:
  - Shared memory
  - Hardware bus
  - Network
- Logical Implementation:
  - Direct or indirect
  - Synchronous or asynchronous
  - Automatic or explicit buffering (bounded or unbounded buffer)






#### **Direct Communication**


- Processes must name each other explicitly:
  - send (P, message) send a message to process P
  - receive(Q, message) receive a message from process Q
- Properties of communication link
  - Links are established automatically, processes need to know only each other's identity to communicate
  - A link is associated with exactly one pair of communicating processes
  - Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional
- Two Variants
  - Both the sender process and the receiver process must name the other to communicate (symmetry in addressing)
  - Sender names the recipient; the recipient is not required to name the sender (asymmetry in addressing)



#### **Indirect Communication**

- Messages are directed and received from mailboxes (also referred to as ports)
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Mailbox can be viewed abstractly as an object into which messages can be placed by processes and from which messages can be removed.
- Properties of communication link
  - Link established only if processes share a common mailbox
  - A link may be associated with many processes
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional






### **Indirect Communication (Cont.)**

- Operations
  - Create a new mailbox (port)
  - Send and receive messages through mailbox
  - Delete a mailbox
- Primitives are defined as:
  - send(A, message) send a message to mailbox A
  - receive(A, message) receive a message from mailbox A






### **Indirect Communication (Cont.)**

- Mailbox sharing
  - P<sub>1</sub>, P<sub>2</sub>, and P<sub>3</sub> share mailbox A
  - P<sub>1</sub>, sends; P<sub>2</sub> and P<sub>3</sub> receive
  - Who gets the message?
- Solutions depends on which of the following methods we choose
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation (How??)
  - Allow the system to select arbitrarily the receiver (may be round robin). Sender is notified who the receiver was.






### **Synchronization**

Message passing may be either blocking or non-blocking

- Blocking is considered synchronous
  - Blocking send -- the sender is blocked until the message is received
  - Blocking receive -- the receiver is blocked until a message is available
- Non-blocking is considered asynchronous
  - Non-blocking send -- the sender sends the message and continue
  - Non-blocking receive -- the receiver receives:
    - A valid message, or
    - Null message





#### **Producer-Consumer: Message Passing**

Producer

```
message next_produced;
while (true) {
   /* produce an item in next_produced */
   send(next_produced);
}
```


Consumer

```
message next_consumed;
while (true) {
    receive(next_consumed);

    /* consume the item in next_consumed */
}
```

blocking send() and receive() statements





### **Buffering**

- Whether communication is direct or indirect, messages exchanged by communicating processes reside in a temporary queue.
- Implemented in one of three ways
  - Zero capacity no messages are queued on a link.
     Sender must wait for receiver
  - 2. Bounded capacity finite length of *n* messages Sender must wait if link full
  - 3. Unbounded capacity infinite length Sender never waits





### **Examples of IPC Systems – Windows**

- Windows provides support for multiple operating environments, or subsystems and application programs communicate with these subsystems via a message-passing mechanism.
  - application programs are clients of a subsystem server
- Message-passing centric via advanced local procedure call (ALPC) facility
  - Only works between processes on the same system
  - Uses ports (like mailboxes) to establish and maintain communication channels






### **Examples of IPC Systems – Windows**

- Communication works as follows:
  - The client opens a handle to the subsystem's connection port object.
  - The client sends a connection request.
  - The server creates two private communication ports and returns the handle to one of them to the client.
    - one for client–server messages, the other for server–client messages
  - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies.
- For small messages (up to 256 bytes), the port's message queue is used as intermediate storage
- Larger messages must be passed through a section object






### **Local Procedure Calls in Windows**








### **Pipes**


- Acts as a channel allowing two processes to communicate
- First IPC mechanisms in early UNIX systems
- Issues:
  - Is communication unidirectional or bidirectional?
  - In the case of two-way communication, is it half or full-duplex?
  - Must there exist a relationship (i.e., parent-child) between the communicating processes?
  - Can the pipes be used over a network?
- Ordinary pipes cannot be accessed from outside the process that created it. Typically, a parent process creates a pipe and uses it to communicate with a child process that it created.
- Named pipes can be accessed without a parent-child relationship.






#### **Ordinary Pipes**

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the read-end of the pipe)
- Ordinary pipes are therefore unidirectional
  - If two-way communication is required, two pipes must be used
- Require parent-child relationship between communicating processes




- Windows calls these anonymous pipes
- UNIX treats a pipe as a special type of file. Thus, pipes can be accessed using ordinary read() and write() system calls





#### **Named Pipes**

- Named Pipes are more powerful than ordinary pipes
- Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several processes can use the named pipe for communication
- Provided on both UNIX and Windows systems





# **Communications in Client-Server Systems**

- Sockets
- Remote Procedure Calls







#### **Sockets**

- A socket is defined as an endpoint for communication
- Concatenation of IP address and port a number included at start of message packet to differentiate network services on a host
- The socket 161.25.19.8:1625 refers to port 1625 on host 161.25.19.8
- Communication consists between a pair of sockets
- All ports below 1024 are well known, used for standard services
  - FTP server listens to port 21; and a web, or HTTP, server listens to port 80
- Special IP address 127.0.0.1 (loopback) to refer to system on which process is running





#### **Socket Communication**







#### **Sockets in Java**

- Three types of sockets
  - Connection-oriented (TCP)
  - Connectionless (UDP)
  - MulticastSocket class— data can be sent to multiple recipients
- Consider this "Date" server in Java:

```
import java.net.*;
import java.io.*;
public class DateServer
  public static void main(String[] args) {
     try {
       ServerSocket sock = new ServerSocket(6013);
       /* now listen for connections */
       while (true) {
          Socket client = sock.accept();
          PrintWriter pout = new
           PrintWriter(client.getOutputStream(), true);
          /* write the Date to the socket */
          pout.println(new java.util.Date().toString());
          /* close the socket and resume */
          /* listening for connections */
          client.close():
     catch (IOException ioe) {
       System.err.println(ioe);
```






#### **Sockets in Java**

#### The equivalent Date client

```
import java.net.*;
import java.io.*;
public class DateClient
  public static void main(String[] args) {
     try {
       /* make connection to server socket */
       Socket sock = new Socket("127.0.0.1",6013);
       InputStream in = sock.getInputStream();
       BufferedReader bin = new
          BufferedReader(new InputStreamReader(in));
       /* read the date from the socket */
       String line;
       while ( (line = bin.readLine()) != null)
          System.out.println(line);
       /* close the socket connection*/
       sock.close();
     catch (IOException ioe) {
       System.err.println(ioe);
```





#### **Remote Procedure Calls**

Read by yourself



# **End of Chapter 3**

