# RSA°Conference2022 San Francisco & Digital | June 6 – 9

SESSION ID: HTA-T02

# My Fuzzy Driver

#### **Eran Shimony**

Senior Security Researcher CyberArk @EranShimony

#### **Mark Cherp**

Senior Security Researcher CyberArk @OcamRazr



#### Disclaimer



Presentations are intended for educational purposes only and do not replace independent professional judgment. Statements of fact and opinions expressed are those of the presenters individually and, unless expressly stated to the contrary, are not the opinion or position of RSA Conference LLC or any other cosponsors. RSA Conference does not endorse or approve, and assumes no responsibility for, the content, accuracy or completeness of the information presented.

Attendees should note that sessions may be audio- or video-recorded and may be published in various media, including print, audio and video formats without further notice. The presentation template and any media capture are subject to copyright protection.

©2022 RSA Conference LLC or its affiliates. The RSA Conference logo and other trademarks are proprietary. All rights reserved.



# RSA°Conference2022

# TL;DR

**kAFL** vs Drivers == Bugs



### **Our Menu**



# Target

What to attack and how?

### Bugs

Vulnerabillities deep dive

# Fuzzing

kAFL setup with some tweaks

### **Internals**

Healthy dose of Windows

### **Automation**

Discovery, harness and grammar



# RSA Conference 2022

# **Target**

What to attack and why?



# Don't run away from Windows



- We aim to escalate privilege from a weak point, accessible drivers are a good candidate
- Windows has more than 300 drivers with tons of legacy code written in C
- Windows is "considered" to be closed source, which makes it harder and less explored
- Windows drivers might be challenging but they are also rewarding ©



# RSA Conference 2022


# **Internals**

**Healthy dose of Windows** 



# Windows' privilege level architecture








#### **Windows Drivers 101**





#### Part of the kernel

- An extension of the Windows kernel
- Share System's address space
- Essentially a part of the kernel



- Must be digitally signed
- Driver signing can be disabled
- Requires Admin+




### Responsibility

- Talking with hardware, devices
- Filtering
- Not blue screening your machine



# **Too many Driver models**







#### **WDM Drivers**



#### **PERSONAL DATA**

Age 23 Years

**Usage** Abundant

Successor KMDF

**Location** Windows OS

Amount Over 200

#### **STATS**

**Flexibility** 

**Development Skills** 

**Security** 

**Documenter** 



#### **PERCENTAGE OF TOTAL**



#### **PURPOSE**

- Talking with devices, power management...
- Supply kernel support for applications



# RSA Conference 2022

# Bugs

**Vulnerabillities deep dive** 



# **Driver Bug Hunting 101**





Which driver do I have access to?

What are my permissions?



How do we communicate with the driver?

How does it parse user data?



# **Driver's Anatomy I**





In Windows, you talk to a driver via a device

The driver creates a device, and it should specify which users can access it. It uses SDDL string for it, or defines it in the inf file:

IoCreateDevice() or IoCreateDeviceSecure()


Followed by exposing the device to the user via calling:

IoCreateSymbolicLink() or IoRegisterDeviceInterface()

The user opens a handle to the device via calling CreateFile()\NtCreateFile()



# Show me some permissions





# **Driver's Anatomy II**





#### **Communication**

The Driver object registers dispatch routines through *DriverObject->MajorFunction[IRP\_MJ\_XXX]* 

The Dispatch routines are invoked by the *IoManager* when the following operations are done on the device:

- Create NtCreateFile
- Close NtCloseFile
- Read NtReadFile
- Write NtWriteFile
- Device\_Control DeviceIoControl -> FileIoControlDevice

These dispatch routines our initial go-to places



# **Typical DriverEntry**



```
extern "C" NTSTATUS DriverEntry(IN PDRIVER OBJECT DriverObject, IN PUNICODE STRING RegistryPath)
   UNICODE STRING DeviceName, SymbolicLink, sddlString;
   PDEVICE OBJECT deviceObject;
   RtlInitUnicodeString(&DeviceName, L"\\Device\\testydrv");
   RtlInitUnicodeString(&SymbolicLink, L"\\DosDevices\\testydrv");
   RtlInitUnicodeString(&sddlString, L"D:P(A;;GA;;;SY)(A;;GA;;;BA)");
   //Create a device
   IoCreateDevice(DriverObject, 65535, &DeviceName, FILE DEVICE UNKNOWN, FILE DEVICE SECURE OPEN, FALSE, &deviceObject);
   //IoCreateDeviceSecure(DriverObject, sizeof(65533), &DeviceName, FILE DEVICE UNKNOWN, FILE DEVICE SECURE OPEN, FALSE, &sddlString, NULL, &deviceObject)
   //Create a symbolic so the user can access the device
   IoCreateSymbolicLink(&SymbolicLink, &DeviceName);
   //Populating Driver's object dispatch table
   DriverObject->MajorFunction[IRP_MJ_DEVICE_CONTROL] = TestyDispatchIoctl;
   DriverObject->MajorFunction[IRP MJ CREATE] = TestyDispatchCreate;
   DriverObject->MajorFunction[IRP_MJ_CLOSE] = TestyDispatchClose;
   DriverObject->MajorFunction[IRP_MJ_READ] = TestyDispatchRead;
   DriverObject->MajorFunction[IRP MJ WRITE] = TestyDispatchWrite;
   DriverObject->MajorFunction[IRP MJ CLEANUP] = TestyDispatchCleanup;
   DriverObject->DriverUnload = TestyUnloadDriver;
   return STATUS_SUCCESS;
```



# **Dispatch Routine**



```
NTSTATUS TestyDispatchIoctl(PDEVICE_OBJECT DeviceObject, PIRP Irp) 🚣
   PIO STACK LOCATION CurrentStackLocation;
   NTSTATUS
                       ntStatus = STATUS SUCCESS;
   PVOID
                       SystemBuffer = NULL;
   ULONG
                       InputBufferLength = 0;
                       OutputBufferLength = 0;
   ULONG
   DWORD
                       IoControlCode = 0;
   CurrentStackLocation = IoGetCurrentIrpStackLocation(Irp);
   InputBufferLength = CurrentStackLocation->Parameters.DeviceIoControl.InputBufferLength;
   OutputBufferLength = CurrentStackLocation->Parameters.DeviceIoControl.OutputBufferLength;
   SystemBuffer = Irp->AssociatedIrp.SystemBuffer;
   IoControlCode = CurrentStackLocation->Parameters.DeviceIoControl.IoControlCode; 4
```



#### **IRPs**



**I/O request packet**, is a struct that has all the parameters any of the dispatch routines would ever need, generated when an action is performed on a device

The driver receives a pointer to the generated IRP structure by the IoManager, it consists of:

*StackLocation* – holds many important members

Requestor mode – Kernel or User

*Buffers* – Depends on the transfer type

*IoStatus.Information* – How many bytes are written to the output buffer

A misuse of any of these fields would probably cause a bug







```
BOOL DeviceIoControl(
   HANDLE hDevice,

   DWORD dwloControlCode,

LPVOID lpInBuffer,

DWORD nInBufferSize,

LPVOID lpOutBuffer,

DWORD nOutBufferSize,

LPDWORD lpBytesReturned,


LPOVERLAPPED lpOverlapped
);
```



### **IOCTL Code**



#### 32-bit IOCTL





# **Required Access**





Two bit number – describes the required permissions to send the DeviceIoControl request, it is based on your permissions in the call to NtCreateFile.

- There are four different options:
  - FILE\_ANY\_ACCESS
  - FILE\_READ\_ACCESS
  - FILE\_WRITE\_ACCESS
  - FILE READ ACCESS | FILE WRITE ACCESS



# **Transfer Type**





The two least significant bits – describe how the loManager treats user's data, there are many nuances the driver developer must know

- There are four different options:
  - METHOD\_NEITHER
  - METHOD\_BUFFERED
  - METHOD\_IN\_DIRECT
  - METHOD\_OUT\_DIRECT







- The two bits are on -> ioctl number ends with 11
- The IoManager is lazy, the buffers and their lengths reside in User-Mode, the kernel does not copy them to kernel space, they can be paged-out
- The input and output buffers are:
  - Irp->CurrentStackLocation.Parameters.DeviceIoControl.Type3InputBuffer
  - Irp->UserBuffer
- The user can allocate and deallocate the buffers making the pages invalid, so you must be cautious when dealing with them
- Every access to the buffers must be in a try except block



# Probing



- Probing validates that an address resides in User-Mode:
  - ProbeForRead (\*Address, Length, Alignment)
  - ProbeForWrite (\*Address, Length, Alignment)
- But if you don't probe or you do not use the function correctly, then:
  - It throws an exception on invalid address so the call must be inside a try except block
  - If Length is 0 it does nothing, it passes the validation without probing
  - If not probed and the kernel reads form it = BSoD or info leak
  - If not probed and the kernel writes to it = BSoD or arbitrary write







```
if ( IOCTL - 0x220C00 <= 0x27 )
                                                          METHOD NEITHER ends with 11
  return sub 140028698(DeviceObject, IRP);
if ( CurrentStackLocation->Parameters.DeviceIoControl.IoControlCode != 0x2F0003 || InputBufferLength < 0x18 )
  return ((__int64 (__fastcall *)(_DEVICE_OBJECT *, IRP *))qword_140065278)(DeviceObject, IRP);
SystemBuffer = (BYTE *)IRP->AssociatedIrp.SystemBuffer;
v13 = 0:
InputBuffer = ( int64)CurrentStackLocation->Parameters.DeviceIoControl.Type3InputBuffer;
InputBuffer2 = InputBuffer;
OutputBufferLength3 = OutputBufferLength;
if ( SystemBuffer && (*(_DWORD *)(InputBuffer + 20) & 1) != 0 )
  OutputBuffer = SystemBuffer:
else
  OutputBuffer = IRP->UserBuffer;
v43 = IRP:
   ( *( QWORD *)InputBuffer == 0x43736C266128A8C4i64 && *( QWORD *)(InputBuffer + 8) == 0x4151AA59370630B6i64
  return sub_140027EC8(DeviceObject, IRP);
if ( *(_QWORD *)InputBuffer == 0x475215BAE7F772BCi64 && *(_QWORD *)(InputBuffer + 8) == 0x57462BA4FA7660BFi64
```



# Method\_Buffered



- The two bits are off -> ioctl number ends with 00
- In METHOD\_BUFFERED the IoManager copies the buffers and their lengths to the kernel in a secure manner. Therefore, they don't reside in the user's memory space.
- No need for probing, but if the buffer has embedded fields, like pointer addresses, lengths and so on, they need to be treated properly!
- The IRP buffer is used both for input and output:
  - Irp->AssociatedIrp.SystemBuffer



# Method\_Buffered - Continued



- The Irp->IoStatus.Information indicates how many bytes are to be copied to user's OutputBuffer
- If Irp->IoStatus.Inforamtion > InputBufferLen and OutputBufferLen > InputBufferLen
  - The rest of the system buffer data copied to (OutputBuffer) is uninitialized data
  - SizeOfData = OutputBufferLen InputBufferLen
- Would cause kernel leak unless the buffer is properly initialized
  - Assuming:
    - OutputBufferLen = 0x1000, InputBufferLen = 0x8
    - Irp->IoStatus.Inforamtion = OutputBufferLen
  - Leakage of 0xFF8 bytes to user-mode



# **Bug Example II**



```
DisptachIoctlFDO (PDEVICE OBJECT Device Object, IRP *IRP)
                           METHOD BUFFRED ends with 00
     NTStatus2 = DoSomething(Device_Object, IRP);
    __int64 __fastcall DoSomething(PDEVICE_OBJECT Device_Object, PIRP irp)
     _IO_STACK_LOCATION *CurrentStackLocation; // rbx
     PVOID Device Extension; // rbp
     BYTE SystemBuffer; // si
     __int64 InputBufferLength; // r9
     ULONG OutputBufferLength; // [rsp+50h] [rbp+8h] BYREF
     CurrentStackLocation = irp->Tail.Overlay.CurrentStackLocation;
       Device Extension = Device Object->DeviceExtension;
     irp->IoStatus.Information = 0i64;
      SystemBuffer = (BYTE *)irp->AssociatedIrp.SystemBuffer;
     InputBufferLength = CurrentStackLocation->Parameters.DeviceIoControl.InputBufferLength;
      OutputBufferLength = CurrentStackLocation->Parameters.DeviceIoControl.OutputBufferLength;
       if ( OutputBufferLength >= 0x107C0 && *( QWORD *) &SystemBuffer )
           FillOutputDataAndRestWithZeros(( int64)Device Extension, *( BYTE **)&SystemBuffer, &OutputBufferLength);
           IRP->IoStatus.Information = OutputBufferLength;
            return 0i64;
          IRP->IoStatus.Information = 0x107C0i64
          return 0x80000005i64;
```



# Direct I/O




- The Right bit is on = METHOD\_IN\_DIRECT and left is off 01
- The Left bit is on = METHOD\_OUT\_DIRECT and right is off 10
- The IRP supply two pointer to buffers, both in kernel:
  - Irp->AssociatedIrp.SystemBuffer The input buffer
  - Irp->MdlAddress A second buffer used or buffered
- The second buffer is the "direct" which always paged = faster access, this buffer can be used for input or output
- The kernel can also create an MDL with IoCreateMdI() followed by locking it with MmProbeAndLockPages() which would throw an exception on invalid page







- "An MDL is a structure that describes the fixed physical memory locations that comprise a contiguous data buffer in virtual memory"
- In simpler words, The MDL describes the data buffer at a fixed position in physical memory, which will always be paged in and locked (you need to do that) in memory. It is a double mapping, one for the user, and another for the kernel







- Most of the bugs involve not checking for null, as the user can send a null buffer, thus causing *MmGetSystemAddressForMDLSafe()* to be sad
- Also, if creating an MDL yourself in the kernel, make sure you use the correct virtual address of a buffer not like in here:

```
ControlableVirtualAddress = (void *)*((_QWORD *)SystemBuffer2 + 3);

if ( ControlableVirtualAddress )


{
    AllocatedMdl = IoAllocateMdl(ControlableVirtualAddress, dwMdlSize, 0, 0, Irp);
    IrqlLevel = GetIRQLLevel(ReGetCurrentIrql());
    LODWORD(Irpb) = *((_DWORD *)SystemBuffer2 + 3);
    // Local pages in physcial memory, would crash on a bad address


| MmProbeAndLockPages(AllocatedMdl, 0, IoModifyAccess);
    if ( (AllocatedMdl->MdlFlags & 5) != 0 )
        LocalMappedSystemVA = AllocatedMdl->MappedSystemVa;
    else
        LocalMappedSystemVA = MmMapLockedPagesSpecifyCache(AllocatedMdl, 0, MmCached, 0i64, 0, dword_1400E8D84 | 0x10u);
}
```






### **How to Be Lazy**









# RSA Conference 2022


# **Automation**


Discovery, harness and grammar



# **Device Handles and IOCTLs Discovery**









**Discover Devices** 


**Enumurate Device Names** and Discover IOCTLS





# **Discovering Accessible Devices**








### **IOCTLs Discovery**









### **Harness Generation**







### **Automation Summary**





#RSAC



### **Grammar 101**

- After discovering some bugs with a simple grammar, we started examining more advanced approaches
- We know the shape of the "high-level" input passed to the IOCTL
- We don't know how the "deserialized" data inside the driver looks like

- We want to guide our Fuzzer towards relevant inputs and that's where grammar comes into play
- Grammar is essentially a way to tell the Fuzzer which inputs are more likely to increase coverage



## **Grammar Approaches**



#### Simple template matching (i.e. Regex)

```
// Regex to match phone numbers

"^[+]*[(]{0,1}[0-9]{1,4}[)]{0,1}[-\\s\\./0-9]*$"

"+972-548099912"
```

#### Input-to-state correspondence (i.e. Redqueen)

```
//Try Input = "SEEDVALUE" //Observe cmp eax, "ABCD" //Replace "SEEDVALUE" with "SEEDABCDE"
```

#### Large-scale mutation (i.e. Grimoire)

```
# Original statement print ("aabbccdd") # Mutated new paths print ("aabbccdd") # print ("aabbccdd")
```



# RS/Conference2022


# **Kernel Fuzzing**

**kAFL** setup with some tweaks



### **Fuzzing Concepts**


- #RSAC
- Feedback Get feedback on target execution state
- Fitness Decide according to some metric (coverage) how





### **AFL Feedback**






- The feedback is implemented by hooking each code block with a special report snippet
- Upon receiving a cue for entering a new block,
   the fuzzer updates the bitmap
- Instrumentation can be done during compile time, binary rewrite or dynamically








- kAFL doesn't modify the target, instead it maps Intel PT to the coverage bitmap
- Intel Processor Tracing is essentially a real-time CPU instructions tracing mechanism
- Intel PT can trace a specific driver at an address range





### **kAFL Virtualization Infra**








### Why Virtualize?





**Crash Protection** 

Crashing the target guest won't crash the Fuzzer on the host



**Closed Source** 

VT-x + Intel PT enbale efficient target agnostic fuzzing




### #RSAC

#### **Host to Guest**

- Send inputs
- Overwrite panic handler

#### **Guest to Host**

- Request and get next payload
- Disclose CR3 value
- Disclose panic handler address






### **Setup Story**



- Fuzzer executes from a VT-x and KVM enabled host (Latest Ubuntu in our case)
- Fuzzing target is virtualized on the Guest (Latest Windows in our case)
- Inputs are requested by the guest via a Hypercall API
- Host passes the input via a shared memory buffer
- Guest harness runs inputs vs kernel
- Host collects Intel PT traces and they are converted to a coverage bitmap



### **Harness: Initialization**





### Harness: Fuzzing Loop

```
this hypercall submits the current CR3 value */
kAFL hypercall(HYPERCALL KAFL SUBMIT CR3, 0);
/* submit the guest virtual address of the payload buffer */
kAFL hypercall(HYPERCALL KAFL GET PAYLOAD, (UINT64)payload buffer);
while(1){
        kAFL hypercall(HYPERCALL KAFL NEXT PAYLOAD, 0);
        /* request new payload (*blocking*) */
        kAFL hypercall(HYPERCALL KAFL ACQUIRE, 0);
        /* validate input (simple grammar) */
        validate input(payload buffer->data, payload buffer->size)
        /* kernel fuzzing */
        DeviceIoControl(kafl vuln handle,
            IOCTL KAFL INPUT,
            (LPVOID)(payload buffer->data),
            (DWORD)payload_buffer->size,
            0,
            NULL,
            NULL
        /* inform fuzzer about finished fuzzing iteration */
        kAFL hypercall(HYPERCALL KAFL RELEASE, 0);
```





# Demo

kAFL in action = Vulnerability




### What's Next?











### **Takeaways**



- What Developers can do:
  - The first step in exploiting drivers is to access them
  - If you restrict that access then the attack surface is nullified
  - You can also fuzz your own drivers as a part of the QA process

- What Attackers can do:
  - Use our automation scripts
  - Start fuzzing the kernel
  - Examine KMDF and NDIS drivers for more bugs



### **Takeaways**

#RSAC

- What Defenders can do:
  - Naïve: Make sure every driver is up-to-date
  - Advanced:
    - Monitor DeviceloControl requests to devices
    - Block / Alert in case the requesting executable is unsigned




### **Credits**

- Google ☺
- Ilja van Sprundel
- James Forshaw
- kAFL
- Syzkaller
- Alex Ionescu
- HackSys Team







# Thank You For Listening!


Do you have any questions?

mark.cherp@gmail.com | @OcamRazr

eranhelforc@gmail.com | @EranShimony









#RSAC