Interfaces between crates

Items each consumer imports from each provider

user ↓ provider →	a2a-worker provides	a2a-client provides	a2a-core provides	a2a-security provides	a2a-audit provides	bus-api provides	bus-nats provides
a2ad uses →	· Worker, WorkerBuilder, FileStore · backend traits, DelegationConfig · Publication, CardSigning, WorkspaceBinding	· allowed, not used	· Allowance, Metering · Clock, SystemClock	· Kid, Signer, storage	· Pipeline, PipelineConfig, Publisher · Redactor, EmitterIdentity, Metrics	· Bus, BusError, Headers	· NatsBus, connect, provision · layout, permissions
a2a-cli uses →	· allowed, not used	· Client, Config, SendReply · ApprovalError, ClientError, SigningHook	· SystemClock · WireError, LocalError	· Signer, storage keys · TrustStore	· verify_paths, CheckpointVerifier	· Bus, BusError	· NatsConfig, Seed
a2a-tui uses →	· allowed, not used	· Event, PendingApproval · signing envelope_hook	· ALLOW_ONCE_ID, REJECT_ONCE_ID · SystemClock	· Signer, TrustStore · storage	· allowed, not used	· Bus, Consumer, StartPosition	· NatsConfig, Seed, layout
gateway-http uses →	· allowed, not used	· Client, Directory, EventStream · CallOptions, Outbound, SendReply	· Allowance, Clock · WireError, BUS_DOMAIN, LocalError	· allowed, not used	· allowed, not used	· Bus, BusError	· allowed, not used
driver-acp uses →	· backend traits · check_turn_stream	· allowed, not used	· DEFAULT_EXPIRY_MS	· allowed, not used	· allowed, not used	· allowed, not used	· allowed, not used
driver-a2a-http uses →	· backend traits	· allowed, not used	· allowed, not used	· allowed, not used	· allowed, not used	· allowed, not used	· allowed, not used
a2a-worker uses →	—	· Client, CallOptions, Directory · Outbound, SendReply, budget	· approval: ALLOW_ONCE_ID, Tier, MAX_OPEN_PER_TASK · budget, task::TaskStore, envelope	· card sign and verify, frame · redact, Signer, TrustStore	· EventBuilder, Pipeline, AuditError	· Bus, RequestStream	· allowed, not used
a2a-client uses →	· allowed, not used	—	· envelope, errors, headers, subject · approval, DelegationRefused	· Ed25519Signer, Signer · verify_card, sign_envelope, TrustStore	· allowed, not used	· Bus, Consumer, Watch · Headers, Reply	· allowed, not used
a2a-core uses →	never: upward edge	× would point upwards	—	· allowed, not used	· allowed, not used	· Headers, Reply, ReplyHandle · InvalidName, Principal, Subject	· allowed, not used

Rule

- Each cell lists the items the row imports from the column (read from use lines).
- Red-outlined cells mark a dependency the layer rule forbids; none is present.

Scope

- Rows are the consumers this page covers; a2a-mcp and a2a-workspace are not drawn.