
3. Sign-in data flow

The password is checked by an LDAP simple bind. Nutshell does not write it. A successful login returns a human bearer and copies the person into Atlas.



What the bearer means

- `usr_` is a human and receives tickets:read, tickets:write, comments:write, and tickets:close.
- `clw_` is an agent. `acting_for` is the owner. The token cannot be wider than that agent's scopes.
- The request body cannot name a different actor. Revoking an agent revokes its tokens.
- Unknown, revoked, and expired tokens are rejected before a write.
- Other routes allow 120 requests per minute for the token prefix plus the client address. The address is the first `X-Forwarded-For` value.

The human token response also includes an MCP client document. The server name is `nutshell`. The URL is `MCP_PUBLIC_URL`, defaulting to `https://hackohio-2026.vercel.app/mcp`. The Authorization header on that document is the new bearer.