Sun Java System Access Manager 7.1 Developer's Guide

Beta



Sun Microsystems, Inc. 4150 Network Circle Santa Clara, CA 95054 U.S.A.

Part No: 819–4675–10 March 2007 Copyright 2007 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and SunTM Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2007 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plusieurs brevets américains ou des applications de brevet en attente aux Etats-Unis et dans d'autres pays.

Cette distribution peut comprendre des composants développés par des tierces personnes.

Certaines composants de ce produit peuvent être dérivées du logiciel Berkeley BSD, licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays; elle est licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, le logo Solaris, le logo Java Coffee Cup, docs.sun.com, Java et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems. Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui, en outre, se conforment aux licences écrites de Sun.

Les produits qui font l'objet de cette publication et les informations qu'il contient sont régis par la legislation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes chimiques ou biologiques ou pour le nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des Etats-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la legislation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement designés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFACON.

Contents

	Preface	11
1	Using the Client SDK	15
	How the Client SDK Works	15
	JDK and CLASSPATH Requirements	16
	Installing the Client SDK	16
	Using the Java Enterprise System 5 Installer	16
	▼ To Install the Client SDK on the Windows Platform	17
	▼ To Install the Client SDK on Sun Java System Web Server and Sun Java System Applic Server	
	▼ To Install the Client SDK on BEA WebLogic Server and IBM WebSphere Server	18
	▼ To Manually Install the Client SDK	18
	▼ To Configure the Client SDK	20
	▼ To Deploy amclientwebapps.war	21
	Initializing the Client SDK	22
	Properties Used by the ClientSDK	22
	Using a Properties File	29
	▼ To Set Client SDK Properties in a Properties File	29
	Using the Java API	29
	Setting Individual Properties	30
	Setting Up a Client Identity	30
	To Set Username and Password Properties	31
	To Set an SSO Token Provider	31
	Building Custom Web Applications	31
	Building Stand-Alone Applications	31
	▼ To Build a Stand-Alone Application	31
	Targets Defined in clientsdk	32
	About the Client SDK Samples	32

	Troubleshooting	33
2	Using Authentication APIs and SPIs	35
_	Overview of Authentication APIs and SPIs	
	How the Authentication Java APIs Work	
	XML/HTTP Interface for Other Applications	
	How the Authentication SPIs Work	
	Using Authentication APIs	
	Running the Sample Authentication Programs	
	LDAPLogin Example	
	CertLogin Example	
	▼ To Run the CertLogin Program	
	JCDI Module Example	
	Using Authentication SPIs	
	Implementing a Custom Authentication Module	
	Implementing Authentication PostProcessing SPI	
	▼ To Compile the ISAuthPostProcessSample Program on Solaris Sparc/x86 or Linux	
	▼ To Deploy the ISAuthPostProcess Sample Program	
	Generating an Authentication User ID	
	▼ To Compile the UserIDGeneratorSample on Solaris Sparc/x86, Linux	61
	▼ To Deploy the UserIDGeneratorSample Program	62
	Implementing A Pure JAAS Module	64
	▼ To Run the Sample on Solaris Sparc x86 or Linux:	65
	▼ To Enable SSL	66
	▼ To Run the Sample on Windows 2000	66
	▼ To Enable SSL	67
3	Using the Policy APIs	60
,	About the Policy APIs	
	Policy Java Packages	
	Policy Management Classes	
	Policy Evaluation Classes	
	Policy Plug-In APIs	
	Using the Policy Code Samples	
	Use Cases Illustrated by Policy Code Samples	

	▼ To Run a Policy Evaluation Program for the URL Policy Agent Service	75
	▼ To Run a Policy Evaluation Program for the URL Policy Agent Service and More	76
	▼ To Run a Policy Evaluation Program for the Sample Service	76
	▼ To Run a Policy Evaluation Program for the Sample Service and More	77
	To Use amadmin to Create Policies for the URL Policy Agent Service	77
	▼ To Use amadmin to Create Policies for the Sample Service	77
	▼ To Programmatically Construct Policies	78
	Compiling the Policy Code Samples	78
	▼ To Compile the Policy Code Samples	78
	Adding a Policy-Enabled Service to Access Manager	78
	▼ To Add a New Policy-Enabled Service to Access Manager	
	Developing Custom Subjects, Conditions, Referrals, and Response Providers	82
	▼ To Add a Sample Implementation to the Policy Framework	86
	Creating Policies for a New Service	
	▼ To Load a Policy XML File	
	Developing and Running a Policy Evaluation Program	
	▼ To Set Policy Evaluation Properties	
	▼ To Run a Policy Evaluation Program	
	Programmatically Constructing Policies	
	▼ To Run the Sample Program PolicyCreator.java	94
4	Using the JAAS Authorization Framework	97
	Overview of JAAS Authorization	
	How Policy Enforcement Works	
	How the JS2E Access Controller Works	
	JAAS Authorization in Access Manager	
	Custom APIs	
	User Interface	
	Enabling the JAAS Authorization Framework	
5	Using Session Service APIs	105
	About the Single Sign-On Java APIs	
	Using the SSO Code Samples	
	Running SSO Code Samples on Solaris	
	▼ To Run a Sample Program from the Access Manager Server	

	▼ To Run a Sample Program on a Remote Client	109
	▼ To Run the Sample Code	110
	▼ To Run a Sample Program on the Remote Client Command Line	111
	▼ To Test the Command Line	111
	Developing Non-Web Based Applications	112
6	Writing Log Operations	113
	About the Logging Samples	113
	Writing LogRecords To A Log File or Table	114
	Reading LogRecords From A Log File or Table	115
	Compiling Logging Programs	121
	Executing Logging Programs	121
	Implementing a Remote Logging Application in a Container	122
	Setting Environment Variables	122
	Logging to a Second Access Manager Server	124
	Using the Logging Sample Files	125
	lacktriangle To Run the Sample Programs on Solaris	125
	▼ To Run the Sample Programs on Windows 2000	126
	Using the Logging SPIs	127
	Log Verifier Plug-In	127
	▼ To Customize Actions to be Taken in Secure Logging	128
	Log Authorization Plug-In	128
	▼ To Implement a Log Authorization Plug-In	128
	▼ To Instantiate a PolicyEvaluator	128
7	Client Detection Service	129
	Overview	129
	Client Detection Process	129
	▼ Enabling Client Detection	130
	Client Data	
	HTML	132
	genericHTML	133
	Client Detection APIs	

8	Using the Access Manager Utilities	135
	Utility APIs	135
	AdminUtils	135
	AMClientDetector	135
	AMPasswordUtil	135
	Debug	136
	Locale	136
	SystemProperties	136
	ThreadPool	136
	Password API Plug-Ins	137
	Notify Password Sample	137
	Password Generator Sample	137
9	Enabling the Access Manager Notification Service	139
	Overview	139
	Enabling The Notification Service	139
	▼ To Receive Session Notifications	140
10	Updating and Redeploying Access Manager WAR Files	143
	WAR Files in J2EE Software Development	143
	Web Components	144
	How Web Components are Packaged	144
	About Access Manager WAR Files	144
	password.war	147
	services.war	147
	Updating Modified WARs	148
	▼ To Update a Modified WAR	148
	Redeploying Modified Access Manager WAR Files	149
	To Redeploy a WAR On BEA WebLogic Server 6.1	149
	To Redeploy a WAR File on Sun Java System Application Server 7.0	150
	Redeploying an Access Manager WAR on IBM WebSphere Application Server	150
11	Customizing the Administration Console	153
	About the Administration Console	153

	Generating The Console Interface	154
	Plug-In Modules	155
	Accessing the Console	155
	Customizing The Console	155
	The Default Console Files	155
	console.war	156
	Creating Custom Organization Files	157
	▼ To Create Custom Organization Files	157
	Alternate Customization Procedure	158
	Miscellaneous Customizations	159
	Console APIs	163
	▼ To Create a Console Event Listener	163
	Precompiling the Console JSP	164
	Console Samples	164
	Modify User Profile Page	164
	Create A Tabbed Identity Management Display	164
	ConsoleEventListener	164
	Add Administrative Function	164
	Add A New Module Tab	164
	Create A Custom User Profile View	
12	Customizing the Authentication User Interface	167
	User Interface Files You Can Modify	
	Staging Area for Files to be Customized	
	Java Server Pages	169
	XML Files	171
	JavaScript Files	174
	Cascading Style Sheets	
	Images	
	Localization Files	176
	Customizing Branding and Functionality	
	▼ To Modify Branding and Functionality	
	Customizing the Self-Registration Page	
	▼ To Modify the Self-Registration Page	
	Updating and Redeploying services.war	
	· · ·	

Index	187
▼ To Customize the Distributed Authentication User Interface	183
Customizing the Distributed Authentication User Interface	183
To Redeploy services.war	182
▼ To Update services.war	181

Preface

Sun Java™ System Access Manager is a component of the Sun Java Enterprise System (Java ES), a set of software components that provide services needed to support enterprise applications distributed across a network or Internet environment. The *Sun Java System Access Manager 7.1 Developer's Guide* provides information about using the Access Manager Java application programming interfaces (APIs) and service preprogramming interfaces (SPIs).

For information about using the Access Manager C-APIs, see Chapter 1, "The C Application Programming Interface Files," in *Sun Java System Access Manager 7.1 C API Reference* in the document *Sun Java System Access Manager 7.1 C API Reference*.

Before You Read This Book

This book is intended for use by IT administrators and software developers who implement a web access platform using Sun Java System servers and software. Readers of this guide should be familiar with the following concepts and technologies:

- Deployment platform: Solaris[™] or Linux operating system
- Web container that will run Access Manager: Sun Java System Application Server, Sun Java System Web Server, BEA WebLogic, or IBM WebSphere Application Server
- Technical concepts: Lightweight Directory Access Protocol (LDAP), Java technology, JavaServer Pages[™] (JSP) technology, HyperText Transfer Protocol (HTTP), HyperText Markup Language (HTML), and eXtensible Markup Language (XML)

Related Books

Related documentation is available as follows:

- "Access Manager Core Documentation" on page 11
- "Sun Java Enterprise System Product Documentation" on page 13

Access Manager Core Documentation

The Access Manager core documentation set contains the following titles:

- The Sun Java System Access Manager 7.1 Release Notes will be available online after the product is released. It gathers an assortment of last-minute information, including a description of what is new in this current release, known problems and limitations, installation notes, and how to report issues with the software or the documentation.
- The Sun Java System Access Manager 7.1 Technical Overview provides an overview of how Access Manager components work together to consolidate access control functions, and to protect enterprise assets and web-based applications. It also explains basic Access Manager concepts and terminology.
- The Sun Java System Access Manager 7.1 Deployment Planning Guide provides planning and deployment solutions for Sun JavaTM System Access Manager based on the solution life cycle.
- The Sun Java System Access Manager 7.1 Postinstallation Guideprovides information about basic Access Manager configuration tasks you must perform immediately after running the Java Enterprise System installer.
- The Sun Java System Access Manager 7.1 Performance Tuning Guide provides information on how to tune Access Manager and its related components for optimal performance.
- The Sun Java System Access Manager 7.1 Administration Guide describes how to use the Access Manager console as well as manage user and service data via the command line interface.
- The Sun Java System Access Manager 7.1 Federation and SAML Administration Guideprovides information about the Federation module based on the Liberty Alliance Project specifications. It includes information on the integrated services based on these specifications, instructions for enabling a Liberty-based environment, and summaries of the application programming interface (API) for extending the framework.
- The Sun Java System Access Manager 7.1 Developer's Guide (this guide) offers information on how to customize Access Manager and integrate its functionality into an organization's current technical infrastructure. It also contains details about the programmatic aspects of the product and its API.
- The *Sun Java System Access Manager 7.1 C API Reference* provides summaries of data types, structures, and functions that make up the public Access Manager C APIs.
- The Sun Java System Access Manager 7.1 2006Q4 Java API Reference (part number 819-2141) provides information about the implementation of Java packages in Access Manager.
- The Sun Java System Access Manager Policy Agent 2.2 User's Guide provides an overview of the policy functionality and the policy agents available for Access Manager.

Updates to the *Release Notes* and links to modifications of the core documentation can be found on the Access Manager page at the Sun Java Enterprise System documentation web site. Updated documents will be marked with a revision date.

Sun Java Enterprise System Product Documentation

Useful information can be found in the documentation for the following products:

- Directory Server
- Web Server
- Application Server
- Web Proxy Server

Related Third-Party Web Site References

Third-party URLs are referenced in this document and provide additional, related information.

Note – Sun is not responsible for the availability of third-party web sites mentioned in this document. Sun does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Sun will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

Documentation, Support, and Training

The Sun web site provides information about the following additional resources:

- Documentation (http://www.sun.com/documentation/)
- Support (http://www.sun.com/support/)
- Training (http://www.sun.com/training/)

Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-1 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories,	Edit your . login file.
	and onscreen computer output	Use ls -a to list all files.
		machine_name% you have mail.

TABLE P-1 Typographic Conventions (Continued)		
Typeface	Meaning	Example
AaBbCc123	What you type, contrasted with onscreen	machine_name% su
	computer output	Password:
aabbcc123	Placeholder: replace with a real name or value	The command to remove a file is rm filename.
AaBbCc123	Book titles, new terms, and terms to be	Read Chapter 6 in the <i>User's Guide</i> .
	emphasized	A <i>cache</i> is a copy that is stored locally.
		Do <i>not</i> save the file.
		Note: Some emphasized items appear bold online.

Shell Prompts in Command Examples

The following table shows the default UNIX* system prompt and superuser prompt for the C shell, Bourne shell, and Korn shell.

TABLE P-2 Shell Prompts

Shell	Prompt
C shell	machine_name%
C shell for superuser	machine_name#
Bourne shell and Korn shell	\$
Bourne shell and Korn shell for superuser	#

Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions.

To share your comments, go to http://docs.sun.com and click Send Comments. In the online form, provide the document title and part number. The part number is a seven-digit or nine-digit number that can be found on the title page of the book or at the top of the document.

For example, the title of this book is *Sun Java System Access Manager 7.1 Developer's Guide*, and the part number is 819-4675–10.

◆ ◆ ◆ CHAPTER 1

Using the Client SDK

The Sun Java™ System Access Manager 7.1 Client SDK package provides Access Management Java libraries for implementing stand-alone applications and web applications. You can use the Client SDK interfaces in your applications to take advantage of Access Manger services such as authentication, Single Sign-On (SSO), authorization, auditing and logging, user management, and Security Assertion Markup Language (SAML). The client SDK libraries communicate with Access Manager using XML (SOAP) over HTTP or HTTPS.

This chapter contains the following topics:

- "How the Client SDK Works" on page 15
- "JDK and CLASSPATH Requirements" on page 16
- "Installing the Client SDK" on page 16
- "Initializing the Client SDK" on page 22
- "Setting Up a Client Identity" on page 30
- "Building Custom Web Applications" on page 31

How the Client SDK Works

The Access Manager Client SDK is a streamlined version of the Access Manager SDK, and includes only the client-side classes and configuration properties you need to connect to Access Manager services. The Client SDK is contained in a smaller jar file, and eliminate the dependency on connections to Directory Server when developing and deploying client applications. The Client SDK and client applications communicate with the Access Manager server. Only the Access Manager server communicates directly with the Directory Server.

When you install the Access Manager server, the Client SDK is contained in the following file:

AccessManager-base/SUNWam/lib/amclientsdk.jar

The following table summarizes items included in the Client SDK.

TABLE 1-1 Contents of Access Manager-base/SUNWam/amclientsdk.jar

File	Description
README.clientsdk	ASCII version of this chapter. Contains information on installing and using Access Manager client SDK.
lib/amclientsdk.jar	Client SDK for stand-alone applications.
amclient.war	Archive of Access Manager samples, web applications, and Javadoc.
Makefile.clientsdk	Defines objects and parameters for building sample properties, stand-alone samples and web applications.

JDK and CLASSPATH Requirements

The Client SDK requires J2SE 1.4.2.

Note - Both amclientsdk. jar and servlet. jar are required in the CLASSPATH.

Installing the Client SDK

Before you can install the Access Manager Client SDK, the Access Manager server must be running on a remote server. You will also need to have ready the following information about the remote installation:

- Protocol used by the web contain instance on which the Access Manager server is deployed.
- Fully qualified domain name of the host on which Access Manager server is deployed.
- Port on which the Access Manager server is running.
- Deployment URI for the services web application (by default amserver).
- Password encryption key used by the Access Manager server.

Two methods exist for installing the Client SDK. You can automatically install the Client SDK using the Java Enterprise System 5 installer, or you can manually deploy the Client SDK WAR file.

Using the Java Enterprise System 5 Installer

If you install the Access Manager Client SDK by running the Java Enterprise System 5 installer, you must choose the Access Manager Client SDK install option. For detailed information, see Chapter 10, "Deploying the Client SDK," in *Sun Java System Access Manager 7.1 Postinstallation Guide*.

▼ To Install the Client SDK on the Windows Platform

On the Windows platform, you must use the "Configure Manually After Installation" option in the Java Enterprise System 5 installer. For detailed information, see "To Install and Configure the Access Manager Client SDK" in *Sun Java System Access Manager 7.1 Postinstallation Guide*. The following is an overview of the steps you must follow

- 1 Invoke the Java Enterprise System 5 installer.
 - a. When prompted for Setup Type, choose Custom.
 - b. When prompted for Product Configuration, choose "Configure manually after install."
 - c. When prompted for Products to Install, select the web container (Web Server or Application Server) and Access Manager Client SDK.
- Configure and start the Web container.
- **3 Edit the file** AccessManager-base\identity\setup\AMConfigurator.properties. See "To Install and Configure the Access Manager Client SDK" in *Sun Java System Access Manager 7.1 Postinstallation Guide* for detailed information.
- 4 Run the amconfig.bat command:

AccessManager-base\identity\setup\amconfig.bat

▼ To Install the Client SDK on Sun Java System Web Server and Sun Java System Application Server

The following is an overview of the steps you must follow. For detailed information, see Chapter 10, "Deploying the Client SDK," in *Sun Java System Access Manager 7.1 Postinstallation Guide*.

- Invoke the JES installer.
- 2 Select the web container (Web Server or Application Server) and Access Manager client SDK.
- 3 Choose "Configure Now."
- 4 Answer the questions provided by the installer.
- 5 After the installation is complete, restart the web container.

▼ To Install the Client SDK on BEA WebLogic Server and IBM WebSphere Server

The third party web container should already be installed and started.

The following is an overview of the steps you must follow. For detailed information, see Chapter 10, "Deploying the Client SDK," in *Sun Java System Access Manager 7.1 Postinstallation Guide*.

- Invoke the JES installer.
- 2 Select Access Manager client SDK.
- 3 Choose "Configure Later."
- 4 After the installation, edit the amsamplesilent file.
 - a. Change the DEPLOY LEVEL value to 9.
 - b. Supply values for all the commented settings.
 - c. Change the value for BASEDIR if needed.
 - d. Edit the web container value (for example, WL8 * or WAS51*) to perform the deployment.
- 5 Run amconfig with the edited amsamplesilent file.
- 6 After the configuration is complete, restart the web container.

To Manually Install the Client SDK

Before You Begin

- The Access Manager server which will be used by the client SDK must be up and running, and you must know the URL for accessing this server.
- The machine where the client SDK will be installed must have an Access Manager supported web container installed. Examples of Access Manager supported web containers are Sun Java System Web Server 6.1 sp5, Sun Java System Application Server 8.1, BEA WebLogic Server 8.1 sp4, and IBM Websphere Application Server 5.1.1.5.
- The web container instance on which the client SDK will be deployed must be up and running.
- The client SDK machine must have access to the Access Manager client SDK package SUNWamclnt through the Java Enterprise System 4 bits or through some other means.

1 Create a package administration file..

Using a text editor, add the following contents to this file.

```
mail=
instance=unique
partial=nocheck
runlevel=nocheck
idepend=nocheck
rdepend=nocheck
space=nocheck
setuid=nocheck
conflict=nocheck
action=nocheck
basedir=ClientSDK-base-directory
```

In this example, the package administration file is named /usr/tmp/pkgadmin.

The value for basediris the directory in which you want to install the Access Manager client SDK.

2 Create a package response file named /usr/tmp/pkgresp.

Using a text editor, place the following three lines (a single y on each line) in this file.

y y

У

3 In the Access Manager package directory, use the pkgadd utility to install the SUNWamcInt package:

```
{\tt cd} \ {\it JES2005Q4-Image-root/OperatingSystem-Architecture/Product/identity\_svr/Packages} \\ {\tt pkgadd-n-a/usr/tmp/pkgadmin-d.-r/usr/tmp/pkgresp-R/SUNWamclnt} \\ {\tt or} \ {\it loss} \ {\it
```

4 In the directory in which you installed the Access Manager client SDK package, make a copy of the file Makefile.clientsdk.

The directory in which you installed the Access Manager client SDK package should be the same as the value you used for *basedir* in the package administration file in step 1a.

On Solaris: cd ClientSDK-base-directory/SUNWam

cp Makefile.clientsdk Makefile.clientsdk.orig

On Linux: cd ClientSDK-base-directory/identity

cp Makefile.clientsdk Makefile.clientsdk.orig

▼ To Configure the Client SDK

1 In Makefile.clientsdk, edit the following parameters:

JAVA_HOME Use the following path: /usr/jdk/entsys-j2se

SERVER_HOSTNAME The fully-qualified domain name of the Access Manager server.

SERVER_PROTOCOL If the Access Manager server is SSL-enabled, change this value to

HTTPS.

SERVER_PORT The port number on which the Access Manager server is running.

ENCRYPTION_KEY This value must be the same value used for the Access Manager

server. You can obtain the value by running one of the following

commands on the Access Manager server:

On Solaris grep pwd

/etc/opt/SUNWam/config/AMConfig.properties

On Linux grep pwd

/etc/opt/sun/identity/config/AMConfig.properties

DEBUG_DIR (Optional) If you don't want the debug logs stored in the tmp

directory, then change this value to the directory where you want

debug logs to be created.

2 Run the make or gmake command:

make -f Makefile.clientsdk

This step generates a sample properties file in the directory temp, standalone samples in the directory clientsdk-samples and a deployable war file, amclientwebapps.war. The following table summarizes the items included in the WAR file.

File	Description
index.html	Instructions for installing and using the Client SDK packages
WEB-INF/web.xml	Client SDK for stand-alone applications
WEB-INF/classes/AMClient.properties	Archive of Access Manager samples, web applications, and Javadoc
WEB-INF/classes/*.classes	File for building stand-alone samples and web applications
WEB-INF/docs	Javadoc (Public Client SDK APIs)
WEB-INF/samples	Sample stand-alone programs
WEB-INF/webapps	Sample web applications

▼ To Deploy amclientwebapps.war

1 Create a deployment directory for amclientwebapps.war.

On Solaris mkdir -p ClientSDK-base-directory/SUNWam/web-src/clientsdk

On Linux mkdir -p *ClientSDK-base-directory*/identity/web-src/clientsdK

2 On the web container instance where you want to use the Access Manager client SDK, deploy the amclientwebapps.war file. See the following examples:

Sun Java Enterprise Web Server on Solaris or Linux

Use the wdeploy command to deploy amclientwebapps.war with a URI of /amcilentwebapps on the Web Server instance https-clientSDKinstance. Example:

WebServer-base-directory/bin/https/httpadmin/bin/wdeploy deploy -u /amclientwebapps -i https-clientSDKinstance -v https-clientsdkinstance -d ClientSDK-base-directory/SUNWam/web-src/clientsdk clientSDK-base-directory/SUNWam/amclientwebapps.war

Sun Java Enterprise Application Server on Solaris

Using the asadmin command to deploy amclientwebapps.war with a URI of /amclientwebapps on the application server instance *clientsSDKinstance*. Example:

ApplicationServer-base-directory/appserver/bin/asadmin deploy -user Admin-User-ID --host ApplicationServer-instanceHost --port ApplicationServer-Admin-Port --contextroot amclientwebapps -name amcilentwebapps -target clientSDKinstance ClientSDK-base-directory/SUNWam/amclientwebapps.war

Be sure to use the fully qualified host name for ApplicationServer-instanceHost.

Enter the Application Server administration password when prompted.

Sun Java Enterprise Application Server on Linux

Using the asadmin command to deploy amclientwebapps .war with a URI of /amclientwebapps on the application server instance *clientsSDKinstance*. Example:

ApplicationServer-base-directory/bin/asadmin deploy -user Admin-User-ID --host ApplicationServer-instanceHost --port ApplicationServer-Admin-Port --contextroot amclientwebapps -name amcilentwebapps -target clientSDKinstance ClientSDK-base-directory/SUNWam/amclientwebapps.war

Be sure to use the fully qualified host name for *ApplicationServer-instanceHost*.

Enter the Application Server administration password when prompted.

If you are deploying the client SDK on a third-party web container such as BEA WebLogic Server or IBM WebSphere Application Server, then see the documentation that comes with that product.

3 Restart the web container instance on which the Access Manager client SDK was deployed.

If the full server instance being accessed by the client SDK is SSL-enabled, then you must install the root CA certificate of the server's certificate in the web container's JVM-wide cacerts keystore. Alternatively, you can create a keystore on the client SDK machine to contain the server's root CA certificate. Then add the necessary JVM options to the client SDK's web container instance to locate the newly created keystore.

Initializing the Client SDK

Before Access Manager Client SDK can communicate with Access Manager Server, you must initialize some properties in the client SDK. You can set these properties in one of three ways:

- "Using a Properties File" on page 29
- "Using the Java API" on page 29
- "Setting Individual Properties" on page 30

Properties Used by the ClientSDK

Access Manager properties are contained in the AMConfig.properties file. Generate the AMConfig.properties for the Client SDK by running the following command:

```
# make -f Makefile.clientsdk properties
```

The following sections describe the properties expected by the Access Manager Client SDK. A client application deployed within a servlet container can register for changes to session, user attributes and policy decisions. These properties must be set to receive such notifications.

Naming URL Properties

```
com.iplanet.am.naming.url
```

This is a required property. The value of this property represents the URL where the Client SDK would retrieve the URLs of Access Manager internal services. This is the URI for the Naming Service. Example:

com.iplanet.am.naming.url=http://AcceessManager-HostName.domain_name:port/amserver/namin

```
com.iplanet.am.naming.failover.url
```

This property can be used by any remote SDK application that wants failover in, for example, session validation or getting the service URLs. Example:

com.iplanet.am.naming.failover.url=http://AcceessManager-HostName.domain_name:
port/amserver/failover

Debug Properties

```
com.iplanet.services.debug.level
```

Specifies the debug level. Possible values are levels are: off, error, warning, or message.

```
com.iplanet.services.debug.directory
```

The value of this property is the output directory for the debug information. This directory should be writable by the server process. Example:

com.iplanet.services.debug.directory=/var/opt/SUNWam/debug

Notification URL Properties

```
com.iplanet.am.notification.url
```

The value of this property is the URI of the Notification Service running on the host machine where you installed the Client SDK. Example:

```
com.iplanet.am.notification.url=
http://clientSDK_host.domain_name:port/amserver/notificationservice
```

com.sun.identity.agents.notification.enabled

Enables or disables notifications for remote policy API. Example:

```
com.sun.identity.agents.notification.enabled=false
```

com.sun.identity.agents.notification.url

Defines the notification URL for remote policy API.

Security Credentials Properties

```
\verb|com.sun.identity.agents.app.username| \\
```

Reads configuration data. Example:

```
com.sun.identity.agents.app.username=APPLICATION_USER
```

com.iplanet.am.service.password

Reads configuration data. Example:

```
com.iplanet.am.service.password=APPLICATION PASSWD
```

com.iplanet.am.service.secret

Contains the encrypted value of the password. Example:

com.iplanet.am.service.secret=ENCRYPTION KEY

Encryption Properties

am.encryption.pwd

This key is needed to decrypt passwords stored in the SMS configuration. Example:

am.encryption.pwd=ENCRYPTION KEY

```
com.sun.identity.client.encryptionKey
```

Encryption key that will be used to encrypt and decrypt data used locally within the client. Example:

```
com.sun.identity.client.encryptionKey=ENCRYPTION KEY LOCAL
```

```
com.iplanet.security.encryptor
```

Property to set JCE as the default encryption classes.

com.iplanet.security.encryptor=com.iplanet.services.util.JCEEncryption

Cache Update Properties

```
com.sun.identity.sm.cacheTime
```

Cache update time (in minutes) for service configuration data if notification URL is not provided. Example:

```
com.sun.identity.sm.cacheTime=1
```

```
com.iplanet.am.sdk.remote.pollingTime
```

Cache update time (in minutes) for user management cache if notification URL is not provided. Example: com.iplanet.am.sdk.remote.pollingTime=1

Authentication Service Properties

```
com.iplanet.am.server.protocol
```

Server protocol to be used by Authentication Service. Example:

```
com.iplanet.am.server.protocol=SERVER PROTOCOL
```

```
com.iplanet.am.server.host
```

Server host to be used by Authentication Service. Example:

```
com.iplanet.am.server.host=SERVER HOST
```

```
com.iplanet.am.server.port
```

Server port to be used by Authentication Service. Example:

```
com.iplanet.am.server.port=SERVER PORT
```

Cookie Property

```
com.iplanet.am.cookie.name
```

Indicates the Access Manager cookie name. Example:

```
com.iplanet.am.cookie.name=AM COOKIE NAME
```

Session Service Properties

```
com.iplanet.am.session.client.polling.enable
   Example:
   com.iplanet.am.session.client.polling.enable=true
com.iplanet.am.session.client.polling.period
   Example:
   com.iplanet.am.session.client.polling.period=180
```

Certificate Database Properties

```
com.iplanet.am.admin.cli.certdb.dir
```

Identifies the certificate database directory path for initializing the JSS Socket Factory when the Access Manager web container is configured for SSL. Example:

```
com.iplanet.am.admin.cli.certdb.dir=
CONTAINER CERTDB DIR
```

```
com.iplanet.am.admin.cli.certdb.passfile
```

Identifies the certificate database password file for initializing the JSS Socket Factory when the Access Manager web container is configured for SSL. Example:

```
com.iplanet.am.admin.cli.certdb.passfile=
BASEDIR/PRODUCT DIR/config/.wtpass
```

```
com.iplanet.am.admin.cli.certdb.prefix
```

Identifies the certificate database prefix for initializing the JSS Socket Factory when the Access Manager web container is configured for SSL. Example:

```
com.iplanet.am.admin.cli.certdb.prefix=
CONTAINER_CERTDB_PREFIX
```

Policy Client Properties

```
com.sun.identity.agents.server.log.file.name
Specifies file name for the policy decision log file. Example:
```

```
com.sun.identity.agents.server.log.file.name=amRemotePolicyLog
```

```
com.sun.identity.agents.logging.level
```

Possible values for policy decision logging level are NONE, ALLOW, DENY, BOTH, and DECISION.

```
\verb|com.sun.identity.agents.notification.enabled| \\
```

Enables Notification URL for updating cache. Default value is false.

```
com.sun.identity.agents.notification.url
```

Specifies use of Notification URL for updating cache.

Example:com.sun.identity.agents.notification.url=NOTIFICATION URL

com.sun.identity.agents.polling.interval

Cache time in minutes. Example:

com.sun.identity.agents.polling.interval=3

com.sun.identity.policy.client.cacheMode

Information to cache. Possible value are subtree or self.

com.sun.identity.policy.client.usePre22BooleanValues

Define and set this property to false if you do not want to use Boolean values. The default value is true if the property is not defined.

Monitoring Framework Property

com.sun.identity.monitoring=off

Explicitly disables Java Enterprise System (JES) monitoring services in the sample client applications.

Remote Client SDK Property

com.iplanet.amsdk.package

If you want to use a remote instance of the Client SDK, set the value of this property as follows:

com.iplanet.amsdk.package=remote

The default value is ldap if the property is not defined.

Federation Properties

The following properties are used to configure interactions in a federated environment. These properties are not automatically generated and placed in the AMConfig.properties file when you run the make -f Makefile.clientsdk properties command. You must manually add the properties to the file as needed.

com.sun.identity.liberty.ws.soap.supportedActor

Supported SOAP actors. Each actor must be separated by a pipe (|). Example:

com.sun.identity.liberty.ws.soap.supportedActors= http://schemas.xmlsoap.org/soap/actor/next

com.sun.identity.liberty.interaction.wspRedirectHandler

Indicates the URL for WSPRedirectHandlerServlet to handle Liberty the WSF web service provider-resource owner. Interactions are based on user agent redirects. The servlet should be running in the same JVM where the Liberty service provider is running.

- com.sun.identity.liberty.interaction.wscSpecifiedInteractionChoice
 Indicates whether the web service client should participate in an interaction. Valid values are
 interactIfNeeded | doNotInteract | doNotInteractForData . Default value is
 interactIfNeeded. Default value is used if an invalid value is specified.
- com.sun.identity.liberty.interaction.wscWillInlcudeUserInteractionHeader Indicates whether the web service client should include userInteractionHeader. Valid values are yes and no (case ignored). Default value is yes. Default value is used if no value is specified.
- com.sun.identity.liberty.interaction.wscWillRedirect
 Indicates whether the web service client will redirect user for an interaction. Valid values are
 yes and no. Default value is yes. Default value is used if no value is specified.
- com.sun.identity.liberty.interaction.wscSpecifiedMaxInteractionTime Indicates the web service client preference for acceptable duration (in seconds) for an interaction. If the value is not specified or if a non-integer value is specified, then the default value is 60.
- com.sun.identity.liberty.interaction.wscWillEnforceHttpsCheck
 Indicates whether the web service client enforces that redirected to URL is HTTPS. Valid
 values are yes and no (case ignored). The Liberty specification requires the value to be yes.
 Default value is yes. Default value is used if no value is specified.
- com.sun.identity.liberty.interaction.wspWillRedirect
 Indicates whether the web service provider redirects the user for an interaction. Valid values are yes and no (case ignored). Default value is yes. Default value is if no value is specified.
- com.sun.identity.liberty.interaction.wspWillRedirectForData
 Indicates whether the web service provider redirects the user for an interaction for data.
 Valid values are yes and no. Default value is yes. If no value is specified, the value is yes.
- com.sun.identity.liberty.interaction.wspRedirectTime Web service provider expected duration (in seconds) for an interaction. Default value if the value is not specified or is a non-integer value is 30.
- com.sun.identity.liberty.interaction.wspWillEnforceHttpsCheck Indicates whether the web service client enforces that returnToURL is HTTP. Valid values are yes and no (case ignored). Liberty specification requires the value to be yes. Default value is yes. If no value is specified, then the value used is yes.
- com.sun.identity.liberty.interaction.wspWillEnforceReturnToHostEqualsRequestHost Indicates whether the web services client enforces that returnToHost and requestHost are the same. Valid values are yes and no. Liberty specification requires the value to be yes.
- com.sun.identity.liberty.interaction.htmlStyleSheetLocation
 Indicates the path to the style sheet used to render the interaction page in HTML.
- com. sun.identity.liberty.interaction.wmlStyleSheetLocation Indicates the path to the style sheet used to render the interaction page in WML.

Example:

com.sun.identity.liberty.interaction.wmlStyleSheetLocation=/opt/SUNWam/lib/is-wml.xsl

com.sun.identity.liberty.ws.interaction.enable

Default value is false

com.sun.identity.wss.provider.config.plugin=com.sun.identity.wss.provider.plugins.AgentPro Used by the web services provider to determine the plug-in that will be used to store the configuration.

Example:

com.sun.identity.wss.provider.config.plugin=com.sun.identity.wss.provider.plugins.Agent

com.sun.identity.loginurl

Used by the web services clients in ClientSDK mode. Example:

com.sun.identity.loginurl=https://hostName:portNumber/amserver/UI/Login

com.sun.identity.liberty.authnsvc.url

Indicates the Liberty authentication service URL.

com.sun.identity.liberty.wsf.version

Used to determine which version of the Liberty identity web services framework is to be used when the framework can not determine from the inbound message or from the resource offering. This property is used when Access Manager is acting as the web service client. The default version is 1.1. The possible values are 1.0 or 1.1.

com.sun.identity.liberty.ws.soap.certalias

Value is set during installation. Client certificate alias that will be used in SSL connection for Liberty SOAP Binding.

com.sun.identity.liberty.ws.soap.messageIDCacheCleanupInterval

Default value is 60000. Specifies the number of milliseconds to elapse before cache cleanup events begin. Each message is stored in a cache with its ownmessageID to avoid duplicate messages. When a message's current time less the received time exceeds thestaleTimeLimit value, the message is removed from the cache.

com.sun.identity.liberty.ws.soap.staleTimeLimit

Default value is 300000. Determines if a message is stale and thus no longer trustworthy. If the message timestamp is earlier than the current timestamp by the specified number of milliseconds, the message the considered to be stale.

com.sun.identity.liberty.ws.wsc.certalias

Value is set during installation. Specifies default certificate alias for issuing web service security token for this web service client.

com.sun.identity.liberty.ws.trustedca.certaliases

Value is set during installation. Specifies certificate aliases for trusted CA. SAML or SAML BEARER token of incoming request. Message must be signed by a trusted CA in this list. The syntax is cert alias 1[:issuer 1]|cert alias 2[:issuer 2]|.... Example:

myalias1:myissuer1|myalias2|myalias3:myissuer3. The value issuer is used when the token doesn't have a KeyInfo inside the signature. The issuer of the token must be in this list, and the corresponding certificate alias will be used to verify the signature. If KeyInfo exists, the keystore must contain a certificate alias that matches the KeyInfo and the certificate alias must be in this list.

Using a Properties File

You can set properties in a properties file and then provide a path to it at runtime. The properties files must be in the CLASSPATH. The default properties file name is AMConfig.properties and is always read at start-up.

To Set Client SDK Properties in a Properties File

1 Generate a sample AMConfig.properties by running the following command:

```
make -f Makefile.clientsdk properties
```

The AMConfig.properties will be present in the temp directory.

2 Edit properties to suit your environment.

Note – At runtime, if the file name is different from AMConfig, provide the file name (without the .properties extension) and path. The path should be in the CLASSPATH by declaring the JVM option:

-Damconfig=filname

Using the Java API

The ClientSDK properties can also be set programmatically using the class: com.iplanet.am.util.SystemProperties. See the following example.

EXAMPLE 1–1 Setting Client SDK Properties

Setting Individual Properties

You can set properties one at a time. For example, you can declare the following JVM option at run time to assign a value to a particular property:

-DpropertyName=propertyValue

Setting Up a Client Identity

Some of the Access Manager components such as SAML, User Management, Policy, require an identity for the client. The client application reads configuration data to identify the client. You can set up the identity for the client in one of two ways:

- Set username and password properties can be authenticated
- Set an SSO Token Provider

Note – Some of the configuration attributes (such as password) are encrypted and stored in the data store as an Encryption/Decryption Key. If such attributes have to be decrypted by the client, the property must be set, and must be the same as that of the Access Manager Server.

This value is generated at installation time and stored in the following file:

```
Solaris /etc/opt/SUNWam/config/AMConfig.properties
Linux /etc/opt/sun/identity/AMConfig.properties
Windows AccessManager-base\identity\config\AMConfig.properties
HP-UX /etc/opt/sun/identity/config/AMConfig.properties
```

To Set Username and Password Properties

The following properties can be used to set the username and password that can be used by client SDK to obtain the configuration parameters. The authenticated username should have permissions to read the configuration data for SAML and User Management.

- The property to provide the user name is: com.sun.identity.agents.app.username
- The property to provide the plain text password is: com.iplanet.am.service.password

For scenarios where plain text password would be security concern, an encrypted password can be provided using the property: com.iplanet.am.service.secret.

If an encrypted password is provided, the encryption key must also be provided using the property: am.encryption.pwd.

To Set an SSO Token Provider

Set the following property: com.sun.identity.security.AdminToken

This provides an implementation for the interface, which returns the following single sign-on (SSO) token: com.sun.identity.security.AppSSOTokenProvider.

Building Custom Web Applications

The Client SDK package contains Makefile.clientsdk that you can use to generate and build samples and web applications. The makefile defines targets to build configuration properties, samples and web applications.

Building Stand-Alone Applications

Use these steps a template for building their identity-enabled web applications.

To Build a Stand-Alone Application

1 Install the Client SDK.

See "Installing the Client SDK" on page 16.

2 Copy servlet.jar to lib directory.

3 Run the stand-alone application.

Change directory to respective components within clientsdk-samples. Each has a Readme.html file explaining the changes to done and a Makefile to rebuild and run the program.

Targets Defined in clientsdk

For web deployment, amclientwebapps.war is ready to be deployed. However, you can make changes in clientsdk-webapps directory and the war file can be recreated.

Custom web applications can use the following as a template to build their identity enabled web application.

properties: Generates AMConfig.properties in the temp directory that can used as a template for setting AM SDK's properties

samples: Copies standalone samples and corresponding Makefiles to samples directory.

webapp: Generates amclientwebapps.war that can be deployed on any Servlet 2.3 compliant web container.

About the Client SDK Samples

Sample files are included in the Client SDK. These demonstrate how to write stand-alone programs and how to write web applications. After you deploy the Client SDK using either the Java ES installer or the amconfig script with DEPLOY_LEVEL=9, the Client SDK samples are available in the following directory:

Solaris AccessManager-base/SUNWam/war/
Linux and HP-UX AccessManager-base/identity/war/
Windows systems AccessManager-base\identity\war\

The subdirectory clientsdk-samples includes samples for authentication, logging, policy and SAML stand-alone programs. The subdirectoryclientsdk-webapps includes samples for user management, service management, and policy programs. Each sample has a Readme.html file with instructions on compiling and running the sample program.

Troubleshooting

If the client program receives a "New Generic Exception" message, one possible cause is that the session has expired. As a workaround, you can increase values of the Session Idle Timeout and Max Session Time attributes. In the Access Manager administration console, click Configuration > Global > Session. See "Maximum Session Time" and "Maximum Idle Time" in the section "Resulting Behavior If Session Quota Exhausted" in *Sun Java System Access Manager 7.1 Administration Reference* for attribute descriptions.

When attempting to authenticate against Access Manager, if the client program receives a "NullPointerException" message, one possible cause is that the client identity username, secret, or password properties are not set correctly. For more information, see "Security Credentials Properties" on page 23 and "Using the Java API" on page 29.



Using Authentication APIs and SPIs

This chapter provides information on using Sun JavaTM System Access Manager 7.1 authentication programming interfaces to use and to extend the Authentication Service.

This chapter contains the following sections:

- "Overview of Authentication APIs and SPIs" on page 35
- "Using Authentication APIs" on page 42
- "Using Authentication SPIs" on page 47

Overview of Authentication APIs and SPIs

Access Manager provides both Java APIs and C APIs for writing authentication clients that remote applications can use to gain access to the Authenticate Service. This communication between the APIs and the Authentication Service occurs by sending XML messages over HTTP(S). The remote-auth.dtd is the template used in formatting the XML request messages sent to Access Manager and for parsing the XML return messages received by the external application. You can access remote-auth.dtd in the directory *AccessManager-base* /SUNWam/dtd.

New authentication modules are added to Access Manager by using the com.iplanet.authentication.spi package. The SPI implements the JAAS LoginModule, and provides additional methods to access the Authentication Service and module configuration properties files. Because of this architecture, any custom JAAS authentication module will work within the Authentication Service.

Note – If contacting the Authentication Service directly through its URL http://AccessManager-HostName.domain_name:port/service_deploy_uri/authservice without the API, a detailed understanding of remote-auth.dtd will be needed for generating and interpreting the messages passed between the client and server.

How the Authentication Java APIs Work

External Java applications can authenticate users with the Access Manager Authentication Service by using the Authentication Java APIs. The APIs are organized in a package called com.sun.identity.authentication and can be executed locally or remotely. The classes and methods defined in this package are used to initiate the authentication process and communicate authentication credentials to the specific modules within the Authentication Service. The classes and methods can be incorporated into a Java application to allow communication with the Authentication Service.

The first step necessary for an external Java application to authenticate to Access Manager is to create a new AuthContext object (com.sun.identity.authentication.AuthContext). The AuthContext class is defined for each authentication request as it initiates the authentication process. Since Access Manager can handle multiple organizations, AuthContext is initialized, at the least, with the name of the organization to which the requestor is authenticating. Once an AuthContext object has been created, the login() method is called indicating to the server what method of authentication is desired.

IndexName is the value of the authentication type. The following table summarizes IndexName values and their corresponding authentication types.

TABLE 2-1 IndexName Values

IndexName Value	Authentication Type
AuthContext.IndexType.ROLE	Role-based
AuthContext.IndexType.SERVICE	Service-based
AuthContext.IndexType.USER	User-based
AuthContext.IndexType.LEVEL	Authentication Level-based
AuthContext.IndexType.MODULE_INSTANCE	Module-based

The <code>getRequirements()</code> method then calls the objects that will be populated by the user. Depending on the parameters passed with the instantiated <code>AuthContext</code> object and the two method calls, Access Manager responds to the client request with the correct login requirement screens. For example, if the requested user is authenticating to an organization configured for LDAP authentication only, the server will respond with the LDAP login requirement screen to

supply a user name and a password. The client must then loop by calling the hasMoreRequirements() method until the required credentials have been entered. Once entered, the credentials are submitted back to the server with the method call submitRequirements(). The final step is for the client to make a getStatus() method call to determine if the authentication was successful. If successful, the caller obtains a session token for the user; if not, a LoginException is thrown.

Because the Authentication Service is built on the JAAS framework, the Authentication API can also invoke any authentication modules written purely with the JAAS API.

For detailed information about Java APIs for authentication, see the Javadoc in the following directory:

AccessManager-base/SUNWam/docs

XML/HTTP Interface for Other Applications

Applications written in a programming language other than Java or C can exchange authentication information with Access Manager using the XML/HTTP(s) interface. Using the URL http://server_name.domain_name:port/service_deploy_uri/authservice, an application can open a connection using the HTTP POST method and exchange XML messages with the Authentication Service. The structure of the XML messages is defined in remote-auth.dtd. In order to access the Authentication Service in this manner, the client application must contain the following:

- A means of producing valid XML compliant with the remote-auth.dtd.
- HTTP 1.1 compliant client implementation to send XML-configured information to Access Manager.
- HTTP 1.1 compliant server implementation to receive XML-configured information from Access Manager.
- An XML parser to interpret the data received from Access Manager.

Examples of XML Messages

The following code examples illustrate how customers might configure the XML messages posted to the Authentication Service.

Note – Although the client application need only write XML based on the remote-auth.dtd, when these messages are sent they include additional XML code produced by the Authentication API. This additional XML code is not illustrated in the following examples.

The following example illustrates the initial XML message sent to the Access Manager. It opens a connection and asks for authentication requirements regarding the exampleorg organization to which the user will login.

EXAMPLE 2-1 Initial AuthContext XML Message

```
<?xml version="1.0" encoding="UTF-8"?>
<AuthContext version="1.0"><Request authIdentifier="0">
<Login orgName="dc=red,dc=iplanet,dc=com">
<IndexTypeNamePair indexType="moduleInstance"><IndexName>LDAP</IndexName>
</IndexTypeNamePair></Login></Request></AuthContext>
```

The following example illustrates the successful response from Access Manager that contains the authIdentifier, the session identifier for the initial request.

EXAMPLE 2-2 AuthIdentifier XML Message Response

```
<?xml version="1.0" encoding="UTF-8"?>
<AuthContext version="1.0"><Response authIdentifier="AQIC5wM2LY4SfczGP8Kp9
cqcaNluW+C7CMdeR2afoN1ZxwY=@AAJTSQACMDE=#">
<GetRequirements><Callbacks length="3">
<PagePropertiesCallback isErrorState="false"><ModuleName>LDAP</ModuleName>
<HeaderValue>This server uses LDAP Authentication</HeaderValue>
<ImageName></ImageName><PageTimeOutValue>120</PageTimeOutValue>
<TemplateName></PageState>
</PagePropertiesCallback>
<NameCallback><Prompt> User Name: </Prompt></NameCallback>
<PasswordCallback echoPassword="false"><Prompt> Password: </Prompt>
</PasswordCallback></Callbacks></GetRequirements></Response></AuthContext>
```

The following example illustrates the client response message back to Access Manager. It specifies the type of authentication module needed by the user to log in.

EXAMPLE 2-3 Second Request Message With Authentication Module Specified

```
<?xml version="1.0" encoding="UTF-8"?>
<AuthContext version="1.0"><Request authIdentifier="AQIC5wM2LY4SfczGP8Kp9cqca
N1uW+C7CMdeR2afoN1ZxwY=@AAJTSQACMDE=#">
<SubmitRequirements><Callbacks length="2"><NameCallback><Prompt>User Name:</Prompt>
<Value>amadmin</Value>
</NameCallback>
<PasswordCallback echoPassword="false"><Prompt>Password:</Prompt>
<Value>admin123</Value>
</PasswordCallback></Callbacks></SubmitRequirements></Request></AuthContext>
```

The following example illustrates the return message from Access Manager which specifies the authentication module's login requirements.

EXAMPLE 2-4 Return XML Message With Login Callbacks

<?xml version="1.0" encoding="UTF-8"?> <AuthContext version="1.0"><Response authIdentifier="AQIC5wM2LY4SfczGP8Kp9cqcaN1uW+</pre> C7CMdeR2afoN1ZxwY=@AAJTS0ACMDE=#"> <LoginStatus status="success" ssoToken="AQIC5wM2LY4SfczGP8Kp9cqcaN1uW+C7CMdeR2afoN1</pre> ZxwY=@AAJTSQACMDE=#" successURL="http://blitz.red.iplanet.com/amserver/console"> <Subject>AQICOIy3FdTlJoAiOyyyZRTjOVBVWAb2e5MOAizI7ky3raaKypFE3e+GGZuX6chvLgDO32Zugn pijo4xW4wUzyh2OAcdO9r9zhMU2Nhm2O6IuAmz9m18JWaYJpSHLqtBEcf1GbDrm3VAkERzIqsvkLKHmS1qc yaT3BJ87wH0YQnPDze4/BroBZ8N5G3mPzPz5RbE07/1/w02yH9w0+UUFwwNBLayywGsr3bJ6emSSYgxos1N 1bo98xqL4FKAzItsfUAMd6v0ylWoqkoyoSdKYNHKbqvLDIeAfhqgoldxt64Or6HMXnOxz/jiVauh2mmwBpH q1H2mOeF3aqfUfuzKxBpLfELLwCH6QWcJmOZl0eNCFkGl7VwfnCJpTx1WcUhPSq0xD26D3dCQNruJpHPqzZ FThe55M2q02qX+I1klmvzqhSqiYfyoGq2SFeBeHE7iHuuj00e6UZqKDr0QPjU9aDh1GxxnsMQmaNkjuW+up ghruWBGy+mDWmPQTme2bQWPIjBgB4wTDXTedeDzDBeulhCH4M0Ak9lvS7EIv6kHX5pRph6d0ND4/RVHka3k WcQ5e0w2HpPj0xzNrWMfyXTkQJwOrA8yh1eBjG04VwiVqDV4wAV5EsIsIt0TrtAW2VZwV/KtLcGmjaKaT0H dwRy0M4DHEqDbc6jF5ItVo9NneGFXMswPIoLm2nLuMrteAt7AtK7FGuCHlfYLavKoROtjaSuYTJGFwqz80i vZ2r9boVnWVlz7ehwlyHvdfmpSKVl76Y4qEclX25m+lddAZE92RgSIrg97fp9gB0k2gVJWoQORNRDV2siHr 26 RiPLdvW3foG0hZapLimJuLdBvThRd/tdknDCCNRzelv7khr6nLPVPFVBaEJWlHmuffkdz4OsL0omFWpi Jq05sQCPs/q6rq9ZJ98a8mcFK10BVPQki/1VfkIbKAdO4eswsIMalYkqlBqXT4ARVTWRCWRNMCTDlQitF3q T51AHn1WioFPm+NZ2KagVjQR6JFxHbdW0bKN7cLQViArJJFRtktR1BJh31/K+dAM2P+KbT1Lq13UUvXCynS QwVbf7HJP5m3XrIQ6PtgZs4TB026H+iKy5T85YNL03j9sNnALiIKJEgvGLg2jxG+SU10xNLz3P3UVqmAnQI 9FIjmCtJcFtlLYR6BbkTvZVKxWz6+SoxNfDeKhIDwxkTNTLOzK491KzU/XAZTKmvdxTqf+WikbriBhFjsJ4 M6Npsq4p9Ksrjun9FVBTE/EUT5X/bY8zXLm0nw5KspQ7XRHPwrpp0MVMMekz5qrNtQ9Cw/TeOhm4jvww/Bz j4rydi7s7D10s2BWMfcuxmwQEipAWNmraKL37wWskrCdAz02HXH4iJjWimiJ6J</Subject> </LoginStatus></Response></AuthContext>

How the Authentication SPIs Work

- "Extending the AMLoginModule Class" on page 39
- "Pluggable JAAS Module" on page 40
- "Authentication Post Processing" on page 40

Access Manager provides the capability to plug new, Java-based authentication modules into its framework allowing proprietary authentication providers to be managed using the Access Manager console. A custom authentication module must first be created using Java. Once created, the custom module can be added to the list of available authentication modules.

Note – This guide does not document the JAAS. For more information on these APIs, see the *Java Authentication And Authorization Service Developer's Guide*. Additional information can be found at http://java.sun.com/products/jaas/.

Extending the AMLoginModule Class

Custom authentication modules extend the com.sun.identity.authentication.spi.AMLoginModule class. The class must also implement the init(), process() and getPrincipal() methods in order to communicate

with the authentication module configuration files. The callbacks are then dynamically generated based on this file. Other methods that can be defined include setLoginFailureURL and setLoginSuccessURL which defines URLs to send the user to based on a failed or successful authentication, respectively.

Note – To make use of the account locking feature with custom authentication modules, the InvalidPasswordException exception should be thrown when the password is invalid.

Pluggable JAAS Module

The Java Authentication and Authorization Service (JAAS) is a set of APIs that enable services to authenticate and enforce access controls upon users. It implements a Java technology version of the standard Pluggable Authentication Module (PAM) framework, and supports user-based authorization. Access Manager supports pure JAAS pluggable authentication modules. In Access Manager, pure JAAS modules extend the JAAS LoginModule rather than AMLoginModule. A pure JAAS module is plugged in to the Authentication framework using the Authentication API.

Authentication Post Processing

The Authentication SPI includes the AMPostAuthProcessInterface which can be implemented for post-processing tasks. The following are examples of post-processing tasks:

- Adding attributes to a user's session after successful authentication
- Sending notification to an administrator after failed authentication
- General clean-up such as clearing cookies after logout or logging out of other system components.

The Core Authentication Service contains the Authentication PostProcessing Class attribute which contains the authentication post-processing class name as its value. Custom post processing interfaces can also be implemented.

AMPostAuthProcessInterface can be implemented for post authentication processing on authentication success, failure and logout. The SPI is configurable at the organization, service and role levels. The Authentication Service invokes the post processing SPI methods on successful, failed authentication and logout.

The AMPostProcessInterface class has 3 methods:

- "onLoginSuccess" on page 41
- "onLoginFailure" on page 41
- "onLogout" on page 41

Some supporting information on these methods is provided in the following sections. For a comprehensive listing and detailed information on all Access Manager methods, see the Javadoc installed in the following directory:

AccessManager-base/SUNWam/docs

onLoginSuccess

This method should be implemented for post-processing after a successful authentication. Authentication Service will invoke this method on successful authentication.

Method signature is:

where

- requestParamaMap is a map containing HttpServletRequest parameters
- request HttpServletRequest object
- response HttpServletResponse objectcom.sun.identity.authentication.spi.AuthenticationException is thrown on error.

onLoginFailure

This method should be implemented for post processing after a failed authentication. Authentication Service will invoke this method on failed authentication.

Method signature is:

where

- requestMap is a map containing HttpServletRequest parameters
- request HttpServletRequest object
- response HttpServletRequest objectcom.sun.identity.authentication.spi.AuthenticationException is thrown on error.

onLogout

This method should be implemented for post-processing on a logout request. Authentication Service will invoke this method on logout.

Method signature is:

where

- request HttpServletRequest object is a map containing HttpServletRequest parameters
- response HttpServletResponse object
- ssoToken authenticated user's single sign on token
 com.sun.identity.authentication.spi AuthenticationException is thrown on error.

Using Authentication APIs

Access Manager comes with a number of sample programs that demonstrate how you can use the Authentication APIs to extend the functionality of the authentication service and authentication modules.

- "Running the Sample Authentication Programs" on page 42
- "LDAPLogin Example" on page 45
- "CertLogin Example" on page 45
- "JCDI Module Example" on page 46
- C-API Sample

Running the Sample Authentication Programs

The source code and Makefile are provided for all sample programs. For some sample programs, additional supporting files are also included. The instructions for compiling and executing the sample programs are the same for all samples described in this section.

Java API Code Samples and Their Locations

The following tables describe the locations of all the files you need to implement the sample programs on various platforms, and the variable names used for default directories in the source code and Makefiles. Table 2–2 summarizes file locations and variable names used for Solaris Sparc/x86.l Table 2–3 summarizes default directories for Linux. Table 2–4 summarizes default directories for Windows 2000.

TABLE 2-2 Default directories for Solaris Sparc/x86

Variable	Description	Location
Api_sample_dir	Directory that contains authentication API sample files	<pre><install_root>/SUNWam/ samples/authenitcation/api</install_root></pre>
Config_directory	Directory that contains configuration files	/etc/opt/SUNWam/config
Product_Directory	Directory where Access Manager is installed.	<pre>install_root>/SUNWam</pre>

TABLE 2-3 Default directories for Linux

Variable	Description	Location
Api_Sample_Dir	Directory that contains authentication API sample files	<pre><install_root>/sun/ identity/samples/authentication/api</install_root></pre>
Config_Directory	Directory that contains configuration files	/etc/opt/sun/identity/config
Product_Directory	Directory where Access Manager is installed.	<pre><install_root>/sun/identity</install_root></pre>

TABLE 2-4 Default directories for Windows 2000

Variable	Description	Location
Api_Sample_Dir	Directory that contains authentication API sample files	<install_root>\samples\ authentication\api</install_root>
Config_Directory	Directory that contains configuration files	<install_root>\lib</install_root>
Product_Directory	Directory where Access Manager is installed.	<install_root></install_root>

These steps are for all platforms.

▼ To Compile and Execute the Java API Samples

1 In the Makefile, modify the following variables as necessary to suit your Access Manager installation:

BASE_DIR: Enter the path to the directory where Access Manager is installed.

JAVA_HOME: Enter the path to the directory where the Java compiler is installed.

DOMAIN: Enter the name of the organization to login to.

SHARE_LIB: Enter the path to the directory where Access Manager jar files are stored.

JSS_JAR_PATH: Enter the path to the directory where JSS jar files are stored.

JSSPATH: Enter the path to the directory where JSS libraries are located.

In the Certificate Sample Makefile only, modify the following as necessary:

CERTNICKNAME: Enter the Certificate nickname.

URL: Enter the Access Manger Server URL.

PASSWORD: Enter the Certificate DB Password.

3 Copy AMConfig.properties from Config_Directory in the Access Manager server installation to the client machine.

(Note: For SSL check SSL Configuration Setup, step 2).

- 4 In the Makefile, update the classpath to include the location of the newly created AMConfig.properties.
- 5 In the client machine, create a directory named locale.

Copy all the property files from the locale directory in the Access Manager server installation machine to the client machine. The locale directory on the server machine can be found under the *Product_Directory*.

- 6 Update the classpath in the Makefile to include the location of newly created locale files.
- 7 Include jaas. jar in your classpath if you are using a JDK version less than JDK1.4
- 8 Compile the program.
 - On Solaris Sparc/x86, Linux, run the gmake command.
 - On Windows 2000, run the make command.
- 9 Run the sample program.
 - On Solaris Sparc/x86 or Linux, run the following command: gmake run
 - On Windows 2000, run the following command: make run

▼ To Configure SSL for Java API Samples

- 1 In the Makefile, add this JVM property in the run target:
 - -D "java.protocol.handler.pkgs=com.iplanet.services.comm"
- 2 Copy AMConfig.properties from Config_Directory in the Access Manager server installation to the client machine.
- 3 Edit the following properties in AMConfig.properties. com.iplanet.am.admin.cli.certdb.dir: Enter the path to the certificate database directory. com.iplanet.am.admin.cli.certdb.prefix: Enter the certificate database prefix.
- In the LDAP and JCDI Samples only:
 com.iplanet.am.server.protocol: Change the value to HTTPS.
 com.iplanet.am.server.port: Enter the appropriate port number from the server machine.
- 5 Create or copy the certificate database file to the certificate db directory. Use the directory name in com.iplanet.am.admin.cli.certdb.dir.
- 6 Rename the file to use the prefix specified in the property com.iplanet.am.admin.cli.certdb.prefix.

 For the details, see the Javadoc for the Remote Client API.

LDAPLogin Example

The LDAPLogin sample is an example of a custom Java application that uses the authentication remote APIs to authenticate to the LDAP module. You can modify the sample source code to authenticate to other existing or customized authentication modules. The sample source code, Makefile, and Readme.html are located in the following directory:

AccessManager-base/SUNWam/samples/authentication/LDAP

To compile and run the sample program, follow the steps in "To Compile and Execute the Java API Samples" on page 43.

CertLogin Example

The CertLogin sample is an example of a custom Java application that uses digital certificates for authentication. You can modify the sample source code to authenticate to other existing or customized authentication modules. The sample source code, Makefile, and Readme.html are located in the following file:

AccessManager-base/SUNWam/samples/authentication/Cert

To Run the CertLogin Program

Enable SSL.

Follow the instructions in "To Configure SSL for Java API Samples" on page 45.

2 Compile and execute the sample code.

See "To Compile and Execute the Java API Samples" on page 43

Using certutil for Client Certificate Management

Certutil is a command-line utility that can create and modify cert7.db and key3.db database files. It can also list, generate, modify, or delete certificates within the cert7.db file and create or change the password, generate new public and private key pairs, display the contents of the key database, or delete key pairs within the key3.db file. The key and certificate management process usually begins with creating keys in the key database, then generating and managing certificates in the certificate database.

JCDI Module Example

The JCDI Module Example demonstrates the use of Java Card Digital ID (JCDI) authentication with Access Manager. The sample has two components:

- Remote client
- Server JCDI authentication module

The remote client component is located in the following directory:

AccessManager-base/samples/authentication/api/jcdi

The server JCDI authentication module is located in the following directory:

AccessManager-basesamples/authentication/spi/jcdi

The sample illustrates JCDI authentication using the Remote Authentication API. You can modify the sample source code to authenticate to other existing or customized authentication modules. The source code, Makefile, and Readme.html are located in the following directory:

AccessManager-basesamples/authentication/api/jcdi

To compile and run the sample program, follow the steps in "Running the Sample Authentication Programs" on page 42.

Using Authentication SPIs

Access Manager provides the following sample programs to demonstrate how you can use the Authentication service programming interfaces (SPIs) to extend authentication functionality:

- "Implementing a Custom Authentication Module" on page 47
- "Implementing Authentication PostProcessing SPI" on page 56
- "Generating an Authentication User ID" on page 61
- "Implementing A Pure JAAS Module" on page 64

Implementing a Custom Authentication Module

Access Manager contains a sample exercise for integrating a custom authentication module with files that have already been created. This sample illustrates the steps for integrating an authentication module into the Access Manager deployment. All the files needed to compile, deploy and run the sample authentication module can be found in the following directory:

AccessManager-base/SUNWam/samples/authentication/providers

The following sections will use files from this sample as example code:

- "Writing a Sample Login Module" on page 47
- "Compiling and Deploying the LoginModule program" on page 51
- "To Deploy the Login Module Sample Program" on page 52
- "Loading the Login Module Sample into Access Manager" on page 53
- "Running the LoginModule Sample Program" on page 55

About the Login Module Sample

<PRODUCT_DIR> setting on different Platforms:

 $\textbf{Solaris Sparc/x86:} < \texttt{PRODUCT_DIR} > = \textit{base-directory/SUNWam}$

Linux: <PRODUCT_DIR> = base-directory/sun/identity

Windows 2000: <PRODUCT_DIR> = *base-directory*

Writing a Sample Login Module

Use the AMLoginModule SPI to write your own sample login module.

▼ To Write a Sample Login Module

- 1 "Creating a Module Properties File" on page 48.
- 2 "Writing the Principal Class" on page 49.
- 3 "Implementing the LoginModule Interface" on page 49.

The following are the default directories used in the sample exercise for the various platforms:

```
Solaris Sparc/x86: <PRODUCT_DIR> = base-directory/SUNWam
```

Linux: <PRODUCT_DIR> = *base-directory*/sun/identity

W2K: <PRODUCT_DIR> = base-directory

Creating a Module Properties File

Create a Module properties XML file with the same name of the class (no package name) and use the extension .xml. You must create an XML file with this naming convention even if no states required

Based on this configuration file, the Authentication user interface will dynamically generate a login page.

You can define page states in the module properties file as shown in "Creating a Module Properties File" on page 48. Each callback element corresponds to one login page state. When an authentication process is invoked, Callback[] values will be generated from the user's Login Module for each state. All login state definitions start with 1. The module controls the login process, and then determines what the next state is.

Auth_Module_Properties.dtd defines the data structure that will be used by each authentication module to specify its properties. Auth_Module_Properties.dtd provides definitions to initiate, construct and send required callbacks information to the Authentication graphical user interface. Auth_Module_Properties.dtd is stored in the <PRODUCT_DIR>/dtd directory.

EXAMPLE 2-5 Module Configuration Sample

EXAMPLE 2-5 Module Configuration Sample (Continued)

In this module configuration sample, page state one has two callbacks. The first callback is for user ID, and second is for Last Name. When the user fills in the callbacks, the following events occur:

- The Callback[] values are sent to the module.
- The process() routine validates the callback values.
- The module writer sets the next page state to 2.

Page state 2 has one callback to request the user to enter a password. The process () routine is again called after the user submits the Callback[] values. If the module writer throws a LoginException, then an Authentication Failed page will be sent to the user. If no exception is thrown, the user is redirected to his or her default page.

Writing the Principal Class

After creating module configuration XML file, the next step is to write a Sample Principal class which implements java.security.Principal. The constructor takes the user's username as an argument. If authentication is successful, the module will return this principal to Authentication framework. The Authentication framework populates a Subject with a SamplePrincipal representing the user.

Implementing the LoginModule Interface

AMLoginModule is an abstract class which implements JAAS LoginModule. AMLoginModule provides methods for accessing Access Manager services and the module XML configuration. Login Module writers must subclass AMLoginModule class and implement the following methods:

- init()
- process()
- getPrincipal()

For detailed descriptions, syntax, and parameters, see the *Sun Java System Access Manager 7.1 2006Q4 Java API Reference*. The following sections provide some supporting information about these methods.

init() This is an abstract method, Module writer should implement to initialize this LoginModule with the relevant information. If this LoginModule does not understand any of the data stored in sharedState or options parameters, the data can be ignored. This method is called by a AMLoginModule after thisSampleLoginModule has been instantiated, and prior to any calls to its other public methods. The method implementation should store away the provided arguments for future use. The init method may additionally peruse the provided sharedState to determine what additional authentication state it was provided by other LoginModules, and may also traverse through the provided options to determine what configuration options were specified to affect the LoginModule's behavior. It may save option values in variables for future use.

process() The process method is called to authenticate a Subject. This method implementation should perform the actual authentication. For example, it may cause prompting for a user name and password, and then attempt to verify the password against a password database. If your LoginModule requires some form of user interaction (retrieving a user name and password, for example), it should not do so directly. That is because there are various ways of communicating with a user, and it is desirable for LoginModules to remain independent of the different types of user interaction. Rather, the LoginModule's process method should invoke the handle method of the CallbackHandler passed to this method to perform the user interaction and set appropriate results, such as the user name and password and the AMLoginModule internally passes the GUI an array of appropriate Callbacks, for example a NameCallback for the user name and a PasswordCallback for the password, and the GUI performs the requested user interaction and sets appropriate values in the Callbacks.

Consider the following points while writing the process () method:

- Perform the authentication. If Authentication succeeded, save the principal who has successfully authenticated.
- Return -1 if authentication succeeds, or throw a LoginException such as AuthLoginException if authentication fails or return relevant state specified in module configuration XML file
- If multiple states are available to the user, the Callback array from a previous state may be retrieved by using the getCallbak(int state) methods. The underlying login module keeps the Callback[] from the previous states until the login process is completed.
- If a module writer needs to substitute dynamic text in next state, the writer could use the getCallback() method to get the Callback[] for the next state, modify the output text or prompt, then call replaceCallback() to update the Callback array. This allows a module writer to dynamically generate challenges, passwords or user IDs. Each authentication session will create a new instance of your Login Module Java class. The reference to the class

will be released once the authentication session has either succeeded or failed. It is important to note that any static data or reference to any static data in your Login module must be thread-safe.

getPrincipal() This method should be called once at the end of a successful authentication session. A login session is deemed successful when all pages in the Module properties XML file have been sent and the module has not thrown an exception. The method retrieves the authenticated token string that the authenticated user will be known by in the Access Manager environment.

Note – If the custom authentication module requires or already uses a service configuration XML file:

- The XML file should contain attribute schema for one of the following attributes: iplanet-am-auth-authModuleName-auth-level or lsunAMAuthauthModuleNameAuthLevel
- The module Java file should invoke the following method in the init method implementation: public boolean setAuthLevel(int auth level)

Compiling and Deploying the LoginModule program

If you are writing your own Custom Authentication module based on the AMLoginModule SPI or a pure JAAS module, then you can skip this step. Otherwise, after writing the sample Login Module, compile and deploy the sample found under

AccessManager-base/samples/authentication/spi/providers.

To compile the Login Module

1 Set the following environment variables.

These variables will be used to run the gmake command. You can also set these variables in the Makefile. This Makefile is in the following directory: *AccessManager-base* /samples/authentication/spi/providers.

JAVA_HOME: Set this variable to your installation of JDK. The JDK should be version 1.3.1_06 or higher.

CLASSPATH: Set this variable to refer to am_services.jar which can be found in the *Idetnity_base*/lib directory. Include jaas.jar in your classpath if you are using JDK version less than JDK1.4

BASE_DIR: Set this variable to the directory where the Access Manager is installed.

BASE_CLASS_DIR: Set this variable to the directory where all the Sample compiled classes are located.

JAR_DIR: Set this variable to the directory where the JAR files of the Sample compiled classes will be created.

2 In the AccessManager-base/samples/authentication/spi/providers directory, run gmake.

To Deploy the Login Module Sample Program

- 1 Copy LoginModuleSample.jar from JAR_DIR to AccessManager-base/web-src/services/WEB-INF/lib.
- **2 Copy LoginModuleSample.xml from** *AccessManager-base* /samples/authentication/spi/providers **to** *AccessManager-base* /web-src/services/config/auth/default.
- 3 Redeploy the amserver . war file.

▼ To Redeploy the amserver.war File

- 1 In AccessManager-base/bin/amsamplesilent, set Deploy Level variable as follows: DEPLOY LEVEL=21
- 2 In AccessManager-base/bin/amsamplesilent, set container-related environment variables.
 - On Sun Java System Web Server 6.1, where /amserver is the default DEPLOY URI:

```
SERVER_HOST=WebServer-hostName
SERVER_PORT=WebServer-portNumber
SERVER_PROTOCOL=[http | https]
SERVER_DEPLOY_URI=/amserver
WEB_CONTAINER=WS6
WS61_INSTANCE=https-$SERVER_HOST
WS61_HOME= WebServer-base-directory
WS61_PROTOCOL=$SERVER_PROTOCOL
WS61_HOST=$SERVER_HOST
WS61_PORT=$SERVER_PORT
WS61_ADMINPORT=WebServer-adminPortWS61_ADMIN=WebServer-adminUserName
```

• On Sun Java System Application Server 7.0, where /amserver is the default DEPLOY_URI:

```
SERVER_HOST=ApplicationServer-hostName
SERVER_PORT=ApplicationServer-portNumber
SERVER_PROTOCOL=[http | https]
SERVER_DEPLOY_URI=/amserver
WEB_CONTAINER=AS7
AS70_HOME=/opt/SUNWappserver7
```

```
AS70_PROTOCOL=$SERVER_PROTOCOL
AS70_HOST=$SERVER_HOST
AS70_PORT=$SERVER_PORT
AS70_ADMINPORT=4848
AS70_ADMIN=admin
AS70_ADMINPASSWD=ApplicationServer-adminPassword
AS70_INSTANCE=server1
AS70_DOMAIN=domain1
AS70_INSTANCE_DIR=/var/opt/SUNWappserver7/domains/
${AS70_DOMAIN:-domain1}/${AS70_INSTANCE:-server1}
AS70_DOCS_DIR=/var/opt/SUNWappserver7/domains/${AS70_DOCS_DIR=/var/opt/SUNWappserver7/domains/${AS70_DOMAIN:-domain1}/$
${AS70_INSTANCE:-server1}/docroot
#If Application Server is SSL Enabled then set the following:
#AS70_IS_SECURE=true
#SSL_PASSWORD=SSLpassword
```

On other supported platforms:

Set platform-specific variables as is appropriate for the container.

3 Redeploy the services web application by running the following command:

```
AccessManager-base/bin/amconfig -s
AccessManager-base/bin/amsamplesilent
```

4 Restart the container instance.

Web Server example:

```
/WebServer-base-directory/
https-WebServer-instanceName/restart
```

Application Server example:

```
/var/opt/SUNWappserver7/domains/${AS70_DOMAIN:-domain1}/
${AS70_INSTANCE:-server1}/bin/restartserv
```

Loading the Login Module Sample into Access Manager

Once you've compiled and deployed the login module, you must load the login module into Access Manager. You can load the login module by using either the Access Manager administration console, or by using the amadmin command.

To Load the Login Module Using the Administration Console

1 Login to Access Manager Console as amadmin, using the URL:

http://host.domain:port/Console-Deploy-URL

- 2 Click Configuration.
- 3 In the Configuration tab, under Authentication, click Core.
- 4 Add class file name com.iplanet.am.samples.authentication.spi.providers. LoginModuleSample to the Pluggable Authentication Modules Classes list.
- 5 Click Save.

▼ To Load the Login Module Using the Command Line

Write a sample XML file as shown in "To Load the Login Module Using the Command Line" on page 54, which will add the LoginModuleSample authentication module entry into the allowed modules and an authenticators list.

```
<!--
      Copyright (c) 2003 Sun Microsystems, Inc.
               All rights reserved
     Use is subject to license terms.
-->
<!DOCTYPE Requests
      PUBLIC "-//iPlanet//iDSAME 5.0 Admin CLI DTD//EN"
     "jar://com/iplanet/am/admin/cli/amAdmin.dtd"
<Requests>
   <SchemaRequests serviceName="iPlanetAMAuthService"</pre>
                      SchemaType="Global">
      <AddDefaultValues>
       <AttributeValuePair>
          <Attribute name="iplanet-am-auth-authenticators"/>
 <Value>com.iplanet.am.samples.authentication.spi.providers.
                      LoginModuleSample</Value>
        </AttributeValuePair>
      </AddDefaultValues>
    </SchemaRequests>
</Requests>
```

2 Use amadmin to load sample.xml:

```
<AMADMIN> --runasdn uid=amAdmin,ou=People,<root_suffix> --password <password>
--data sample.xml
```

Solaris Sparc/x86: AMADMIN = <PRODUCT DIR>/bin/amadmin

On W2K: AMADMIN = <PRODUCT DIR>\\bin\\amadmin

Running the LoginModule Sample Program

This sections provides instructions for running the login module on Solaris and on Windows platforms.

▼ To Run the LoginModule on Solaris

1 Use the following URL to log in to Access Manager console as amAdmin:

http://host.domain:port/Console-Deploy-URI

- 2 Click Identity Management, and in the Identity Management view select your organization.
- 3 From the View menu, select Services.
- 4 In the navigation frame, under Authentication, click Core.
- 5 SelectLoginModuleSample to add it to the list of highlighted modules in Organization Authentication Modules.

Make sure LDAP module is also selected. If not selected, you will not be able to login to Access Manager Console. You can use Control + mouse click to add additional modules.

- 6 Click Save.
- 7 Log out.
- 8 Enter the following URL:

http://host.domain:port/Service-Deploy-URI/UI/Login?module=LoginModuleSample

If you choose to use an organization other than the default, be sure to specify that in the URL using the org parameter.

▼ To Run the Login Module on Windows 2000

1 Set the following environment variables. These variables will be used to run the make command. You can also set these variables in the Makefile.

This Makefile is in the same directory as the Login Module Sample program files: AccessManager-base\samples\authentication\spi\providers

JAVA_HOME: Set this variable to your installation of JDK. The JDK should be version 1.3.1_06 or higher.

BASE: Set this variable to *base-directory*

CLASSPATH: Set this variable to refer to am_services.jar which can be found in the *base-directory*\lib directory. Include jaas.jar in your classpath if you are using JDK version less than JDK1.4

BASE_CLASS_DIR: Set this variable to the directory where all the Sample compiled classes are located.

JAR_DIR: Set this variable to the directory where the JAR files of the Sample compiled classes will be created.

2 In the base-directory\samples\authentication\spi\providers directory, run the make command

To Deploy the Login Module

- 1 Copy LoginModuleSample.jarfrom JAR_DIR to
 AccessManager-base\web-src\services\WEB-INF\lib
- 2 In the Web Container from which this sample has to run, update the classpath with LoginModuleSample.jar.
- 3 Update server. xml with the new classpath and server. xml locations:
 - Sun Java System Web Server: <WS-install-dir>\https-<WS-instance-name>\config\server.xml
 - Sun Java System Application Server: <AS-install-dir>\domain<appserver domain><appserver_instance>\config\server.xml

Example:<AS-install-dir>\domain\domain1\server1\config\server.xml

- 4 Copy LoginModuleSample.xml from base-directory \samples \authentication \spi \providers to base-directory \web-src\services \config\auth\default.
- 5 Restart the web container

Web Server: <WS-home-dir>\https-<WS-instance-name>\restart

Application Server: AppServer-home-dir>\domains\<domain
name><server instance>\bin\restartserv

Implementing Authentication PostProcessing SPI

The Authentication SPI includes the AMPostAuthProcessInterface which can be implemented for post-processing tasks. The AMPostProcessInterface Javadoc are available at:

AccessManager-base/SUNWam/docs/com/sun/identity/authentication/spi/AMPostAuthProcessInterface.html

The SPI is configurable at the organization, service and role levels. The Authentication Service invokes the post processing SPI methods on successful or failed authentication and on logout.

About the PostProcessing SPI Sample

<PRODUCT_DIR> or AccessManager-base directory on different Platforms:

- Solaris Sparc/x86: AccessManager-base/SUNWam
- Linux: AccessManager-base/sun/identity

▼ To Compile the ISAuthPostProcessSample Program on Solaris Sparc/x86 or Linux

Follow these steps given below to compile the sample found under *AccessManager-base*/samples/authentication/spi/postprocess.

1 Set the following environment variables.

JAVA_HOME: Set this variable to your installation of JDK. The JDK should be version 1.3.1_06 or higher.

CLASSPATH: Set this variable to refer to am_services.jar which can be found in the *AccessManager-base/*lib directory. Include jaas.jar in your classpath if you are using JDK version lower than JDK1.4

BASE_DIR: Set this variable to the directory where Access Manager is installed.

BASE_CLASS_DIR: Set this variable to the directory where all the Sample compiled classes are located.

JAR_DIR: Set this variable to the directory where the JAR files of the Sample compiled classes will be created.

These variables will be used to run the gmake command. You can also set these variables in the Makefile. This Makefile is in the following directory:

AccessManager-base/samples/authentication/spi/postprocess.

2 In the directory *AccessManager-base* /samples/authentication/spi/postprocess, run the gmake command.

To Deploy the ISAuthPostProcess Sample Program

- **1 Copy** ISAuthPostProcess.jar **from** JAR DIR **to** *AccessManager-base*/lib.
- 2 Update the Web Container configuration file server.xml.

Add ISAuthPostProcessSample.jar to the classpath. The server.xml file for different web containers can be found at the following locations:

Web Server: <WS-home-dir>/https-<WS-instance-name>/config/

Application Server: <AS-home-dir > / domain / domain 1 / server 1 / config /

For all other web containers consult, the manufacturer's documentation.

3 Restart the web container.

Web Server: <WS-home-dir>/https-<WS-instance-name>/restart

Application Server: <aS-install-dir>/<domains>/<domain name>/<server instance>/bin/restartserv Example:

/<AS-home-dir>/domains/domain1/server1/bin/restartserv

For all other web containers consult their documentation.

Configuring the Authentication Post Processing SPI

The Authentication PostProcessing Sample can be configured at the Organization, Service or Role level.

To Configure ISAuthPostProcess Sample for an Organization

1 Log in to Access Manager console as amAdmin. Use the following URL:

http://host.domain:port/Console-Deploy-URI

- 2 Click Identity Management, and select your organization.
- 3 From the View menu, click Services.
- 4 In the navigation frame, under Authentication, click Core.
- 5 Add the following to the Authentication PostProcessing Class attribute:

com.iplanet.am.samples.authentication.spi.postprocess

6 Add the following to the Authentication PostProcessing Class attribute:

ISAuthPostProcessSample

- 7 Click Save.
- 8 Log out.

9 Go to the following URL

If you choose to use an organization other than the default, be sure to specify that in the URL using the org parameter.

The postprocessing SPI will be executed on successful authentication, on failed authentication, and on Logout.

▼ To Configure the ISAuthPostProcess Sample for a Service

1 Log in to Access Manager console as amAdmin. Use the following URL:

http://<host>.<domain>:<port>/<Console-Deploy-URI>

- 2 Click Identity Management, and select your organization.
- 3 From the View menu, select Services.
- 4 Select Authentication Configuration
- 5 From the Service Instance frame, select New Instance.
- 6 Enter a name for the service.
- 7 Add the following to the Authentication PostProcessing Class attribute: com.iplanet.am.samples.authentication.spi.postprocess. ISAuthPostProcessSampl
- 8 Click Submit to save the changes.
- 9 Click Service Name and define the Authentication Configuration for the new service.
- 10 Log out.
- **11 Go to the following URL:** http://host.domain:port/Service-Deploy-URI/UI/Login? service=servicename

If you choose to use an organization other than the default, be sure to specify that in the URL using the org parameter.

The postprocessing SPI will get executed on successful authentication, failed authentication and on Logout for the service accessed.

To Configure ISAuthPostProcess Sample for a Role

1 Log in to Access Manager console as amAdmin. Use the following URL:

http://host.domain:port/Console-Deploy-URI

- 2 Click the Identity Management tab, and select your organization.
- 3 From the View menu, select Roles to view the role properties.
- 4 From the View menu, select Services.
- 5 Click Edit to edit the authentication configuration.
- 6 Add the following to the Authentication post Processing Class attribute:

com.iplanet.am.samples.authentication.spi.postprocess. ISAuthPostProcessSample

- 7 Click Submit to save the changes.
- B Log out.
- 9 Go to the following URL:

http://host.domain:port/Service-Deploy-URI/UI/Login?role=roleName

If you choose to use an organization other than the default, be sure to specify that in the URL using the org parameter. Example: org=orgName

The postprocessing SPI will be executed for the service accessed on successful authentication, on failed authentication, and on Logout.

Compiling On Windows 2000

Go to the *base-directory*\samples\authentication\spi\postprocess directory and run the make command.

▼ To Deploy the ISAuthPostProcessSample Program

- 1 Copy ISAuthPostProcess.jarfrom JAR DIRto base-directory\lib
- 2 In the Web Container from which this sample has to run, update the classpath with ISAuthPostProcess.jar.
- 3 Restart Access Manager.

base-directory\bin\amserver start

To Configure Authentication Post Processing SPI

This sample can be can be set in the Core Authentication Service for Organization and Authentication Configuration Service for Role OR Service.

See the section "Configuring the Authentication Post Processing SPI" on page 58.

Generating an Authentication User ID

This file explains how to compile, deploy and configure the Authentication User ID Generation SPI Sample.

- "To Compile the UserIDGeneratorSample on Solaris Sparc/x86, Linux" on page 61
- "To Deploy the UserIDGeneratorSample Program" on page 62
- "Configuring the UserIDGeneratorSample Program" on page 62
- "Compiling the UserIDGeneratorSample Program on Windows 2000" on page 63

In the following sections, the PRODUCT_DIR setting depends on which platform you're using:

Solaris Sparc/x86: PRODUCT DIR = <install root>/SUNWam

Linux: PRODUCT_DIR = <install_root>/sun/identity

▼ To Compile the UserIDGeneratorSample on Solaris Sparc/x86, Linux

The sample is located in the following directory:

AccessManager-base/samples/authentication/spi/genuid

1 Set the following environment variables.

These variables will be used to run the gmake command. You can also set these variables in the Makefile which is located in the following directory:

AccessManager-base/samples/authentication/spi/genuid

JAVA_HOME: Set this variable to your installation of JDK. The JDK should be version 1.3.1_06 or higher.

CLASSPATH: Set this variable to refer to am_services.jar which can be found in the <PRODUCT_DIR>/lib directory. Include jaas.jar in your classpath if you are using JDK version less than JDK1.4.

BASE_DIR: Set this variable to the directory where the Access Manager is installed.

BASE_CLASS_DIR: Set this variable to the directory where all the Sample compiled classes are located.

JAR_DIR: Set this variable to the directory where the JAR files of the Sample compiled classes will be created.

In the directory AccessManager-base /samples/authentication/spi/genuid, run the gmake command:

▼ To Deploy the UserIDGeneratorSample Program

- 1 **Copy** UserIDGeneratorSample.jar**from** JAR DIR**to** AccessManager-base/lib.
- 2 in the Web Container from which this sample has to run, update the classpath with UserIDGeneratorSample.jar.
 - On Sun ONE Web Server, go to server instance configuration directory:
 <WS-home-dir>/https-<WS-instance-name>/config/
 - On Sun ONE Application Server, in the directory
 AS-home-dir>/domain/domain1/server1/config/ update server.xml with the new classpath.
 - For all other containers, consult the documentation that came with the product.
- 3 Restart web container.<WS-home-dir>/https-<WS-instance-name>/start
 <AS-home-dir>/domains/domain1/server1/bin/start

Configuring the UserIDGeneratorSample Program

The Authentication User ID Generation Sample can be configured at the Organization level, and then used or invoked by the out-of-box Membership/Self- registration authentication module.

▼ To Configure UserIDGeneratorSample for an Organization

- 1 Log in to Access Manager console as amAdmin. Use the following URL: http://host.domain:port/Console-Deploy-URI
- 2 Click the Identity Management tab, and select your organization.
- 3 From the View menu, select Services.
- 4 In the navigation frame, under Authentication, click Core.
- **5** Add the following to the Pluggable User Name Generator Class attribute: com.iplanet.am.samples.authentication.spi.genuid. UserIDGeneratorSample
- 6 Click Save to save the changes.
- 7 Log out.

▼ To Access an Authentication Module for an Organization

This module is the one which invokes the UserIDGenerator SPI implementation class. By default, only the Membership/Self-registration authentication module calls this SPI implementation.

1 Make sure that you have registered and enabled the Membership authentication module, and that you have created a template for the organization.

2 Enter the following URL:

http://host.domain:port/Service-Deploy-URI/UI/Login?module=Membership

If you choose to use an organization other than the default, be sure to specify that in the URL using the org parameter. Example: org=orgName

3 Click New User.

You should be able to register any existing username or user ID.

The UserIDGeneratorSample will be executed. You will be presented with the generated User IDs choice menu to choose any one username or user ID.

Compiling the UserIDGeneratorSample Program on Windows 2000

In the <install-root>\samples\authentication\spi\genuid directory, run the make command.

To deploy the UserIDGeneratorSample Program

- 1 **Copy** UserIDGeneratorSample.jar**from** JAR DIR**to** < install-root>\\lib
- 2 In the Web Container from which this sample has to run, update the classpath with UserIDGeneratorSample.jar.
- 3 Restart Access Manager.

<install-root>\bin\amserver start

To Configure the UserIDGeneratorSample Program

Configuring the program on Windows 2000 is similar to configuring the program on Solaris. See "Configuring the Authentication Post Processing SPI" on page 58.

Implementing A Pure JAAS Module

A sample program demonstrates how to write pure a JAAS module to replay callbacks by authenticating using Access Manager Authentication Client API. It will authenticate a user by replaying the callbacks required by Access Manager the Authentication Module. You can modify this program to use other existing or customized Access Manager Authentication modules. This sample module can be plugged in into any standard JAAS framework using the JAAS API.

Note – For detailed information on JAAS, see the Sun Developer Documentation at the following URL:http://java.sun.com/products/jaas/. For detailed information on how to write a JAAS module, see the *JAAS LoginModule Developer's Guide* at the following URL:

http://java.sun.com/j2se/1.4.2/docs/guide/security/ jaas/JAASLMDevGuide.html

Conventions Used in the Samples

TABLE 2-5 Default directories for Solaris Sparc/x86

Variable	Description	Location
Config_directory	Directory that contains configuration files	/CONFIG_DIR = /etc/opt/SUNWam/config
Product_Directory	Directory where Access Manager is installed.	PRODUCT_DIR = <install_root>/SUNWam</install_root>

TABLE 2-6 Default directories for Linux

Variable	Description	Location
Config_Directory	Directory that contains configuration files	<pre>CONFIG_DIR = /etc/opt/sun/identity/config</pre>
Product_Directory	Directory where Access Manager is installed.	PRODUCT_DIR = <install_root>/sun/identity</install_root>

TABLE 2-7 Default directories for Windows 2000

Variable	Description	Location
Config_Directory	Directory that contains configuration files	<pre>CONFIG_DIR = <install_root>\lib</install_root></pre>

	TABLE 2-7 Default directories f	or Windows 2000	(Continued)
Variable	Description	Location	
Product_Directory	Directory where Access Manager is installed.		

▼ To Run the Sample on Solaris Sparc x86 or Linux:

1 In the Makefile, set the following variables:

BASE: Enter the path to the directory where Access manager is installed.

JAVA_HOME: Enter the path to the directory where Java compiler is installed

CONFIG: Enter the entry specified in the login configuration file. This entry will be used to do the user authentication

- 2 Copy AMConfig.properties from Access Manager server installation machine location <CONFIG_DIR> to the client machine where the sample will be run.
- 3 On the client machine, be sure the following are in your classpath:
 - am services.jar
 - jaas.jar
 - jss3.jar
 - AMConfig.properties

Include jaas. jar in your classpath if you are using a JDK version less than JDK1.4

4 A sample configuration file pure jaassample.config is provided for testing this sample.

The file contains only one entry named Sample. Sample is the name to be entered for CONFIG in the Makefile:

The entry specifies that the LoginModule to be used to do the user authentication is the PureJAASSampleLoginModule and that this SampleLoginModule must succeed in order for authentication to be considered successful. It passes options with ORG_NAME as the organization name and INDEX_NAME as the Access Manager authentication module to which this sample must authenticate.

If you must use a different login configuration, modify the Makefile. For example, change the following:

-Djava.security.auth.login.config=purejaassample.config

to this:

- -Djava.security.auth.login.config=your_jaas_config_file .config
- 5 To compile, run the gmake command.
- 6 To run the sample program run the gmake run command.

▼ To Enable SSL

- 1 In the sample client program, add this JVM property:
 - -D "java.protocol.handler.pkgs=com.iplanet.services.comm"
- 2 In the AMConfig. properties file, edit the following properties:

com.iplanet.am.admin.cli.certdb.dir:<PRODUCT DIR>/servers/alias

com.iplanet.am.admin.cli.certdb.prefix: https-machine1.com-machine1-

com.iplanet.am.server.protocol: https

com.iplanet.am.server.port: Enter the appropriate port on the server machine where machinel is the host name of the server

To Run the Sample on Windows 2000

- 1 In make.bat, set the following properties:
 - **BASE:** Enter the path to the directory where Access manager is installed

JAVA_HOME: Enter the path to the directory where the Java compiler is installed.

CONFIG: Enter the entry which will be used for user authentication. This entry is specified in the login configuration file.

- 2 Copy AMConfig.properties from Access Manager server installation machine location <CONFIG DIR> to the client machine where this sample will be run.
- 3 On the client machine, make sure the following are in your classpath:
 - am services.jar
 - jaas.jar
 - jss3.jar
 - AMConfig.properties
 Include jaas.jar in your classpath if you are using JDK version less than JDK1.4.

4 A sample configuration file pure jaassample.config is provided for testing this sample.

The file contains only one entry named. Sample. Sample is the name to be entered for CONFIG in the Makefile.

The entry specifies that the LoginModule to be used to do the user authentication is the PureJAASSampleLoginModule. SampleLoginModule is must succeed in order for authentication to be considered successful. It passes options with ORG_NAME as the organization name and INDEX_NAME as the Access Manager authentication module to which this sample has to authenticate.

If you must use a different login configuration, modify the Makefile. For example, change the following:

```
-Djava.security.auth.login.config=purejaassample.config to this:
```

- -Djava.security.auth.login.config=your_jaas_config_file.config
- 5 To compile, run the make command.
- 6 To run the sample program, run the make run command.

▼ To Enable SSL

1 In the sample client program, add this JVM property:

```
-D "java.protocol.handler.pkgs=com.iplanet.services.comm"
```

2 Edit the following properties in the AMConfig. properties file:

```
com.iplanet.am.admin.cli.certdb.dir:
```

```
<install-dir>\SUN\IdentityServer6\Servers\alias
```

com.iplanet.am.admin.cli.certdb.prefix: https-machine1.red.iplanet.com-machine1-

com.iplanet.am.server.protocol: https

com.iplanet.am.server.port: Enter the appropriate port on the server machine where machinel is the host name of the server

For the detailed information, see the Javadoc for Remote Client APIs. By default, Access Manager Javadoc is installed in the following directory:

AccessManager-base/SUNWam/docs

For the detailed information on how to plug the Login Module into the standard JAAS Context, see the *JAAS Reference Guide* at the following URL:

http://java.sun.com/j2se/1.5.0/docs/guide/security/jaas/JAASRefGuide.html



Using the Policy APIs

The Sun Java™ System Access Manager 7.1 Policy Service enables you to define, manage, and enforce policies that control access to protected resources. Administrators use the Policy Service to configure and manage conditions for applications, resources, and identities managed within the Access Manager deployment. For detailed information about what the Policy Service does and how it works, see *Chapter 4*, "Authorization and the Policy Service," in Sun Java System Access Manager 7.1 Technical Overview.

This chapter provides information about the Policy APIs and how to use them to enable your service to use Access Manager policies. The chapter includes the following topics:

- "About the Policy APIs" on page 69
- "Using the Policy Code Samples" on page 75
- "Compiling the Policy Code Samples" on page 78
- "Adding a Policy-Enabled Service to Access Manager" on page 78
- "Developing Custom Subjects, Conditions, Referrals, and Response Providers" on page 82
- "Creating Policies for a New Service" on page 88
- "Developing and Running a Policy Evaluation Program" on page 89
- "Programmatically Constructing Policies" on page 90

About the Policy APIs

The Policy Java APIs enable you to do the following:

- Develop and add custom subjects, referrals, and conditions to Access Manager.
- Develop and run policy evaluation programs
- Programmatically construct policies and add them to the policy store.

This chapter describes Java Policy Service packages and classes, and provides instructions for using the Policy APIs and code samples. For a comprehensive listing of Policy Java methods and their usage, see the Sun Java System Access Manager 7.1 2006Q4 Java API Reference.

Access Manager also provides C APIs to enable external applications to connect to the Policy Service framework. For information about using the Policy C APIs, see *Chapter 3*, "Policy Data Types and Functions," in Sun Java System Access Manager 7.1 C API Reference Chapter 3, "Policy Data Types and Functions," in Sun Java System Access Manager 7.1 C API Reference.

Policy Java Packages

The following Java packages comprise the Policy APIs:

com.sun.identity.policy Contains policy evaluation classes for policy

administration and evaluation. Policy evaluation classes from this package require a direct connection to the policy data store. These classes should be used with caution, and only when classes from com.sun.identity.policy.client

cannot handle your use case.

com.sun.identity.policy.client Contains classes used by remote Java applications

to evaluate policies and to get policy decisions.

com.sun.identity.policy.interfaces Contains interfaces for writing custom Policy

plug-ins for conditions, subjects, referrals and

resources.

Policy Management Classes

Policy Management classes are used by system administrators to manage policies in Access Manager. The interfaces for this functionality are contained in the com.sun.identity.policy package and including the following:

- "PolicyManager" on page 70
- "Policy" on page 71

PolicyManager

com.sun.identity.policy.PolicyManager is the top-level administrator class for policy management.com.sun.identity.policy.PolicyManager provides methods that enable an administrator to create, modify, or delete realm policies. The PolicyManager can be obtained by passing a privileged user's session token or by passing a privileged user's session token with a realm name. Some of the more widely used methods of this class include the following:

getPolicyNames Retrieves all named policies created for the realm for which the policy

manager was instantiated. This method can also take a pattern (filter) as

an argument.

getPolicy Retrieves a policy when given the policy name.

addPolicy Adds a policy to the specified realm. If a policy with the same name

already exists, it will be overwritten.

removePolicy Removes a policy from the specified realm.

replacePolicy Replaces policy with a new policy.

Policy

com.sun.identity.policy.Policy represents a policy definition with all its intended parts (rules, subjects, referrals, conditions, and response providers). The policy object is saved in the data store if the addPolicy or replacePolicy methods from the PolicyManager class are invoked. This class contains methods for adding, removing, replacing or getting any of the parts of a policy definition.

Policy Evaluation Classes

Policy evaluation classes compute policy decisions which allow or deny access to a protected resource. Policy evaluation classes are contained com.sun.identity.policy package and include the following:

- PolicyEvaluator
- ProxyPolicyEvaluator
- ClientPolicyEvaluator
- PolicyEvent

PolicyEvaluator Class

com.sun.identity.policy.PolicyEvaluator can be integrated into Java applications to evaluate policy privileges and provide policy decisions. This class provides support for both boolean and non-boolean type policies. Create a PolicyEvaluator by calling the constructor with a service name. Public methods of this class include the following:

is Allowed Evaluates the policy associated with the given resource and returns a

boolean value indicating whether the policy evaluation resulted in an

allow or deny.

getPolicyDecision Evaluates policies and returns decisions. Returns a decision that gives

a user permission to perform specified actions on a specified resource.

getResourceResult Obtains the policy and decisions for a hierarchy of resources. Possible

values for the scope of this method are self, subtree, and

strict-subtree. Use the self value to get the policy decision for the specified resource only. Use the subtree value to include the policy

decisions for all resources defined in the policies which are sub-resources of the specified resource.

For example, the PolicyEvaluator class can be used to display the links for a list of resources to which an authenticated user has access. The getResourceResult method is used to get the list of resources. The resourceName parameter would be http://host.domain:port which returns all the resources to which the user has access on that server. These resources are returned as a PolicyDecision based on the user's defined policies. If the user is allowed to access resources on different servers, this method needs to be called for each server.

Note – Not all resources that have policy decisions are accessible to the user. Access depends on ActionDecision(s) contained in policy decisions.

ProxyPolicyEvaluator Class

com.sun.identity.policy.ProxyPolicyEvaluator allows a privileged user (top-level administrator, organization administrator, policy administrator, or organization policy administrator) to get policy privileges and evaluate policy decisions for any user in their respective scope of administration.

com.sun.identity.policy.ProxyPolicyEvaluatorFactory is the singleton class used to get ProxyPolicyEvaluator instances.

EXAMPLE 3-1 Public Methods For ProxyPolicyEvaluator

EXAMPLE 3–1 Public Methods For ProxyPolicyEvaluator (Continued)

```
/**
* Gets policy decision for the user identified by the
* principalName for the given resource
* @param principalName principal name for whom to compute the
* policy decision
* @param resourceName name of the resource for which to
* compute policy decision
* @param env run time environment parameters
* @return the policy decision for the principal for the given
* @throws PolicyException exception form policy framework
* @throws SSOException if sso token is invalid
*/
public PolicyDecision getPolicyDecision(String principalName,
   String resourceName, Map env)
   throws PolicyException, SSOException;
/**
* Gets protected resources for a user identified by the
* principalName. Conditions defined in the policies
* are ignored while computing protected resources.
* Only resources that are subresources of the given
* rootResource or equal to the given rootResource would
* be returned.
* If all policies applicable to a resource are
* only referral policies, no ProtectedResource would be
* returned for such a resource.
* @param principalName principal name for whom
* to compute the privilege.
* @param rootResource only resources that are subresources
* of the given rootResource or equal to the given
* rootResource would be returned. If
* <code>PolicyEvaluator.ALL RESOURCES</code>
* is passed as rootResource, resources under
* all root resources of the service
* type are considered while computing protected
* resources.
* @return set of protected resources. The set contains
* ProtectedResource objects.
```

EXAMPLE 3-1 Public Methods For ProxyPolicyEvaluator (Continued)

Client PolicyEvaluator Class

com.sun.identity.policy.client.PolicyEvaluator evaluates policies and provides policy decisions for remote applications. This does not require direct access to a policy stores such as Directory Server (for example, if there is a firewall).

com.sun.identity.policy.client.PolicyEvaluator get policy decision from Access Manager using XML over HTTP(s). It stores a cache of policy decisions for faster responses and maintains the cache in sync with the Policy Service on the instance of Access Manager using the notification and polling mechanism.

PolicyEvent Class

com.sun.identity.policy.PolicyEvent represents a policy event that could potentially change the current access status. For example, a policy event is created and passed to the registered policy listeners whenever there is a change in a policy rule. This class works with the PolicyListener class in the com.sun.identity.policy.interface package.

Policy Plug-In APIs

The Policy plug-in classes are contained in the com.sun.identity.policy.interfaces package. The following classes are used by service developers and policy administrators who need to provide additional policy features as well as support for legacy policies.

-	
ResourceName	Provides methods to determine the hierarchy of the resource names for a determined service type. For example, these methods can check to see if two resources names are the same or if one is a sub-resource of the other.
Subject	Defines methods that can determine if an authenticated user (possessing an SSOToken) is a member of the given subject.
Referral	Defines methods used to delegate the policy definition or evaluation of a selected resource (and its sub-resources) to another realm or policy

server.

Condition Provides methods used to constrain a policy to, for example, time-of-day

or IP address. This interface allows the pluggable implementation of the

conditions.

PolicyListener Defines an interface for registering policy events when a policy is added,

removed or changed. PolicyListener is used by the Policy Service to send notifications and by listeners to review policy change events.

Using the Policy Code Samples

Access Manager provides Policy code samples to perform the following tasks:

- Add a new service which has a policy schema to Access Manager
- Develop and add custom developed subjects, referrals, conditions and response providers to Access Manager
- Develop and run Policy evaluation programs
- Construct policies programmatically and add them to the policy store
- Create policies using amadmin command

All the files you need to run the policy code samples are located in the following directories:

Solaris Platform AccessManager-base\samples\policy

Use Cases Illustrated by Policy Code Samples

Each of the following sections describes a sequence of steps you must take when using various means to run a policy evaluation program or to create policies. Each step in a sequence is linked to detailed instructions further down in this chapter.

▼ To Run a Policy Evaluation Program for the URL Policy Agent Service

Use this sequence to runs a policy evaluation program for the iPlanetAMWebAgentService service.

Compile the Policy code samples.

See Compiling the Policy Code Samples.

2 Develop and run a Policy evaluation program.

See "Developing and Running a Policy Evaluation Program" on page 89.

To Run a Policy Evaluation Program for the URL Policy Agent Service and More

This sequence runs the evaluation program for iPlanetAMWebAgentService and the sample subject, condition, ResponseProvider, and referral implementations.

Compile the Policy code samples.

See "Compiling the Policy Code Samples" on page 78.

2 Develop custom subjects, conditions, and referrals.

See "Developing Custom Subjects, Conditions, Referrals, and Response Providers" on page 82.

3 Develop and run a Policy evaluation program.

See "Developing and Running a Policy Evaluation Program" on page 89.

▼ To Run a Policy Evaluation Program for the Sample Service

This sequence runs the evaluation program for the SampleWebService.

Compile the Policy code samples.

See "Compiling the Policy Code Samples" on page 78.

2 Add a Policy-enabled service to Access Manager.

See "Adding a Policy-Enabled Service to Access Manager" on page 78.

3 Create policies for the new service.

See "Creating Policies for a New Service" on page 88.

4 Develop and run a Policy evaluation program.

"Developing and Running a Policy Evaluation Program" on page 89.

▼ To Run a Policy Evaluation Program for the Sample Service and More

This sequence runs the evaluation program for SampleWebService and the sample subject, condition, Response Provider, and referral implementations.

1 Compile the Policy code samples.

See "Compiling the Policy Code Samples" on page 78.

2 Add a Policy-enabled service to Access Manager.

See "Adding a Policy-Enabled Service to Access Manager" on page 78.

3 Develop custom subjects, conditions, and referrals.

See "Developing Custom Subjects, Conditions, Referrals, and Response Providers" on page 82.

4 Create policies for the new service.

See "Creating Policies for a New Service" on page 88.

5 Develop and run a Policy evaluation program.

See "Developing and Running a Policy Evaluation Program" on page 89.

To Use amadmin to Create Policies for the URL Policy Agent Service

Use amadmin to create policies for the service. See "Creating Policies" in *Sun Java System Access Manager 7.1 Administration Guide* for detailed instructions.

▼ To Use amadmin to Create Policies for the Sample Service

This sequences creates policies for SampleWebService.

Compile the Policy code samples.

See "Compiling the Policy Code Samples" on page 78.

2 Develop and run a Policy evaluation program.

See "Developing and Running a Policy Evaluation Program" on page 89.

▼ To Programmatically Construct Policies

This sequence constructs policies and adds them to the policy store.

1 Compile the Policy code samples.

See "Compiling the Policy Code Samples" on page 78.

2 Programmatically construct policies.

See "Programmatically Constructing Policies" on page 90.

Compiling the Policy Code Samples

Samples can be run both on Solaris, Linux, HP-UX, and Windows platforms. In the sample files, root suffix DNs are specified as dc=example, dc=com. Substitute the root suffix with the actual root suffix of your Access Manager installation.

▼ To Compile the Policy Code Samples

Set the following variables in the Makefile (or make.bat in Windows):

BASE Set this to refer the directory where Access Manager is installed.

JAVA HOME Set this variable to your installation of JDK. The JDK version should be higher

than JDK 1.4

- 2 To compile the sample program, run the gmake all command (or make . bat in Windows).
- 3 In the sample files, replace the root suffix DNs with values appropriate for your environment.

Adding a Policy-Enabled Service to Access Manager

You can load into Access Manager a service that already contains policy schema. Access Manager provides a sample XML file for a new service that contains policy schema. You can modify *AccessManager-base*/SUNWam/samples/policy/SampleWebService.xml to fit your needs, and then add your service to Access Manager.

The Policy element contains AttributeSchema elements to define applicable actions and values for actions. While defining policies, you can define access rules for those actions.

Examples include canForwardEmailAddress and canChangeSalaryInformation. The actions specified by these attributes can be associated with a resource if the IsResourceNameAllowed element is specified in the attribute definition. For example, in the web agent XML service file, amWebAgent.xml, GET and POST are defined as policy attributes with an associated URL resource as IsResourceNameAllowed is specified.

EXAMPLE 3-2 SampleWebService.xml

```
<!DOCTYPE ServicesConfiguration</pre>
    PUBLIC "=//iPlanet//Service Management Services (SMS) 1.0 DTD//EN"
    "jar://com/sun/identity/sm/sms.dtd">
<ServicesConfiguration>
    <Service name="SampleWebService" version="5.0">
        <Schema
            serviceHierarchy="/DSAMEConfig/SampleWebService"
            i18nFileName="SampleWebService"
            i18nKey="SampleWebService">*
        <Global>
        <AttributeSchema name="serviceObjectClasses" type="list" syntax="string"</pre>
                                 i18nKey="SampleWebService"/>
            </Global>
        <Policy>
        <AttributeSchema name="GET"</pre>
                    type="single"
                    syntax="boolean"
                    uitype="radio"
                    i18nKey="get">
                    <IsResourceNameAllowed/>
                    <BooleanValues>
                         <BooleanTrueValue i18nKey="allow">allow/BooleanTrueValue>
                         <BooleanFalseValue i18nKey="deny">deny</BooleanFalseValue>
                    </BooleanValues>
        </AttributeSchema>
        <AttributeSchema name="POST"
            type="single"
                    syntax="boolean"
                    uitype="radio"
            i18nKey="post">
            <IsResourceNameAllowed/>
                    <BooleanValues>
                         <BooleanTrueValue i18nKey="allow">allow/BooleanTrueValue>
                         <BooleanFalseValue i18nKey="deny">deny</BooleanFalseValue>
                    </BooleanValues>
        </AttributeSchema>
```

EXAMPLE 3-2 Sample WebService.xml (Continued)

```
<AttributeSchema name="PUT"
            type="single"
                    syntax="boolean"
                    uitype="radio"
            i18nKev="put">
            <IsResourceNameAllowed/>
                    <BooleanValues>
                        <BooleanTrueValue i18nKey="allow">allow/BooleanTrueValue>
                        <BooleanFalseValue i18nKey="deny">deny/BooleanFalseValue>
                    </BooleanValues>
       </AttributeSchema>
       <AttributeSchema name="DELETE"
            type="single"
                    syntax="boolean"
                    uitvpe="radio"
            i18nKey="delete">
            <IsResourceNameAllowed/>
                    <BooleanValues>
                        <BooleanTrueValue i18nKey="allow">allow/BooleanTrueValue>
                        <BooleanFalseValue i18nKey="deny">deny</BooleanFalseValue>
                    </BooleanValues>
       </AttributeSchema>
       </Policy>
       </Schema>
   </Service>
</ServicesConfiguration>
```

▼ To Add a New Policy-Enabled Service to Access Manager

1 Run the amadmin command to load the policy-enabled service.

```
AccessManager-base/bin/amadmin
--runasdn "uid=amAdmin,ou=People,default_org,root_suffix"
--password password
--schema AccessManager-base/samples/policy/SampleWebService.xml
```

2 Copy the properties file to the locale directory of the Access Manager installation.

cp SampleWebService.properties AccessManager-base/locale

- **3** Create a service XML file that conforms to *AccessManager-base*/dtd/sms.dtd, and contains the <Policy> element. See example below.
- **4** Create and copy locale properties file to AccessManager-base/locale.
- 5 Use amadmin to load the service into Access Manager.

Once the new service is added, you can define rules for the new service in policy definitions.

Example 3–3 XML for Policy-Enabled Service

```
/etc/opt/SUNWam/config/xml/amWebAgent.xml (Solaris)
/etc/opt/sun/identity/config/xml/amWebAgent.xml(Linux and HP-UX)
AccessManager-base\AccessManager\identity\config\xml\amWebAgent.xml
(Windows)
<!DOCTYPE ServicesConfiguration
    PUBLIC "=//iPlanet//Service Management Services (SMS) 1.0 DTD//EN"
    "jar://com/sun/identity/sm/sms.dtd">
<ServicesConfiguration>
    <Service name="iPlanetAMWebAgentService" version="1.0">
    <Schema
            i18nFileName="amWebAgent"
            i18nKey="iplanet-am-web-agent-service-description">
    <Global>
        <AttributeSchema name="serviceObjectClasses"</pre>
                    type="list"
                    syntax="string"
    i18nKey="">
                    <DefaultValues>
            <Value>iplanet-am-web-agent-service</Value>
    </DefaultValues>
        </AttributeSchema>
            </Global>
            <Policy>
        <AttributeSchema name="GET"
                    type="single"
    syntax="boolean"
                    uitype="radio"
                    i18nKey="GET">
    <IsResourceNameAllowed/>
                    <BooleanValues>
            <BooleanTrueValue i18nKey="allow">allow/BooleanTrueValue>
```

```
<BooleanFalseValue i18nKey="deny">deny</BooleanFalseValue>
                    </BooleanValues>
        </AttributeSchema>
        <AttributeSchema name="POST"
                    type="single"
    svntax="boolean"
                    uitvpe="radio"
                    i18nKey="POST">
   <IsResourceNameAllowed/>
                    <BooleanValues>
                   <BooleanTrueValue i18nKey="allow">allow</BooleanTrueValue>
            <BooleanFalseValue i18nKey="deny">deny/BooleanFalseValue>
                    </BooleanValues>
        </AttributeSchema>
            </Policy>
   </Schema>
   </Service>
</ServicesConfiguration>
```

Developing Custom Subjects, Conditions, Referrals, and Response Providers

Access Manager provides subject, condition, referral, and response provider interfaces that enable you to develop your own custom subjects, conditions, referrals, and response providers. A sample implementation is provided for the following four interfaces.

SampleSubject.java Implements the Subject interface. This subject applies to

all the authenticated users who have valid SSOTokens.

SampleCondition.java Implements the Condition interface. This condition

makes the policy applicable to those users whose user name length is greater than or equal to the length specified

in the condition.

SampleReferral.java Implements the Referral interface.

SampleReferral.java gets the referral policy decision from a text file SampleReferral.properties located in

the /samples directory.

SampleResponseProvider.java Implements the ResponseProvider interface.

SampleResponseProvider. java takes as input the attribute for which values are retrieved from the Access Manager and sent back in the Policy Decision. If the attribute does not exist in the user profile, no value is sent back in the response. SampleResponseProvider. java

relies on the underlying Identity Repository service to retrieve the attribute values for the Subject(s) defined in the policy.

You must add the subject, condition, response provider, referral implementations to iPlanetAMPolicyService and iPlanetAMPolicyConfigService in order to make them available for policy definitions. These services are loaded into Access Manager during installation. To add the sample implementations to the Policy framework, modify the iPlanetAMPolicy service and iPlanetAMPolicyConfig service. The service XML files are located in the following directory:

AccessManager-base/SUNWam/samples/policy

The following is the text of the amPolicy mod.xml file for the iPlanetAMPolicy service.

```
EXAMPLE 3-4 Text of the Default amPolicy_mod.xml File
```

```
<?xml version="1.0" encoding="UTF-8"?>
<!--
    Copyright (c) 2005 Sun Microsystems, Inc. All rights reserved
    Use is subject to license terms.
- - >
<!DOCTYPE ServicesConfiguration</pre>
    PUBLIC "=//iPlanet//Service Management Services (SMS) 1.0 DTD//EN"
    "jar://com/sun/identity/sm/sms.dtd">
<ServicesConfiguration>
    <Service name="iPlanetAMPolicyService" version="1.0">
        <PluginSchema className="SampleSubject"
                      i18nFileName="amPolicy"
                      i18nKey="iplanet-subject-SampleSubject-name"
                      interfaceName="Subject"
                      name="SampleSubject" >
        </PluginSchema>
        <PluginSchema className="SampleCondition"
                      i18nFileName="amPolicy"
                      i18nKey="iplanet-samplecondition-condition-name"
                      interfaceName="Condition"
                      name="SampleCondition" >
        </PluginSchema>
        <PluginSchema className="SampleReferral"
                      i18nFileName="amPolicy"
```

```
EXAMPLE 3-4 Text of the Default amPolicy mod.xml File
                                                    (Continued)
                       i18nKey="iplanet-sample-referral"
                       interfaceName="Referral"
                       name="SampleReferral" >
        </PluginSchema>
        <PluginSchema className="SampleResponseProvider"
                       i18nFileName="amPolicy"
                       i18nKey="iplanet-sample-responseprovider"
                       interfaceName="ResponseProvider"
                       name="SampleResponseProvider" >
        </PluginSchema>
    </Service>
</ServicesConfiguration>
The following is the text of the amPolicyConfig mod.xml file for the iPlanetAMPolicyConfig
service.
EXAMPLE 3-5 Text of the Default amPolicyConfig mod.xml File
<?xml version="1.0" encoding="UTF-8"?>
<! - -
    Copyright (c) 2005 Sun Microsystems, Inc. All rights reserved
   Use is subject to license terms.
<!DOCTYPE Requests
    PUBLIC "-//iPlanet//Sun Java System Access Manager 2005Q4 Admin CLI DTD//EN"
 "jar://com/iplanet/am/admin/cli/amAdmin.dtd"
<Requests>
    <SchemaRequests serviceName="iPlanetAMPolicyConfigService"</pre>
        SchemaType="Organization"
        i18nKey="a163">
        <AddChoiceValues>
            <AttributeValuePair>
            <Attribute name="sun-am-policy-selected-responseproviders"/>
                <Value>SampleResponseProvider</Value>
            </AttributeValuePair>
        </AddChoiceValues>
    </SchemaRequests>
```

EXAMPLE 3-5 Text of the Default amPolicyConfig mod.xml File (Continued)

```
<SchemaReguests serviceName="iPlanetAMPolicyConfigService"</pre>
    SchemaType="Organization"
    i18nKey="">
    <AddDefaultValues>
        <AttributeValuePair>
        <Attribute name="sun-am-policy-selected-responseproviders"/>
            <Value>SampleResponseProvider</Value>
        </AttributeValuePair>
    </AddDefaultValues>
</SchemaRequests>
<SchemaReguests serviceName="iPlanetAMPolicyConfigService"</pre>
    SchemaType="Organization"
    i18nKey="a160">
    <AddChoiceValues>
        <AttributeValuePair>
        <Attribute name="iplanet-am-policy-selected-subjects"/>
            <Value>SampleSubject</Value>
        </AttributeValuePair>
    </AddChoiceValues>
</SchemaRequests>
<SchemaReguests serviceName="iPlanetAMPolicyConfigService"</pre>
    SchemaType="Organization"
    i18nKey="">
    <AddDefaultValues>
        <AttributeValuePair>
        <Attribute name="iplanet-am-policy-selected-subjects"/>
            <Value>SampleSubject</Value>
        </AttributeValuePair>
    </AddDefaultValues>
</SchemaRequests>
<SchemaReguests serviceName="iPlanetAMPolicyConfigService"</pre>
    SchemaType="Organization"
    i18nKey="a161">
    <AddChoiceValues>
        <AttributeValuePair>
        <Attribute name="iplanet-am-policy-selected-conditions"/>
            <Value>SampleCondition</Value>
        </AttributeValuePair>
    </AddChoiceValues>
</SchemaRequests>
<SchemaRequests serviceName="iPlanetAMPolicyConfigService"</pre>
```

EXAMPLE 3-5 Text of the Default amPolicyConfig mod.xml File (Continued)

```
SchemaType="Organization"
        i18nKev="">
        <AddDefaultValues>
            <AttributeValuePair>
            <Attribute name="iplanet-am-policy-selected-conditions"/>
                <Value>SampleCondition</Value>
            </AttributeValuePair>
        </AddDefaultValues>
   </SchemaRequests>
   <SchemaReguests serviceName="iPlanetAMPolicyConfigService"</pre>
        SchemaType="Organization"
        i18nKey="a162">
        <AddChoiceValues>
            <AttributeValuePair>
            <Attribute name="iplanet-am-policy-selected-referrals"/>
                <Value>SampleReferral</Value>
            </AttributeValuePair>
        </AddChoiceValues>
   </SchemaRequests>
   <SchemaRequests serviceName="iPlanetAMPolicyConfigService"</pre>
        SchemaType="Organization"
        i18nKey="">
        <AddDefaultValues>
            <AttributeValuePair>
            <Attribute name="iplanet-am-policy-selected-referrals"/>
                <Value>SampleReferral</Value>
            </AttributeValuePair>
        </AddDefaultValues>
   </SchemaRequests>
</Requests>
```

▼ To Add a Sample Implementation to the Policy Framework

1 Use dscfg to back up iPlanetAMPolicy and iPlanetAMPolicyConfig services.

```
# cd DirectoryServer-base/ds6/bin
# ./dscfg export
-s "ou=iPlanetAMPolicyService,ou=services,root_suffix" output_file
```

- # ./dscfg export
- -s "ou=iPlanetAMPolicyConfigService,ou=services,root_suffix" output_file
- 2 Set the environment variable LD LIBRARY PATH.

On Solaris, add /usr/lib/mps/secv1 to LD LIBRARY PATH.

On Linux, add /opt/sun/private/lib to LD LIBRARY PATH.

On HP-UX, add /opt/sun/private/lib to SHLIB PATH.

3 Run the following commands:

- # cd AccessManager-base/samples/policy
 - AccessManager-base/bin/amadmin
- --runasdn "uid=amAdmin,ou=People, default_org, root_suffix
- --password password
- --schema amPolicy mod.xml

AccessManager-base/bin/amadmin

- --runasdn "uid=amAdmin,ou=People, default_org, root_suffix
- -- password password
- --data amPolicyConfig mod.xml
- 4 Change the properties files of the iPlanetAMPolicy and iPlanetAMPolicyConfig services to add messages related to the new implementations.

```
# cd AccessManager-base/locale
```

```
cp amPolicy.properties amPolicy.properties.orig
```

cp amPolicy en.properties amPolicy en.properties.oriq

cp amPolicyConfig.properties amPolicyConfig.properties.orig

cp amPolicyConfig en.properties amPolicyConfig en.properties.orig

cat <BASE_DIR>/samples/policy/amPolicy.properties >>

<BASE_DIR>/locale/amPolicy.properties

cat <BASE_DIR>/samples/policy/amPolicy_en.properties >>

<BASE_DIR>/locale/amPolicy_en.properties

cat <BASE_DIR>/samples/policy/amPolicyConfig.properties >>

<BASE DIR>/locale/amPolicyConfig.properties

5 Deploy the sample plug-ins.

Copy SampleSubject.class, SampleCondition.class, SampleResponseProvider.class, SampleReferral.class from the /samples/policy directory to *AccessManager-base*/lib.

6 Restart the Access Manager server.

The sample subject, condition, response provider, and referral implementations are now available for policy definitions through the administration console or amadmin tool.

Creating Policies for a New Service

Access Manager policies are managed through the Administration console or through the amadmin command. However, policies cannot be modified using amadmin command. You must delete the policy, and then add the modified policy using amadmin. To add policies using amadmin, the Policy XML file must be developed following

AccessManager-base/dtd/policy.dtd. Once the Policy XML file is developed, you can load the Policy XML file.

Two sample Policy XML files exist in the Policy /samples directory. The sample Policy XML files define policies for the Sample Web Service service. Sample Policy.xml defines a normal policy for Sample Web Service with a Sample Subject, a Sample Response Provider, and a Sample Condition. Sample referral Policy.xml defines a referral policy for Sample Web Service with a Sample Referral.

▼ To Load a Policy XML File

Before You Begin

You must compile the Policy code samples and develop custom subjects, conditions, response providers, and referrals before you can load policies present in the Policy XML files. See "Compiling the Policy Code Samples" on page 78 and "Developing Custom Subjects, Conditions, Referrals, and Response Providers" on page 82 for detailed instructions.

1 Run the following command:

AccessManager-base/bin/amadmin

- --runasdn "uid=amAdmin,ou=People,<default_org>,root_suffix>"
- --password <password>
- --data <policy.xml>

2 Run the following command:

AccessManager-base/bin/amadmin

- --runasdn "uid=amAdmin,ou=People, default_org,root_suffix"
- -- password password
- --data AccessManager-base/samples/policy/SamplePolicy.xml
 AccessManager-base/bin/amadmin
- --runasdn "uid=amAdmin,ou=People, default_org, root_suffix"
- --password password
- --data AccessManager-base/samples/policy/ SampleReferralPolicy.xml

You can verify the newly added policies in Administration Console.

Developing and Running a Policy Evaluation Program

Access Manager provides a Policy Evaluation API. This API has one Java class, PolicyEvaluator. The package for this class is com.sun.identity.policy.PolicyEvaluator. Access Manager provides a sample policy evaluator program, PolicyEvaluation.java.You can use this program to run policy evaluations for different services. The policy evaluation is always based on a service such as iPlanetAMWebAgentService or SampleWebService. The sample policy evaluation program uses the PolicyEvaluation.properties file. Specify the input for the evaluation program in this file. Examples are service name, action names, condition environment parameters, user name, and user password.

To Set Policy Evaluation Properties

Set the value of pe.servicename to the service name.
Examples: iPlanetAMWebAgentService or SampleWebService.

- 2 Set the pe. resoucename to the name of the resource that you want to evaluate the policy against.
- 3 Specify the action names in the pe.actionnames.

Separate the action names with a colon (:) If you want to get all the action values, leave the pe.actionnamesblank.

- 4 Set other required properties such as pe. username and pe. password.
- 5 (Optional) Set the following properties pe.authlevel, pe.authscheme, pe.requestip, pe.dnsname, pe.time if you use the corresponding conditions in your policy definitions.

If you don't want to set these environment parameters, just leave their values as blank.

pe.authlevel Used to evaluate AuthLevel Condition. pe.authlevel takes a positive

integer.

pe.authscheme Used to evaluate AuthScheme Condition. pe.authschemetakes a set of

colon—separated AuthScheme names.

pe.requestip Used to evaluate the IP Condition. pe.requestip takes an IP address

string.

pe.dnsname Used to evaluate the IP Condition. pe.dnsname takes a set of colon—

separated DNS names.

property pe.time Used to evaluate the Simple Time Condition. property pe.time

specifies the request time in milliseconds. If its value is set to the current

time, then it takes the current time in milliseconds.

▼ To Run a Policy Evaluation Program

Before You Begin You must set up policies before running a policy evaluation program.

1 Set the environment variable LD_LIBRARY_PATH.

On Solaris, add/usr/lib/mps/secv1 to LD LIBRARY PATH.

On Linux, add /opt/sun/private/lib to LD LIBRARY PATH.

On HP-UX, add /opt/sun/private/lib to the environment variable SHLIB PATH.

2 Run the gmake run command (On Windows, make.bat run).

Programmatically Constructing Policies

Access Manager provides Policy Management APIs that enable you to programmatically create, add, update and remove policies. The sample program PolicyCreator. java demonstrates how to programmatically construct policies and add them to policy store. The program creates one normal policy named policy1 and one referral policy named refpolicy1 and adds both policies to the policy store. The normal policy has one subject of each subject type, one condition of each condition type, and one response provider of each response provider type that comes with Access Manager at installation.

```
/**
    * $Id: PolicyCreator.java,v 1.5 2005/06/24 16:53:50 vs125812 Exp $
    * Copyright © 2005 Sun Microsystems, Inc. All rights reserved.
    *
    import com.sun.identity.policy.PolicyManager;
    import com.sun.identity.policy.ReferralTypeManager;
    import com.sun.identity.policy.SubjectTypeManager;
    import com.sun.identity.policy.ConditionTypeManager;
    import com.sun.identity.policy.Policy;
    import com.sun.identity.policy.Rule;
    import com.sun.identity.policy.interfaces.Referral;
    import com.sun.identity.policy.interfaces.Subject;
    import com.sun.identity.policy.interfaces.Condition;
    import com.sun.identity.policy.PolicyException;

import com.iplanet.sso.SSOToken;
import com.iplanet.sso.SSOException;
```

EXAMPLE 3-6 Sample Program PolicyCreator.java (Continued) import java.util.Set; import java.util.HashSet; import java.util.Map; import java.util.HashMap; public class PolicyCreator { public static final String DNS NAME="DnsName"; public static final String DNS VALUE="*.red.iplanet.com"; public static final String START TIME="StartTime"; public static final String START TIME VALUE="08:00"; public static final String END TIME="EndTime"; public static final String END TIME VALUE="21:00"; public static final String AUTH LEVEL="AuthLevel"; public static final String AUTH LEVEL VALUE="0"; public static final String AUTH SCHEME="AuthScheme": public static final String AUTH SCHEME VALUE="LDAP"; private String orgDN; private SSOToken ssoToken; private PolicyManager pm; private PolicyCreator() throws PolicyException, SSOException { BaseUtils.loadProperties(); orgDN = BaseUtils.getProperty("pe.realmname"); System.out.println("realmDN = " + orgDN); ssoToken = BaseUtils.getToken(); pm = new PolicyManager(ssoToken, orgDN); } public static void main(String[] args) { try { PolicyCreator pc = new PolicyCreator(); pc.addReferralPolicy(); pc.addNormalPolicy(); System.exit(0); } catch(Exception e) { e.printStackTrace(); } } private void addNormalPolicy() throws PolicyException, SSOException { System.out.println("Creating normal policy in realm:" + orgDN);

PolicyManager pm = new PolicyManager(ssoToken, orgDN);

EXAMPLE 3–6 Sample Program PolicyCreator.java (Continued)

```
SubjectTypeManager stm = pm.getSubjectTypeManager();
ConditionTypeManager ctm = pm.getConditionTypeManager();
Policy policy = new Policy("policy1", "policy1 description");
Map actions = new HashMap(1):
Set values = new HashSet(1);
values.add("allow"):
actions.put("GET", values);
String resourceName = "http://myhost.com:80/hello.html";
Rule rule = new Rule("rule1", "iPlanetAMWebAgentService",
        resourceName, actions);
policy.addRule(rule);
Subject subject = stm.getSubject("Organization");
Set subjectValues = new HashSet(1);
subjectValues.add(orgDN):
subject.setValues(subjectValues);
policy.addSubject("organization", subject);
subject = stm.getSubject("LDAPUsers");
subjectValues = new HashSet(1);
String userDN = "uid=user1,ou=people" + "," + orgDN;
subjectValues.add(userDN);
subject.setValues(subjectValues);
policy.addSubject("ldapusers", subject);
subject = stm.getSubject("LDAPGroups");
subjectValues = new HashSet(1);
String groupDN = "cn=group1,ou=groups" + "," + orgDN;
subjectValues.add(groupDN);
subject.setValues(subjectValues);
policy.addSubject("ldapgroups", subject);
subject = stm.getSubject("LDAPRoles");
subjectValues = new HashSet(1);
String roleDN = "cn=role1" + "," + orgDN;
subjectValues.add(roleDN);
subject.setValues(subjectValues);
policy.addSubject("ldaproles", subject);
subject = stm.getSubject("IdentityServerRoles");
subjectValues = new HashSet(1);
roleDN = "cn=role1" + "," + orgDN;
subjectValues.add(roleDN);
subject.setValues(subjectValues);
```

```
EXAMPLE 3-6 Sample Program PolicyCreator.java
                                               (Continued)
        policy.addSubject("is-roles", subject);
        Condition condition = ctm.getCondition("IPCondition");
       Map conditionProperties = new HashMap(1);
        Set propertyValues = new HashSet(1):
        propertyValues.add(DNS VALUE);
        conditionProperties.put(DNS NAME, propertyValues);
        condition.setProperties(conditionProperties);
        policy.addCondition("ip condition", condition);
        condition = ctm.getCondition("SimpleTimeCondition");
        conditionProperties = new HashMap(1);
        propertyValues = new HashSet(1);
        propertyValues.add(START TIME VALUE);
        conditionProperties.put(START TIME, propertyValues);
        propertvValues = new HashSet(1):
        propertyValues.add(END TIME VALUE);
        conditionProperties.put(END TIME, propertyValues);
        condition.setProperties(conditionProperties);
        policy.addCondition("time condition", condition);
        condition = ctm.getCondition("AuthLevelCondition");
        conditionProperties = new HashMap(1);
        propertyValues = new HashSet(1);
        propertyValues.add(AUTH LEVEL VALUE);
        conditionProperties.put(AUTH LEVEL, propertyValues);
        condition.setProperties(conditionProperties):
        policy.addCondition("auth level condition", condition);
        condition = ctm.getCondition("AuthSchemeCondition");
        conditionProperties = new HashMap(1);
        propertyValues = new HashSet(1);
        propertyValues.add(AUTH SCHEME VALUE);
        conditionProperties.put(AUTH SCHEME, propertyValues);
        condition.setProperties(conditionProperties);
        policy.addCondition("auth scheme condition", condition);
       pm.addPolicy(policy);
        System.out.println("Created normal policy");
    }
    private void addReferralPolicy()
```

EXAMPLE 3-6 Sample Program PolicyCreator.java (Continued)

```
throws PolicyException, SSOException {
        System.out.println("Creating referral policy for realm1");
        ReferralTypeManager rtm = pm.getReferralTypeManager();
        String subOrgDN = "o=realm1" + ",ou=services," + orgDN;
        Policy policy = new Policy("refpolicy1", "ref to realm1",
                true);
        Map actions = new HashMap(1);
        Rule rule = new Rule("rule1", "iPlanetAMWebAgentService",
                "http://myhost.com:80/realm1", actions);
        policy.addRule(rule);
        Referral referral = rtm.getReferral("SubOrgReferral");
        Set referralValues = new HashSet(1);
        referralValues.add(subOrgDN);
        referral.setValues(referralValues);
        policy.addReferral("ref to realm1" , referral);
        pm.addPolicv(policv):
        System.out.println("Created referral policy for realm1");
    }
}
```

▼ To Run the Sample Program PolicyCreator.java

Compile the sample code.

See "Compiling the Policy Code Samples" on page 78 above.

2 Set the environment variable LD LIBRARY PATH.

```
On Solaris, add /usr/lib/mps/secv1 to LD_LIBRARY_PATH.

On Linux, add /opt/sun/private/lib to LD_LIBRARY_PATH.
```

On HP-UX, add /opt/sun/private/lib to the environment variable SHLIB PATH.

- 3 In the administration console, go to Access Control > root_realm> Services > Policy Configuration.
- 4 Under "Selected Dynamic Attributes," add the following as the two dynamic attributes to be retrieved as part of the Policy Decision:
 - uid
 - cn
- 5 Set the following properties in the PolicyEvaluation.properties file:

pe.realmname DN of the root realm.

pe.username UserId to authenticate as.

pe.password Password to use to authenticate.

6 Run the gmake createPolicies **command. (On Windows,** make.bat createPolicies.) gmake createPolicies.

Use the administration console to verify that the policies policy1 and refpolicy1 are added to Access Manager.

• • • CHAPTER 4

Using the JAAS Authorization Framework

Previous versions of Access Manager (Identity Server 6.0 and 6.1) provided custom policy APIs to define and evaluate access policies. This model provided centralized management of policies in its own policy store, the Sun ONE or Java Enterprise System (JES) Directory Server. In Sun JavaTM System Access Manager 6.2 and beyond, the authorization segment of the Java Authentication and Authorization Service (JAAS) framework is added to the original model. This model is based on JAAS 1.0 and Java 2 Platform, Standard Edition (J2SE) 1.3.1.

Access Manager now bridges the gap between J2SE and Access Manager APIs. In this framework, Access Manager maps its private APIs to JAAS interfaces. This makes it possible for you to use the JAAS interface to access the Access Manager policy framework.

The topics covered in this chapter are:

- "Overview of JAAS Authorization" on page 97
- "JAAS Authorization in Access Manager" on page 101
- "Enabling the JAAS Authorization Framework" on page 102

Overview of JAAS Authorization

JAAS is a set of APIs that enable services to authenticate and enforce access controls upon users. It implements a Java technology version of the standard Pluggable Authentication Module (PAM) framework, and supports user-based authorization. JAAS authorization extends the Java security architecture which uses a security policy to specify what access rights are granted to executing code. That architecture, introduced in the Java 2 platform, is code-based. The permissions are granted based on code characteristics such as where the code is coming from, whether it is digitally signed, and if so, the identity of the signer.

"Overview of JAAS Authorization" on page 97 illustrates a Java security policy. This grants the code in the am_services.jar file, located in the current directory, the specified permission. No signer is specified, so it doesn't matter whether the code is signed or not.

JAAS authorization adds user centric access control that applies control based on what code is running as well as on who is running it.

By default, JAAS comes with a reference implementation of Policy (com.sun.security.auth.PolicyFile) which is file-based. This implementation parses the Java.policy file \${java.home}/lib/security directory and uses that to direct the associations of permissions to code. You can change the pointer to some other PolicyFile implementation or use a combination of files. By default, two files are consulted to evaluate policy. One is com.sun.security.auth.PolicyFile, mentioned above, and the other is .java.policy as defined in user's home directory.

To make JAAS authorization take place, include a Principal field in the grant statement or statements in your policy file. A Principal field indicates which user executing the code is allowed the designated permissions. The Policy file grant statements can now optionally include one or more Principal fields. Including Principal field in the grant statement indicates that the user represented by the specified Principal, who is executing the specified code, has the designated permissions. See the Principal field example in "Overview of JAAS Authorization" on page 97.

EXAMPLE 4–2 A Policy File Grant Statement

```
grant codebase "file:./am_services.jar",

Principal javax.security.auth.XXXprincipal

"your_user_name@your_domain" {

permission java.util.PropertyPermission "java.home", "read";
permission java.util.PropertyPermission "user.home", "read";
permission java.io.FilePermission "foo.txt", "read";
};
```

How Policy Enforcement Works

The Java 2 runtime enforces access controls via the java.lang.SecurityManager, which is consulted any time untrusted code attempts to perform a sensitive operation (accesses to the local file system, for example). To determine whether the code has sufficient permissions, the SecurityManager implementation delegates responsibility to the java.security.AccessController, which first obtains an image of the current AccessControlContext, and then ensures that the retrieved AccessControlContext contains sufficient permissions for the operation to be permitted.

JAAS supplements this architecture by providing the method Subject.doAs to dynamically associate an authenticated subject with the current AccessControlContext. As subsequent access control checks are made, the AccessController can base its decisions upon both the executing code itself, and upon the principals associated with the subject. Access Manager provides support for JAAS authentication, which results in the population of the subject with Principals that represents the user.

To illustrate a usage scenario for the doAs method, consider a service that authenticates a remote subject, and then performs some work on behalf of that subject. For security reasons, the server should run in an AccessControlContext bound by the subject's permissions. Using JAAS, the server can ensure this by preparing the work to be performed as a java.security.PrivilegedAction. Then, by invoking the doAs method, the server provides both the authenticated subject and the prepared PrivilegedAction. The doAs implementation associates the subject with the current AccessControlContext and then executes the action. When security checks occur during execution, the Java 2 SecurityManager queries the JAAS policy, updates the current AccessControlContext with the permissions granted to the subject and the executing codesource, and then performs its regular permission checks. When the action is completed, the doAs method removes the subject from the current AccessControlContext, and returns the result back to the caller. "How Policy Enforcement Works" on page 99 illustrates this flow.

EXAMPLE 4-4 Sample Code for Subject.doAS

```
public static void main(String[] args) {
       try {
            // Create an SSOToken
            AuthContext ac = new AuthContext("dc=iplanet,dc=com");
            ac.login();
            Callback[] callbacks = null;
            if (ac.hasMoreRequirements()) {
                callbacks = ac.getRequirements();
                if (callbacks != null) {
                    try {
                        addLoginCallbackMessage(callbacks);
                        // this method sets appropriate responses in the callbacks.
                        ac.submitRequirements(callbacks);
                    } catch (Exception e) { }
                }
            }
            if (ac.getStatus() == AuthContext.Status.SUCCESS) {
                  Subject subject = ac.getSubject();
                        // get the authenticated subject
                  FilePermission perm = new FilePermission("/tmp/test", "read");
                      Subject.doAs(subject, new PrivilegedExceptionAction() {
                      /* above statement means execute run() method of the
                                 /* Class PrivilegedExceptionAction()
                          as the specified subject */
                      public Object run() throws IOException {
                          // if the above run() was not throwing Exception
                                    /* could have created an instance of PrivilegedAction
                          // instead of PrivilegedExceptionAction here
                          AccessController.checkPermission(perm);
                            File = new File("/tmp/test");
                            return null;
                      }
                 });
             }
   }
```

In this example, the AccessController is checking the application's current policy implementation. If any permission defined in the policy file implies the requested permission, the method will simply return; otherwise an AccessControlException will be thrown. The check is actually redundant in this example, because the constructor for the default File implementation performs the same check. The sample is meant to illustrate the flow.

How the JS2E Access Controller Works

AccessController works with the java.security.Policy implementation to securely process application requests. In JS2E, a typical checkPermission(Permission p) method call on the AccessController class might result in the following sequence:

- 1. The AccessController invokes the getPermisisons() method of the javax.security.auth policy passing in the subject and the code source.
- 2. The getPermissions() method returns a PermissionCollection class instance, which represents a collection of same types of permissions.
- 3. The elements() method of the returned PermissionCollection gets called, which returns an enumeration of the permissions held in this PermissionCollection.
- 4. For each of the permissions returned in the enumeration (in step 3), the perm.newPermissionCollection() method gets called to obtain the PermissionCollection used to store the permission.
- 5. PermissionCollection.add(perm) gets called by the J2SE internal code to store the permission in its PermissionCollection.
- 6. The AccessController calls the implies (Permission p) method of the PermissionCollection returned in step 2.
- 7. Once the implies() of PermissionCollection is called, it in turn triggers the calling of implies(Permission p) of the individual permission objects contained in the PermissionCollection. These methods return true if the current permission object in the collection implies the specified permission; the methods return false the current permission object in the collection does not imply the specified permission. This outcome is implementation dependent and can be changed.

JAAS Authorization in Access Manager

Access Manager provides a custom implementation of the JAAS javax.security.auth.Policy. The customized implementation leverages the J2SE access controller and security manager to provide policy evaluation for all Access Manager related permissions. The customized implementation also falls back on the J2SE default Policy implementation com.sun.security.auth.PolicyFile for access to system level resources. Access Manager policy does not control access to com.sun.security.auth.PolicyFile.

Access Manager uses both JAAS and J2SE's file-based policy for all the resources for which Access Manager does not provide access control. For Access Manager resources such as URLs and so forth, new policy and permissions are defined. This model leverages the best of JAAS and the best of J2SE in one solution. It uses the JAAS framework for its default access control where needed, and then enhances the framework to incorporate the Access Manager policy evaluation. In this way, you can use the Access Manager policy implementation to make policy evaluations pertaining to Access Manager policies, but revert back to the default method of controlling access to resources not under Access Manager control.

Custom APIs

Access Manager provides the following custom APIs:.

■ Package com.sun.identity.policy.jaas

This package includes classes for performing policy evaluation against Access Manager using JAAS (Java Authentication and Authorization) framework.

ISPermission

This class provides the support for JAAS Authorization service. It is a new JAAS Permission which extends the Permission class and is defined to evaluate permission against the Access Manager policy framework.

ISPolicy

This is an implementation of abstract class javax.security.auth.Policy for representing the system security policy for a Java application environment. It performs policy evaluation against the Access manager policy service instead of against the default file-based PolicyFile.

For a comprehensive listing of related APIs, see the Javadoc in the following directory: *AccessManager-base*/SUNWam/docs.

User Interface

The user interface for entering permissions and policy is the Access Manager administration console which works with the policy administration API. Once the policy is defined, the evaluation is done using the J2SE architecture and enhanced policy implementation.

ISPermission covers the case when additional policy services are defined and imported, provided they only have boolean action values. In fact boolean evaluation is all that can be done using JAAS since JAAS permissions have a boolean result.

Enabling the JAAS Authorization Framework

You enable the JAAS authorization framework by resetting policy. Use the Policy.setPolicy(Policy) API to reset policy during run time. In "Enabling the JAAS Authorization Framework" on page 102,

Policy.setPolicy(com.sun.identity.policy.jaas.ISPolicy) resets the policy. In this example, the client application wants to use JAAS authorization API to communicate with the Access Manager and to perform policy evaluation. Access Manager provides the support needed to use Access Manager policy so that policy can be defined through the new ISPermission.

EXAMPLE 4–5 Sample JAAS Authorization Code

```
public static void main(String[] args) {
       try {
           // Create an SSOToken
          AuthContext ac = new AuthContext("dc=iplanet,dc=com");
           ac.login();
           Callback[] callbacks = null:
           if (ac.hasMoreRequirements()) {
               callbacks = ac.getRequirements();
               if (callbacks != null) {
                   try {
                       addLoginCallbackMessage(callbacks);
                   // this method sets appropriate responses in the callbacks.
                       ac.submitRequirements(callbacks);
                   } catch (Exception e) { }
               }
           if (ac.getStatus() == AuthContext.Status.SUCCESS) {
                 Subject subject = ac.getSubject();
                           // get the authenticated subject
                   Policy.setPolicy(new ISPolicy()); // change the policy to our own Policy
                   ISPermission perm = new ("iPlanetAMWebAgentService",
                       "http://www.sun.com:80", "GET");
                 Subject.doAs(subject, new PrivilegedExceptionAction() {
                     /* above statement means execute run() method of the
                                /* Class PrivilegedExceptionAction()
                         as the specified subject */
                     public Object run() throws Exception {
                         AccessController.checkPermission(perm);
                           // the above will return quietly if the Permission
                                        // has been granted
                           // else will throw access denied
                           // Exception, so if the above highlighed ISPermission
                                        // had not been granted, this return null;
                });
           }
 }
```

EXAMPLE 4-5 Sample JAAS Authorization Code (Continued)



Using Session Service APIs

The Session Service component of the Sun Java TM System Access Manager 7.1 enables single sign-on (SSO) functionality. In a single sign-on session, a user authenticates or logs in to a protected resource once. Until the user logs out, the user can access a number of other protected resources without having to present credentials again. For detailed information about how the Session Service and SSO work, see Chapter 2, "User Session Management and Single Sign-On," in Sun Java System Access Manager 7.1 Technical Overview.

This chapter describes the Session Service Java APIs, and related sample code that comes with Access Manager. Topics included in this chapter are:

- "About the Single Sign-On Java APIs" on page 105
- "Using the SSO Code Samples" on page 106
- "Developing Non-Web Based Applications" on page 112

About the Single Sign-On Java APIs

Once a user has successfully authenticated to Access Manager, the user object uses browser cookies or URL query parameters to carry a Session ID from one application to the next. Each time the user requests access to a protected application, the new application must verify the user's identity. For example, a user successfully authenticates to the application at http://orgA.company.com/Store, and then later tries to access http://orgA.company.com/UpdateInfo, a service that is SSO-enabled. The UpdateInfo application does not ask for the user to present credentials. Instead, the application uses the Session APIs and the user session to determine if the user is already authenticated. If the Session methods determine that the user has already been authenticated and that the session is still valid, then the UpdateInfo application allows the user access to its data and operations. If the user is not already authenticated, or if the session is no longer valid, then the UpdateInfo application prompts the user to present credentials a second time. The SSO APIs can also be used to create or destroy a SSOToken, or to listen for SSOToken events.

Using the SSO Code Samples

Access Manager provides the following code samples that demonstrate how you can use the Single Sign-On APIs. These samples are in the form of either standalone Java application or Java servlets.

SDKCommandLineSSO.java Standalone Java program.

Creates a new SSO token given a valid SSO token

id.

Input: Token id.

Output: Basic SSO token information.

CommandLineSSO. java Standalone Java program.

Demonstrates the usage of retrieving the user profile given the correct user credentials.

Input: Organization name (in DN format).

Output: User profile attributes.

SSOTokenSample.java Standalone Java program.

Serves as a basis for using SSO API. It

demonstrates creating an SSO token and calling various methods from the token including getting/setting the session properties.

Input: Token id.

Output: Basic SSO token information and session

properties.

SDKSampleServlet.java Java Servlet.

Demonstrates the usage of retrieving the user profile given the valid cookie set in the browser.

Input: None, but require AM session cookie set in

the browser.

Output: SSO token information and user profile

attributes.

SSOTokenSampleServlet.java SampleTokenListener.java Java Servlet.

Given the valid cookie sent in the browser, these serve as the basis for using the SSO API.

Demonstrates use of the of Session Notification Service as well as getting and setting session properties.

Input: None. Requires Access Manager session cookie set in the browser.

Output: Basic SSO token information and session properties.

Running SSO Code Samples on Solaris

On the Solaris platform, you can run the sample programs in one of the following ways:

▼ To Run a Sample Program from the Access Manager Server

Set the environment variables.

The following environment variables are used to run the make command. You can also set these variables in the Makefile which is in the same directory as the sample files.

BASE Specify the directory where the Access Manager Server is installed.

CLASSPATH Specify the directory where all the . JAR files are installed. Example:

AccessManager-base/SUNWam/lib

JAVA HOME Specify the JDK version your are using. The version must be JDK 1.3.1 or

higher.

BASE CLASS DIR Specify the directory where you will keep the sample compiled classes.

JAR DIR Specify the directory where the . JAR of the sample classes will be created.

The default is the current directory.

- 2 In the directory Access Manager-base/SUNWam/samples/sso, run the gmake command.
- **From the directory** JAR_DIR, **copy the file** SSOSample.jar **to the directory** *AccessManager-base*/SUNWam/lib.
- 4 Update the web container classpath.
 - a. Create a web server admin password file.

echo "wadm_password=<WS_ADMINPASSWD>" > /tmp/ws70adminpasswd

b. Use wadm get-jvm-prop to retrieve the current classpath for the Web Server instance.

```
ORIGCLASSPATH='$WADM get-jvm-prop --user=$WS_ADMIN --password-file=/tmp/ws70adminpasswd--host=$WS_HOST --port=$WS_ADMINPORT --config=$WS_CONFIG_class-path-suffix'
```

c. Use wadm set-jvm-prop to add the SSOSample.jar to the Web Server instance's classpath.

```
$WADM set-jvm-prop --user=$WS_ADMIN --password-file=/tmp/ws70adminpasswd
--host=$WS_HOST --port=$WS_ADMINPORT --config=$WS_CONFIG class-path-suffix=
"$ORIGCLASSPATH: AccessManager-base/SUNWam/lib/SSOSample.jar"
```

5 Register the Sample servlet.

a. In the file

WebContainer-base/https-host.domain/web-app/SERVICES_DEPLOY_URI/WEB-INF/web.xml, insert the following lines immediately after the last </servlet> tag:

b. Insert the following lines immediately after the last </servlet-mapping> tag.

6 Restart the Access Manager server.

7 Log in to the Access Manager console.

To execute SSOTokenSampleServlet, you must be authorized to access that resource. If you do not have authorization, the request will be denied. See the instructions for setting policy in the Administration Guide.

8 Use a browser to access the following URL:

protocol://host:port/SERVICES-DEPLOY-URI/SSOTokenSampleServlet

The default value of SERVICES-DEPLOY-URI is amserver.

The host name must be a fully qualified name. Your sample program should display the output in the browser.

▼ To Run a Sample Program on a Remote Client

Before You Begin

Install the Access Manager Client APIs in a web container and perform the following steps. In the following example, Sun Java System Web Server is installed in a directory named iws, and the Access Manager client APIs are installed in a directory named opt. For information on installing the Client APIs, see Chapter 1.

- 1 In the directory Access Manager-base/SUNWam/samples/sso, run the gmake command.
- 2 Be sure that the following are included in the Web Server classpath in the server .xml file:
 - /opt/SUNWam/samples/sso/SSOSample.jar
 - /opt/SUNWam/lib/am sdk.jar
 - /usr/share/lib/mps/secv1/jss4.jar
 - /opt/SUNWam/lib/jaxp.jar
 - /opt/SUNWam/lib/dom.jar
 - /opt/SUNWam/lib/xercesImpl.jar
 - /opt/SUNWam/lib/jaas.jar (Add this only if you are using a JDK version lower than JDK1.4)
 - /opt/SUNWam/localeand/opt/SUNWam/lib directories
- 3 Include java.protocol.handler.pkgs=com.iplanet.services.comm as an argument to be passed into the Web Server virtual machine (VM).

```
$WADM create-jvm-options --user=$WS_ADMIN --password-file=/tmp/ws70adminpasswd
--host=$WS_HOST --port=$WS_ADMINPORT --config=$WS_CONFIG --
-Djava.protocol.handler.pkgs=com.iplanet.services.comm
```

4 Restart Sun Java System Web Server.

If the Access Manager server is running with the Secure Socket Layer (SSL) protocol enabled, you may need to add the following line to the AMConfig.properties file for testing purposes:

```
com.iplanet.am.jssproxy.trustAllServerCerts=true
```

This property tells the SSL client in the Client APIs to trust all certificates presented by the servers. Adding this property enables you test the SSL connection without having the root CA for your test certificate installed on the this client. Without this property configured, you must install the SSL server rootCA certificate in client trust database, and then make sure that the following properties in AMConfig.properties are set to the same values:

- com.iplanet.am.admin.cli.certdb.dir
- com.iplanet.am.admin.cli.certdb.prefix
- com.iplanet.am.admin.cli.certdb.passfile

To Run the Sample Code

1 In the /opt/SUNWam/samples/sso directory, run the gmake command.

This compiles the samples and creates the necessary JAR files.

- 2 Register the sample servlet.
 - a. In the file

WebServer-base/https-hostName.domainName.com/is-web-apps/services/WEB-INF/web.xml, insert the following lines immediately after the last </servlet>tag.

```
<servlet>
    <servlet-name>SSOTokenSampleServlet</servlet-name>
    <description>SSOTokenSampleServlet</description>
    <servlet-class>SSOTokenSampleServlet</servlet-class>
    </servlet>
```

b. Insert the following lines immediately after the last </servlet-mapping> tag.

```
<servlet-mapping>
    <servlet-name>SSOTokenSampleServlet</servlet-name>
    <url-pattern>/SSOTokenSampleServlet</url-pattern>
    </servlet-mapping>
```

- 3 Restart the web container where the Access Manager Client APIs are installed.
- 4 Log in to the Access Manager server.
- 5 To Invoke the servlet, use a browser to go to the following URL:

http://amsdk-server.sub.domain/servlet/SSOTokenSampleServlet

The SSOTokenSampleServlet servlet validates the session and prints out all relevant session information. You may have to reload the URL (Shift + Reload Button) to see updated information.

6 Log out of the Access Manager server.

Because no log out link exists in the sample servlet, you must use a browser to access the Access Manager server log out URL. Example:

https://hostName.domainName.com/amserver/UI/Logout

7 To verify that the client SSOtoken is no longer valid, invoke the servlet a second time.

Use a browser to go to the following URL:

http://amsdk-server.sub.domain/servlet/SSOTokenSampleServlet

This time, a session exception occurs. Reload the URL to see the updated information.

▼ To Run a Sample Program on the Remote Client Command Line

Before You Begin

You must install the Access Manager Client APIs before you can run a sample program on the remote client command line. For more information on using the Client APIs, see Chapter 1.

When you run a single sign-on (SSO) program from the command line, your application is not running in a web container, but your application must have access to the cookies from the web container HTTP requests. Your application must extract the Access Manager cookie from the request, and then pass the string value of the cookie into the createSSOToken method. Because notifications are only supported in a web container, and because your application is not running in a web container, notifications are not supported in this sample.

- 1 In the directory *AccessManager-base*/SUNWam/samples/sso, run the gmake command.
- 2 Modify the script *AccessManager-base*/SUNWam/samples/sso/run to specify the sample program that you want to test.

For example, to run SDKCommandLineSSO. java, in the last line in the script, replace CommandLineSSO with SDKCommandLineSSO. The result looks like this:

```
${JAVA_EXEC} -Xbootclasspath ...SDKCommandLineSSO $@
```

3 If you are using a JDK version lower than JDK1.4, add the following to the classpath:

```
/opt/SUNWam/lib/jaas.jar
```

4 If SSL is enabled, in the script Access Manager-base/SUNWam/samples/sso/run, add the following VM argument when executing your Java code:

```
java.protocol.handler.pkgs=com.iplanet.services.comm
```

▼ To Test the Command Line

To test the command line you can run the servlet test above, cut and paste the cookie value and pass it in as the token value.

1 Use a browser to access the following URL:

```
http://test-server.sun.com:80/amserver/SSOTokenSampleServlet
```

The following output is displayed:

```
SSOToken host name: 123.123.123.123 (Your server's ip address)
SSOToken Principal name: uid=amAdmin,ou=People,dc=example,dc=com
Authentication type used: LDAP
```

IPAddress of the host: 123.123.123.123 (Your server's ip address) The token id is AQIC5wM2LY4Sfcwbdp3gWuB38NA26klnTJlLPknN8t0fPVY=

Property: Company is - Sun Microsystems

Property: Country is - USA

SSO Token Validation test Succeeded

2 In the AccessManager-base/SUNWam/samples/sso directory, execute the run command:

run AQIC5wM2LY4Sfcwbdp3gWuB38NA26klnTJlLPknN8t0fPVY=

The following result is displayed:

SSO "AQIC5wM2LY4Sfcwbdp3gWuB38NA26klnTJlLPknN8t0fPVY="

SSOToken host name: 123.123.123.123 (Your server's ip address) SSOToken Principal name: uid=amAdmin,ou=People,dc=example,dc=com

Authentication type used: LDAP

IPAddress of the host: 123.123.123.123 (Your server's ip address)

Developing Non-Web Based Applications

Access Manager provides the SSO APIs primarily for web-based applications although the APIs can be extended to any non-web-based applications with limitations. When developing non-web-based applications, you can use the SSO APIs in one of two ways:

- The application must obtain the Access Manager cookie value and pass it into the SSO client methods to get to the session token. The method used for this process is application-specific.
- You can use command-line applications such as amadmin. In this case, session tokens can be created to access the Directory Server directly. There is no session created, making the Access Manager access valid only within that process or VM.



Writing Log Operations

Sun Java[™] System Access Manager 7.1 provides a Logging Service for recording information such as user activity, traffic patterns, and authorization violations. The Access Manager Logging APIs enable external applications to take advantage of the Logging Service.

For information about how the Logging Service works and what it logs, see Chapter 6, "Logging and the Java Enterprise System Monitoring Framework," in *Sun Java System Access Manager 7.1 Technical Overview*. This chapter describes how to use the Logging APIs to write log operations and customize logging plug-ins. Topics in this chapter include:

- "About the Logging Samples" on page 113
- "Writing LogRecords To A Log File or Table" on page 114
- "Reading LogRecords From A Log File or Table" on page 115
- "Compiling Logging Programs" on page 121
- "Implementing a Remote Logging Application in a Container" on page 122
- "Logging to a Second Access Manager Server" on page 124
- "Using the Logging Sample Files" on page 125
- "Using the Logging SPIs" on page 127

About the Logging Samples

Access Manager provides two comprehensive Logging example programs in the *AccessManager-base* /SUNWam/samples/logging directory. LogSample.java is a log-writing program, and LogReaderSample.java is a log-reading program. The logging directory also includes the Makefile for compiling and scripts to facilitate running the programs.

Writing LogRecords To A Log File or Table

LogSample. java takes several command-line arguments, authenticates with the Access Manager server, creates a LogRecord, then logs the log record to the specified log file or table. The Access Manager Logging Service determines whether the log records go to a flat file or to a relational database management system (RDBMS), according to the service configuration. The following example command line uses the LogSample script:

```
./RunSample -o dc=iplanet,dc=com -u amadmin -p mypassword -n mylog \
-m "my message to log in mylog" -l user1 -w user1password
```

In LogSample. java, the command-line arguments are read. The following arguments are used to acquire the SSOToken that is specified in invoking the LogRecord(loglevel, message, token) method:

- o organization name
- -u userID
- -p userID password

The Logging Service extracts other pieces of information from this userID SSOToken when processing the LogRecord request. Ideally, the userID specified is the user who is the subject of the record being logged. The -m (message) argument is also used in the LogRecord call.

```
userToken =getSessionToken(orgname, args[userSID], args[userPWD]);
logRecord = new LogRecord(java.util.logging.Level.INFO, args[message], userToken);
logRecord.addLogInfo("ModuleName", "MyModule");
```

MyModule is added as the ModuleName property is added to the LogRecord using the addLogInfo() call. The -n (log name) argument is used in the Logger.getLogger(logname) call. The -l (logged by userID) and -w (logged by userID's password) are used to get the SSOToken specified in the logger.log(logRecord, loggedByToken) call. Where the userID associated with the LogRecord SSOToken is usually the subject of the log record, the userID associated with the log() SSOToken is the user doing the logging. In the actual log file, the values for the log record fields come from the following parameters:

time added by the Logging Service, and is taken from the Access Manager system

clock when the LogRecord is instantiated.

Data The message as specified in the LogRecord() call. In LogSample.java, the

value after the -m option: my message to log in mylog.

ModuleName The value specified for the ModuleName property (or

LogConstants.MODULE NAME property in the addLogInfo() call. If no value is

specified, this field will read:Not Available.

MessageID The value specified for the MessageID property (or

LogConstants.MESSAGE_ID property in an addLogInfo() call. If no value is specified, this field will read: Not Available. LogSample.java does not add a

value for this property.

Domain The value for this field is extracted from the SSOToken specified in the

LogRecord() call. This corresponds to the subject, userID's domain, or

organization.

ContextID The value for this field is extracted from the SSOToken specified in the

LogRecord() call.

LogLevel The value specified in the LogRecord() call. In LogSample. java, the value is

java.util.logging.Level.INFO (INFO in the log file).

LoginID The value for this field is extracted from the SSOToken specified in the

LogRecord() call. For example, the value can be the DN for the userID

specified in the -u command-line option.

IPAddr The value for this field is extracted from the SSOToken specified in the

LogRecord() call.

LoggedBy The value for this field is extracted from the SSOToken specified in the

logger.log() call. For example, the value can be the DN for the userID

specified in the -1 command-line option.

HostName The value for this field is extracted from the SSOToken specified in the

LogRecord() call. The value is the host name that corresponds to the address

in the IPAddr field, if it can be resolved.

Reading LogRecords From A Log File or Table

The log writing sample program LogSample.java is fairly straightforward in the way the program writes a single record to a file or table as determined by the Logging Service's configuration. In contrast, the log reading sample program is more complex because you can specify that queries are applied to multiple files or tables.



Caution – Log files and tables in particular can become very large. If you specify multiple logs in a single query, create queries that are very specific, or limited in the number of records to return, or both specific and limited. If a large number of records are returned, the Access Manager resource limits (including those of the hosting system) may be exceeded.

LogReaderSample. java requires three command-line arguments which are used to authenticate with the Access Manager server. If you specify a log name, then the sample

becomes a single-log reading application. If you don't specify a log name, reading from multiple logs is allowed. Reading from multiple logs does not preclude reading from a single log. Reading from multiple logs is useful when the exact log names available are unknown. The log reading sample is also very interactive. The following command-line example uses the LogReaderSample script:

```
./RunLogReader -o dc=iplanet,dc=com -u amadmin -p mypassword
```

In LogReaderSample.java, the command-line arguments are read. The following arguments are used to obtain the SSOToken that is specified in invoking the various LogReader.read() methods:

- -o organization name
- u userID
- p userID password

The LDAP login utility ldapLogin() is provided in a separate file, LogSampleUtils.java.

Next, the Logging Service configuration is read to determine, for example, whether file or database logging is specified and which log fields are logged.

```
manager.readConfiguration();
String logStorageType = manager.getProperty(LogConstants.BACKEND);
```

Depending on whether Access Manager Logging Service is logging to a file or to a database, when the LogReader.getSize() method is invoked on a particular log name, LogReader.getSizeUnits() will return either LogConstants.NUM_BYTES or LogConstants.NUM RECORDS. For example:

```
i3 = LogReader.getSizeUnits();
```

The LogConstants.LOG_FIELDS property specifies which log fields have been specified for inclusion in the log record. For example:

```
String selFldsStr = manager.getProperty(LogConstants.LOG_FIELDS);
```

The time and Data fields are mandatory, thus they do not appear in the Logging Service list. They must be explicitly added to the Set of Fields to Retrieve.

```
StringTokenizer stoken = new StringTokenizer(selFldsStr, ", ");
    String [] sFields = new String[stoken.countTokens() + 3];
    Set allFields = new HashSet();
    allFields.add("time");
    allFields.add("data");
```

To get the Set of Log Names Available to read and their sizes:

LogReaderSample. java allows you to select reads on a single or multiple logs. If a log name was specified on the command line with the -n option, then you can select from among the following types of reads:

read all records
 specify logType
 specify logType and timeStamp
 specify logType and logQuery
 specify logType, timeStamp, and logQuery
 specify logQuery

If no log name was specified on the command line, and you select single log to read, you may select from only a list of pre—configured reports:

```
Single (s) or multiple (m) file/table read: [s]
What type of audit report to generate:

1. all records from file/table
2. authentication successes
3. authentication failures
4. login/logout activity
5. policy allows
6. policy denies
7. amAdmin CLI activity
8. amAdmin console activity
9. Federation access
10. Federation errors
11. Liberty access
12. Liberty errors
13. SAML access
```

```
14. SAML error enter type [1..14]:
```

If you want to read from a selected single log, but specify the logQuery settings, do not use the -n command-line option. Select multiple log read, and then select the single log from which to read:

```
Available files:
        file 0 = amAuthentication.access contains 1595 bytes.
        file 1 = amPolicy.access contains 2515 bytes.
        file 13 = amAuthentication.error contains 795 bytes.
        Single (s) or multiple (m) file/table read: [s] m
        Available files:
        0: amAuthentication.access
        1: amPolicv.access
        . . .
        12: amConsole.access-1
        13: amAuthentication.error
        Enter selections (space-separated): 0
        What type of read to use:
            1. read all records
            2. specify logQuery
                 enter type [1 or 2]:
```

The following table provides brief descriptions of the LogReader. read() methods.

TABLE 6-1 LogReader.read() Methods

Returns all of the records from the specified log, ignoring the maximum number of records specified in the Logging Service configuration.

Specifies the log name and its suffix (type) separately, where the suffix can be access or error. All records are retrieved from the specified log.

Used when reading secure log files. The timeStamp is the suffix that appears after the file logType (access or error). All records are retrieved from the specified log.

```
TABLE 6-1 LogReader.read() Methods
                                         (Continued)
 read(String logName.
                                                    Performs a query, as specified by the logQuery
     String logType,
                                                    parameter. The log name and type (access or error)
     LogQuery logQuery,
                                                    are also specified.
     Object userCrdential)
 read(String logName,
                                                    Corresponds to the method described above. Used in
     String logType,
                                                    the secure logging case.
     String timeStamp,
     LogQuery logQuery,
     Object userCrdential)
 read(String logName,
                                                    Performs a query on the specified log.
     LogQuery logQuery,
     Object userCrdential)
                                                    Performs a query on the specified Set of Logs.
 read(String logName,
     Set fileNames,
     LogQuery logQuery,
     Object userCrdential)
```

The LogQuery, along with the QueryElements that may be specified, are constructed in the getLogQuery() routine in LogReaderSample.java.

LogQuery(int max Record, int matchCriteria, java.lang.String sortingBy)

The following are brief descriptions of the LogQuery constructors.

LogQuery()

Creates a new LogQuery object with the following default values:

```
maxRecord =
    LogQuery.MOST_RECENT_MAX_RECORDS
    globalOperand =
    LogQuery.MATCH_ANY_CONDITION
    queries = null (QueryElement)
    columns = null (columns to return)
    sortBy = null (field to sort on)

LogQuery(int max_record)
    Creates a new LogQuery object with the following values:

maxRecord = max_record
    globalOperand = LogQuery.MATCH_ANY_CONDITION
    queries = null (QueryElement)
    columns = null (columns to return)
    sortBy = null (field to sort on)
```

Creates a new LogQuery object with the following values:

```
maxRecord = max_Record
globalOperand = matchCriteria
queries = null (QueryElement)
columns = null (columns to return)
sortBy = sortingBy (field to sort on)
```

The LogQuery object created with the constructors may be subsequently modified with the following set* methods:

- setColumns(java.util.ArrayList columns)
- setGlobalOperand(int no)
- setMaxRecord(int value)
- setSortingField(java.lang.String fieldName)

A LogQuery may specify a List of QueryElements, each containing a value for a field (column) and a relationship. The following sample code queries for all successful authentications in domain dc=iplanet,dc=com, and returns the time, Data, MessageID, ContextID, LoginID, and Domain fields, sorted on the LoginID field:

```
ArrayList al = new ArrayList();
al.add (LogConstants.TIME);
al.add (LogConstants.Data);
al.add (LogConstants.MESSAGE ID);
al.add (LogConstants.CONTEXT ID);
al.add (LogConstants.LOGIN ID);
al.add (LogConstants.DOMAIN);
LogQuery lq = new LogQuery(LogQuery.ALL RECORDS,
        LogQuery.MATCH ALL CONDITIONS,
        LogConstants.LOGIN ID);
QueryElement qe1 = new QueryElement(LogConstants.MESSAGE ID,
        "AUTHENTICATION-105",
        QueryElement.EQ);
lq.addQuery(qe1);
QueryElement qe2 = new QueryElement(LogConstants.DOMAIN,
        "dc=iplanet,dc=com",
        QueryElement.EQ);
lq.addQuery(qe2);
QueryElement supports the following relationships:
QueryElement.GT
                     Greater than
                     Less than
QueryElement.LT
QueryElement.EQ
                     Equal to
                     Not equal to
QueryElement.NE
```

QueryElement.GE Greater than or equal to

QueryElement.LE Less than or equal to

QueryElement.CN Contains
QueryElement.SW Starts with
QueryElement.EW Ends with

In the example, assuming that dc=iplanet, dc=com is the root domain, changing the qe2relationship field to QueryElement.EW (Ends with) or QueryElement.CN (Contains) changes the query to include all successful authentications in all domains. To read the example query from the amAuthentication.access log, assuming the SSOToken is in ssoToken:

```
String[][] result = new String[1][1];
result = read("amAuthentication.access", lq, ssoToken);
```

The first record (row 0) contains the field and column names. See the printResults() method in LogReaderSample. java for a sample display routine.

Compiling Logging Programs

Included with the sample log programs is a gmake Makefile which compiles both LogSample.java and LogReaderSample.java, as well as the utilities module LogSampleUtils.java. The item of most interest is the CLASSPATH setting.

Executing Logging Programs

The sample standalone log programs include ksh scripts. There are considerations for running on Solaris or Linux handled by the scripts, but a few less obvious settings concern whether there is local or remote logging, if database logging is configured, and if Access Manager is configured for SSL. The LOCAL_LOGGING shell variable is set to true by default. If the logging program is executing on a remote system, using the Access Manager client APIs, then the LOCAL_LOGGING shell variable this must be set to false. The LOCAL_LOGGING setting later determines the setting of the CONFIGOPTION variable. When the logging program is running on the same system as the Access Manager server, and logging to a database is configured, then the database JDBC driver must also be included in the CLASSPATH. If the Access Manager server is configured for SSL, and the logging program is executing on a remote system using the Access Manager client APIs, be sure that the following parameter is set in the script:

```
-D"java.protocol.handler.pkgs=com.iplanet.services.comm"
```

The certificate database conforming to the Access Manager server container must be provided, and the com.iplanet.am.admin.cli.certdb.dir property in the AMConfig.properties file must point to the Access Manager server container. For example, for non-production testing to an Access Manager server running in a Application Server 8.1 container, you can copy (assuming default installation of AS 8.1) /var/opt/SUNWappserver/domains/domain1/config to the remote system, and set com.iplanet.am.admin.cli.certdb.dir to that location. You must also set the following:

```
com.iplanet.am.admin.cli.certdb.prefix=
    com.iplanet.am.admin.cli.certdb.passfile=/etc/opt/SUNWam/config/.wtpass
```

The .wtpass file needs to be created. More detailed information about certificates, see the file AccessManager-base/SUNWam/samples/authentication/api/Readme setup.html.

Implementing a Remote Logging Application in a Container

If your remote logging application is running in a container such as Sun Java System Application Server or Web Server, at the command line, set the following properties:

The -Djava.util.logging.manager property occurs in the Java System Web Server server.xml file. JVM options are typically added to the server.xml file in Java System Web Server, or to the domain.xml file in Java System Application Server.

Setting Environment Variables

You must set the following shared library environment variables in the executable for an application that is using the Logging Service. You can determine how to set the variables depending upon three things:

- Whether the application can execute in the local Access Manager server, or executes only a in remote server
- Whether or not you want the Access Manager LogManager class to override the native LogManager class
- Whether or not SSL is enabled in your deployment

If Client Can Execute in the Local Access Manager Server

When the client application can execute in either the local Access Manager server JVM or in a remote server JVM, choose one of the following two configurations:

■ If it is acceptable for the native LogManager class to be overridden by the Access Manager LogManager class in the JDK1.4 environment, then set the following variables:

• If it is *not* acceptable for the native LogManager class to be overridden by the Access Manager LogManager class in the JDK1.4 environment, then set the following variables:

```
-DLOG_COMPATMODE=Off
-Dslis.java.util.logging.config.class=com.sun.identity.log.
slis.LogConfigReader
```

If Client Executes Only in a Remote Server

When the client application can execute only in a remote server JVM, choose one of the following two configurations:

- If it is acceptable for the native LogManager class to be overridden by the Access Manager LogManager class in the JDK1.4 environment, then follow these steps:
 - 1. Set the following variables:

```
-Djava.util.logging.manager=com.sun.identity.log.LogManager
```

2. In LogConfig.properties, or in the logging.properties file supplied by JDK, set the following properties:

- If it is *not* acceptable for the native LogManager class to be overridden by the Access Manager LogManager class in the JDK1.4 environment, then follow these steps:
 - 1. Set the following variables:
 - -DLOG COMPATMODE=Off
 - -Dslis.java.util.logging.config.file=/AccessManager-base/SUNwam/lib/LogConfig.proper
 - 2. In LogConfig.properties, or in the logging.properties file supplied by JDK, set the following properties:

The Client APIs use this logging configuration by default. In this case, the Logging API will configure a remote handler for all logs. Access to the Directory Server is not required in this case.

If SSL is Enabled

If SSL is enable and uses JSS for Access Manager, set the following parameter:

-D"java.protocol.handler.pkgs=com.iplanet.services.comm"

Logging to a Second Access Manager Server

For a remote Access Manager server to use another Access Manager server's logging service, set the Logging Service URL in the remote Access Manager server Naming Service to specify the Access Manager server that will be performing the actual logging. User the following form:

http://host:port/amserver/loggingservice

Using the Logging Sample Files

The sample files demonstrate how you can use the Access Manager Logging APIs for to log operations. You can execute the samples through the command line. You must have super user privileges to run the RunSample and RunLogReader programs and to access AMConfig.properties.

To Run the Sample Programs on Solaris

1 In the Makefile, RunSample, and RunLogReader files, set the following variables. The variables may already have been set during installation.

AM_HOME Set this to refer to the where Access Manager server is installed.

JAVA HOME Set this variable to your installation of the JDK. The JDK version should be

greater than or equal to 1.3.1_06.

JDK14 Set this variable to true if your JAVA_HOME points to JDK 1.4 or newer

version else set it to false

LOCAL_LOGGING Set this variable to true if you are executing this sample at complete Access

Manager installation which will perform local logging. If you are executing this sample from a SUNWamsdk only install then set it to false which will

perform remote logging (logging at server side).

- 2 Set the LD_LIBRARY_PATH as is appropriate for your installation.
- 3 Run the gmake command to compile the sample program.
- 4 Run the following chmod command:

chmod +x RunSample RunLogReader

- 5 Run the following command to run the logging sample program:
 - ./RunSample [-o organizationName] [-u userName -p userPassword]
 - -n logName -m message -l loggedByUser -w loggedByUserPassword

orgName Name of the organization. This is an optional parameter. If a value is

not provided, Access Manager assumes the value to be the root

organization.

userName Name of the user on whose behalf the logging is performed. This is

an optional parameter.

userPassword Password for authenticating the user. This value must be provided if

userName is provided.

logName Name of the log file.

message Message to be logged to the log file.

loggedByUser Name of the administrator user who is logging the message.

loggedByUserPassword Password to authenticate the administrator user.

Example:

\$./RunSample -u amadmin -p 11111111 -n testLog.access -m "trying test logging"
-l amadmin -w 11111111

6 Run the log reader program by running the following command:

 $./ Run Log Reader \ -o \ organization Name \ -u \ user Name$

-p userPassword [-n logName]

organizationName Name of the organization. This is a required parameter.

username Name of the user who is accessing the log file or table. This is a required

parameter.

userpassword Password to authenticate the user. This is a required parameter.

logName Name of the log file or table. This parameter is optional. You can select

the log file or table when running the program.

Example:

▼ To Run the Sample Programs on Windows 2000

1 In the make. bat file, set the following variables:

BASE Set this to refer to the where Access Manager server is installed.

JAVA_HOME Set this variable to your installation of the JDK. The JDK version should be

greater than or equal to 1.3.1_06.

JDK14 Set this variable to true if your JAVA HOME points to JDK 1.4 or newer

version. Otherwise, set it to false.

LOCAL_LOGGING Set this variable to true if you are executing this sample at complete Access

Manager installation which will perform local logging. If you are executing this sample from an SUNWamsdk only install then set it to false which will

perform remote logging (logging at server side).

- 2 Set the LD LIBRARY PATH as is appropriate for your installation.
- 3 Compile the program by running the make command.
- 4 Run the sample program by running the make run command:

orgName Name of the organization. This is an optional parameter. If a value is

not provided, Access Manager assumes the value to be the root

organization.

userName Name of the user on whose behalf the logging is performed. This is

an optional parameter.

userPassword Password for authenticating the user. This value must be provided if

userName is provided.

logName Name of the log file.

message Message to be logged to the log file.

loggedByUser Name of the administrator user who is logging the message.

loggedByUserPassword Password to authenticate the administrator user.

Example:

Using the Logging SPIs

The Logging SPI are Java packages that can be used to develop plug-ins for customized features. The SPI are organized in the com.sun.identity.log.spi package. For more information, see the Sun Java System Access Manager 7.1 2006Q4 Java API Reference.

Log Verifier Plug-In

If secure logging is enabled, the log files are verified periodically to detect any attempt of tampering. If tampering is detected, the action taken can be customized by following the steps.

▼ To Customize Actions to be Taken in Secure Logging

- 1 Implement the com. sun.identity.log.spi.IVerifierOutput interface with the desired functionality.
- 2 Add the implementing class in the classpath of Access Manager.
- 3 Modify the property iplanet-am-logging-verifier-action-class in the /etc/opt/SUNWam/config/xml/amLogging.xml file with the name of the new class.

Log Authorization Plug-In

The Logging Service enables you to plug in a class that will determine whether a LogRecord is logged or discarded. The determination is based on the authorization of the owner of the session token performing the event.

Note - The IAuthorizer interface accepts an SSOToken and the log record being written.

There are several ways to accomplish this. The following procedure is one example.

To Implement a Log Authorization Plug-In

- 1 Get the applicable role or DN of the user from the SSOToken and check it against a pre-configured (or hardcoded) list of roles or users that are allowed access.
 - The administrator must configure a role and assign all policy agents and entities such as applications that can possibly log into Access Manager and into this role.
- 2 Instantiate a PolicyEvaluator and call PolicyEvaluator.isAllowed(ssotoken, logname);.

▼ To Instantiate a PolicyEvaluator

This entails defining a policy XML to model log access and registering it with Access Manager.

- 1 Implement the com. sun.identity.log.spi.IAuthorizer interface with the desired functionality.
- 2 Add the implementing class in the classpath of Access Manager.
- Modify the property iplanet-am-logging-authz-class in the /etc/opt/SUNWam/config/xml/amLogging.xml file with the name of the new class.

◆ ◆ ◆ CHAPTER 7

Client Detection Service

The Sun Java[™] System Access Manager 7.1 Authentication Service has the capability of being accessed from many client types, whether HTML-based, WML-based or other protocols. In order for this function to work, Access Manager must be able to identify the client type. The Client Detection Service is used for this purpose. This chapter offers information on the service, and how it can be used to recognize the client type. It contains the following sections:

- "Overview" on page 129
- "Client Data" on page 132
- "Client Detection APIs" on page 133

Overview

The Access Manager Authentication Service has the capability to process requests from multiple browser type clients. Thus, the service can be used to authenticate users attempting to access applications based in HTML, WML or other protocols.



Caution – The Access Manager console though cannot be accessed from any client type except HTML.

The client detection API can be used to determine the protocol of the requesting client browser and retrieve the correctly formatted pages for the particular client type.

Client Detection Process

Since any user requesting access to Access Manager must first be successfully authenticated, browser type client detection is accomplished within the Authentication Service. When a client's request is passed to Access Manager, it is directed to the Authentication Service. Within this service, the first step in user validation is to identify the browser type using the User-Agent field stored in the HTTP request.

Note – The User-Agent field contains *product tokens* which contains information about the browser type client originating the HTTP request. The tokens are a standard used to allow communicating applications to identify themselves. The format is software/version library/version.

The User-Agent information is then matched to browser type data defined and stored in the amClientData.xml file.



Caution – User-Agent information is defined in amClientData.xml but this information is stored in Directory Server under Client Detection Service.

Based on this client data, correctly formatted browser pages are sent back to the client for authentication (for example, HTML or WML pages). Once the user is validated, the client type is added to the session token (as the key clientType) where it can be retrieved and used by other Access Manager services. (If there is no matching client data, the default type is returned.)

Note – The userAgent must be a part of the client data configured for all browser type clients. It can be a partial string or the exact product token.

▼ Enabling Client Detection

By default, the client detection capability is disabled; this then assumes the client to be of the genericHTML type (For example Access Manager will be accessed from a HTML browser). The preferred way to enable the Client Detection Service is to use the Access Manager console and select the option in the Client Detection Service itself. For more information, see the Administration Guide. To enable client detection using the amclientDetection.xml, the iplanet-am-client-detection-enabled attribute must be set to true. amclientDetection.xml must then be deleted from Directory Server and reloaded using amAdmin. The following procedure illustrates the complete enabling process.

- 1 Import client data XML file using the amadmin command / AccessManager-base amadmin_DN-w amadmin_password t name_of_XML_file
 This step is only necessary if the client data is not already defined in amClientData.xml.
 - Restart Access Manager.
- 3 Login to Access Manager console.
- 4 Go to Service Configuration and click ClientDetectionproperties.
- 5 Enable Client Detection.

6 Make sure the imported data can be viewed with Access Manager console.

Click on the Edit button next to the Client Data attribute.

7 Create a directory for new client type and add customized JSPs.

Create a new directory in

<?xml version="1.0"?>

/*AccessManager-base*/SUNWam/web-src/services/config/auth/default/ and add JSPs for the new client type. Client Detection Process is a login page written for a WML browser.

```
<!DOCTYPE wml PUBLIC "-//WAPFORUM//DTD WML 1.1//EN">
<"http://www.wapforum.org/DTD/wml 1.1.xml">
<!-- Copyright Sun Microsystems, Inc. All Rights Reserved -->
<wml>
<head>
<meta http-equiv="Cache-Control" content="max-age=0"/>
</head>
<card id="authmenu" title="Username">
<do type="accept" label="Enter">
<go method="get" href="/wireless">
<postfield name="TOKEN0" value="$username"/>
<postfield name="TOKEN1" value="$password"/>
</qo>
</do>
>
Enter username:
<input type="text" name="password"/>
>
Enter password:
<input type="text" name="username"/>
</card>
</wml>
```

Client Data

In order to detect client types, Access Manager needs to recognize their identifying characteristics. These characteristics identify the features of all supported types and are defined in the amClientData.xml service file. The full scope of client data available is defined as a schema in amClientData.xml. The configured Access Manager client data available for HTML-based browsers is defined as sub-configurations of the overall schema: genericHTML and its parent HTML.

Note – Parent profiles (or *styles*, as they are referred to in the Access Manager console) are defined with properties that are common to its configured child devices. This allows for the dynamic inheritance of the parent properties to the child devices making the device profiles easier to mange.

HTML

cookieSupport

HTML is a base style containing properties common to HTML-based browsers. It might have several branches including web-based HTML (or genericHTML), cHTML (Compact HTML) and others. All configured devices for this style could inherit these properties which include:

	parentId	Identifies the base profile	e. The default value is HTML
--	----------	-----------------------------	------------------------------

clientType A	Arbitrai	ry string w	hich unio	juely i	identifies t	he client.	The default

value is HTML.

filePath Used to locate the client type files (templates and JSP files). The

default value is html.

contentType Defines the content type of the HTTP request. The default value is

text/html.

genericHTML—defines Client that will be treated as HTML. The default value is true. This

attribute does not refer to the similarly named generic HTML style. Defines whether cookies are supported by the client browser. The

default value is true which sets a cookie in the response header. The other two values could be False which sets the cookie in the URL and Null which allows for dynamic cookie detection. In the first request, the cookie is set in both the response header and the URL; the actual mode is then detected and set from the subsequent

request.

Although the Client Detection Service supports a cookieless mode, Access Manager console does not. Therefore, enabling this function will not allow login to the console. This feature is provided for

wireless applications and others that will support it.

CcppAccept-Charset

Defines the character encoding used by Access Manager to send a response to the browser. The default value is UTF-8.

genericHTML

genericHTMLrefers to an HTML browser such as Netscape Navigator $^{\text{TM}}$, Microsoft $^{\text{TM}}$ Internet Explorer, or Mozilla $^{\text{TM}}$. As a configured device, inherits properties from the HTML style as well as defining its own properties. genericHTML properties include the following:

parentId Identifies the base profile for the configured device. The default value

is HTML.

clientType An arbitrary string which uniquely identifies the client. The default

value is genericHTML.

userAgent Search filter used to compare/match the user agent defined in the

HTTP header. The default value is Mozilla/4.0.

CcppAccept-Charset

Defines the character encoding set supported by the browser.

The default values are:

UTF-8;ISO-8859-1;ISO-8859-2; ISO-8859-3;ISO-8859-4;ISO-8859-5; ISO-8859-6;ISO-8859-7;ISO-8859-8; ISO-8859-9;ISO-8859-10;ISO-8859-14; ISO-8859-15;Shift_JIS;EUC-JP; ISO-2022-JP;GB18030;GB2312;BIG5; EUC-KR;ISO-2022-KR;TIS-620;KOI8-R

The character set can be configured for any given locale by adding charset_locale=codeset where the code set name is based on the

Internet Assigned Numbers Authority (IANA) standard.

Client Detection APIs

Access Manager is packaged with Java APIs which can implement the client detection functionality. The client detection APIs are contained in a package named com.iplanet.services.cdm. This package provides the interfaces and classes you need to retrieve client properties. The client detection procedure entails defining the client type characteristics and implementing the client detection API within the external application.

The client detection capability is provided by ClientDetectionInterface, a pluggable interface (not an API invoked by a regular application). ClientDetectionInterface provides a

getClientType method. The getClientType method extracts the client data from the browser's incoming HttpRequest, matches the user agent information and returns the ClientType as a string. Upon successful authentication, the client type is added to the user's session token. The ClientDetectionException handles any error conditions.



Using the Access Manager Utilities

Sun Java™ System Access Manager 7.1 provides scripts to backup and restore data as well as APIs that are used by the server itself or by external applications. This chapter describes the scripts and the APIs. The chapter contains the following sections:

- "Utility APIs" on page 135
- "Password API Plug-Ins" on page 137

Utility APIs

The utilities package is called com.iplanet.am.util. It contains utility programs that can be used by external applications accessing Access Manager. Following is a summary of the utility API and their functions.

AdminUtils

This class contains the methods used to retrieve the TopLevelAdmin DN and password. The information comes from the server configuration file, serverconfig.xml, located in *AccessManager-base*/SUNWam/config/ums.

AMClientDetector

The AMClientDetector interface executes the Client Detection Class configured in the Client Detection Service to get the client type.

AMPasswordUtil

The AMPasswordUtil interface has two purposes:

Encrypting and decrypting any string.

 Encrypting and decrypting special user passwords such as the password for dsameuser or proxy user.

Any remote application using this utility should have the value of the AMConfig property am.encryption.pwd copied to a properties file on the client side. This value is generated at installation time and stored in /etc/opt/SUNWam/config/AMConfig.properties on Solaris, /etc/opt/sun/identity/AMConfig.properties on Linux.

Debug

The Debug utility allows an interface to file debug and exception information in a uniform format. It supports different levels of information (in the ascending order): OFF, ERROR, WARNING, MESSAGE and ON. A given debug level is enabled if it is set to at least that level. For example, if the debug state is ERROR, only errors will be filed. If the debug state is WARNING, only errors and warnings will be filed. If the debug state is MESSAGE, everything will be filed. MESSAGE and ON are the same level except MESSAGE writes to a file, whereas ON writes to System.out.

Note – Debugging is an intensive operation and can hurt performance. Java evaluates the arguments to message() and warning() even when debugging is turned off. It is recommended that the debug state be checked before invoking any message() or warning() methods to avoid unnecessary argument evaluation and maximize application performance.

Locale

This class is a utility that provides the functionality for applications and services to internationalize their messages.

SystemProperties

This class provides functionality that allows single-point-of-access to all related system properties. First, the class tries to find AMConfig.class, and then a file, AMConfig.properties, in the CLASSPATH accessible to this code. The class takes precedence over the flat file. If multiple servers are running, each may have their own configuration file. The naming convention for such scenarios is AMConfig serverName.

ThreadPool

ThreadPool is a generic thread pool that manages and recycles threads instead of creating them when a task needs to be run on a different thread. Thread pooling saves the virtual machine the work of creating new threads for every short-lived task. In addition, it minimizes the overhead

associated with getting a thread started and cleaning it up after it dies. By creating a pool of threads, a single thread from the pool can be reused any number of times for different tasks. This reduces response time because a thread is already constructed and started and is simply waiting for its next task.

Another characteristic of this thread pool is that it is fixed in size at the time of construction. All the threads are started, and then each goes into a wait state until a task is assigned to it. If all the threads in the pool are currently assigned a task, the pool is empty and new requests (tasks) will have to wait before being scheduled to run. This is a way to put an upper bound on the amount of resources any pool can use up. In the future, this class may be enhanced to provide support growing the size of the pool at runtime to facilitate dynamic tuning.

Password API Plug-Ins

The Password API plug-ins can be used to integrate password functions into applications. They can be used to generate new passwords as well as notify users when their password has been changed. These interfaces are PasswordGenerator and NotifyPassword, respectively. They can be found in the com.sun.identity.password.plugins package.

Note – The Access Manager Javadocs can be accessed from any browser by copying the complete AccessManager-base/SUNWam/docs/ directory into the AccessManager-base /SUNWam/public_html directory and pointing the browser to http:// AcceessManager-HostName.domain_name :port/docs/ index.html.

There are samples (which include sample code) for these API that can be accessed from the Access Manager installation. They are located in *AccessManager-base* /SUNWam/samples/console. They include:

Notify Password Sample

This sample details how to build a plug-in which an administrator can define their own method of notification when a user has reset a password. Instructions for this sample are in the Readme.txt or Readme.html file located in

 $Access Manager-base/{\tt SUNWam/samples/console/NotifyPassword}\,.$

Password Generator Sample

This sample details how to build a plug-in which an administrator can define their own method of random password generation when a user's password is reset using the Password Reset Service. Instructions for this sample are in the Readme.txt or Readme.html file located in AccessManager-base/SUNWam/samples/console/PasswordGenerator.



Enabling the Access Manager Notification Service

Sun Java $^{\text{TM}}$ System Access Manager 7.1 Notification Service allows for session notifications to be sent to remote web containers. It is necessary to enable this service for use by SDK applications running remotely from the Access Manager server itself. This chapter explains how to enable a remote web container to receive the notifications. It contains the following sections:

- "Overview" on page 139
- "Enabling The Notification Service" on page 139

Overview

The Notification Service allows for session notifications to be sent to web containers that are running the Access Manager SDK remotely. The notifications apply to the Session, Policy and Naming Services only. In addition, the remote application must be running in a web container. The purpose of the notifications would be:

- To sync up the client side cache of the respective services.
- To enable more real time updates on the clients. (Polling is used in absence of notifications.)
- No client application changes are required to support notifications.

Note that the notifications can be received only if the remote SDK is installed on a web container.

Enabling The Notification Service

Following are the steps to configure the remote SSO SDK to receive session notifications.

▼ To Receive Session Notifications

- 1 Install Access Manager on Machine 1.
- 2 Install Sun Java System Web Server on Machine 2.
- 3 Install the SUNWamsdk on the same machine as the Web Server.

For instructions on installing the Access Manager SDK remotely, see the *Sun Java Enterprise System 5 Installation Guide for Unix*.

- 4 Ensure that the following are true concerning the machine where the SDK is installed.
 - a. Ensure that the right access permissions are set for the /remote_SDK_server/ SUNWam/lib and /remote_SDK_server/ SUNWam/locale directories on the server where the SDK is installed.

 These directories contains the files and jars on the remote server.
 - b. Ensure that the following permissions are set in the Grant section of the server. policy file of the Web Server.

server.policy is in the config directory of the Web Server installation. These permissions can be copied and pasted, if necessary:

```
permission java.security.SecurityPermission
"putProviderProperty.Mozilla-JSS"
permission java.security.SecurityPermission "insertProvider.Mozilla-JSS";
```

c. Ensure that the correct classpath is set in server.xml.

server.xml is also in the config directory of the Web Server installation. A typical classpath would be:

```
//usr/share/lib/jaxrpc-api.jar:
                //usr/share/lib/jaxrpc-impl.jar:
                //export/SUNWam/lib/jaxm-runtime.jar:
                //usr/share/lib/saaj-impl.jar:/export/SUNWam
                //lib:/export/SUNWam/locale:
                //usr/share/lib/mps/jss3.jar:
                //export/SUNWam/lib/
                                        am sdk.jar:
                //export/SUNWam/lib/am services.jar:
                //export/SUNWam/lib/am sso provider.jar:
                //export/SUNWam/lib/swec.jar:
                //export/SUNWam/lib/acmecrypt.jar:
                //export/SUNWam/lib/iaik ssl.jar:
                //usr/share/lib/jaxp-api.jar:
                //usr/share/lib/mail.jar:
                //usr/share/lib/activation.jar:
                //export/SUNWam/lib/servlet.jar:
                //export/SUNWam/lib/am logging.jar:
                //usr/share/lib/commons-logging.jar:
                //IS CLASSPATH END DELIM:"
envclasspathignored="true" debug="false"
debugoptions="-Xdebug -Xrunjdwp:
transport=dt socket,
server=y, suspend=n"
javacoptions="-q"
dynamicreloadinterval="2">
```

- 5 Use the SSO samples installed on the remote SDK server for configuration purposes.
 - a. Change to the / remote SDK server / SUNWam/samples/sso directory.
 - b. Run gmake.
 - c. Copy the generated class files from / remote_SDK_server / SUNWam/samples/sso to / remote_SDK_server / SUNWam/lib/.
- 6 Copy the encryption value of am.encryption.pwd from the AMConfig.properties file installed with Access Manager to the AMConfig.properties file on the remote server to which the SDK was installed.

The value of am. encryption.pwd is used for encrypting and decrypting passwords.

7 Login into Access Manager as amadmin.

http://*AcceessManager-HostName*:3000/amconsole

8 Execute the servlet by entering http://

 $remote_SDK_host$: 58080/servlet/SSOTokenSampleServlet into the browser location field and validating the SSOToken.

SSOTokenSampleServlet is used for validating a session token and adding a listener. Executing the servlet will print out the following message:

SSOToken host name: 192.18.149.33 SSOToken Principal name: uid=amAdmin,ou=People,dc=red,dc=iplanet,dc=com Authentication type used: LDAP IPAddress of the host: 192.18.149.33 The token id is AQIC5wM2LY4SfcyURnObg7vEgdkb+32T43+RZN30Req/BGE= Property: Company is - Sun Microsystems Property: Country is - USA SSO Token Validation test Succeeded

Set the property com.iplanet.am.notification.url=in AMConfig.properties of the machine where the Client SDK is installed:

```
com.iplanet.am.notification.url=http://clientSDK_host.domain:port
/servlet
com.iplanet.services.comm.client.PLLNotificationServlet
```

- 10 Restart the Web Server.
- 11 Login into Access Manager as amadmin.

http://AcceessManager-HostName:3000/amconsole

12 Execute the servlet by entering http://

remote_SDK_host: 58080/servlet/SSOTokenSampleServlet into the browser location field and validating the SSOToken again.

When the machine on which the remote SDK is running receives the notification, it will call the respective listener when the session state is changed. Note that the notifications can be received only if the remote SDK is installed on a web container.

♦ ♦ ♦ CHAPTER 10

Updating and Redeploying Access Manager WAR Files

Access Manager contains a number of web archive (WAR) files. These packages contain Java servlets and JavaServer PagesTM (JSP) pages you can modify to customize Access Manager to meet your needs. The chapter contains the following sections:

- "WAR Files in J2EE Software Development" on page 143
- "About Access Manager WAR Files" on page 144
- "Updating Modified WARs" on page 148
- "Redeploying Modified Access Manager WAR Files" on page 149

WAR Files in J2EE Software Development

Access Manager is built upon the Java 2 Platform, Enterprise Edition (J2EE) platform which uses a component model to create full-scale applications. A component is self-contained functional software code assembled with other components into a J2EE application. The J2EE application components can be deployed separately on different servers. J2EE application components include the following:

- Client components such as including dynamic web pages, applets, and a Web browser that run on the client machine.
- Web components such as servlets and Java Server Pages (JSPs) that run within a web container.
- Business components, which can be code that meets the needs of a particular enterprise domain such as banking, retail, or finance. Such business components also run within the web container.
- Enterprise infrastructure software that runs on legacy machines.

Web Components

When a web browser executes a J2EE application, it deploys server-side objects known as web components. Java Server Pages (JSPs) and corresponding servlets are two such web components.

Servlets Small Java programs that dynamically process requests and

construct responses from a web browser. Servlets run within web

containers.

Java Server Pages (JSPs) Text-based documents that contain static template data such as

HTML, Scalable Vector Graphics (SVG), Wireless Markup Language (WML), or eXtensible Markup Language (XML). JSPs also contain elements such as servlets that construct dynamic

content.

How Web Components are Packaged

J2EE components are usually packaged separately, and then bundled together into an Enterprise Archive (EAR) file for application deployment. Web components are packaged in web application archives, also known as WAR files. Each WAR file contains servlets, JSPs, a deployment descriptor, and related resource files.

Static HTML files and JSP are stored at the top level of the WAR directory. The top-level directory contains the WEB-INF subdirectory which contains tag library descriptor files in addition to the following:

Server-side classes Servlets, JavaBean components and related Java class files. These must be

stored in the WEB-INF/classes directory.

Auxiliary JARs Tag libraries and any utility libraries called by server-side classes. These

must be stored in the WEB-INF/lib directory.

web.xml The web component deployment descriptor is stored in the WEB-INF

directory

About Access Manager WAR Files

When you customize Access Manager, sometimes you must also modify the Access Manager WAR files. The modifications in turn result in changes to the web components.

Access Manager provides two types of WAR files. One type of Access Manager WAR file is automatically built and deployed for you at installation. The password.war and services.war files are of this type. Both password.war and services.warare related to features and services

that power the Access Manager server. At installation, based on the source files in the staging directory <code>AccessManager-base/web-src/</code>, both <code>password.war</code> and <code>services.war</code> are automatically generated and deployed into the <code>AccessManager-base/SUNWam/war</code> directory. When you want to customize Access Manager features or services, you must make changes in the source files contained in the staging directory, and then regenerate and redeploy the appropriate WAR files.



Caution – When you apply a patch or an upgrade to Access Manager, any customizations you have implemented may be overwritten.

The second type of Access Manager WAR is a specialized WAR file that you must manually deploy. The amaduthdistui.war for the Distributed Authentication UI, and the amclient.war for the Client SDK are such WARs. You can install amaduthdistui.war or amclient.warthrough the JES installer, or you can manually deploy one or both of them.

The following Access Manager WAR files are located in this directory:

AccessManager-base/SUNWam/

amcommon.war Automatically deployed at installation, and builds the Liberty IDFF profile

named Identity Provider Introduction which is used in implementing a

circle of trust. You do not need to redeploy this WAR.

amconsole.war If you choose the Legacy mode option during installation, this WAR is

automatically deployed at installation, and builds the legacy mode administration console. Redeploy this WAR after you make changes to

AccessManager-base/web-src/services/console/* source files.

ampassword.war Automatically deployed at installation, and builds the password reset

feature. Redeploy this WAR after you make changes to *AccessManager-base*/web-src/password/* source files.

amserver.war Automatically deployed at installation, and builds Access Manager service

components. Redeploy this WAR after you make changes to *AccessManager-base*/web-src/services/* source files.

The following Access Manager WARs are located in this directory:

AccessManager-base/SUNWam/war.

am_server.war Use this WAR to manually install Access Manager as a stand-alone

product, and without using the JES installer. For more information, see Chapter 12, "Deploying Access Manager as a Single WAR File," in *Sun*

Java System Access Manager 7.1 Postinstallation Guide.

amclient.war Uset

Use this WAR to manually install the Client SDK on a container remote from the Access Manager server. For more information, see "Installing the Client SDK" on page 16.

amauthdistui.war

Use this WAR to manually install the Distributed Authentication UI server on a container remote from the Access Manager server. You can install this WAR using the JES installer. For more information, see Chapter 11, "Deploying a Distributed Authentication UI Server," in *Sun Java System Access Manager 7.1 Postinstallation Guide*. You can also manually deploy this WAR. For more information, see "Customizing the Distributed Authentication User Interface" on page 183.

amconsole.war

Access Manager uses this WAR to build the realm mode administration console. The amconsole.war file is automatically generated and deployed, based on the source code in AccessManager-base/web-src/services/console, when Access Manager is installed. You cannot customize this WAR.

console.war

Access Manager uses this WAR to build the legacy mode administration console. The console. war file is automatically generated and deployed, based on the source code in *AccessManager-base/web-src/services/console*, when Access Manager is installed. You can customize this WAR. For more information, see Chapter 11.

introduction.war

This WAR is related to the Liberty IDFF profile named Identity Provider Introduction which is used in implementing a circle of trust. The introduction.war file is automatically generated and deployed, based on the source code in

AccessManager-base/web-src/services/common, when Access Manager is installed. You cannot customize this WAR.

password.war

Access Manager uses this WAR for the password reset service. The password.war file is automatically generated and deployed, based on the source code in *AccessManager-base*/web-src/services/password, when Access Manager is installed. You can customize this WAR. For more information, see the section "password.war" on page 147.

services.war

Access Manager uses this WAR to build the UI for various Access Manager Services. The services . war file is automatically generated and deployed, based on the source code in

AccessManager-base/web-src/services/services, when Access

Manager is installed. You can customize this WAR. For more information, see the section "services.war" on page 147.

password.war

The password.war contains files used by the Access Manager password reset service.

Files You Can Modify

You can modify the following password.war files:

- web.xml and related XML files used for constructing it are located in AccessManager-base/SUNWam/web-src/password/WEB-INF/.
- JSPs located in /SUNWam/web-src/password/password/ui/.
- Image files located in SUNWam/web-src/password/password/images/.
- Stylesheets located in AccessManager-base/SUNWam/web-src/password/password/css/.

Files You Must Not Modify

Do not modify the following password.war files. Modifying the following files may cause unintended Access Manager behaviors.

- JARs located in AccessManager-base/SUNWam/web-src/password/WEB-INF/lib/.
- Tag library descriptor (.tld) files located in AccessManager-base/web-src/password/WEB-INF/.

services.war

The services.war contains files used by various Access Manager services.

Files You Can Modify

You can modify the following services.war files:

- web.xml and related XML files used for constructing it are located in AccessManager-base/SUNWam/web-src/services/WEB-INF/.
- JavaScript files are located in AccessManager-base/SUNWam/web-src/services/js/.
- JSP are located in the following directories:
 - AccessManager-base/SUNWam/web-src/services/config/auth/default/
 - AccessManager-base/SUNWam/web-src/services/config/federation/default/

Image files are located in the following directories:

- AccessManager-base/SUNWam/web-src/services/images/
- AccessManager-base/SUNWam/web-src/services/fed images/
- AccessManager-base/SUNWam/web-src/services/login_images/

Stylesheets are located in the following directories:

- AccessManager-base/SUNWam/web-src/services/css/.
- AccessManager-base/SUNWam/web-src/services/fed_css/.

Files You Must Not Modify

Do not modify the following services.war files. Modifying the following files may cause Access Manager to fail:

- Non-modifiable JARs are located in AccessManager-base/SUNWam/web-src/services/WEB-INF/lib/.
- Non-modifiable Tag Library Descriptor (.tld) files are located in AccessManager-base/SUNWam/web-src/services/WEB-INF/.

Updating Modified WARs

Once a file within a WAR is modified, the WAR itself needs to be updated with the newly modified file. Following is the procedure to update a WAR.

▼ To Update a Modified WAR

1 Go to the directory where the WAR files are kept.

cd AccessManager-base/ SUNWam/war

2 Run the jar command.

jar -uvf WARfilename.war path_to_modified_file

The -uvf option replaces the old file with the newly modified file. For example:

jar -uvf console.war newfile/index.html

This command replaces the index.html file in console.war with the index.html file located in *AccessManager-base*/SUNWam/newfile.

3 Delete the modified file.

rm newfile/index.html

Delete the modified file.

Redeploying Modified Access Manager WAR Files

Once updated, the WARs must be redeployed to their web container. The web container provides services such as request dispatching, security, concurrency, and life cycle management. The web container also gives the web components access to the J2EE APIs.

The BEA WebLogic Server 6.1 and Sun Java System Application Server web containers do not require WARs to be exploded. The servers themselves are deployed as WARs. After WAR files are installed on these servers, you must restart all related servers.

To Redeploy a WAR On BEA WebLogic Server 6.1

Run the Java command on the BEA WebLogic 6.1 Server using the following form:

java weblogic.deploy -url protocol://server_host:server_port

-component amconsole: WL61 _server_name

deploy WL61_admin_password deployment_URI AccessManager-base/SUNWam/WARname.war

where the following variables are used:

protocol://server_host:server_port The protocol [http | https] and fully-qualified name

of the Access Manager server.

WL61 _server_name The name of the WebLogic server.

WL61_admin_password The WebLogic administrator password.

deployment_URI For console.war, the deployment URI is amconsole.

For services.war, the deployment URI is amserver.

For password.war, the deployment UIR is ampassword.

AccessManager-base The directory where the Access Manager server is

installed.

WARname.war The name of the WAR file to deploy.

[console.war | server.war | password.war]

For more complete information on the Java utility weblogic.deploy and its options, see the BEA WebLogic Server 6.1 documentation

(http://edocs.bea.com/wls/docs61/index.html).

To Redeploy a WAR File on Sun Java System Application Server 7.0

On the Application Server, run the asadmin command using the following form:

asadmin deploy -u S1AS_administrator

- -w S1AS_administrator_password -H console_server_host
- -p S1AS_server_port --type web secure_flag
- --contextroot deploy_uri --name deploy_uri
- --instance S1AS_instanceAccessManager-base/SUNWam/WARname

where the following variables are used:

S1AS_administrator Application Server administrator

S1AS_administrator_password Application Server administrator password

console_server_host Access Manager server host name

\$1AS_server_port Application Server port number

deploy_uri For console.war, the deployment URI is amconsole.

For password.war, the deployment URI is

ampassword.

For services.war, the deployment URI is

amservices.

S1AS_instance/AccessManager-base Application Server directory where Access Manager

server is installed

WARname.war The name of the WAR file to deploy.

[console.war | services.war | password.war]

For more information on the asadmin deploy command and its options, see the *Sun Java System Application Server 7.0 Developer's Guide.*

Redeploying an Access Manager WAR on IBM WebSphere Application Server

For detailed instructions on how to deploy WARs in an IBM WebSphere Application Server container, see the documentation that comes with the product:

http://www-3.ibm.com/software/webservers/studio/doc/v40/studioguide/en/html/sdsscenario1.html

(http://www-3.ibm.com/
software/webservers/studio/doc/v40/studioguide/en/html/sdsscenario1.html).

◆ ◆ ◆ CHAPTER 11

Customizing the Administration Console

The Sun Java™ System Access Manager 7.1 console is a web-based interface for creating, managing, and monitoring the identities, web services, and enforcement policies configured throughout an Access Manager deployment. It is built with Sun Java System Application Framework, a Java 2 Enterprise Edition (J2EE) framework used to help developers build functional web applications. XML files, JavaServer Pages™ (JSP) and Cascading Style Sheets (CSS) define the look of the Access Manager HTML pages.

This chapter describes the Access Manager administration console, its pluggable architecture, and how to customize the Legacy mode user interface. The chapter contains the following sections:

- "About the Administration Console" on page 153
- "Customizing The Console" on page 155
- "Console APIs" on page 163
- "Precompiling the Console JSP" on page 164
- "Console Samples" on page 164

Note – At this time, no documentation or code samples exist for modifying the Realm mode user interface. For customized information on modifying the Realm mode user interface in your environment, contact your Sun Sales Representative.

About the Administration Console

The console is divided into three frames: Header, Navigation and Data. The Header frame displays corporate branding information as well as the first and last name of the currently logged-in user as defined in their profile. It also contains a set of tabs to allow the user to switch between the management modules, a hyperlink to the Access Manager Help system, a Search function and a Logout link. The Navigation frame on the left displays the object hierarchy of the chosen management module, and the Data frame on the right displays the attributes of the object selected in the Navigation frame.




FIGURE 11-1 Legacy Mode Administration Console

For information about what the Console does and about the differences between the Realm mode and Legacy mode console interfaces, see Chapter 1, "The Access Manager Console," in Sun Java System Access Manager 7.1 Administration Guide.

Generating The Console Interface

When the Access Manager console receives an HTTP(S) request, it first determines whether the requesting user has been authenticated. If not, the user is redirected to the Access Manager login page supplied by the Authentication Service. After successful authentication, the user is redirected back to the console which reads all of the user's available roles, and extracts the applicable permissions and behaviors. The console is then dynamically constructed for the user based on this information. For example, users with one or more administrative roles will see the administration console view while those without any administrative roles will see the end user console view. Roles also control the actions a user can perform and the identity objects that a user sees. Pertaining to the former, the organization administrator role allows the user read and write access to all objects within that organization while a help desk administrator role only permits write access to the users' passwords. With regards to the latter, a person with a people container administrator role will only see users in the relevant people container while the organization administrator will see all identity objects. Roles also control read and write permissions for service attributes as well as the services the user can access.

Plug-In Modules

An external application can be plugged-in to the console as a module, gaining complete control of the Navigation and Data frames for its specific functionality. In this case, a tab with the name of the custom application needs to be added to the Header frame. The application developer would create the JSPs for both left and right frames, and all view beans, and models associated with them

Accessing the Console

The Naming Service defines URLs used to access the internal services of Access Manager. The URL used to access the Administration Console web application is:

http://AcceessManager-HostName.domain_name:port/ amconsole

The first time Administration Console (amconsole) is accessed, it brings the user to the Authentication web application (amserver) for authentication and authorization purposes. After login, amserver redirects the user to the configured success login URL. The default successful login URL is:

http(s)://AcceessManager-HostName.domain_name:port/ amconsole/base/AMAdminFrame

Customizing The Console

The Access Manager Legacy mode console uses JSP and CSS to define the look and feel of the pages used to generate its frames. A majority of the content is generated dynamically—based on where, and at what, the user is looking. In that regard, the modification of the content is somewhat restricted. Within the Navigation frame, the layout of the controls (the view menu), the action buttons, and the table with current objects in each JSP can be changed. In the Data frame, the content displayed is dynamically generated based on the XML service file being accessed but the layout, colors, and fonts are controlled by the adminstyle.css style sheet.

The Default Console Files

An administrator can modify the console by changing tags in the JSPs and CSS's. All of these files can be found in the *AccessManager-base/SUNWam/web-src/services/console* directory. The files in this directory provide the default Sun Java System interface. Out of the box, it contains the following subdirectories:

base contains JSP that are not service-specific.

- css contains the adminstyle.css which defines styles for the console.
- federation contains JSP related to the Federation Management module.
- html contains miscellaneous HTML files.
- images contains images referenced by the JSP.
- js contains JavaScriptTM files.
- policy contains JSP related to the Policy Service.
- service contains JSP related to the Service Management module.
- session contains JSP related to the Current Sessions (session management) module.
- user contains JSP related to the Identity Management module.

Note – Console-related JSP contain HTML and custom library tags. The tags are defined in tag library descriptor files (.tld) found in the *AccessManager-base*/SUNWam/web-src/WEB-INF directory. Each custom tag corresponds to a view component in its view bean. While the tags in the JSP can be removed, new tags can not be added. For more information, see the Sun Java System Application Framework documentation

(http://docs.sun.com/db/coll/S1 appframe20 en).

console.war

The console.war contains files used by the Access Manager administration console.

Files You Can Modify

You can modify the following console.war files:

- web.xml and related XML files used for constructing it are located in AccessManager-base /SUNWam/web-src/services/WEB-INF/.
- Modifiable JavaScript files are located in AccessManager-base /SUNWam/web-src/services/console/js/.
- Modifiable JSP are located in the following directories dependant upon the service that deploys them:
 - AccessManager-base / SUNWam/web-src/services/console/auth/
 - AccessManager-base / SUNWam/web-src/services/console/federation/
 - AccessManager-base / SUNWam/web-src/services/console/policy/
 - AccessManager-base / SUNWam/web-src/services/console/service/
 - AccessManager-base / SUNWam/web-src/services/console/session/
 - AccessManager-base / SUNWam/web-src/services/console/user/

Modifiable image files are located in *AccessManager-base* /SUNWam/web-src/services/console/images/.

 Modifiable stylesheets are located in AccessManager-base/SUNWam/web-src/services/console/css/.

Files You Must Not Modify

Do not modify the following console.war files. Modifying these files may cause unintended Access Manager behaviors.

- JARs are located in AccessManager-base/SUNWam/web-src/services/WEB-INF/lib/.
- Tag Library Descriptor (.tld) files are located in AccessManager-base/SUNWam/web-src/services/WEB-INF/.

Creating Custom Organization Files

To customize the console for use by a specific organization, the *AccessManager-base*/SUNWam/web-src/services/console directory should first be copied, renamed and placed on the same level as the default directory. The files in this new directory can then be modified as needed.

Note – There is no standard to follow when naming the new directory. The new name can be any arbitrarily chosen value.

For example, customized console files for the organization dc=new_org, dc=com might be found in the *AccessManager-base*/SUNWam/web-src/services/custom_directory directory.

To Create Custom Organization Files

1 Change to the directory where the default templates are stored:

cd AccessManager-base/SUNWam/web-src/services

2 Make a new directory at that level.

The directory name can be any arbitrary value. For this example, it is named *AccessManager-base*/SUNWam/web-src/services/custom_directory/.

3 Copy all the JSP files from the console directory into the new directory.

AccessManager-base/SUNWam/web-src/services/console contains the default JSP for Access Manager. Ensure that any image files are also copied into the new directory.

4 Customize the files in the new directory.

Modify any of the files in the new directory to reflect the needs of the specific organization.

5 Modify the AMBase. jsp file.

٥,

In our example, this file is found in

Custom Organization Files" on page 157.

AccessManager-base/SUNWam/web-src/services/custom_directory/base. The line String console = "../console"; needs to be changed to String console = "../new_directory_name";. The String consoleImages tag also needs to be changed to reflect a new image directory, if applicable. The contents of this file are copied in "Creating"

<!-Copyright © 2002 Sun Microsystems, Inc. All rights reserved.
Use is subject to license terms.
-->
<% String console = "../console";
String consoleUrl = console + "/";

String consoleImages = consoleUrl + "images";

6 Change the value of the JSP Directory Name attribute in the Administration Service to match that of the directory created in "Creating Custom Organization Files" on page 157.

The JSP Directory Name attribute points the Authentication Service to the directory which contains an organization's customized console interface. Using the console itself, display the services registered to the organization for which the console changes will be displayed. If the Administration Service is not visible, it will need to be registered. For information on registering services, see the Administration Guide.

Once the new set of console files have been modified, the user would need to log into the organization where they were made in order to see any changes. Elaborating on our example, if changes are made to the JSP located in the

AccessManager-base/SUNWam/web-src/services/custom_directory directory, the user would need to login to that organization using the URL:

```
http://server_name.domain_name:port//
service_deploy_uri/UI/Login?org=
    custom_directory_organization.
```

Alternate Customization Procedure

The console can also be modified by simply replacing the default images in AccessManager-base/SUNWam/web-src/services/console/images, with new, similarly named images.

Miscellaneous Customizations

Included in this section are procedures for several specific customizations available to administrators of the Access Manager console.

To Modify The Service Configuration Display

A *service* is a group of attributes that are managed together by the Access Manager console. Out-of-the-box, Access Manager loads a number of services it uses to manage its own features. For example, the configuration parameters of the Logging Service are displayed and managed in the Access Manager console, while code implementations within Access Manager use the attribute values to run the service.

To Modify The User Profile View

The Access Manager console creates a default User Service view based on information defined in the amUser.xml service file.

A modified user profile view with functionality more appropriate to the organization's environment can be defined by creating a new ViewBean and/or a new JSP. For example, an organization might want User attributes to be formatted differently than the default vertical listing provided. Another customization option might be to break up complex attributes into smaller ones. Currently, the server names are listed in one text field as:

protocol://Access Manager_host. domain:port

Instead, the display can be customized with three text fields:

 $protocol_chooser_field://server_host_field:port_number_field$

A third customization option might be to add JavaScript to the ViewBean to dynamically update attribute values based on other defined input. The custom JSP would be placed in the following directory: <code>AccessManager-base/SUNWam/web-src/services/console/user</code>. The ViewBean is placed in the classpath com.iplanet.am.console.user. The value of the attribute User Profile Display Class in the Administration Service (iplanet-am-admin-console-user-profile-class in the amAdminConsole.xml service file) would then be changed to the name of the newly created ViewBean. The default value of this attribute is com.iplanet.am.console.user.UMUserProfileViewBean.

Display Options For The User Profile Page

There are a number of attributes in the Administration Service that can be selected to display certain objects on the User Profile page. Display User's Roles, Display User's Groups and User Profile Display Options specify whether to display the roles assigned to a user, the groups to which a user is a member and the schema attributes, respectively. More information on these service attributes can be found in the Administration Guide.

To Localize The Console

All textual resource strings used in the console interface can be found in the amAdminModuleMsgs.properties file, located in *AccessManager-base/SUNWam/locale/*. The default language is English (en_US). Modifying this file with messages in a foreign language will localize the console.

To Display Service Attributes

Service attributes are defined in XML service files based on the sms.dtd. In order for a particular service attribute to be displayed in the console, it must be configured with the any XML attribute. The any attribute specifies whether the service attribute for which it is defined will display in the Access Manager console.

To Customize Interface Colors

All the colors of the console are configurable using the Access Manager style sheet adminstyle.css located in the *AccessManager-base/SUNWam/web-src/services/console/css* directory. For instance, to change the background color for the navigation frame, modify the BODY.navFrame tag; or to change the background color for the data frame, modify the BODY.dataFrame. The tags take either a text value for standard colors (blue, green, red, yellow, etc.) or a hexadecimal value (#ff0000, #aadd22, etc.). Replacing the default with another value will change the background color of the respective frame after the page is reloaded in the browser. "Miscellaneous Customizations" on page 159 details the tag in adminstyle.css.

To Change The Default Attribute Display Elements

The console auto-generates Data frame pages based on the definition of a service's attributes in an XML service definition file. Each service attribute is defined with the XML attributes type, uitype and syntax. Type specifies the kind of value the attribute will take. uitype specifies the HTML element displayed by the console. syntax defines the format of the value. The values of these attributes can be mixed and matched to alter the HTML element used by the console to display the values of the attributes. For example, by default, an attribute of the single_choice type displays its choices as a drop down list in which only one choice can be selected. This list can also be presented as a set of radio buttons if the value of the uitype attribute is changed to radio. "Miscellaneous Customizations" on page 159 illustrates this concept.

EXAMPLE 11-2 uitype XML Attribute Sample

"Miscellaneous Customizations" on page 159 is a listing of the possible values for each attribute, and the corresponding HTML element that each will display based on the different groupings.

TABLE 11-1 Service Attribute Values and Corresponding Display Elements

type Value	syntax Value	uitype Value	Element Displayed In Console
single_choice	string	No value defined	pull-down menu choices
		radio	radio button choices
Single	boolean	No value defined	checkbox
		radio	radio button
	string	No value defined	text field
		link	hyperlink
		button	clickable button
	password	No value defined	text field
	paragraph	No value defined	scrolling text field
list	string	No value defined	Add/Delete name list
		name_value_list	Add/Edit/Delete name list
multiple_choice	string	No value defined	choice list

To Add A Module Tab

The section "Plug-In Modules" mentions the capability to plug-in external applications as modules. Once this is accomplished, the module needs to be accessible via the console by adding a new module tab. Label information for module tabs are found in the amAdminModuleMsgs.properties console properties file located in <code>AccessManager-base/SUNWam/locale/</code>. To add label information for a new module, add a key and value pair similar to module105_NewTab=My New Tab. "Miscellaneous Customizations" on page 159 illustrates the default pairs in the file.

EXAMPLE 11-3 Module Tab Key And Value Pairs

module101_identity=Identity Management module102_service=Service Configuration module103_session=Current Sessions module104 federation=Federation Management

The module name and a URL for the external application also need to be added to the View Menu Entries attribute in the Administration Service (or

iplanet-am-admin-console-view-menu in the amAdminConsole.xml service file). When a module tab in the Header frame is clicked, this defined URL is displayed in the Navigation frame. For example, to define the display information for the tab sample, an entry similar to module105_NewTab|/amconsole/custom_directory/custom_NavPage would be added to the View Menu Entries attribute in the Administration Service.

Note – The console retrieves all the entries from this attribute and sorts them by i18n key. This determines the tab display order in the Header frame.

After making these changes and restarting Access Manager, a new tab will be displayed with the name My New Tab.

To Display Container Objects

In order to create and manage LDAP organizational units (referred to as *containers* in the console), the following attributes need to be enabled (separately or together) in the Administration Service.

- Display Containers In Menu—Containers are organizational units as viewed using the Access Manager console. If this option is selected, the menu choice Containers will be displayed in the View menu for top-level Organizations, Sub-Organizations and other containers.
- Show People Containers—People containers are organizational units containing user profiles. If this option is selected, the menu choice People Containers will be displayed in the View menu for Organizations, Containers and Sub-Organizations.

 Show Group Containers—Group containers are organizational units containing groups. If this option is selected, the menu choice Group Containers will be displayed in the View menu for Organizations, Containers and Group Containers.

Viewing any of these display options is also dependent on whether the Enable User Management attribute is selected in the Administration Service. (This attribute is enabled by default after a new installation.) More information on these attributes can be found in the Administration Guide.

Console APIs

The public console API package is named com.iplanet.am.console.base.model. It contains interfaces that can be used to monitor and react to events that occur in the console. This *listener* can be called when the user executes an action on the console that causes an event. An event can have multiple listeners registered on it. Conversely, a listener can register with multiple events. Events that might be used to trigger a listener include:

- Displaying a tab in the Header frame.
- Creating or deleting identity-related objects.
- Modifying the properties of an identity-related object.
- Sending attribute values to the console ViewBean for display purposes.

When a listener is created all the methods of that interface must be implemented thus, the methods in the AMConsoleListener interface must be implemented. The AMConsoleListenerAdapter class provides default implementations of those methods and can be used instead. Creating a console event listener includes the following:

▼ To Create a Console Event Listener

- 1 Write a console event listener class or implement the default methods in the AMConsoleListenerAdapter class.
- 2 Compile the code.
- 3 Register the listener in the Administration Service.

Access Manager includes a sample implementation of the ConsoleEventListener. The Sun Java System Access Manager 7.1 2006Q4 Java API Reference also contains more detailed information on the listener interfaces and class.

Precompiling the Console JSP

Each JSP is compiled when it is first accessed. Because of this, there is a delay when displaying the HTML page on the browser. To avoid this delay, the system administrator can precompile the JSP by running the following command:

WebServer_install_directory/servers/bin/https/bin/jspc -webapp AccessManager-base/SUNWam/web-src/services

where, by default, WebServer_install_directory is /opt/SUNWwbsvr.

Console Samples

Sample files have been included to help understand how the Access Manager console can be customized. The samples include instructions on how to:

Modify User Profile Page

This sample modifies the user interface by adding a hyperlink that allows an existing user to change their configured password. It is in the ChangeUserPassword directory.

Create A Tabbed Identity Management Display

This sample creates a custom user profile which displays the profile with three tabs. The sample is in the UserProfile directory.

ConsoleEventListener

This sample displays the parameters passed to AMConsoleListener class in the amConsole debug file. It is in the ConsoleEventListener directory.

Add Administrative Function

This sample adds functionality to the Identity Management module that allows an administrator to move a user from one organization to other. It is in the MoveUser directory.

Add A New Module Tab

This sample adds a new tab into the Header frame. This tab will connect to an external application and can be configured using the console. It is in the NewTab directory.

Create A Custom User Profile View

This sample creates a custom user profile view to replace the default user profile view. A different user profile view can be created for each configured organization. A custom class would need to be written that extends the default user profile view bean. This class would then be registered in the User Profile Display Class attribute of the Administration Service. There is an example of how to do this in the samples directory. This sample is in the UserProfile directory.

These samples are located in *AccessManager-base*/SUNWam/samples/console. Open the README file in this directory for general instructions. Each specific sample directory also contains a README file with instructions relevant to that sample.

Note – The console samples are only available when Access Manager is installed on the Solaris $^{\text{TM}}$ operating system.

♦ ♦ ♦ CHAPTER 12

Customizing the Authentication User Interface

The Authentication Service provides the web-based Graphical User Interface (GUI) for all default and custom authentication modules installed in the Sun Java™ System Access Manager 7.1 deployment. This interface provides a dynamic and customizable means for gathering authentication credentials by presenting the web-based login requirement pages to a user requesting access.

The Authentication Service GUI is built on top of JATO (J2EE Assisted Take-Off), a Java 2 Enterprise Edition (J2EE) presentation application framework. This framework is used to help developers build complete functional Web applications. You can customize this user interface per client type, realm, locale, or service.

For more information about what the Authentication Service does and how it works, see Chapter 3, "Authentication," in *Sun Java System Access Manager 7.1 Technical Overview* and Chapter 11, "Deploying a Distributed Authentication UI Server," in *Sun Java System Access Manager 7.1 Postinstallation Guide*.

The following topics are covered in this chapter:

- "User Interface Files You Can Modify" on page 167
- "Customizing Branding and Functionality" on page 177
- "Customizing the Self-Registration Page" on page 179
- "Updating and Redeploying services.war" on page 181
- "Customizing the Distributed Authentication User Interface" on page 183

User Interface Files You Can Modify

The authentication GUI dynamically displays the required credentials information depending upon the authentication module invoked at run time. The "User Interface Files You Can Modify" on page 167 lists the types of files you can modify to convey custom representations of Login pages, Logout pages, and error messages. Detailed information is provided in following sections.

TABLE 12-1 Authentication User Interface Files and Their Locations at Installation

File Type	Default Location
"Staging Area for Files to be Customized" on page 168	AccessManager-base/SUNWam/web-src/services
"Java Server Pages" on page 169	$Access Manager-base/{\tt SUNWam/web-src/services/config/auth/default}$
"XML Files" on page 171	$Access Manager-base/{\tt SUNWam/web-src/services/config/auth/default}$
"JavaScript Files" on page 174	AccessManager-base/SUNWam/web-src/services/js
"Cascading Style Sheets" on page 175	<pre><accessmanager-base css<="" pre="" services="" sunwam="" web-src=""></accessmanager-base></pre>
"Images" on page 175	AccessManager-base/SUNWam/web-src/services/login_images
"Localization Files" on page 176	AccessManager-base/SUNWam/locale

To access the default Login page, use the following URL:

To access the default Logout page, use the following URL:

Staging Area for Files to be Customized

When Access Manager is installed, a staging area exists in the following location:

AccessManager-base/SUNWam/web-src/services

This directory content is identical to the content of the services.war.

The AccessManager-base/SUNWam/web-src/services contains all the files you need to modify the authentication GUI. When you install Access Manager on Sun Java System Application Server, on Sun Java System Web Server, or on BEA WebLogic Web Server, services.war (the services web application) is automatically installed and deployed.

If you install Access Manager on other web containers, you may have to manually deploy services, war. See the documentation that comes with the web container.

Once you've modified the authentication GUI files in the staging area, in order to see the changes in the actual GUI, you must update and then redeploy services.war. See "Updating and Redeploying services.war" on page 181.

Java Server Pages

All authentication GUI pages are . jsp files with embedded JATO tags. You do not need to understand JATO to customize Access Manager GUI pages. Java server pages handle both the UI elements and the disciplines displayed through peer ViewBeans. By default, JSP pages are installed in the following directory:

AccessManager-base/SUNWam/web-src/services/config/auth/default

Java server pages are looked up from the deployed location. In previous Access Manager versions, the Java server pages were looked up from the installed location.

Customizing the Login Page

The Login page is a common Login page used by most authentication modules except for the Membership module. For all other modules, at run time the Login page dynamically displays all necessary GUI elements for the required credentials. For example, the LDAP authentication module Login page dynamically displays the LDAP module header, LDAP User name, and Password fields.

You can customize the following Login page UI elements:

- Module Header text
- User Name label and field
- Password label and field
- Choice value label and field.
 The field is a radio button by default, but can be change to a check box.
- Image (at the module level)
- Login button

Customizing JSP Templates

Use the JSP templates to customize the look and feel presented in the graphical user interface (GUI). "Customizing JSP Templates" on page 169 provides descriptions of templates you can customize. The templates are located in the following directory:

AccessManager-base/SUNWam/web-src/services/config/auth/default

TABLE 12-2 Customizable JSP Templates

File Name	Purpose
account_expired.jsp	Informs the user that their account has expired and should contact the system administrator.

TABLE 12-2 Customizable JSP Templates	(Continued)
File Name	Purpose
auth_error_template.jsp	Informs the user when an internal authentication error has occurred. This usually indicates an authentication service configuration issue.
authException.jsp	Informs the user that an error has occurred during authentication.
configuration.jsp	Configuration error page that displays during the Self-Registration process.
disclaimer.jsp	This is a customizable disclaimer page used in the Self-registration authentication module.
Exception.jsp	Informs the user that an error has occurred.
invalidAuthlevel.jsp	Informs the user that the authentication level invoked was invalid.
invalid_domain.jsp	Informs the user that no such domain exists.
invalidPassword.jsp	Informs the user that the password entered does not contain enough characters.
invalidPCookieUserid.jsp	Informs the user that a persistent cookie user name does not exist in the persistent cookie domain.
Login.jsp	This is a Login/Password template.
login_denied.jsp	Informs the user that no profile has been found in this domain.
<pre>login_failed_template.jsp</pre>	Informs the user that authentication has failed.
Logout.jsp	Informs the user that they have logged out.
maxSessions.jsp	Informs the user that the maximum sessions have been reached.
membership.jsp	A login page for the Self-registration module.
Message.jsp	A generic message template for a general error not defined in one of the other error message pages.
missingReqField.jsp	Informs the user that a required field has not been completed.
module_denied.jsp	Informs the user that the user does not have access to the module.
<pre>module_template.jsp</pre>	A customizable module page.
new_org.jsp	This page is displayed when a user with a valid session in one organization wants to login to another organization.
noConfig.jsp	Informs the user that no module configuration has been defined.
noConfirmation.jsp	Informs the user that the password confirmation field has not been entered.
noPassword.jsp	Informs the user that no password has been entered.

TABLE 12-2 Customizable JSP Templates	(Continued)
File Name	Purpose
noUserName.jsp	Informs the user that no user name has been entered. It links back to the login page.
noUserProfile.jsp	Informs the user that no profile has been found. It gives them the option to try again or select New User and links back to the login page.
org_inactive.jsp	Informs the user that the organization they are attempting to authenticate to is no longer active.
passwordMismatch.jsp	This page is called when the password and confirming password do not match.
profileException.jsp	Informs the user that an error has occurred while storing the user profile.
Redirect.jsp	This page carries a link to a page that has been moved.
register.jsp	A user self-registration page.
session_timeout.jsp	Informs the user that their current login session has timed out.
userDenied.jsp	Informs the user that they do not possess the necessary role (for role-based authentication.)
userExists.jsp	This page is called if a new user is registering with a user name that already exists.
user_inactive.jsp	Informs the user that they are not active.
userPasswordSame.jsp	Called if a new user is registering with a user name field and password field have the same value.
wrongPassword.jsp	Informs the user that the password entered is invalid.

XML Files

XML files describe the authentication module-specific properties based on the Authentication Module Properties DTD file: $AccessManager-base/SUNWam/Auth_Module_Properties.dtd$. Access Manager defines required credentials and callback information for each of the default authentication modules. By default, Authentication XML files are installed in the following directory:

AccessManager-base/SUNWam/web-src/services/config/auth/default The table "XML Files" on page 171 provides descriptions of the authentication module configuration files.

XML files are looked up from the deployed location. In previous Access Manager versions, the XML files were looked up from the installed location.

TABLE 12-3 List of Authentication Module Configuration Files

File Name	Purpose
AD.xml	Defines a Login screen for use with Active Directory authentication.
Anonymous.xml	For anonymous authentication, although there are no specific credentials required to authenticate.
Application.xml	Needed for application authentication.
Cert.xml	For certificate-based authentication although there are no specific credentials required to authenticate.
HTTPBasic.xml	Defines one screen with a header only as credentials are requested via the user's web browser.
JDBC.xml	Defines a Login screen for use with Java Database Connectivity (JDBC) authentication.
LDAP.xml	Defines a Login screen, a Change Password screen and two error message screens (Reset Password and User Inactive).
Membership.xml	Default data interface which can be used to customize for any domain.
MSISDN.xml	Defines a Login screen for use with Mobile Subscriber ISDN (MSISDN).
NT.xml	Defines a Login screen.
RADIUS.xml	Defines a Login screen and a RADIUS Password Challenge screen.
SafeWord.xml	Defines two Login screens: one for User Name and the next for Password.
SAML.xml	Defines a Logins screen for Security Assertion Markup Language (SAML) authentication.
SecurID.xml	Defines five Login screens including UserID and Passcode, PIN mode, and Token Passcode.
Unix.xml	Defines a Login screen and an Expired Password screen.

Callbacks Element

The Callbacks element is used to define the information a module needs to gather from the client requesting authentication. Each Callbacks element signifies a separate screen that can be called during the authentication process.

Nested Elements

The following table describes nested elements for the Callbacks element.

Element	Required	Description
NameCallback	*	Requests data from the user; for example, a user identification.
PasswordCallback	*	Requests password data to be entered by the user.
ChoiceCallback	*	Used when the application user must choose from multiple values.
ConfirmationCallback	*	Sends button information such as text which needs to be rendered on the module's screen to the authentication interface.
HttpCallback	*	Used by the authentication module with HTTP-based handshaking negotiation.
SAMLCallback		Used for passing either Web artifact or SAML POST response from SAML service to the SAML authentication module when this module requests for the respective credentials. This authentication module behaves as SAML recipient for both (Web artifact or SAML POST response) and retrieves and validates SAML assertions.

Attributes

The following table describes attributes for the Callbacks element.

length	The number or length of callbacks.
order	Is the sequence of the group of callbacks.
timeout	Number of seconds the user has to enter credentials before the page times out. Default is 60 .
template	Defines the UI .jsp template name to be displayed.
image	Defines the UI or page-level image attributes for the UI customization
header	Text header information to be displayed on the UI. Default is Authentication.

error

Indicates whether authentication framework/module needs to terminate the authentication process. If yes, then the value is true. Default is false.

ConfirmationCallback Element

The ConfirmtationCallback element is used by the authentication module to send button information for multiple buttons. An example is the button text which must be rendered on the UI page. The ConfirmationCallback element also receives the selected button information from the UI.

Nested Element

ConfirmationCallback has one nested element named OptionValues. The OptionValues element provides a list or an array of button text information to be rendered on the UI page.OptionValues takes no attributes.

If there is only one button on the UI page, then the module is not required to send this callback. If ConfirmationCallback is not provided through the Authentication Module properties XML file, then anAuthUI.properties will be used to pick and display the button text or label for the Login button. anAuthUI.properties is the global UI i18n properties file for all modules.

Callbacks length value should be adjusted accordingly after addition of the new callback.

Example:

JavaScript Files

JavaScript files are parsed within the Login.jsp file. You can add custom functions to the JavaScript files in the following directory: *AccessManager-base/*SUNWam/web-src/services/js

.

The Authentication Service uses the following JavaScript files:

auth.js Used by Login.jsp for parsing all module files to display login

requirement screens.

browserVersion.js Used by Login.jsp to detect the client type.

Cascading Style Sheets

To define the look and feel of the UI, modify the cascading style sheets (CSS) files. Characteristics such as fonts and font weights, background colors, and link colors are specified in the CSS files. You must choose the appropriate . css file for your browser in order to customize the look and feel on the User Interface.

In the appropriate . css file, change the background-color attribute. Examples:

```
.button-content-enabled { background-color:red; }
button-link:link, a.button-link:visited { color: #000;
background-color: red;
text-decoration: none; }
```

A number of browser-based CSS files are installed with Access Manager in the following directory:

AccessManager-base/SUNWam/web-src/services/css.

The following table provides a brief description of each CSS file.

TABLE 12-4 Cascading Style Sheets

File Name	Purpose
css_generic.css	Configured for generic web browsers.
css_ie5win.css	Configured specifically for Microsoft $^{\circ}$ Internet Explorer v.5 for Windows $^{\circ}$.
css_ns4sol.css	Configured specifically for Netscape $^{\text{TM}}$ Communicator v. 4 for Solaris $^{\text{TM}}.$
css_ns4win.css	Configured specifically for Netscape Communicator v.4 for Windows.
styles.css	Used in JSP pages as a default style sheet.

Images

The default authentication GUI is branded with Sun Microsystems, Inc. logos and images. By default, the GIF files are installed in the following directory:

SUNWam/web-src/services/login_images

These images can be replaced with images relevant to your company. The following table provides a brief description for each GIF image used for the default GUI.

TABLE 12-5 Sun Microsystems Branded GIF Images

File Name	Purpose
Identity_LogIn.gif	Sun Java System Access Manager banner across the top.
Registry_Login.gif	No longer used.
bannerTxt_registryServer.gif	No longer used.
logo_sun.gif	Sun Microsystems logo in the upper right corner.
spacer.gif	A one pixel clear image used for layout purposes.
sunOne.gif	Sun Java System logo in the lower right corner.

Localization Files

Localization files are located in the following directory: AccessManager-base/SUNWam/locale

These are i18n properties files global to the Access Manager instance. A localization properties file, also referred to as an *i18n* (*internationalization*) properties file specifies the screen text and error messages that an administrator or user will see when directed to an authentication module's attribute configuration page. Each authentication module has its own properties file that follows the naming format amAuthmodulename.properties; for example, amAuthLDAP.properties. They are located in *AccessManager-base*/SUNWam/locale/. The default character set is ISO-8859-1 so all values are in English, but Java applications can be adapted to various languages without code changes by translating the values in the localization properties file.

The following table summarizes the localization properties files configured for each module. These files can be found in *AccessManager-base/SUNWam/locale*.

TABLE 12-6 List of Localization Properties Files

File Name	Purpose
amAuth.properties	Defines the parent Core Authentication Service.
amAuthAD.properties	Defines the Active Directory Authentication Module.
amAuthAnonymous.properties	Defines the Anonymous Authentication Module.
amAuthApplication.properties	For Access Manager internal use only. Do not remove or modify this file.
amAuthCert.properties	Defines the Certificate Authentication Module.
amAuthConfig.properties	Defines the Authentication Configuration Module.

TABLE 12-6 List of Localization Properties Files	(Continued)
File Name	Purpose
amAuthContext.properties	Defines the localized error messages for the AuthContext Java class.
amAuthContextLocal.properties	For Access Manager internal use only. Do not remove or modify this file.
amAuthHTTPBasic.properties	Defines the HTTP Basic Authentication Module.
amAuthJDBC.properties	Defines the Java Database Connectivity (JDBC) Authentication Module.
amAuthLDAP.properties	Defines the LDAP Authentication Module.
amAuthMembership.properties	Defines the Membership Authentication Module.
amAuthMSISDN.properties	Defines the Mobile Subscriber ISDN Authentication Module.
amAuthNT.properties	Defines the Windows NT Authentication Module.
amAuthRadius.properties	Defines the RADIUS Authentication Module.
amAuthSafeWord.properties	Defines the Safeword Authentication Module.
amAuthSAML.properties	Defines the Security Assertion Markup Language (SAML) Authentication Module.
amAuthSecurID.properties	Defines the SecurID Authentication Module.
amAuthUI.properties	Defines labels used in the authentication user interface.
amAuthUnix.properties	Defines the UNIX Authentication Module.

Customizing Branding and Functionality

You can modify JSP templates and module configuration properties files to reflect branding or functionality specified for any of the following:

- Organization of the request
- SubOrganization of the request.
- Locale of the request
- Client Path
- Client Type information of the request
- Service Name (serviceName)

▼ To Modify Branding and Functionality

1 Go to the directory where default JSP templates are stored.

cd AccessManager-base/SUNWam/web-src/services/config/auth

2 Create a new directory.

Use the appropriate customized directory path based on the level of customization. Use the following forms:

```
org_locale/orgPath/filePath
  org/orgPath/filePath
  default_locale/orgPath/filePath
  default/orgPath/filePath
```

In these examples,

orgPath represents subOrg1/subOrg2

filePath represents clientPath + serviceName

clientPath represents clientType/sub-clientType

In these paths, SubOrg, Locale, Client Path, Service Name (which represents orgPath and filePath) are optional. The organization name you specify may match the organization attribute set in the Directory Server. For example, if the organization attribute value is SunMicrosystems, then the organization customized directory should also be SunMicrosystems. If no organization attribute exists, then use the lowercase value of the organization name (sunmicrosystems).

For example, for the following attributes:

```
org = SunMicrosystems
locale = en
subOrg = solaris
clientPath = html/ customerName/
serviceName = paycheck
customized directory paths would be:
SunMicrosystems_en/solaris/html/ customerName / paycheck
SunMicrosystems/solaris/html/ customerName / paycheck
default_en/solaris/html/ customerName/paycheck
default/solaris/html/ customerName / paycheck
```

3 Copy the default templates.

to the new directory:

Copy all the JSP templates (*.jsp) and authentication module configuration properties XML files (*.xml) from the default directory:

 $Access Manager-base \verb|/SUNWam/web-src/services/config/auth/default|$

AccessManager-base /SUNWam/web-src/services/config/ auth/CustomizedDirectoryPath

4 Customize the files in the new directory.

The files in the new directory can be customized if necessary, but not this is not required. See "Customizing the Login Page" on page 169 and "Customizing JSP Templates" on page 169 for information on what you can modify.

5 Update and redeploy services.war.

Once you've modified the authentication GUI files, in order to see the changes in the actual GUI, you must update and then redeploy services.war. See "Updating and Redeploying services.war" on page 181 in this chapter for instructions. See Chapter 10 for general information on updating and redeploying Access Manager .war files.

6 Restart both Access Manager and the web container server.

Customizing the Self-Registration Page

You can customize the Self-registration page which is part of Membership authentication module. The default data and interface provided with the Membership authentication module is generic and can work with any domain. You can configure it to reflect custom data and information. You can add custom user profile data or fields to register or to create a new user.

▼ To Modify the Self-Registration Page

1 Customize the Membership.xml file.

By default, the first three data fields are required in the default Membership Module configuration:

- User name
- User Password
- Confirm User Password

You can specify which data is requested, which is required, and which is optional. The sample below illustrates how to add a telephone number as requested data.

You can specify or add data which should be requested from a user as part of the User Profile. By default you can specify or add any attributes from the following objectClasses:

- top
- person
- organizationalPerson
- inetOrgPerson
- iplanet-am-user-service
- inetuser

Administrators can add their own user attributes to the User Profile.

2 Update and redeploy services.war.

Once you've modified the authentication GUI files, in order to see the changes in the actual GUI, you must update and then redeploy services.war. See "Updating and Redeploying services.war" on page 181 in this chapter for instructions. See Chapter 10 for general information on updating and redeploying Access Manager.war files.

3 Restart both Access Manager and the web container server.

```
<Callbacks length="9" order="16" timeout="300"
header="Self Registration" template="register.jsp" >
   <NameCallback isRequired="true" attribute="uid" >
   <Prompt> User Name: </Prompt>
   </NameCallback>
   <PasswordCallback echoPassword="false" isReguired="true"</pre>
                attribute="userPassword" >
   <Prompt> Password: </Prompt>
   </PasswordCallback>
   <PasswordCallback echoPassword="false" isRequired="true" >
   <Prompt> Confirm Password: </Prompt>
   </PasswordCallback>
   <NameCallback isRequired="true" attribute="givenname" >
   <Prompt> First Name: </Prompt>
   </NameCallback>
   <NameCallback isRequired="true" attribute="sn" >
   <Prompt> Last Name: </Prompt>
   </NameCallback>
   <NameCallback isRequired="true" attribute="cn" >
   <Prompt> Full Name: </Prompt>
   </NameCallback>
```

```
<NameCallback attribute="mail" >
    <Prompt> Email Address: </Prompt>
    </NameCallback>
<NameCallback isRequired="true"attribute="telphonenumber">
<Prompt> Tel:</Prompt>
</NameCallback>
    <ConfirmationCallback>
        <OptionValues>
        <OptionValue>
        <Value> Register </Value>
        </OptionValue>
        <OptionValue>
        <Value> Cancel </Value>
        </OptionValue>
        </OptionValues>
    </ConfirmationCallback>
</Callbacks>
```

Updating and Redeploying services.war

If Access Manager is installed on BEA WebLogic, IBM WebSphere, or Sun ONE Application Server, you must update and redeploy services.war before you can see any changes in the user interface. Once you've made changes to the authentication GUI files, regardless of the brand of web container you're using, it is a good practice to update and redeploy the services.war file. When you update and redeploy services.war, you overwrite the default GUI files with your changes, and the changed files are placed in their proper locations. The section "Staging Area for Files to be Customized" on page 168 provides background information on this file.

▼ To Update services.war

1 cd AccessManager-base/SUNWam This is the directory in which the WARs are kept. **2 jar-uvf** *WARfilename.***war** < *path_to_modified_file*>

The -uvf option replaces the old file with the newly modified file. For example:

```
jar -uvf services.war newfile/index.html
```

replaces the index.html file in console.war with the index.html file located in *AccessManager-base*/SUNWam/newfile.

3 rm newfile/index.html
Deletes the modified file

To Redeploy services.war

The services.war will be in the following directory:

AccessManager-base/SUNWam

Depending upon the brand of web container you are using, execute one of the following commands.

On BEA WebLogic

```
java weblogic.deploy -url ServerURL -component
    {ServerDeployURI}: { WL61 Server}
    deploy WL61AdminPassword {ServerDeployURI }
```

{AccessManager-base}/{SUNWam}/services.war

In this example,

ServerURL uses the form protocol:// host:port

Example: http://abc.com:58080

ServerDeployURI represents the server Universal Resource Identifier

Example: amserver

WL61 Server represents the Weblogic Server nam.e

Example: name.com

On Sun ONE Application Server

```
ServerDeployURI --name amserver --instance IAS7Instance {AccessManager-base}/{SUNWam}/services.war
```

On IBM WebSphere

See the deployment documentation that comes with the IBM WebSphere product:

http://www-3.ibm.com/software/webservers/studio/doc/v40/studioguide/en/html/sdsscenario1.html (http://www-3.ibm.com/software/webservers/studio/doc/v40/studioguide/en/html/sdsscenario1.html)

Customizing the Distributed Authentication User Interface

Access Manager provides a remote Authentication user interface component to enable secure, distributed authentication across two firewalls. You can install the remote authentication user interface component on any servlet-compliant web container within the non-secure layer of an Access Manager deployment. The remote component works with Authentication client APIs and authentication utility classes to authenticate web users. The remote component is customizable and uses a JATO presentation framework.

For detailed information on how Distributed Authentication works, see "Distributed Authentication User Interface" in *Sun Java System Access Manager 7.1 Technical Overview* and Chapter 11, "Deploying a Distributed Authentication UI Server," in *Sun Java System Access Manager 7.1 Postinstallation Guide*.

Once the Distributed Authentication component is installed and deployed, you can modify the JSP templates and module configuration properties files to reflect branding and specific functionality for any of the following:

Organization/SubOrganization This is the organization or sub-organization of the request.

Locale of the request.

Client Path Client Type information of the request.

Service Name (serviceName) Service name for service-based authentication.

▼ To Customize the Distributed Authentication User Interface

Before You Begin

The Distributed Authentication User Interface package must already be installed. For detailed installation instructions, see "Installing and Configuring a Distributed Authentication UI Server" in Sun Java System Access Manager 7.1 Postinstallation Guide.

- 1 Explode the Distributed Authentication User Interface WAR.
- 2 At the command line, go to the directory where the default JSP templates are stored. Example:

cd DistributedAuth-base/config/auth

where *DistributedAuth-base* is the directory where the Distributed Authentication User Interface package is exploded.

3 Create a new directory using the appropriate directory path based on the level of customization.

Use the following form:

```
org_locale/orgPath/filePath
    org/orgPath/filePath
    default_locale/orgPath/filePath
    default/orgPath/filePath
```

where:

```
orgPath = subOrg1/subOrg2
    filePath = clientPath + serviceName
    clientPath = clientType/sub-clientType
```

The following are optional: Sub-org, Locale, Client Path, and Service Name. In the following example, orgPath and filePath are optional.

For example, given the following:

```
org = iplanet
locale = en
subOrg = solaris
clientPath = html/nokia/
serviceName = paycheck
```

the appropriate directory paths for the above are:

```
iplanet_en/solaris/html/nokia/paycheck
iplanet/solaris/html/nokia/paycheck
default_en/solaris/html/nokia/paycheck
default/solaris/html/nokia/paycheck
```

4 Copy all the JSP templates and authentication module configuration properties XML files from the default directory to the new directory.

```
cp DistributedAuth-base/config/auth/default/*.xml
    DistributedAuth-base/config/auth/new_directory_path
```

- 5 (Optional) Modify the files in the new directory to suit your needs.
 - For information about customizing the . jsp files, see "Java Server Pages" on page 169.
 - For information about customizing the .xml files, "XML Files" on page 171.
- **6 Create a new** .WAR **file named** amauthdistui deploy .war **from** *DistributedAuth-base*.
- 7 Deploy amauthdistui deploy.war.

The web container administrator deploys the file in the remote web container.

Index

A	Authentication Service (Continued)
administration console	login page, customizing, 169
accessing the console, 155	pluggable JAAS Module, 40
APIs, 163	post processing SPI, 56-61
code samples, list of, 164-165	self-registration page, customizing, 179-181
customizing, 155-163	user ID, generating, 61-63
event listener, 163	XML files, 171-174
legacy mode, 153-155	authorization, See Policy Service
plug-in modules, 155	·
AdminUtils, 135	
AMClientDetector, 135	
AMLoginModule, extending, 39-40	C
AMPasswordUtil, 135-136	CertLogin, 45-46
Authentication Service	classpath requirements, 16
AMLoginModule, 39-40	client APIs, See client SDK
APIs and SPIs, 35-42	client detection
cascading style sheets, 175	APIs, 133-134
CertLogin example, 45-46	data types, 132-133
custom authentication module, 47-56	defined, 129-131
customizing branding and functionality, 177-179	enabling, 129-131
customizing the user interface, 167-185	client identity, 30-31
distributed authentication user interface, 183-185	client SDK, 15-33, 22-30
files you can modify, 167-177	sample files, 32
image files, 175-176	setting up a client identity, 30-31
IndexName, 36-37	targets, 32
JAAS module, 64-68	console, See administration console
Java Server Pages, 169-171	custom authentication module, 47-56
JavaScript files, 174	
JCDI module example, 46	
JSP templates, 169-171	_
LDAPLogin example, 45	D
localization files, 176-177	Debug utility, 136

distributed authentication user interface, See Authentication Service documentation related Access Manager books, 11-13 related Sun JES books, 13	N notification defined, 139-142 enabling, 139-142
IndexName values, 36-37 initializing, 22-30 installing, 16-22	password API plug-ins, 137 password.war, 147 plug-in, Policy APIs, 74-75 policy evaluation program, 89-90 Policy Service adding policy-enabled service, 78-82 APIs, overview, 69-75
J JAAS authentication module, 64-68 authorization framework, 97-104 enabling authorization framework, 102-104 JS2E access controller, 101 pluggable authentication module, 40 JCDI module, 46	code samples, 75-78 conditions, customizing, 82-87 evaluation classes, 71-74 Java packages, 70 management classes, 70-71 plug-in APIs, 74-75 policy evaluation program, 89-90 referrals, customizing, 82-87 subjects, customizing, 82-87 post processing SPI, authentication, 56-61
L LDAPLogin, 45 legacy mode, administration console, 153-155 Locale utility, 136 log verifier plug-in, 127-128	R redeploying WARs, 149-151 response provider, 82-87
logging log authorization plug-in, 128 log verifier plug-in, 127-128 reading log records, 115-121 remote logging application, 122-124 sample programs, 113 secure logging, 128 to second Access Manager server, 124 writing log records, 114-115	self-registration page, customizing, 179-181 services.war, 147-148 services.war content and staging area, 168 updating and redeploying, 181-183 Session Service APIs, See Single Sign-On Single Sign-On APIs, 105-112 code samples, list of, 106-112 non-web based applications, 112

```
SSO, See Single Sign-On SystemProperties, 136
```

Т

ThreadPool, 136-137

U

updating WARs, 148
utilities
AdminUtils, 135
AMClientDetector, 135
AMPasswordUtil, 135-136
APIs, 135-137
Debug, 136
Locale, 136
password API plug-ins, 137
SystemProperties, 136
ThreadPool, 136-137

W

WARs redeploying, 149-151 updating, 148 WARs in Access Manager, 144-148