# Uninstalling xCAT2.0 04/24/2008

#### **Table of Contents**

1.0 Removing xCAT2.0.	1
1.1 Backup you xCAT database ( if you want to keep it)	
1.2 Stop xcatd	
1.3 Remove xCAT rpms	
1.4 Remove OSS prerequisites installed for xCAT.	1
1.5 Remove xCAT ssh keys and credentials.	2
1.6 Remove xCAT data directories.	
1.7 Remove xCAT install Directories	2
1.8 Extraneous files.	
1.9 Remove Postgresql Database (if using Service Nodes)	

## 1.0 Removing xCAT2.0

#### 1.1 Backup you xCAT database (if you want to keep it)

dumpxCATdb -p <path to where to save the database>

## 1.2 Stop xcatd

Service xcatd stop

# 1.3 Remove xCAT rpms

- rpm -e xCAT-2.0
- rpm -e xCAT-server-2.0
- rpm -e xCAT-client-2.0
- rpm -e perl-xCAT-2.0
- rpm -e xCAT-nbroot-oss-x86-64
- rpm -e xCAT-nbroot-core-x86 64
- rpm -e xCAT-nbkernel-x86 64

## 1.4 Remove OSS prerequisites installed for xCAT

- rpm -e fping-2.2b1-1
- rpm -e perl-Digest-MD5-2.36-1
- rpm -e perl-Net SSLeay.pm-1.30-1

- rpm -e perl-IO-Socket-SSL-1.06-1
- rpm -e perl-IO-Stty-.02-1
- rpm -e perl-IO-Tty-1.07-1
- rpm -e perl-Expect-1.21-1
- rpm -e conserver-8.1.16-2
- rpm -e expect-5.42.1-3
- rpm -e tk-8.4.7-3
- rpm -e tcl-8.4.7-3
- rpm -e perl-DBD-SQLite-1.13-1
- rpm -e perl-DBI-1.55-1

#### 1.5 Remove xCAT ssh keys and credentials

- rm -rf \$ROOTHOME/ssh
- rm -rf \$ROOTHOME/.xcat

#### 1.6 Remove xCAT data directories

- rm -rf /install
- rm -rf /tftpboot/xcat\*
- rm -rf /etc/xcat
- rm -rf /etc/sysconfig/xcat ( may not exist)

#### 1.7 Remove xCAT install Directories

• rm -rf \$ROOTHOME/xcat2

#### 1.8 Extraneous files

- /tmp/genimage\*
- /tmp/packimage\*
- /tmp/mknb\*

## 1.9 Remove Postgresql Database ( if using Service Nodes)

- su postgres
- dropdb -h 11.16.0.1 -i -e --username xcatadmin xcatdb
- Database "xcatdb" will be permanently removed.
- Are you sure? (y/n) y
- Password:
- DROP DATABASE xcatdb;
- DROP DATABASE
- service postgresql stop