# **Niftyswap Specification**

\* Certain sections of this document were taken directly from the <u>Uniswap</u> documentation.

# **Table of Content**

- Overview
- Contracts
  - NiftyswapExchange.sol
  - NiftyswapFactory.sol
- Contract Interactions
  - Exchanging Tokens
  - Managing Reserves Liquidity
- Price Calculations
- <u>Assets</u>
  - o Base Currency
  - Tokens
- Trades
  - Base Currency to Token i
  - Token i to Base Currency
- Liquidity Reserves Management
  - o Adding Liquidity
  - Removing Liquidity
- Data Encoding
  - baseToToken()
  - o tokenToBase()
  - addLiquidity()
  - removeLiquidity()
  - Relevant Methods
    - getBaseTokenReserves()
    - getPrice baseToToken()
    - getPrice tokenToBase()
    - getTokenAddress()
    - getBaseTokenInfo()
- Miscellaneous
  - Rounding Errors

# **Overview**

Niftyswap is a fork of <u>Uniswap</u>, a protocol for automated token exchange on Ethereum. While Uniswap is for trading <u>ERC-20</u> tokens, Niftyswap is a protocol for <u>ERC-1155</u> tokens. Both are designed to favor ease of use and provide guaranteed access to liquidity on-chain.

Most exchanges maintain an order book and facilitate matches between buyers and sellers. Niftyswap smart contracts hold liquidity reserves of various tokens, and trades are executed directly against these reserves. Prices are set automatically using the constant product x \* y = K market maker mechanism, which keeps overall reserves in relative equilibrium. Reserves are pooled between a network of liquidity providers who supply the system with tokens in exchange for a proportional share of transaction fees.

An important feature of Nitfyswap is the utilization of a factory/registry contract that deploys a separate exchange contract for each ERC-1155 token contract. These exchange contracts each hold independent reserves of a single fungible ERC-1155 base currency and their associated ERC-1155 token id. This allows trades between the <u>Base Currency</u> and the ERC-1155 tokens based on the relative supplies.

This document outlines the core mechanics and technical details for Niftyswap.

## **Contracts**

#### NiftyswapExchange.sol

This contract is responsible for permitting the exchange between a single base currency and all tokens in a given ERC-1155 token contract. For each token id i, the NiftyswapExchance contract holds a reserve of base currency and a reserve of token id i, which are used to calculate the price of that token id i denominated in the base currency.

### NiftyswapFactory.sol

This contract is used to deploy a new NiftyswapExchange.sol contract for ERC-1155 contracts without one yet. It will keep a mapping of each ERC-1155 token contract address with their corresponding NiftyswapExchange.sol contract address.

# **Contract Interactions**

All methods should be free of arithmetic overflows and underflows.

Methods for exchanging tokens and managing reserves liquidity are all called internally via the ERC-1155 onercontent on the four methods that can be called via onercontent on the four methods that can be called via onercontent of the safe against re-entrancy attacks.

The first 4 bytes of the \_data argument indicate which of the four main <u>NiftyswapExchange.sol</u> methods to call. How to build and encode the \_data payload for the respective methods is explained in the <u>Data Encoding</u> section.

# **Exchanging Tokens**

In NiftyswapExchange.sol, there are two methods for exchanging tokens:

```
/**
* @notice Convert Base Tokens to Tokens id and transfers Tokens to recipient.
 * @dev User specifies MAXIMUM inputs ( maxBaseTokens) and EXACT outputs.
* @dev Assumes that all trades will be successful, or revert the whole \mathsf{tx}
* @dev Sorting IDs can lead to more efficient trades with some ERC-1155 implementations
                    Array of Tokens ID that are bought
* @param tokenIds
* @param tokensBoughtAmounts Amount of Tokens id bought for each id in tokenIds
* @param maxBaseTokens Total maximum amount of base tokens to spend for whole
trade
* @param deadline
                            Block # after which this tx can no longer be executed.
* @param recipient
                            The address that receives output Tokens.
*/
function baseToToken(
 uint256[] memory tokenIds,
 uint256[] memory tokensBoughtAmounts,
 uint256 maxBaseTokens,
 uint256 deadline,
 address recipient)
 internal nonReentrant();
* @notice Convert Tokens id to Base Tokens and transfers Tokens to recipient.
* @dev User specifies EXACT Tokens id sold and MINIMUM Base Tokens received.
* @dev Assumes that all trades will be valid, or the whole tx will fail
 * @param tokenIds
                    Array of Token IDs that are sold
* @param tokensSoldAmounts Array of Amount of Tokens sold for each id in tokenIds.
 * @param deadline
                         Block # after which this tx can no longer be executed.
 * @param recipient
                         The address that receives output Base Tokens.
```

```
function _tokenToBase(
  uint256[] memory _tokenIds,
  uint256[] memory _tokensSoldAmounts,
  uint256 _minBaseTokens,
  uint256 _deadline,
  address _recipient)
  internal nonReentrant();
```

# **Managing Reserves Liquidity**

In NiftyswapExchange.sol, there are two methods for managing token reserves supplies:

```
/**
 * @notice Deposit max Base Tokens & exact Tokens at current ratio to get share tokens.
 * @dev min liquidity does nothing when total NIFTY liquidity token supply is 0.
 * @dev Assumes that sender approved this contract on the baseToken
* @param provider
                      Address that provides liquidity to the reserve
* @param tokenIds
                       Array of Token IDs where liquidity is added
* @param tokenAmounts Array of amount of Tokens deposited for ids in tokenIds
 * @param maxBaseTokens Array of maximum number of tokens deposited for ids in
_tokenIds.
                        Deposits max amount if total NIFTY supply is 0.
* @param deadline
                       Block # after which this transaction can no longer be executed.
* /
function addLiquidity(
 address provider,
 uint256[] memory tokenIds,
 uint256[] memory tokenAmounts,
 uint256[] memory maxBaseTokens,
 uint256 deadline)
 internal nonReentrant();
* @dev Burn liquidity pool tokens to withdraw Base Tokens && Tokens at current ratio.
* @param provider
                         Address that removes liquidity to the reserve
* @param _tokenIds
                          Array of Token IDs where liquidity is removed
* @param poolTokenAmounts Array of Amount Niftyswap shared burned for ids in tokenIds.
 * @param _minTokens Minimum Tokens id withdrawn for each Token id in _tokenIds.

* @param _deadline Block # after which this transaction can no longer be
executed.
* /
function removeLiquidity(
 address provider,
 uint256[] memory tokenIds,
 uint256[] memory poolTokenAmounts,
 uint256[] memory _minBaseTokens,
 uint256[] memory minTokens,
 uint256 deadline)
 internal nonReentrant();
```

# **Price Calculations**

In Niftyswap, like Uniswap, the price of an asset is a function of a base currency reserve and the corresponding token reserve. Indeed, all methods in Niftyswap enforce that the following equality remains true:

 $BaseReserve_i * TokenReserve_i = K$ 

where  $BaseReserve_i$  is the base currency reserve size for the corresponding token id i,  $TokenReserve_i$  is the reserve size of the ERC-1155 token id i and K is an arbitrary constant.

**Ignoring the** <u>Liquidity Fee</u>, purchasing some tokens i with the base currency (or vice versa) should increase the  $BaseReserve_i$  and decrease the  $TokenReserve_i$  (or vice versa) such that

 $BaseReserve_i * TokenReserve_i == K.$ 

Determining the cost of  $purchasing \Delta TokenReserve_i$  tokens i therefore depends on the quantity purchased, such that

$$\Delta BaseReserve_i = rac{K}{TokenReserve_i - \Delta TokenReserve_i} - BaseReserve_i$$

with substitution, the purchase cost can also be written as

$$\Delta BaseReserve_i = rac{BaseReserve_i*\Delta TokenReserve_i}{TokenReserve_i-\Delta TokenReserve_i}$$

where  $\Delta BaseReserve_i$  is the amount of base currency assets that must be sent cover the cost of the  $\Delta TokenReserve_i$  purchased. The latter form of this equation is the one used in the <code>getBuyPrice()</code> function. Inversely, determining the revenue from  $selling \Delta TokenReserve_i$  tokens i can be done with

$$\Delta BaseReserve_i = BaseReserve_i - \frac{K}{TokenReserve_i + \Delta TokenReserve_i}$$

with substitution, the purchase cost can also be written as

$$\Delta BaseReserve_i = rac{BaseReserve_i*\Delta TokenReserve_i}{TokenReserve_i+\Delta TokenReserve_i}$$

where  $\Delta BaseReserve_i$  is the amount of base currency that a user would receive. The latter form of this equation is the one used in the <code>getSellPrice()</code> function.

Note that the implementation of these equations is subjected to arithmetic rounding errors. To see how these are mitigated, see the <u>Rounding Errors</u> section.

# **Liquidity Fee**

A liquidity provider fee of 0.5% paid in the base currency is added to every trade, increasing the corresponding  $BaseReserve_i$ . Compared to the 0.3% fee chosen by Uniswap, the 0.5% fee was chosen to ensure that token reserves are deep, which ultimately provides a better experience for users (less slippage, better price discovery and lower risk of transactions failing). This value could change for Niftyswap V2.

While the  $BaseReserve_i$  /  $TokenReserve_i$  ratio is constantly shifting, fees makes sure that the total combined reserve size increases with every trade. This functions as a payout to liquidity providers that is collected when they burn their liquidity pool tokens to withdraw their portion of total reserves.

This fee is asymmetric, unlike with Uniswap, which will bias the ratio in one direction. However, one the bias becomes large enough, an arbitrage opportunity will emerge and someone will correct that bias. This leads to some inefficiencies, but this is necessary as some ERC-1155 tokens are non-fungible (0 decimals) and the fees can only be paid with the base currency.

# **Assets**

Within Niftyswap, there are two main types of assets: the base currency and the tokens. While the base currency is also expected to be an ERC-1155 token, this document always refer to the ERC-1155 token that act as currency as the "Base Currency" or "Base token", while using the tokens that are traded against that base currency as simply referred to as "tokens" or "token i" to indicate an arbitrary token with an id i.

## **Base Currency**

The base currency is an ERC-1155 token that is fungible (>0 decimals) that is used to price each token i in a given ERC-1155 token contract. For instance, this base currency could be wrapped Ether or wrapped DAI (see <a href="erc20-meta-wrapper">erc20-meta-wrapper</a>). Since the Base Currency is an ERC-1155, the NiftyswapExchange.sol contract also needs to be aware of what the Base Currency id is in the Base Currency contract. The Base Currency can be the same contract as the Tokens contract.

Both the address and the token id of the base currency can be retrieved by calling getBaseTokenInfo().

#### **Tokens**

The tokens contract is an ERC-1155 compliant contract where each of its token id is priced with respect to the <u>Base Currency</u>. These tokens *can* have 0 decimals, meaning that some token ids are not divisible. The liquidity provider fee accounts for this possibly as detailed in the <u>Liquidity Fee</u> section.

The address of the ERC-1155 token contract can be retrieved by calling getTokenAddress().

# **Trades**

All trades are done by specifying exactly how many tokens i a user wants to buy or sell, without exactly knowing how much base currency they will send or receive. This design choice was necessary considering ERC-1155 tokens can be non-fungible, unlike the base currency which is assumed to be fungible (non-zero decimals). All trades will update the corresponding base currency and token reserves correctly and will be subjected to a <u>liquidity provider fee</u>.

It is possible to buy/sell multiple tokens at once, but if any one fails, the entire trade will fail as well. This could change for Niftyswap V2.

## Base Currency to Token i

To trade base currency  $\Rightarrow$  token i, a user would call

baseToToken( tokenIds, tokensBoughtAmounts, maxBaseTokens, deadline, recipient);

as defined in the  $\underline{\text{Exchaging Tokens}}$  section and specify *exactly* how many tokens i they expect to receive from the trade. This is done by specifying the token ids to purchase in the  $\underline{\text{tokenIds}}$  array and the amount for each token id in the  $\underline{\text{tokensBoughtAmounts}}$  array.

Since users can't know exactly how much base currency will be required when the transaction is created, they must provide a  $_{\tt maxBaseTokens}$  value which contain the maximum amount of base currency they are willing to spend for the entire trade. It would've been possible for Niftyswap to support a maximum amount per token i, however this would increase the gas cost significantly. If proven to be desired, this could be incorporated in Niftyswap V2.

Additionally, to protect users against miners or third party relayers withholding their Niftyswap trade transactions, a \_deadline parameter must be provided by the user. This \_deadline is a block number after which a given transaction will revert.

Finally, users can specify who should receive the tokens with the <u>\_recipient</u> argument. This is particularly useful for third parties and proxy contracts that will interact with Niftyswap.

The \_maxBaseTokens argument is specified as the amount of base currency sent to the NiftyswapExchange.sol contract via the onERC1155BatchReceived() method:

```
// Tokens received need to be Base Currency contract
require(msg.sender == address(baseToken), "NiftyswapExchange#onERC1155BatchReceived:
INVALID_BASE_TOKENS_TRANSFERRED");
require(_ids.length == 1, "NiftyswapExchange#onERC1155BatchReceived:
INVALID_BASE_TOKEN_ID_AMOUNT");
require(_ids[0] == base_curency_id, "NiftyswapExchange#onERC1155BatchReceived:
INVALID_BASE_TOKEN_ID");

// Decode BuyTokensObj from _data to call _baseToToken()
BuyTokensObj memory obj;
(functionSignature, obj) = abi.decode(_data, (bytes4, BuyTokensObj));
address recipient = obj.recipient == address(0x0) ? _from : obj.recipient;

// Buy tokens
_baseToToken(obj.tokensBoughtIDs, obj.tokensBoughtAmounts, _amounts[0], obj.deadline, recipient);
```

where any difference between the actual cost of the trade and the amount sent will be refunded to the specified recipient.

To call this method, users must transfer sufficient base currency to the NiftyswapExchange.sol, as follow:

```
// Call _baseToToken() on NiftyswapExchange.sol contract
IERC1155(BaseCurrencyContract).safeTranferFrom(_from, niftyswap_address, base_curency_id,
_maxBaseTokens, _data);
```

where \_data is defined in the <u>Data Encoding: baseToToken()</u> section.

### Token i to Base Currency

To trade token  $i \Rightarrow$  base currency, a user would call

```
_tokenToBase(_tokenIds, _tokensSoldAmounts, _minBaseTokens, _deadline, _recipient);
```

as defined Exchanging Tokens and specify exactly how many tokens i they sell. This is done by specifying the token ids to sell in the tokenIds array and the amount for each token id in the tokenSoldAmounts array.

Since users can't know exactly how much base currency they would receive when the transaction is created, they must provide a  $\_minBaseTokens$  value which contain the minimum amount of base currency they are willing to accept for the entire trade. It would've been possible for Niftyswap to support a minimum amount per token i, however this would increase the gas cost significantly. If proven to be desired, this could be incorporated in Niftyswap V2.

Additionally, to protect users against miners or third party relayers withholding their Niftyswap trade transactions, a <u>\_\_deadline</u> parameter must be provided by the user. This <u>\_\_deadline</u> is a block number after which a given transaction will revert.

Finally, users can specify who should receive the base currency with the <u>recipient</u> argument upon the completion of the trade. This is particularly useful for third parties and proxy contracts that will interact with Niftyswap.

The \_tokenIds and \_tokensSoldAmounts arguments are specified as the token ids and token amounts sent to the NiftyswapExchange.sol contract via the oneRC1155BatchReceived() method:

```
// Tokens received need to be correct ERC-1155 Token contract
require(msg.sender == address(token), "NiftyswapExchange#onERC1155BatchReceived:
INVALID_TOKENS_TRANSFERRED");

// Decode SellTokensObj from _data to call _tokenToBase()
SellTokensObj memory obj;
(functionSignature, obj) = abi.decode(_data, (bytes4, SellTokensObj));
address recipient = obj.recipient == address(0x0) ? _from : obj.recipient;

// Sell tokens
_tokenToBase(_ids, _amounts, obj.minBaseTokens, obj.deadline, recipient);
```

To call this method, users must transfer the tokens to sell to the NiftyswapExchange.sol contract, as follow:

```
// Call _tokenToBase() on NiftyswapExchange.sol contract
IERC1155(TokenContract).safeBatchTranferFrom(_from, niftyswap_address, _ids, _amounts,
_data);
```

where data is defined in the Data Encoding: tokenToBase() section.

# **Liquidity Reserves Management**

Anyone can provide liquidity for a given token i, so long as they also provide liquidity for the corresponding base currency reserve. When adding liquidity to a reserve, liquidity providers should not influence the price, hence the contract ensures that calling  $\_addLiquidity()$  or  $\_removeLiquidity()$  does not change the  $BaseReserve_i/TokenReserve_i$  ratio.

### **Adding Liquidity**

To add liquidity for a given token i, a user would call

```
_addLiquidity(_provider, _tokenIds, _tokenAmounts, _maxBaseTokens, _deadline);
```

as defined in <u>Managing Reserves Liquidity</u> section. Similarly to trading, when adding liquidity, users specify the exact amount of token *i* without knowing the exact amount of base currency to send. This is done by specifying the token ids to sell in the <u>\_tokenIds</u> array and the amount for each token id in the <u>\_tokenAmounts</u> array.

Since users can't know exactly how much base currency will be required when the transaction is created, they must provide a  $_{\tt maxBaseTokens}$  array which contains the maximum amount of base currency they are willing to add as liquidity for each token i.

Additionally, to protect users against miners or third party relayers withholding their Niftyswap trade transactions, a \_deadline parameter must be provided by the user. This \_deadline is a block number after which a given transaction will revert.

The \_provider argument is the address of who sent the tokens and the \_tokenIds and \_tokenAmounts arguments are specified as the token ids and token amounts sent to the NiftyswapExchange.sol contract via the onERC1155BatchReceived() method:

```
// Tokens received need to be correct ERC-1155 Token contract
require(msg.sender == address(token), "NiftyswapExchange#onERC1155BatchReceived:
INVALID_TOKEN_TRANSFERRED");

// Decode AddLiquidityObj from _data to call _addLiquidity()
AddLiquidityObj memory obj;
(functionSignature, obj) = abi.decode(_data, (bytes4, AddLiquidityObj));

// Add Liquidity
_addLiquidity(_from, _ids, _amounts, obj.maxBaseTokens, obj.deadline);
```

To call this method, users must transfer the tokens to add to the NiftyswapExchange.sol liquidity pools, as follow:

```
// Call _addLiquidity() on NiftyswapExchange.sol contract
IERC1155(TokenContract).safeBatchTranferFrom(_provider, niftyswap_address, _ids,
_amounts, _data);
```

where data is defined in the <u>Data Encoding: addLiquidity()</u> section.

### **Removing Liquidity**

To remove liquidity for a given token i, a user would call

```
_removeLiquidity(_provider, _tokenIds, _poolTokenAmounts, _minBaseTokens, _minTokens,
_deadline);
```

as defined in <u>Managing Reserves Liquidity</u> section. Users must specify *exactly* how many liquidity pool tokens they want to burn. This is done by specifying the token ids to sell in the <u>\_tokenIds</u> array and the amount for each token id in the <u>\_poolTokenAmounts</u> array.

Since users can't know exactly how much base currency and tokens they will receive back when the transaction is created, they must provide a  $_{\tt minBaseTokens}$  and  $_{\tt minTokens}$  arrays, which contain the minimum amount of base currency and tokens i they are willing to receive when removing liquidity.

Additionally, to protect users against miners or third party relayers withholding their Niftyswap trade transactions, a \_deadline parameter must be provided by the user. This \_deadline is a block number after which a given transaction will revert.

The \_provider argument is the address of who sent the liquidity pool tokens, the \_tokenIds and \_poolTokenAmounts arguments are specified as the token ids and liquidity pool token amounts sent to the NiftyswapExchange.sol contract via the onERC1155BatchReceived() method:

```
// Tokens received need to be NIFTY-1155 tokens (liquidity pool tokens)
require(msg.sender == address(this), "NiftyswapExchange#onERC1155BatchReceived:
INVALID_NIFTY_TOKENS_TRANSFERRED");

// Decode RemoveLiquidityObj from _data to call _removeLiquidity()
RemoveLiquidityObj memory obj;
(functionSignature, obj) = abi.decode(_data, (bytes4, RemoveLiquidityObj));

// Remove Liquidity
_removeLiquidity(_from, _ids, _amounts, obj.minBaseTokens, obj.minTokens, obj.deadline);
```

To call this method, users must transfer the liquidity pool tokens to burn to the NiftyswapExchange.sol contract, as follow:

```
// Call _removeLiquidity() on NiftyswapExchange.sol contract
IERC1155(NiftyswapExchange).safeBatchTranferFrom(_provider, niftyswap_address, _ids,
    _amounts, _data);
```

where data is defined in the Data Encoding: removeLiquidity() section.

# **Data Encoding**

In order to call the correct NiftySwap method, users must encode a data payload containing the function signature to call and the method's receptive argument objects. All method calls must be encoded as follow:

```
// bytes4 method_signature
// Obj method_struct
_data = abi.encode(method_signature, method_struct);
```

where the <code>method\_signature</code> and <code>method\_struct</code> are specific to each method. The <code>\_data</code> argument is then passed in the <code>safeBatchTransferFrom(..., \_data)</code> function call.

### \_baseToToken()

The bytes4 signature to call this method is 0x24c186e7

```
// bytes4(keccak256(
// "_baseToToken(uint256[],uint256[],uint256,uint256,address)"
// ));
bytes4 internal constant BUYTOKENS_SIG = 0x24c186e7;
```

The method struct for this method is structured as follow:

Elements	Туре	Description
recipient	address	Who receives the purchased tokens
tokensBoughtIDs	uint256[]	Token IDs to buy
tokensBoughtAmounts	uint256[]	Amount of token to buy for each ID
deadline	uint256	Block # after which the tx isn't valid anymore

or

# \_tokenToBase()

The bytes4 signature to call this method is 0x7db38b4a

```
// bytes4(keccak256(
// "_tokenToBase(uint256[],uint256[],uint256,uint256,address)"
// ));
bytes4 internal constant SELLTOKENS_SIG = 0x7db38b4a;
```

The method struct for this method is structured as follow:

Elements	Туре	Description
recipient	address	Who receives the base currency for the sale
minBaseTokens	uint256	Minimum number of base tokens expected for all tokens sold
deadline	uint256	Block # after which the tx isn't valid anymore

or

# \_addLiquidity()

The bytes4 signature to call this method is 0x82da2b73

```
// bytes4(keccak256(
// "_addLiquidity(address,uint256[],uint256[],uint256[],uint256)"
// ));
bytes4 internal constant ADDLIQUIDITY_SIG = 0x82da2b73;
```

The method struct for this method is structured as follow:

Elements	Туре	Description
maxBaseTokens	uint256[]	Maximum number of base currency to deposit with tokens
deadline	uint256	Block # after which the tx isn't valid anymore

or

```
struct AddLiquidityObj {
    uint256[] maxBaseTokens; // Maximum number of base tokens to deposit with tokens
    uint256 deadline; // Block # after which the tx isn't valid anymore
}
```

### \_removeLiquidity()

The bytes4 signature to call this method is 0x5c0bf259

```
// bytes4(keccak256(
// "_removeLiquidity(address, uint256[], uint256[], uint256[], uint256[], uint256[], uint256[]
// ));
bytes4 internal constant REMOVELIQUIDITY_SIG = 0x5c0bf259;
```

The method struct for this method is structured as follow:

Elements	Туре	Description
minBaseTokens	uint256[]	Minimum number of base tokens to withdraw
minTokens	uint256[]	Minimum number of tokens to withdraw
deadline	uint256	Block # after which the tx isn't valid anymore

or

```
struct RemoveLiquidityObj {
    uint256[] minBaseTokens; // Minimum number of base tokens to withdraw
    uint256[] minTokens; // Minimum number of tokens to withdraw
    uint256 deadline; // Block # after which the tx isn't valid anymore
}
```

### **Relevant Methods**

There methods are useful for clients and third parties to query the current state of a NiftyswapExchange.sol contract.

#### getBaseTokenReserves()

```
function getBaseTokenReserves(
    uint256[] calldata _ids
) external view returns (uint256[] memory)
```

This method returns the amount of Base Currency in reserve for each Token i in  $\boxed{\text{ids}}$ .

### getPrice\_baseToToken()

```
function getPrice_baseToToken(
    uint256[] calldata _ids,
    uint256[] calldata _tokensBoughts
) external view returns (uint256[] memory)
```

This method will return the current cost for the token \_ids provided and their respective amount.

## getPrice\_tokenToBase()

```
function getPrice_tokenToBase(
    uint256[] calldata _ids,
    uint256[] calldata _tokensSold
) external view returns (uint256[] memory)
```

This method will return the current amount of base currency to be received for the token \_ids and their respective amount in tokensSold.

### getTokenAddress()

```
function tokenAddress() external view returns (address);
```

Will return the address of the corresponding ERC-1155 token contract.

### getBaseTokenInfo()

```
function getBaseTokenInfo() external view returns (address, uint256);
```

Will return the address of the Base Token contract that is used as currency and its corresponding id.

# **Miscellaneous**

# **Rounding Errors**

Some rounding errors are possible due to the nature of finite precision arithmetic the Ethereum Virtual Machine (EVM) inherits from. To account for this, some corrections needed to be implemented to make sure these rounding errors can't be exploited.

Three main functions in NiftyswapExchange.sol are subjected to rounding errors: \_addLiquidity(), baseToToken() and tokenToBase().

For addLiquidity(), the rounding error can occur at

```
uint256 baseTokenAmount = (tokenAmount.mul(baseReserve) /
(tokenReserve.sub(tokenAmount))).add(1);
```

where <code>baseTokenAmount</code> is the amount of Base Currency that needs to be sent to NiftySwap for the given <code>tokenAmount</code> of token i added to the liquidity. Rounding errors could lead to a smaller value of <code>baseTokenAmount</code> than expected, favoring the liquidity provider, hence we add 1 to the amount that is required to be sent.

For baseToToken(), the rounding error can occur at

```
// Calculate buy price of card
uint256 numerator = _baseReserve.mul(_tokenBoughtAmount);
uint256 denominator = (_tokenReserve.sub(_tokenBoughtAmount));
uint256 cost = (numerator / denominator).add(1);
```

where cost is the amount of Base Currency that needs to be sent to NiftySwap for the given  $\_tokenBoughtAmount$  of token i being purchased. Rounding errors could lead to a smaller value of  $\_baseTokenAmount$  than expected, favoring the buyer, hence we add 1 to the amount that is required to be sent

For tokenToToken(), the rounding error can occur at

```
// Calculate sell price of card
uint256 numerator = _tokenSoldAmount.mul(_baseReserve);
uint256 denominator = _tokenReserve.add(_tokenSoldAmount);
uin256 revenue = numerator / denominator;
```

where [revenue] is the amount of Base Currency that will to be sent to buyer for the given [tokenSoldAmount] of token i being sold. Rounding errors could lead to a smaller value of [tokenAmount] than expected, disfavoring the buyer, hence no correction necessary.

Notably, rounding errors and the applied correction only have a significant impact when the Base Currency use has a low number of decimals.