

Centos 系统安装 tensorflow-gpu

张桐 | | 2019.7.24

python3 安装 (python 版本 3.5.0)

安装

安装必要工具 yum-utils,它的功能是管理 repository 及扩展包的工具 (主要是针对 repository)

\$ sudo yum install yum-utils

使用 yum-builddep 为 Python3 构建环境,安装缺失的软件依赖,使用下面的命令会自动处理。

\$ sudo yum-builddep python

完成后下载 Python3 的源码包, Python 源码包目录:

https://www.python.org/ftp/python/

\$ curl -O https://www.python.org/ftp/python/3.5.0/Python-3.5.0.tgz

最后一步,编译安装 Python3,默认的安装目录是 /usr/local 如果你要改成其他目录可以在编译(make)前使用 configure 命令后面追加参数 "-prefix=/alternative/path"来完成修改。

\$ tar xf Python-3.5.0.tgz

\$ cd Python-3.5.0

\$./configure

\$ make

\$ sudo make install

查看版本

输入 python3, 出现如图信息即为安装成功

```
[root@localhost ~]# python3
Python 3.5.0 (default, Jul 22 2019, 16:06:17)
[GCC 4.8.5 20150623 (Red Hat 4.8.5-36)] on linux
Type "help", "copyright", "credits" or "license" for more information.
>>>
```

显卡驱动安装 (GeForce RTX 2080 驱动版本 430.34)

查看驱动版本

安装 nvidia-detect 命令,从 ELRepo 源安装

\$ rpm --import https://www.elrepo.org/RPM-GPG-KEY-elrepo.org

\$ rpm -Uvh http://www.elrepo.org/elrepo-release-7.0-2.el7.elrepo.noarch.rpm

安装显卡驱动检查

\$ yum install nvidia-detect

安装完成运行 nvidia-detect -v 查看

```
[root@localhost ~]# nvidia-detect -v
Probing for supported NVIDIA devices...
[10de:1e82] NVIDIA Corporation Device 1e82
This device requires the current 430.34 NVIDIA driver kmod-nvidia
WARNING: Xorg log file /var/log/Xorg.0.log does not exist
WARNING: Unable to determine Xorg ABI compatibility
WARNING: The driver for this device does not support the current Xorg version
```

没找到 GTX2080 不重要,自己知道显卡是什么就好。没有搜到 1e82 是什么。

注意驱动版本是 430.34 需要下载对应的显卡驱动

下载安装显卡驱动

显卡驱动下载地址

https://www.geforce.cn/drivers





下载的同时做如下准备工作

安装前的准备工作

(前两句我没运行)

- \$ yum -y update //注意这是升级系统比较慢
- \$ yum -y groupinstall "GNOME Desktop" "Development Tools"
- \$ sudo yum install "kernel-devel-uname-r == \$(uname -r)"
- \$ yum -y install epel-release
- \$ yum -y install dkms

编辑 grub 文件

\$ vi /etc/default/grub

在"GRUB_CMDLINE_LINUX"中添加

rd.driver.blacklist=nouveau nouveau.modeset=0

```
[RUB_TIMEOUT=5
GRUB_DISTRIBUTOR="$(sed 's, release .*$,,g' /etc/system-release)"
GRUB_DETANULT=saved
GRUB_DETANULT=saved
GRUB_DISABLE_SUBMENU=true
GRUB_TERMINAL_OUTPUT="console"
GRUB_TERMINAL_OUTPUT="console"
GRUB_GRUB_TIME_LINUS="crashkernel=auto rd.lvm.lv=centos/root rd.lvm.lv=centos/swap rhgb quiet
GRUB_GRUB_CRECOVERY="true"
```

随后生成配置

\$ grub2-mkconfig -o /boot/grub2/grub.cfg

创建 blacklist

\$ vi /etc/modprobe.d/blacklist.conf

添加 blacklist nouveau (添加到文件内就行,哪行都行)

更新配置

\$ mv /boot/initramfs-\$(uname -r).img /boot/initramfs-\$(uname -r)-nouveau.img

\$ dracut /boot/initramfs-\$(uname -r).img \$(uname -r)

重启系统

\$ shutdown -r now

确认禁用了 nouveau

\$ Ismod | grep nouveau

若无输出则禁用成功

驱动下载完成,传到服务器上开始安装 (sh 后边跟的参数为下载的驱动名称 注意: 我下载的这个驱动是 430.34 版本,跟上文中查看的驱动版本对应)


\$ sh NVIDIA-Linux-x86 64-430.34.run

安装完成之后重启

查看安装结果

\$ nvidia-smi

显示如下信息,安装显卡驱动成功



CUDA、CUDNN 安装 (CUDA 10.1,CUDNN 7.4.2)

版本对照关系确认以及下载

CUDA 下载 https://developer.nvidia.com/cuda-toolkit-archive CUDNN 下载 https://developer.nvidia.com/rdp/cudnn-archive

由于 CUDA 目前最高支持 418.67。因此下载驱动版本为 418.67 的 CUDA 10.1 版本



手册中出现的\$开头的命令都是在终端进行

根据 tensorflow 官网经过测试的构建配置对比选择 CUDNN 版本 7.4 https://tensorflow.google.cn/install/source

版本	Python 版本	编译器	编译工具	cuDNN	CUDA
tensorflow_gpu-1.13.1	2.7、3.3-3.6	GCC 4.8	Bazel 0.19.2	7.4	10.0
tensorflow_gpu-1.12.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.15.0	7	9
tensorflow_gpu-1.11.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.15.0	7	9
tensorflow_gpu-1.10.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.15.0	7	9
tensorflow_gpu-1.9.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.11.0	7	9
tensorflow_gpu-1.8.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.10.0	7	9
tensorflow_gpu-1.7.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.9.0	7	9
tensorflow_gpu-1.6.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.9.0	7	9
tensorflow_gpu-1.5.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.8.0	7	9
tensorflow_gpu-1.4.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.5.4	6	8
tensorflow_gpu-1.3.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.4.5	6	8
tensorflow_gpu-1.2.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.4.5	5.1	8
tensorflow_gpu-1.1.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.4.2	5.1	8
tensorflow_gpu-1.0.0	2.7、3.3-3.6	GCC 4.8	Bazel 0.4.2	5.1	8

CUDNN 下载界面如图 (选择 7.4.1 或 7.4.2 都可以, 我选择的是 7.4.2)



选择 CUDNN Library for Linux

Download cuDNN v7.4.2 (Dec 14, 2018), for CUDA 10.0

```
Library for Windows, Mac, Linux, Ubuntu and RedHat/Centos(x86_64 architecture)
cuDNN Library for Windows 7
cuDNN Library for Windows 10
cuDNN Library for Linux
cuDNN Library for OSX
cuDNN Runtime Library for Ubuntu18.04 (Deb)
cuDNN Developer Library for Ubuntu18.04 (Deb)
cuDNN Code Samples and User Guide for Ubuntu18.04 (Deb)
cuDNN Runtime Library for Ubuntu16.04 (Deb)
cuDNN Developer Library for Ubuntu16.04 (Deb)
cuDNN Code Samples and User Guide for Ubuntu16 04 (Deb)
cuDNN Runtime Library for Ubuntu14.04 (Deb)
cuDNN Developer Library for Ubuntu14.04 (Deb)
cuDNN Code Samples and User Guide for Ubuntu14.04 (Deb)
cuDNN Runtime Library for RedHat/Centos 7.3 (RPM)
cuDNN Developer Library for RedHat/Centos 7.3 (RPM)
```

CUDA 安装

将下载的安装包上传到 Centos 服务器,使用命令进行安装

\$ sh cuda 10.1.168 418.67 linux.run

cuDNN Code Samples and User Guide for RedHat/Centos 7.3 (RPM)

按照命令行提示操作

Accept 然后 都是默认 选择 install 等待结果

安装成功如图 (这张图网上找的 类似界面为安装成功)

配置环境变量

\$ vi /etc/profile

末尾添加

export PATH=/usr/local/ cuda-10.1/bin:\$PATH export LD_LIBRARY_PATH=/usr/local/ cuda-10.1/lib64:\$LD_LIBRARY_PATH

其中 cuda-10.1 的文件根据实际位置的文件名决定

使环境变量立即生效 或者 重启系统

\$ source /etc/profile

CUDA 验证

执行以下命令验证是否安装成功

\$ /usr/local/cuda-10.1/extras/demo suite/deviceQuery

其中 cuda-10.1 的文件根据实际位置的文件名决定

```
| Trott@localhost -| # /usr/local/cuda-10.1/extras/demo_suite/deviceQuery Starting...
| CUDA Device Query (Runtime API) version (CUDART static linking)
| Device Query (Runtime API) version (CUDART static linking)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Starting...)
| Device Query (Runtime API) version (Device Query Cuttor Query (Device Query Cuttor Query Cuttor Query Cuttor Query (Cuttor Query Cuttor Query Cuttor Query Cuttor Query (Cuttor Query Cuttor Query Cuttor Query (Cuttor Query Cuttor Query (Cuttor Query Cuttor Query Cuttor Query (Cuttor Query (Cuttor Query Cuttor Query (Cuttor Query (C
```

CUDNN 安装

cuDNN 的安装,只需要将压缩包解压,并把文件覆盖到 CUDA 对应的目录中去即可

手册中出现的\$开头的命令都是在终端进行

- \$ tar -zxvf cudnn-10.0-linux-x64-v7.4.2.24.solitairetheme8
- \$ cp cuda/include/cudnn.h /usr/local/cuda/include/
- \$ cp cuda/lib64/libcudnn* /usr/local/cuda/lib64/

Tensorflow-gpu 安装 (最终安装版本 1.14.0)

对比上节对照表中 tensorflow 的版本应该为 1.13.0, 实际上 1.13.0 并不兼容 CUDA10.1 与 CUDNN7.4.2, 兼容版本是 10 与 7.4。因此提升 tensorflow 版本到 1.14.0,成功兼容。

首次安装的 python3 需要先升级 pip

默认 centos 系统自带 python2,因此给 python3 安装库需要使用 pip3,给 python2 安装使用 pip

\$ pip3 install --upgrade pip

安装 tensorflow

\$ pip3 install tensorflow-gpu==1.14.0 -i https://pypi.tuna.tsinghua.edu.cn/simple/

安装成功末尾如下图

```
Installing collected packages: tensorflow-estimator, setuptools, tensorboard, wrapt, google-pasta, tensorflow-gpu
Found existing installation: tensorflow-estimator 1.13.0
Uninstalling tensorflow-estimator-1.13.0
Successfully uninstalled tensorflow-estimator-1.13.0
Found existing installation: setuptools 18.2
Uninstalling setuptools-18.2:
Successfully uninstalled setuptools-18.2
Found existing installation: tensorboard 1.13.1
Uninstalling tensorboard-1.13.1:
Successfully uninstalled ensorboard-1.13.1
Successfully uninstalled tensorboard-1.13.1
Successfully uninstalled tensorboard-1.13.1
```

测试 tensorflow-gpu 能否使用

进入 python3.5

\$ python3

导入 tensorflow

\$ import tensorlfow

手册中出现的\$开头的命令都是在终端进行

不报错即为安装成功

安装 tensorflow 高级库 keras

\$ pip3 install keras -i https://pypi.tuna.tsinghua.edu.cn/simple/

所有安装完成