
Configuring SAML for Atlassian JIRA version 6 on Linux

OneLogin Configuration


- 1. Go to Apps > Find Apps. Search for "JIRA" and add JIRA
- 2. In the subsequent page select SAML 2.0 for the Connector Version and click Continue.
- 3. Select Configuration and insert the Login URL value. If you access JIRA at http://jiraserver:8080 you would add jiraserver:8080 to this field




4. Click the **Parameters** tab and select **Configured by admin**. Generally, you want to use Email name part for **Username**.



5. Click the SSO tab and copy with the button SAML Login URL and click on View Details to see the certificate:





- 6. Under Access and Users, assign the JIRA app to the appropriate Role in OneLogin and independent users.
- 7. Select save, you are now done.

JIRA Configuration

- 1. Edit the jira_onelogin.xml to include your x509 certificate from OneLogin and the SAML Login URL we made note of in step 4 above.
- 2. Open jira_onelogin.xml in a text editor and copy the value of the x509 certificate from your OneLogin account between the <certificate></certificate> tags remove all line feeds/carriage returns in the certificate value.

<config><certificate>MIICMTCCAiWgAwIBAgIBATADBgEAMGcxCzAJBgNVBAYTAlVTMRMwEQYDVQQIDApDYWxpZm9ybmlhMRUwEw
YDVQQHDAMA8GA1UECgwIT25lTG9naW4xGTAXBgNVBAMMEGFwcC5vbmVsb2dpbi5jb20wggEiMA0GCSqGSIb3DQEBAQUAA4IBDwAwggE
KAoIBAQDKvNTqqXMUv2kbVIaAeov5qOaVrbDQwj/65aaCs8CuXwC1Ks69Z3/D5qGHLDqVCR7+BhbVEiZRK/tb/LcW1qsFySXlgbGY5z
qvHXjQ2ChYDofpTV8iMr7klHBXweP+pxvrknsmMUxlmaH7gcvRBN9UkdXds0pXTYBho0TnCDljEvktwKg7e02FyUgwM1xSJSYTm3IDV
NSyfWiZ4H51vOUz80ulIUoHtu5WHPdvzP3vdokRbW5akN/rE2T6ws0CuTdd+LKyxdIuuJP3MseMG8HIf9C/4wWXkxWB9amCzujsmBJu
aEduKX0OP7T8XyOZoQ7A0BjM18eqxx/rOmr6O0ztAgMBAAEwAwYBAAMBAA==</certificate><assertion>http://server1:808
0/login.jsp</assertion><issuer>http://server1:8080/secure/Dashboard.jspa</issuer><ssotarget>https://app
.onelogin.com/saml/signon/49097</ssotarget></config>

Note: The default JIRA INSTALL directory is **/opt/atlassian/jira**)

- 3. Copy the jira_onelogin.xml file into JIRA_INSTALL and JIRA_INSTALL/bin directory.
- 4. Copy the customauth-jira-6.1.jar file into JIRA_INSTALL/atlassian-jira/WEB-INF/lib directory
- 5. Open in your text editor the file named **seraph-config.xml** which can be found on the Jira server into JIRA_INSTALL/atlassian-jira/WEB-INF/classes directory
- 6. From within this file, do the following:
 - a. Modify the login.url parameter. Find the line <param-name>link.login.url</param-name> and make sure the corresponding value is

```
<param-name>link.login.url</param-name>
<param-value>/login.jsp?os_destination=${originalurl}</param-value>
```

b. Comment out the following line:

```
before: <authenticator class="com.atlassian.jira.security.login.JiraSeraphAuthenticator"/>
after: <!--<authenticator class="com.atlassian.jira.security.login.JiraSeraphAuthenticator"/>-->
```

c. Add the following before the <services> tag

- d. Save and close the seraph-config.xml file
- 7. Open in your text editor the file named loginform.jsp located in JIRA INSTALL/atlassian-jira/includes directory
- 8. From within this file, do the following:
 - a. Find the line: <\@ page import="com.atlassian.jira.web.filters.JiraLoginInterceptor" %> and add the following on the line below it:

```
<%@ page import= "com.onelogin.jira.saml.SSOAuthenticator" %>
```

b. Within loginform.jsp locate the following line:

```
request.setAttribute("loggedInUser", jiraAuthenticationContext.getLoggedInUser()
== null ? null : jiraAuthenticationContext.getLoggedInUser().getDisplayName());
```

c. Add the following immediately after:

- d. Save and close the loginform.jsp file
- 9. Restart the Atlassian JIRA service on the server.