GKV User's Manual

Version 1.2

W.M. Nevins LLNL

7/28/02

Table of Contents

T	able of Contents	2
1.	Introduction	5
2.	Initializing GKV	6
	2.1 IDL Version Requirements	6
	2,2 For pg3eq Users Only	7
	2.3 Compiling GKV	7
	2.4 Initializing GKV	8
	2.5 Choosing Working and Source Directories	8
3.	Importing Data from Simulation Code Output Files	10
	3.1 Importing Data from NETCDF Files in Standard Format	
	3.2 Standard NetCDF File Format	. 11
	3.3 Importing Data from NetCDF Files in pg3eq Format	. 13
	3.4 Importing Data from GTC	. 14
	GTC_HistoryGTC_ShearEB,	
	GTC_DATA	
	3.5 Importing Data From TUBE	. 18
	3.6 Importing Data from GYRO	. 20
	ALL_k	
4.	Transforming the Representation of Data	22
	4.1 FFT	. 22
	4.3 FUNCTION KtoX	. 23
	4.4 FUNCTION ROTATE	. 23
5.	Arithmetic on Objects	25
	5.1 FUNCTION Plus	. 25
	5.2 FUNCTION Minus	. 25
	5.3 FUNCTION Times	. 25
	5.4 FUNCTION Over	. 26
	5.5 Arithmetic Keywords	. 26
	5.6 Derivatives of Objects — DbyD and D2byD	. 27
	5.7 Integrals of Objects — Int and CInt	. 28
	5.8 Access to IDL Functions — GKVsd::Execute	. 29
6.	Basic Analysis I: Compressing Dimensionality	30

6.1 FUNCTION Slice	30
6.2 Function Avg	31
6.3 FUNCTION Moments,	32
6.4 FUNCTION Delta	34
7. Basic Analysis II: Time Series Analysis	35
7.1 PROCEEDURE RMSNorm	35
7.2 FUNCTION DeTrend	35
7.3 FUNCTION XCORR	35
7.4 FUNCTION XCORR0	36
7.5 FUNCTION XSPECT	37
7.6 Function Filter	39
7.7 Function BiSpect	40
8. Analysis Protocols	
8.1 Function TauCorrs	43
8.2 AnalysisProtocol	46
8.3 LinearModes	48
9. Outputting Results	49
9.1 View	49
9.2 GKVs1D::Draw	49
9. 3 PRO GKVs1D::oPlot	50
9.4 Pro GKVs2D::Draw	51
9.5 Pro Shade_Surf	52
9.6 Outputting Objects to a TIFF file	53
10. Producing Animations	55
10.1 Movie	55
10.2 MPeg,	56
10.3 Jpegs	57
10.4 TIFFs	59
11. Memory Management	61
11.1 FUNCTION MakeCopy	61
11.2 PRO Trash	61
11.3 PRO GKVdelete, arg	61
11.4 Pro GKVsd::Save	62
11.5 FUNCTION GKV RESTORE	62

11.6 Procedure GKV_SaveArray	62
11.7 Function GKV_RestoreArray	63
11.8 Procedure GKV_SaveStructure	64
11.9 FUNCTION GKV_RestoreStructure	65
11. Basic GKVsd Object Management	66
11.1 Procedure Info	66
11.2 Function Cat	66
11.3 FUNCTION SubSample	66
11.4 GKVs1D::Squash	68
11.5 PRO SignalWindow,	68
11.6 PRO GET	69
11.7 PRO SET	70
11.8 FUNCTION GetValues	70
11.9 FUNCTION GKVsND Gen	

1. Introduction

GKV is an interactive data analysis and visualization tool designed for use in analyzing output from plasma turbulence simulations. Developed as part of the Plasma Microturbulence Project, it is an object-oriented application built upon IDL (the Interactive Data Language, a product of Research Systems, Inc.). GKV imports turbulence simulation data from data files written by various plasma simulation codes. Data which has been imported into GKV is represented as a GKVsd object. Data analysis and visualization are then accomplished within GKV through Methods which act on the GKVsd objects to produce new GKVsd objects containing analyzed data (e.g., the method XCORR acts on a GKVsd object and produces correlation functions, which are returned as a new GKVsd object). These methods enhance the power of the native IDL language, making it possible to perform significant amounts of data analysis and to produce presentation quality graphics with a relatively few lines of IDL script which can either be entered interactively at the IDL command line (for interactive use), or through the use of IDL scripts (for batch use).

We assume that the reader is familiar with the use of *IDL*. Object-oriented *IDL* differs slightly from what some *IDL* users may be familiar with in that

- 1) An objects data is only available through that objects methods so you can only access the data within *GKVsd* objects through the methods provided by *GKV*.
- 2) All *methods* which act on objects within *IDL* are either *Procedures* or *Functions*. You invoke Procedure method as follows:

where "Obj" is an IDL object, Procedure is a Procedure method previously defined on this class of objects, and args are the various arguments expected by this procedure. The compound symbol "->" (a hyphen, "-", immediately followed by a greater than sign, ">") is used by IDL to invoke procedures.

3) Function methods are invoked as follows:

$$result = Obj \rightarrow Function(args)$$

Where *result* is the information returned by this Function Method, *Obj* is an *IDL* object, *Function* is a Function method previously defined on this class of objects, and *args* (now enclosed in parenthesis) are the arguments expected by this function..

2. Initializing GKV

You must first obtain a copy of the (hopefully current) *GKV* distribution folder. Within this folder you will find

- 1) *GKV.prj*, which is an *IDL* "project file". Project files are rather like *make* files, and are used to control the compilation order of the associated *IDL* source files. These project files are **not** backward compatible. If your version of *IDL* does not recognize *GKV.prj* as a valid project file, look for a file named *GKV_X.X.prj*, where "*X.X*" corresponds to the version of *IDL* which you are currently running.
- 2) source, which contains the *IDL* source files for *GKV*.
- 3) *NETCDF_pg3eq*, which contains the *IDL* source files for various routines which you will *only* require if you need to import data from the *.h.nc, *.x.nc, and *.c.nc NetCDF files which are written only by the plasma micro turbulence code *pg3eq*.
- 4) *data*, which contains some sample data (from simulations of the *CYCLONE base case*) which you can use to practice with *GKV*.

2.1 IDL Version Requirements.

GKV is an IDL application, so the first step is to initialize IDL. This requires a license for IDL, which may be obtained from Research Systems, Inc.¹ I chose to write GKV as an IDL application because most fusion laboratories already have licenses for IDL. Research Systems periodically updates IDL, and I expect GKV users to see that the version of IDL available at their site is up-to-date. I currently support a version of GKV which operates under IDL Version 5.4; and expect to develop new procedures which require IDL Version 5.5 (particularly procedures for importing data from HDF5 files) for full functionality.

On MACs, *IDL* can be initialized by simply "double-clicking" on the project file, *GKV.prj*, On UNIX systems I generally use the *IDL Development Environment* (a part of the normal *IDL* distribution), which is invoked by entering *IDLDE* on the command line. *IDL* is also available for *WINDOWS* systems. I've very little experience with using *IDL* under WINDOWS, but those users who have used *GKV* under WINDOWS have report that it works pretty much as advertised.

fax: (303)786-9900 fax: (303) 786-9909 e-mail: info@rsinc.com http://www.rsinc.com

¹ Research Systems, Inc. 2995 Wilderness Place Boulder, CO 80301 phone: (303)786-9900

2,2 For pg3eq Users Only

If you are not planning to import data from NetCDF files produced by pg3eq in the current GKV session, skip this section. For those of you planing to import such data it is necessary to compile the source files in $NETCDF_pg3eq$ directory before compiling GKV. This is accomplished by going to the "file" menu of IDL; choosing "open"; using the "widget" which pops up to open the $NETCDF_pg3eq$ directory, and choosing the file $make_NETCDF_pg3eq.pro$ within this directory. Now type

@make_NETCDF_pg3eq

on *IDL*'s command line (NOTE: *case* is important within *IDL* only when referring to files by name — this is, in exactly the context described here! Get those CAPS in the right place). *IDL* should respond by printing out a few pages of "module names" as they are compiled. It is good practice to close *make_NETCDF_pg3eq.pro* once *IDL* finishes compiling these modules.

If you need to compile the files in the *NETCDF_pg3eq* directory after compiling *GKV*, it will be necessary to recompile *GKV* after compiling *NETCDF_pg3eq* to avoid naming conflicts. This can be done from the "*Project*" menu as described in §2.3 below.

Finally, to avoid conflicts relating to color tables, etc. it is best to import data from *pg3eq* immediately after compiling *GKV*, and *before* running *GKV_INIT* (as described in §2.4 below).

2.3 Compiling GKV

After starting *IDL* (and compiling *NETCDF_pg3eq* if this is necessary for you) open the project file, *GKV.prj*. If you are on a MAC, and you initialized *IDL* by clicking on this project file, then it is already open. If you are on a MAC, but have initialized *IDL* without "double-clicking" on the *GKV.prj* project file, then you can open it by going to the "file" menu of *IDL*; choosing "Open"; and using the "widget" which pops up to select *GKV.prj* within the *GKV* distribution folder. Once *GKV.prj* is open, *GKV* can be compiled by either selecting the "Compile Modified Files" button at the top of the project window, or by going to the "Project" menu and selecting "Compile All Files" (or, "Compile Modified Files" — it really doesn't make any difference here).

On UNIX systems the *GKV.prj* project file can be opened by going to the "file" menu of *IDL*; choosing "Open Project ..."; and using the "widget" which pops up to select *GKV.prj* from within the *GKV* distribution folder. Once the project file *GKV.prj* has been opened, go to the "Project" menu; choose "Compile" and then "All Files".

IDL should respond to your "Compile" command by printing out several pages of

- % Compiled module: COLOR_TRUE.
- % Compiled module: COLOR_LIST.
- % Compiled module: COLOR_INDEX.
- % Compiled module: COLOR_INDEX_TEST.
- % Compiled module: COLOR_IMAGE_BOTTOM.
- % Compiled module: COLOR_IMAGE_NCOLORS.
- % Compiled module: COLOR_IMAGE_RANGE.
- % Compiled module: COLOR_IMAGE_SET.
- % Compiled module: COLOR_SETUP.

etc.

If you get any compile errors, this is most likely due to a problem with the order in which routines have been compiled. If this is the case, it can be remedied by simply issuing the compile command again.

2.4 Initializing GKV

After having compiled GKV it must be initialized. This is accomplished by typing

GKV_INIT

on the *IDL* command line. Successful initialization will result in a window popping up containing a line plot (necessary as *IDL*'s graphics state is altered on many platforms when the first plot is drawn); a disclaimer being printed in the output window (necessary to keep the University of California's lawyers happy); and the *IDL* prompt changing from "*IDL*" to "*GKV*".

If you're planning to import data from pg3eq it's best to do this **before** running GKV_INIT . Executing $pg3eq_Data$ after running GKV_INIT leads to conflicts with color tables, etc.

2.5 Choosing Working and Source Directories

While it is not strictly necessary, it is very useful to begin your *GKV* session by defining two string variables: *work*, which should contain the full path to the directory containing the data files which you plan to analyze (and, where we will store our analyzed data); and *source*, which should contain the full path to the directory containing any *IDL* source files which you are using in you data analysis that may require debugging (I generally have *source* contain the full path to the *GKV* source directory within the *GKV* distribution folder). This is easily accomplished with the widget *GKV_ChangeDir*. Simply enter

or

on the *IDL* command line and use the widget which will pop up to choose the appropriate directory. You can verify that you have chosen defined the proper paths by examining the contents of the string variables, *source* and *work* within *IDL*'s Variable Watch window.

3. Importing Data from Simulation Code Output Files

GKV provides routines for importing data from output files created by various plasma turbulence simulation codes. These routines both read in the data and create GKV objects.

3.1 Importing Data from NETCDF Files in Standard Format

NETCDF DATA

Usage:

```
result = NETCDF_DATA( keyword = value, ... )
```

Where, on return, *result* is an object array containing one GKV object for each dependent variable which was read from the NETCDF file.

NETCDF_DATA is the basic routine for reading data from NETCDF files in standard format (see below for a description of the standard NETCDF file format). Note that this routine should be able to read pretty much any NETCDF file. However, use of the 'standard' format is recommended because it allows you to transfer information about independent variables, titles, units, etc. automatically from your code to the GKV objects.

KEYWORDS:

FileName Name of netCDF file. Must include either full path, or else the

path from the current working directory. If FileName is not provided, DIALOG_PICKFILE will be called to allow the user to

select an appropriate netCDF file. (Optional)

Path Sets path to initial directory selected by DIALOG_PICKFILE

(which will allow user to change to other directories...). If no path is provided, DIALOG_PICKFILE will default to current working

directory. (Optional)

ArrayStyle Set to the string 'c' if netCDF file was written by code (like C or

PASCAL) which stores array data in 'column major' format. Default is 'fortran', appropriate when the netCDF file was written by code (like FORTRAN or IDL) which stores array data in 'row major' format. This issue is discussed in Chapter 5 of 'Building

IDL Applications'. Defaults to 'fortran'.

Threshold Size (in units of 10⁶ elements) of threshold between 'large' and

'small' data sets. User will be prompted before reading a data array

of more than 'Threshold*10^6' elements from the netCDF file, while all small data sets will be read. Default is $1 (x10^6)$.

Species

A string containing the name (within the netCDF file) of the DIMENSION which indexes particle species. NetCDF Data will break separate data corresponding to different species into separate GKV objects. The species index (incremented by 1, so that the first species will be '1', rather than '0') will be appended to the objects mnemonic and added (as a subscript) to the objects title.

Defaults to 'species'.

RI

A string containing the name (within the netCDF file) of the DIMENSION which is used to index the real and imaginary part of a complex variable. Within IDL's 'row major' format this MUST be the first (that is, most rapidly varying) dimension of the array. ***NOTE*** that NCDUMP (which is implemented as a C code) should show 'RI' as the LAST INDEX of the array within the netCDF file (consistent with C's use of 'column major' format).

Defaults to 'ri'.

Debug

Set (i.e., put '/Debug' within the argument string) to turn off error trapping. Turning off error trapping is useful if you are debugging NetCDF Data.

Default is Debug=0 (error trapping on)

3.2 Standard NetCDF File Format

The data to be analyzed and/or archived should be stored in one or more NetCDF files, each of which has the same basic format. For our purposes, we assume that the data is stored in rectangular arrays (which isn't always the case, see GTC_DATA for an example of reading data which is not stored in rectangular arrays). Each NetCDF file contains:

1) Information on the simulation code and the particular physics run stored as character-type GLOBAL ATTRIBUTE. The global attribute names which NETCDF DATA searches for are:

CodeID Identifies simulation code which originated this data CodePI Provides further information about this simulation code. Identifies particular simulation run which generated this data. RunID RunInfo Provides further information about this simulation run.

2) Dimensions and Independent Variables. When creating a NetCDF file, dimensions must be declared and given a symbolic name. Typically, dimensions correspond to independent variables (however, see below for some exceptions). When this is the case,

then a 1-D VARIABLE should be included in the NetCDF file with the *same* name as the corresponding dimension (having the same name for both a dimension and a variable is both legal and encourages in the NetCDF documentation).² This 1-D variable contains the values of the independent variable at the grid points. Information about these independent variables should be stored as VARIABLE ATTRIBUTES associated with this 1-D variable array. Possible variable attributes are:

mnemonic a terse identifier in all ASCII characters

idl_name in which you can use Hershey Vector Fonts to introduce Greek

characters (see IDL manual).

pretty_name Which is a synonym for 'idl_name' title Another synonym for 'idl_name Yet another synonym for idl_name'

units n which you give the units (DON'T make the units part of the

name! Hershey fonts are OK here as well)

boundary Information about the boundary conditions in this independent

variable. Supported values of 'boundary' are 'periodic (open)', 'periodic (closed)', and 'open'. 'periodic (open)' is used to describe periodic systems in which only one boundary point is stored; while 'periodic (closed)' is used to describe systems in which the boundary values are repeated at both the beginning and

end of the data arrays.

3) Auxiliary Dimensions. You may require some AUXILIARY DIMENSIONS (not corresponding to independent variables) to deal with multiple species (e.g., a 'species' dimension) and with the regrettable fact that NetCDF files don't support complex data (so use 'ri' to dimension the real and imaginary parts of your complex data). These dimension names are, in effect, keywords which NETCDF_DATA recognizes and treats specially. Currently supported 'auxiliary dimensions' are:

species Dimension name for species index. NETCDF_DATA will make a

separate GKV object for each species.

ri Dimension name for complex data. Put real part of data at ri=0,

and imaginary part of data at ri=1.

Note that the symbol corresponding to both of these auxiliary dimensions can be over ridden on the NETCDF_DATA command line.

² See http://www.unidata.ucar.edu/packages/netcdf/ for information about netCDF files and common netCDF file conventions.

4) Dependent Variables, like the electrostatic potential or the vector potential. This data is stored in arrays of appropriate dimensionality. NetCDF files allow a single 'unlimited' dimension which should be used to index 'time'. If an unlimited dimension is used, it must be the least rapidly varying index of the array. Information about each dependent variable is stored as VARIABLE ATTRIBUTES associates with the dependent variables. Note that it is legal for different variables to have attributes with the same name. NETCDF_DATA looks for the following VARIABLE ATTRIBUTES associated with each dependent variable:

mnemonic a terse identifier in all ASCII characters

idl_name in which you can use Hershey Vector Fonts to introduce Greek

characters

pretty_name Which is a synonym for 'idl_name' title Another synonym for 'idl_name' Yet another synonym for idl_name'

units in which you give the units--DON'T make the units part of the

name! Hershey fonts are OK here as well

3.3 Importing Data from NetCDF Files in pg3eq Format

PG3EQ_DATA

Usage:

```
result = PG3EQ\_DATA(keyword = value, ...)
```

Where, on return, result is an anonymous structure with one tag for each data field selected using the widget which will pop p upon invoking PG3EQ_DATA. The value associated with each of these tags is a *GKVsd* object.

PG3EQ_DATA imports data from the netcdf files (*.x.nc, *.h.nc and *.c.nc) produced by the microturbulence simulation code pg3eq. These files should be in the same directory — presumably that whose path is contained in the string variable work (see §2.5 above). Generally, the data is chosen by "pointing and clicking" within the widgets which pop up when PG3EQ_DATA is invoked. PG3EQ_DATA must be invoked separately to access data from each of the three NetCDF files with suffixes *.h.nc (which contains scalar data vs. time and also time histories of the amplitudes of selected Fourier modes), *.x.nc (which contains flux-surface-averaged data as a function of the flux surface label, x, and time), and *.c.nc (which contains scalar fields as a function of. two spatial co-ordinates — generally x and y and time).

KEYWORDS:

path Set this keyword equal to a legal path to the directory at which you

wish to begin your search for the appropriate NetCDF file (e.g., set *path=work*, where *work* was set as described in §2.5 above).

Defaults to the current working directory. (Optional)

file Set this keyword equal to the name of the appropriate NetCDF file.

Default is to use DIALOG_PICKFILE to choose the appropriate

NetCDF file. (Optional)

var Set this equal to the name of the variable within the NetCDF file

which you wish to import into GKV. Default is to us a pop up widget to select data from that which is contained in the selected

NetCDF file. (Optional)

3.4 Importing Data from GTC

GTC writes data to (at least) three different types of files: *hist.out* files, *ShearEB.out* files, and families of *Piiii.ncd* files. Three different routines have been written to import data into *GKV* from each of these file types.

GTC_History

Which imports data from GTC's History.out files.

Usage:

```
result = GTC\_HISTORY(keywords = value, ...)
```

Where, on return, result is an anonymous structure with one tag for each piece of data contained within the *history.out* file. The value associated with each of these tags is a *GKVsd* object.

Keywords:

FileName An optional 'string' argument containing the FULL name of the

'history.out' file. If this keyword is not set (or the requested file cannot be found) then a dialogue box will pop up to allow the user to select the 'history.out' file. When in doubt, *****DON'T***** set

this keyword! (Optional)

Path An optional 'string' argument containing the path to the directory

(folder on MACs) where the pop-up dialogue box will initialize the user's search for the 'history.out' file. When in doubt, *****PO***** set this keyword using, for example, the string work initialized as

described in §2.5 above.

Debug Set this keyword (i.e, put "/Debug" on the command line) to turn

off error trapping. Disabling error trapping is most useful while

debugging.

GTC_ShearEB,

Which imports data from GTC's ShearEB.out files.

Usage:

 $result = GTC_ShearEB(keyword = value, ...)$

Where, on return, result contains an anonymous structure with one tag for each data set stored in the *ShearEB.out* file. The values associated with each tag are *GKVsd* objects.

Keywords:

FileName An optional 'string' argument containing the FULL name of the

'ShearEB.out' file. If this keyword is not set (or the requested file cannot be found) then a dialogue box will pop up to allow the user to select the 'ShearEB.out' file. When in doubt, ***DON'T*** set

this keyword.

Path An optional 'string' argument containing the path to the directory

(folder on MACs) where the pop-up dialogue box will initialize the user's search for the 'ShearEB.out' file. When in doubt, ***DO*** set this keyword using, for example, the string work initialized as

described in §2.5 above.

NT An optional argument containing (on input) the number of time slices to be read from 'sheareb.out'. If set, NT ***MUST*** be

less than or equal to the total number of time slices in 'ShearEB.out'. If NT is not set, then GTC_SearEB reads all time slices in 'ShearEB.out' using READ_ASCII. It's best to set NT if you know how many time slices are present, as this speeds the

reading process.

DT An optional argument containing (on input) the interval between

time slices (in units of 1/Omega_ci). Defaults to 20.

Debug Set this keyword (i.e, "/Debug") to turn off error trapping.

Disabling error trapping is most useful during debugging.

Verbose Set this keyword (i.e., "/Verbose") so that READ_ASCI prints out

a message upon reading ***EACH*** record in 'ShearEB.out'; This ***REALLY*** slows the read to a crawl, so ***DON'T*** set 'Verbose' unless you know that 'ShearEB.out' has less than about 1000 records (or so...), or you are really

motivated to know how many records are in 'ShearEB.out'.

GTC DATA

Which imports data from the *RUNdimenID* file, and from GTC's sequence of *Piiii.ncd* files. The *RUNdimenID* file contains information about both the *q*-profile (and the *iota*-profile) and the structure of the data arrays within the *Piiii.ncd* files. The *Piiii.ncd* files contain scalar data as a function of three spatial variables and time (they also contain information about the grid metric which is not used by GTC_DATA).

Usage:

```
result = GTC\_DATA(keywords = value, ...)
```

Where, on return, *result* is an anonymous structure containing one tag for each data set imported. The values associated with these tags are *GKVsd* objects.

The present version will only allow ONE type of data (i.e., output resulting from a single keyword) from a given call to GTC_Data.

Keywords:

Info If this keyword is set (e.g., /Info), GTC_Data prints

information about the grid structure and the RETURNS. Selected information is PRINTed to the IDL output log, and more information will be found within the structure returned. On this call to GTC_Data. NO *GKVsd* data objects are returned. This is mainly useful for determining

if you have a useful RUNdimenID file.

IsurfaceNormal Set to an integer array containing indices to the flux

surfaces on which data is desired vs. usual poloidal (theta)

and toroidal (zeta) angle.

IsurfaceFieldLine Set to an integer array containing indices to the flux

surfaces on which data is desired vs. poloidal angle (theta) and the field-line label zeta_0 (the toroidal angle at which field line in question passes through the outer midplane).

IradialNormal Set to a floating point array containing the values of the

poloidal angle at which slices of the data vs. radial

coordinate (r) and toroidal angle (zeta) are desired.

PoloidalAvg Set this keyword (e.g., /PoloidalAvg) to get data averaged

over fieldlines (over poloidal angles - to) vs. radial

coordinate (r) and field-line label zeta_o

ZetaCut Set this keyword to a floating point array of zeta values at

which cuts of the data vs. radius and poloidal angle are

desired.

Thetacut Set this keyword to a floating point array of theta values at

which cuts of the data vs. radius and toroidal angle are

desired.

ToroidalAvg Set this keyword (e.g., /ToroidalAvg) to get data averaged

along field line (over one cycle of poloidal angle from - to) vs. radius and poloidal angle theta 0 (a field-line label).

IfluxLimits Set to a two-element integer array containing the indices of

the first and last flux surfaces to be included in forming

IradialNormal or IradailFieldLIne data.

TimeSteps Set this keyword to the number of timesteps which you

desire in the output file. If not set, defaults to timeslice from selected Pxxxx file. If it is set, then you can only get ONE *GKVsd* object from this call to GTC_Data. If timeSteps is set to an integer array (and the second value of this array is less than the first element) then the first element determines the number of files to be read (in total) while the second element determines the interval between

files (defaults to 1, or every file)

Dt Set this keyword to the time interval between GTC data file

files.

R_range Set this keyword to a two-element floating-point array

containing the range of 'r/q' values corresponding to the full

range of 'iflux'. Default is [0.1, 0.9].

Qprofile	Set this keyword ((e.g., /Oprofile) to	obtain the q-profile as
Q prome	Dot tills ito , " of a ,	(O.S., / Qpromiso, to	octain the q profile as

a GKVsd object.

IotaProfile Set this keyword (e.g., /IotaProfile) to obtain the iota-

profile as a GKVsd object.

Q_0 Set this keyword to the value of q on axis. (defaults to the

range $0.5 < Q_0 = 1.0$

Iota_0 Alternatively, you can set this keyword to the value of iota

on axis (defaults to the range 1 iota < 2).

Variable Set this keyword to a STRING containing the name of the

variable within the Pxxxx file desired. This defaults to 'potential'. If 'variable' is set to a non-zero integer, then will attempt to extract data corresponding to the (Variable+1)th variable within the Pxxxx file (set Variable = 0 to get first,

and probably only variable in the Pxxxx file).

ncd Set this keyword to the suffix of the sequence of netcdf

files. Defaults to "ncd" (optional).

Path Path to begin search for the GTC netcdf files. Defaults to

current directory. (Optional)

3.5 Importing Data From TUBE

The microturbulence simulation code *TUBE* stores data in ASCII output files with names *hist.out*, *Phixy.out*, *Phixz.out*, *Phir.out*, etc. *TUBE_DATA* simultaneously imports data from all of these files.

Tube Data,

Usage:

```
result = TUBE_DATA( keyword = value, ... )
```

Where, on return, result is an anonymous structure containing a combination of *GKVsd* objects and other anonymous structures (which, in turn, contain a combination of *GKVsd* objects and other anonymous structures ...).

Keywords:

Path	The	path	at	which	DIALOGUE	PICKFILE	begins	its

search for the directory containing the TUBE output files.

Defaults to the current working directory. (Optional)

TubePath The full and correct path to the directory containing the

> If this keyword is set, then TUBE output files.

DIALOGUE_PICKFILE will not be used. (Optional)

Number of time steps the history file. This is only used if nt

there is NOT a 'hist.out' file in the selected directory.

Set this keyword (i.e., put "/Yang" on the command line) to Yang

> interpret the third integer in the first record of the phi**.out, etc. files as the number of time slices in the file (instead of the interval between time slices in these files relative to the history files). Has the side effect of Changing default value for "CodePi" to Y. Chen.

(Optional)

Codename Set this keyword to the name of the code which generated

the output files. Defaults to "TUBE". (Optional)

CodePi Set this keyword to the name of the PI responsible for this

> simulation data. Defaults to "S.E. Parker" (unless the keyword 'Yang' is set, in which case 'CodePi' defaults to

"Y. Chen"). (Optional)

RunId Set this keyword to a terse phrase describing this run.

> (Hershey vector font conventions can be employed). No default, so that the RunID field on output will be blank if

this keyword is not set. (Optional)

FileId Set this keyword to a terse phrase further describing this

> run. (Hershey vector font conventions can be employed). No default, so that the FileID field on output will be blank

if this keyword is not set. (Optional)

Debug Set this keyword to obtain relatively verbose behavior

which may be useful in debugging this routine. (Optional)

Side Effects:

On return from *Tube_Data* the current working directory will be set to the directory containing the TUBE output files.

3.6 Importing Data from GYRO

The GYRO code writes NetCDF files in the standard format described in §3.2 above. Data from these files is imported using the routine NETCDF_DATA as described in §3.1. For example, the call

```
GyroData = NetCDF \ Data()
```

will generate the structure GyroData containing data imported from a NetCDF file produced by Gyro. However, field quantities, like the electrostatic potential, are stored as a function of radius, r, and toroidal mode number, n. GYRO only provides fourier amplitudes for positive values of n. It is a consequence of the reality condition that the fourier amplitudes at negative values of n are simply the complex conjugate of those at the corresponding positive value of n.

You may wish to transform this data into a configuration-space (r, ζ) representation, where ζ is the toroidal angle.. This is accomplished by first applying the function method:

ALL_k

Usage:

```
result = GyroData.potential \rightarrow All\_k(arg, keyword = value, ...)
```

or

```
GyroData.potential -> All_k, arg, keyword = value, ...
```

All_k can be called either as a function method or as a procedure method. When called as a function the result is stored in *result*, while when called as a procedure the "result" will overwrite the object which it acts on. The function method All_k expects that the object it acts on (GyroData.potential in this case) contains the non-negative Fourier coefficients (vs. the independent variable 'arg') from a real data series. On return, result will contain a full set of both positive and negative Fourier coefficients, where the coefficients for negative values of 'arg' are formed by taking the complex conjugate of those at positive values of 'arg'.

Arguments:

arg A valid axis ID. That is, the axis number or any valid axis mnemonic. Defaults to axis 1. (Optional)

(-1----

Keywords:

'mnemonic' Alternatively, the independent variable labeling the Fourier

coefficients can be specified in the form 'mnemonic'=value, where 'mnemonic' is a valid axis mnemonic, and value is the maximum absolute value of this independent variable to be retained on return. If 'value' is greater than the maximum value of this independent variable in GyroData.potential, then the additional Fourier coefficients

will be set to zero. (Optional).

kmax Set this keyword equal to the maximum absolute value of

the Fourier transformed variable desired in 'self' on return.

NoAvg Set this keyword (i.e., put '/NoAvg' on the command line)

to remove the k=0 component of the Fourier transformed

signal.

NoNegative Set this keyword (i.e., put '/NoNegative' on the command

line) to put zeros in the negative 'n' components. Default is to put the complex conjugate of the positive components in

the negative 'n' components. (Optional).

Having completed the Fourier representation of the data contained within GyroData.potential, it can now be transformed into an configuration space (r,ζ) representation using the function FFT (see §4.11 below). Be sure to set the keyword Inverse as it requires an **inverse** transform to go from (r,n)-space to (r,ζ) -space.

A final note — the GKV convention for spatial fourier transforms [that the configuration space representation of a quantity is $A(\zeta)=A_n exp(+in\zeta)$] differs from that employed in the GYRO code [$A(\zeta)=A_n exp(-in\zeta)$]]. As a result, the positive sense of the toroidal angle in the GKV representation of the imported data is opposite to the positive sense of the toroidal angle within GYRO. Keep this in mind when working out which is the ion (electron) diamagentic direction!

4. Transforming the Representation of Data

Data is generally stored within microturbulence simulations in the most parsimonious possible manner because such a representation minimizes both the memory requirements and the computational effort. However, such parsimonious representations are often not the optimal representation for data analysis where memory is less of an issue. The methods described in this chapter allow conversion between several widely used data representations.

4.1 FFT

Usage:

```
result = object -> FFT(arg, keyword = values, ...)
```

Transforms data between a configuration space and a Fourier representation in the specified independent variable. Normalization of the forward transform is chosen such that the signal A*cos(2*pi*n*x/L) will have an amplitude of A in the n^{th} Fourier harmonic (and zero elsewhere). result will contain both positive and negative k's — a redundant representation for real data. For a more parsimonious Fourier representation, see ktox in §4.2 below.

Argument: Any legal axis identifier. Defaults to the final axis. The

independent variable may also be identified using an axis

mnemonic. (Optional)

Input Keywords:

'mnemonic' Where 'mnemonic' is the mnemonic for the independent

variable over which the fourier transform is to be applied. 'Mnemonic' should be set equal to the range in this variable over which you wish to transform the data. Defaults to the

final axis and current irange. (Optional)

Inverse 'Set' this keyword (i.e., put '/Inverse') to perform an inverse

Fourier transform in. the indicated variable. Defaults to forward (i.e., configuration space to k-space) transform.

(Optional)

Offset Set this keyword to the (floating point) offset value which

the specified independent variable will assume on completion of the inverse transform. Defaults to zero.

(Optional)

4.2 FUNCTION XtoK

Usage:

$$result = Object \rightarrow XtoK()$$

This function method transforms the data in *Object* from a configuration space representation (like that output by *GTC*, *pg3eq*, and *TUBE*) into a Fourier space representation like that output by *GS2*, thus enabling convenient comparison with data from plasma micro turbulence simulation code which output data in a Fourier space representation (like *GS2*). If *Object* has three dimensions, then *XtoK* assumes that the first two dimensions correspond to configuration space values, while the third dimension is time. At each time-slice the configuration space representation of data in *Object* is converted to a k-space representation in *result*. This function method is the inverse of the function *KtoX* (see §4.3 below)

4.3 FUNCTION KtoX

Usage:

```
result = Object \rightarrow KtoX()
```

This function method transforms the data in *Object* from a Fourier space representation (like that output by *GS2*) into a configuration space representation, thus enabling convenient comparison with data from plasma micro turbulence simulation code which output data in a configuration space representation (like *GTC*, *pg3eq*, and *TUBE*). If *Object* has three dimensions, then *KtoX* assumes that the first two dimensions correspond to k-values, while the third dimension is time. At each time-slice the k-space representation of data in *Object* is converted to a configuration space representation in *result*. This function method is the inverse of the function method *XtoK* (see §4.2 above)

4.4 FUNCTION ROTATE

Usage:

```
result = Object -> Rotate(arg, keyword = value, ...)
```

This function method rotates the data in 'self' through an angle specified by the argument 'arg'. If *Object* is a 3-D object, then the third independent variable is assumed to be timelike, and for each time-slice the data is rotated in the plane defined by the first two independent variables.

Argument: The argument to this function method is the desired

(clockwise) angle of rotation in degrees.

Input Keywords:

value of first independent variable rotate about ('center of

rotation'). Defaults to 0. (Optional)

'mnemonic1'_0 A synonym for x0 (see above), where 'mnemonic1' is the

mnemonic for the first independent variable. (Optional)

y0 Value of second independent variable rotate about ('center

of rotation'). Defaults to 0. (Optional)

'mnemonic2'_0 A synonym for y0 (see above), where 'mnemonic2' is the

mnemonic for the first independent variable. (Optional)

title1 Set to an ascii string containing the title associated with the

first independent variable. Defaults to 'x!D1!N' (that is, x₁

in Hershey vector font). (Optional)

mnemonic1 Set to an ascii string containing the mnemonic associated

with the first independent variable. Defaults to 'x1'.

(Optional)

units 1 Set to an ascii string containing the units associated

with the first independent variable. Defaults to input value

of these units. (Optional)

title2 Set to an ascii string containing the title associated with the

second independent variable. Defaults to 'x!D2!N' (that is,

 x_2 in Hershey vector font). (Optional)

mnemonic2 Set to an ascii string containing the mnemonic associated

with the second independent variable. Defaults to 'x2'.

(Optional)

units2 Set to an ascii string containing the units associated with

the second independent variable. Defaults to input value of

these units. (Optional)

Output KeyWords: None

5. Arithmetic on Objects

Once data has been inserted into IDL objects it is no longer possible to perform basic arithmetic operations on it using only IDL's command-line parser ("only an objects methods can access an object's data"—an edict which is strictly enforced by IDL in its object-oriented programming!). This functionality is recovered in GKV by providing METHODs to perform basic arithmetic operations. All four of these methods have common keywords as described below.

5.1 FUNCTION Plus

Usage:

```
result = object -> Plus(arg, keyword = values, ...)
```

Defines basic arithmetic operation: addition. *Arg* can be a scalar; an array with the same dimensionality as *object*; another GKVsd object of the same dimensionality as *object* and having. the same independent variables; a 0-D GKVsd object; or a string containing the mnemonic of any of *object*'s independent variables. On return, *result* is a *GKVsd* object whose data values are formed by adding the data values of *object* to those of *arg*.

5.2 FUNCTION Minus

Usage:

```
result = object -> Minus(arg, keyword = values, ...)
```

Defines basic arithmetic operation: subtraction. Arg can be a scalar; an array with the same dimensionality as *object*; another GKVsd object of the same dimensionality as *object* and having. the same independent variables; a 0-D GKVsd object; or a string containing the mnemonic of any of *object*'s independent variables. On return, result is a GKVsd object whose data values are formed by subtracting the data values of arg from those of object.

5.3 FUNCTION Times

Usage:

```
result = object -> Times(arg, keyword = values, ...)
```

Defines basic arithmetic operation: multiplication. *Arg* can be a scalar; an array with the same dimensionality as *object*; another GKVsd object of the same dimensionality as *object* and having. the same independent variables; a 0-D GKVsd object; or a string containing the mnemonic of any of *object*'s independent variables. On return, *result* is a *GKVsd* object whose data values are formed by multiplying the data values of *object* by those of *arg*.

5.4 FUNCTION Over

Usage:

```
result = object -> Over(arg, keyword = values, ...)
```

Defines basic arithmetic operation: division. *Arg* can be a scalar; an array with the same dimensionality as *object*; another GKVsd object of the same dimensionality as *object* and having. the same independent variables; a 0-D GKVsd object; or a string containing the mnemonic of any of *object*'s independent variables. On return, *result* is a *GKVsd* object whose data values are formed by dividing the data values of *object* by those of *arg*.

5.5 Arithmetic Keywords

All of these arithmetic operations share a common set of keywords which can be used to set the *title*, *mnemonic*, and *units* of the result.

Keywords:

Title Set this keyword to a *string* containing the title of *result*.

Hershey vector fonts can be used to get Greek or special

characters. (Optional)

Mnemonic Set this keyword to a *string* containing the mnemonic of

result. Use only ascii characters (an nothing which *IDL* might interpret as a command delimiter). Be TERSE, as you may find yourself typing this *string* several times!

(Optional)

Units Set this keyword to a *string* containing the units of *result*.

Hershey vector fonts can be used to get Greek or special

characters. (Optional)

5.6 Derivatives of Objects — DbyD and D2byD

Usage:

result = Object -> DbyD(arg or keyword = value)

 $result = Object \rightarrow D2byD((arg\ or\ keyword = value))$

The function methods *DbyD* (*D2byD*) returns a *GKVsd* object (of the same dimensionality as *object*) containing the first (second) partial derivative of *Object* with respect to the indicated independent variable. The algorithms employed provide a reasonable approximation to the partial derivative for BOTH uniform and non-uniform grids.

Argument: The (optional) argument is any legal axis identifier. That

is, either an integer between 1 and nDims, or a STRING

containing an axis mnemonic.

Keywords:

Axis If no argument is provided, then this keyword may be used

to identify independent variable with respect to which the partial derivative is to be taken. Set axis equal to any legal

axis identifier (see discussion under Argument above).

mnemonic Set the mnemonic of the selected axis equal to a two-

element array, [min, max], to both identify the independent variable for which the (partial) derivative is to be taken, and to reset the signal window on this axis (before taking the derivative). This two-element array is interpreted as the desired *RANGE* in the independent variable, NOT the

integer 'irange'

irange Set 'irange' to a two-element (integer) array to reset the

signal window before taking the derivative w.r.t. the

selected independent variable.

range Set 'range' to a two-element (floating point) array to set the

range in the independent variable over which the (partial)

derivative is to be taken.

Side Effects:

If a 'range' or 'irange' is specified on the command line (either directly, or via 'mnemonic' = ...) then the *SignalWindow* method will be invoked on 'self' and, on return, the signal window of the selected independent variable will have been modified.

5.7 Integrals of Objects — Int and CInt

Usage:

result = Object ->Int(arg or keyword = value)

result = Object -> CInt(arg or keyword = value)

The function method *Int* returns a *GKVsd* object with dimensionality one degree lower than that of *object*' containing the definite integral of 'self' over the selected independent variable; while the function method *CInt* returns a *GKVsd* object of the same dimensionality as *Object* containing the indefinite integral of *Object*. A "Simpson's Rule' algorithm is used which does not require that the data in *Object* be on a uniform grid in the selected independent variable.

Argument: The (optional) argument is any legal axis identifier. That

is, either an integer between 1 and nDims, or a STRING

containing an axis mnemonic.

Keywords:

Axis If no argument is provided, then this keyword may be used

to identify independent variable to be integrated over. Set

axis equal to any legal axis identifier (see above).

mnemonic Set the mnemonic of the selected axis equal to a two-

element array, [min, max], to both identify the independent variable to be integrated over, and to set the range of integration. This two-element array is interpreted as the desired RANGE in the independent variable, NOT the

integer 'irange'

irange Set 'irange' to a two-element (integer) array to set the range

of integration through indices into the corresponding

grid.values array.

range Set 'range' to a two-element (floating point) array to set the

range of integration.

Side Effects:

If a 'range' or 'irange' is specified on the command line (either directly, or via 'mnemonic' = ...) then the SignalWindow method will be invoked on 'self' and, on return, the signal window of the selected independent variable will have been modified.

5.8 Access to IDL Functions — GKVsd::Execute

Usage:

This method allows the user to apply any legal *IDL* function to the data contained in *Object*. It returns a *GKVsd* object of the same dimensionality as *Object* who data values are obtained by applying the specified function to the corresponding data value of *Object*.

Arguments:

Accepts a string argument containing the name of

an IDL function.

arg1, arg2 Up to two additional arguments can be passed to

this IDL function by setting these (optional)

arguments to Execute.

6. Basic Analysis I: Compressing Dimensionality

What computer visualization is mainly about is painting colors onto a 2-D screen. In plasma micro turbulence simulations we are blessed with (generally scalar) data as a function of four independent variables. Since it is not really convenient to display fields vs. more than two independent variables (I know that *Advanced Computer Visualization* is soon going to change all this, but bear with me ...) it is generally necessary to compress the dimensionality before analyzing and/or displaying the data.

6.1 FUNCTION Slice

Usage:

```
result = object -> slice(keyword=value, ...)
```

Object is sliced at the specified location, returning a GKVsd object of lower (by one) dimensionality.

Input Keywords:

identifier—that is, an ascii string containing a valid axis mnemonic or an positive integer (no larger than the number of independent variables of this object). The axis can also be identified by a runtime keyword (see below). If no axis identifier is provided defaults

to the final (usually 'time') axis. (Optional)

Value Value of the independent variable at the 'slice'. This can also be

set using run-time keywords (see below). Defaults to the first (presumably lowest) value of the selected independent variable.

(Optional)

Index Alternatively, the value of the independent variable at the 'slice'

can be specified by providing an index into the array of grid

values. Defaults to 0. (Optional)

Max Set this keyword (that is, put /Max on the command line) to 'slice'

along the maxima of the dependent variable over the selected axis (implemented only for GKVs2D objects at present). Default is to

slice at a selected value of the independent variable. (Optional).

MaxLocation If the keyword Max (see above) has been set, then also setting MaxLocation (i.e., put /MaxLocation on the command line) will cause Slice to return an anonymous structure with tags slice (corresponding to the slice from object) and maxLocation (corresponding to a GKVs1D object containing the location of the slice in the selected independent variable vs. the remaining independent variable). (Optional)

Run-time Keywords:

mnemonic

Put *mnemonic*=value on the command, where *mnemonic* is the mnemonic corresponding to one of the axes (independent variables) of object will cause object to be sliced on the corresponding axis at the specified value. (Optional).;

6.2 Function Avg

Usage:

$$result = Object \rightarrow Avg(arg)$$

or

This function returns a GKVsd object with dimensionality one less than that of Object containing the average of *Object* over the selected independent variable.

Argument: The (optional) argument is any legal axis identifier.

> That is, either an integer between 1 and nDims (the dimensionality of *Object*), or a STRING containing

an axis mnemonic

Keywords:

If no argument is provided, then this keyword may Axis

> be used to identify independent variable over which the average is to be taken. Set axis equal to any

legal axis identifier (see above).

mnemonic Set the mnemonic of the selected axis equal to a

two-element array, [min, max], to both identify the independent variable and the range in this variable over which the average is to be taken. This two-

element array is interpreted as the desired *RANGE* in the independent variable, NOT the integer

'irange'. (Optional)

irange Set 'irange' to a two-element (integer) array to reset

the signal window before taking the average w.r.t.

the selected independent variable. (Optional)

range Set 'range' to a two-element (floating point) array to

set the range in the independent variable over which

the average is to be taken. (Optional)

Side Effects: If a 'range' or 'irange' is specified on the command

line (either directly, or via 'mnemonic' = ...) then the SignalWindow method will be invoked on 'Object' and, on return, the signal window of the selected

independent variable will have been modified.

6.3 FUNCTION Moments,

Usage:

result = object -> Moments(keyword = value, ...)

Where *object* is a valid GKVsd object (of dimensionality 1 or greater) and *result* is a three-element object array. Default is to return the integral of the dependent variable over the selected axis in the 0^{th} element of the output array; the integral of the product of the dependent and the selected independent variable over this independent variable in the 1^{st} element of the output array; and the integral of the product of the dependent variable times the square of the deviations of the dependent variable from its mean in the 2^{nd} element of the output array. If the keyword Avg is set then these are replaced by the average value of the dependent variable; the mean value of the selected independent variable; and the standard deviation of the selected independent variable about this mean.

Keywords:

Axis

Identifies the independent variable over which the moments are to be taken. Set to a legal axis identifier—that is, an ascii string containing a valid axis mnemonic or a positive integer (no larger than the number of independent variables of this object). The axis can also be identified by a run-time keyword (see below). If no axis identifier is provided (either with this keyword, or by using a

run-time keyword) then an error message is printed and 0 is returned. (Optional)

Range

Set to a two-element floating point array (IDL will convert integer arrays to floating point) to set the range of the independent variable (in that variable's proper units) over which the moments are to be taken. Defaults to the current signal window for the selected independent variable. (Optional)

Irange

Alternatively, set *irange* to a two-element integer array to set the range of grid-indices for the independent variable over which the moments are to be taken. Defaults to the current signal window for the selected independent variable. (Optional)

Avg

Set this keyword (i.e., put /Avg on the command line) to request this method to return the average over the selected axis, mean value of the selected dependent variable (using the dependent variable as the weighting function), and standard deviation of the independent variable about this mean instead of the first three moments. Default is to return first 0^{th} through 2^{nd} moments. (Optional)

Runtime Keywords:

mnemonic

Put *mnemonic=[xmin, xmax]* where *=[xmin, xmax]* is a twoelement floating point array (IDL will automatically convert integer arrays) on the command line to simultaneously specify the axis over which the moments (or average) is to be taken and the range of the selected independent variable. See **Range** keyword above. (Optional)

6.4 FUNCTION Delta

Usage:

result = object -> delta(keywords)

Where *object* is a valid GKVsd object of dimensionality 1 or greater. The output (*result*) is a structure with two tags: *result .avg* contains the average of the dependent variable over the selected independent variable while *result .delta* contains the deviations from this average.

Keywords:

Axis

Identifies the independent variable over which the independent variable is to be decomposed into an average and deviations from its average. Set to a legal axis identifier—that is, an ascii string containing a valid axis mnemonic or a positive integer (no larger than the number of independent variables of this object). The axis can also be identified by a run-time keyword (see below). If no axis identifier is provided (either with this keyword, or by using a run-time keyword) then an error message is printed and 0 is returned. (Optional)

Range

Set to a two-element floating point array (IDL will convert integer arrays to floating point) to set the range of the independent variable (in that variable's proper units) over which the average and deviations are to be taken. Defaults to the current signal window for the selected independent variable. (Optional)

Irange

Alternatively, set *irange* to a two-element integer array to set the range of grid-indices for the independent variable over which the average and deviations are to be taken. Defaults to the current signal window for the selected independent variable. (Optional)

RunTime Keywords:

mnemonic

Put *mnemonic=[xmin, xmax]* where *[xmin, xmax]* is a twoelement floating point array (IDL will automatically convert integer arrays) on the command line to simultaneously specify the axis over which the average and deviations are to be taken and the range of the selected independent variable. See **Range** keyword above to understand the usage for *[xmin, xmax]*. (Optional)

7. Basic Analysis II: Time Series Analysis

7.1 PROCEEDURE RMSNorm

Usage:

Object -> RMSNorm, keyword = value

This is a **proceedure** — that is it multiplies the dependent variable within *Object* by a constant such that RMS value of the dependent variable within the 'SignalWindow' of *Object* is equal to *rmsValue*.

Arguments: None

Keywords:

RMSValue Set this keyword equal to the desired rms value of signal. Defaults

to 1.0. (Optional)

7.2 FUNCTION DeTrend

Usage:

 $Result = Object \rightarrow DeTrend(Order = iOrder)$

This function acts on GKVs1D objects (only) and returns in a *Result* which contains the data from *Object* with the average, trend, etc removed. This is accomplished by making a least-squares-fit of the data in *Object* to a polynomial of order *iOrder*, and then subtracting this polynomial from the dependent variable in *Object* to obtain the dependent variable of *Result*.

7.3 FUNCTION XCORR

Usage:

result = object -> XCorr(keywords)

where *object* is a valid GKVsd object of dimensionality 1 through 3. Returns the auto (or cross) variance of the data. The auto (or cross) variance is computed using the

Blackman–Tukey fast Fourier transform algorithm. See any standard text on time series analysis for a discussion of data windows, etc.

Keywords:

Ref Set this keyword equal to a valid GKV object of the same or lower

dimensionality to compute the cross variance between the object being acted on and the reference object. If this keyword is not set,

the autovariance will be computed.

No_Avg Set this keyword (i.e., put /No_Avg on the command line) to

remove the average before computing the auto (or cross) variance.

Dw Set this keyword to determine the length of the cosine roll-off in

time (the data window) to be applied to the data. If DW is set to a real number, then it is interpreted the length of this roll off in the proper time units. If DW is set to an integer, then it is interpreted as the length in units of integer time-steps. Default data window is

a cosine roll-off with a length equal to $1/10^{th}$ that of the input data.

Norm Set this keyword to normalize the result such that the value of the

auto-correlation function at zero lag is 1.0 — that is, to return the correlation function instead of the auto-variance. Note that this only works on auto-correlation functions (that is, when the keyword *Ref* has **not** been set!). Default is to compute the (auto-)

variance. (Optional)

Hamming Set this keyword (i.e., put /Hamming on the command line) to

specify a Hamming window as the data window.

Hanning Set this keyword c to specify a Hanning window as the data

window.

Double Set this keyword (i.e., put /double on the command line) to request

double precision arithmetic.

7.4 FUNCTION XCORR0

Usage:

 $Result = Object \rightarrow XCORRO(Arg, keyword = value)$

This function returns the auto or cross correlation between *Object* and the reference Object (see *Ref* keyword below) as a function of the specified independent variable of

Object' at zero lag (or displacement) in the remaining independent variable(s). The correlation function is obtained by averaging over the remaining variable(s), so the data should be homogeneous in these independent variables. This function is significantly faster than XCORR for large (generally *GKVs3D*) objects, and so is useful when only the correlation function at zero lag in all but one independent variable is required.

Argument:

Arg

Any legal axis identifier. This axis will become the independent variable of *Result*. Defaults to the first axis. The independent variable may also be identified using an Axis mnemonic as described below. (Optional)

Input Keywords:

'mnemonic'

Where 'mnemonic' is the mnemonic for the independent variable desired for the correlation function. 'Mnemonic' should be set equal to the reference value of this independent variable. Defaults to the initial value of this axis. (Optional)

Ref

Set this keyword to a GKVsd object of whose independent variable(s) are the same as the remaining independent variables of *Object* (that is, the independent variables **not** identified by *Arg* or by the *'mnemonic'* keyword. Defaults to first element of the data in *Object*. with respect to the selected independent variable. (Optional)

Norm

Set this keyword (i.e., put '/Norm' on the command line) to normalize the cross-correlation such that the maximum value is 1. Default is no normalization — that is, to return the cross-variance between *Object* and *Ref.* (Optional)

7.5 FUNCTION XSPECT

Usage:

result = object -> XSpect(keywords)

Where *object* is a valid GKVsd object of dimensionality 1 through 3. The output, *result*, is a GKVsd object of the same dimensionality containing the auto (or cross) spectrum. The auto (or cross) spectrum is computed using the Blackman–Tukey fast Fourier transform algorithm. See any standard text on time series analysis for a discussion of lag and data windows, etc.

Keywords:

Ref Set this keyword equal to a valid GKV object of the same or lower

dimensionality to compute the cross spectrum between the object being acted on and the reference object. If this keyword is not set,

the autospectrum will be computed.

No_Avg Set this keyword (i.e., put /No_Avg on the command line) to

remove the average and trend before computing the auto (or cross)

spectrum.

Dw Set this keyword to determine the length of the cosine roll-off in

time (the data window) to be applied to the data. If DW is set to a real number, then it is interpreted the length of this roll off in the proper time units. If DW is set to an integer, then it is interpreted as the length in units of integer time-steps. Default data window is a cosine roll-off with a length equal to $1/10^{th}$ that of the input

data.

LW Set this keyword to determine the length of the cosine roll-off in

time (the lag window) to be applied to the correlation function. If LW is set to a real number, then it is interpreted the length of this roll off in the proper time units. If LW is set to an integer, then it is interpreted as the length in units of integer time-steps. Default lag window is a cosine roll-off with a length equal to 1/2 of the correlation function (which is itself equal to the next power of 2

greater than the length of the data).

Hamming Set this keyword (i.e., put /Hamming on the command line) to

specify a Hamming window for both lag and data windows.

Hanning Set this keyword c to specify a Hanning window for both lag and

data windows.

Double Set this keyword (i.e., put /double on the command line) to request

double precision arithmetic.

7.6 Function Filter

Usage:

result = Object -> Filter(arg, Keyword = value, ...)

This function returns a GKVsd object of the same dimensionality as Object containing the data values from *Object* acted on by a band-pass filter.

Any legal axis identifier. Defaults to the final Arguments:

> (generally time-like) axis. The independent variable may be identified using either an integer axis number, or by an Axis mnemonic. (Optional)

;Input Keywords:

'mnemonic' Where 'mnemonic' is the mnemonic for the

> independent variable over which the filter is to be 'Mnemonic' should be set equal to the applied. range in this variable over which you wish to have filtered data returned. Defaults to the final axis and

the current *irange*. (Optional)

Omega_0 Central frequency of the digital filter. Defaults to

zero. (Optional)

k 0Central wavenumber of the digital filter. Defaults

> to zero. This keyword is really a synonym for 'Omega 0', and is included to maintain an intuitive interface when the axis in question corresponds to a

spatial (rather than time-like) variable. (Optional).

Width of the filter in frequency. Defaults to 10/T, dOmega

where 'T' is the length of the time interval over

which data is available from *Object*. (Optional)

dk A synonym for dOmega--the width of the filter in

> wavenumber space which defaults to 10/L, where 'L is the length of the interval over which data is

available from 'self'. (Optional)

dT An alternative means of specifying the filter width--

if set, dT gives the width of the support of the

digital filter in the time-domain, corresponding to a frequency width of dOmega=2 /dT.

dL

A synonym for dT--the width of the support of the digital filter in the spatial-domain, corresponding to a frequency width of dk=2 /dT.

Output Keywords:

Filter If this keyword is set equal to symbol on the

command line then, on return, that symbol will refer to a *GKVs1D* object containing the frequency

representation the filter applied.

7.7 Function BiSpect

Usage:

Output_Structure = Object -> Bispect(arg1, arg2, keyword = Value, ...)

This function performs a bispectral analysis of the data in *Object*' (a GKVs1D object) with the data in arguments 'arg1' and arg2'. It returns a structure (*Output_Structure*) containing the biSpectrum; the biCoherence; the biCorrelation function; the spectral densities of '*Object*', 'arg1', and 'arg2'; The auto-correlation functions of 'self', 'arg1', and 'arg2'; and the length of the data and lag windows.

The algorithm used here is avoids being a memory hog by sequentially performing bispectral analyses over subsets of the data whose length is defined by the *Lag Window* (see description of the *LW* keyword below), and then averaging the result.

Arguments:

arg1 A GKVs1D time series. Defaults to 'Object'.

(Optional)

arg2 A GKVs1D time series. Defaults to 'Object'.

(Optional)

Keywords:

dw

The length of the data window in proper time units. Ideally, the data window should be chosen to shorter compared to the lag window, but longer than the characteristic period of oscillation of the data (Optional).

idw

The (integer) length of the data window in time steps. If 'idw' is set, its value over rides value given with 'dw'. Defaults to 1/100 of the length of the data series. (Optional).

lw

The length of the lagwindow in proper time units. The lag window should be chosen to be greater than the correlation time (which is easily determined using the function proceedure *XCORR*), but short compared to the length of the data set. It is important not to choose too long a lag window, as this controls the size of intermediate arrays and output objects. (Optional).

ilw

The (integer) length of the lag window. If 'ilw' is set, its value over rides the value given with 'lw'. Defaults to 1/10 of the length of the data series.

order

Order at which to detrend the data in *Object*, *arg1*, and *arg2* within each data subset before computing bicorrelations (0 to just remove average, 1 to remove average and trend, etc.). Defaults to 1. (Optional).

epsilon

Fractional decrement allowed in norm used to compute the bicoherence. Such a limit is required because the alternative leads to spurious divides by small numbers resulting from zeros in the fourier transform of the lag window. If uncorrected, this would result in unwanted, large-amplitude noise in the estimate of the bicoherence. Defaults to 0.0085, the ratio of the first subsidiary maximum in the FT of a Hanning window (used here as the lag window) to the maximum value. (Optional... and only experts should mess with this!).

Output:

The output structure contains the following tags:

Name Ascii string used to form default directory name

when *Output_Structure* is saved using

GKV_SaveStructure. Defaults to 'Bispect'.

tauLags A three-element, floating-point array containing the

lag window specified for each of the three input objects, *Object*, *arg1*, *and arg2*. (note, it is possible, but **not** necessary to specify a separate lagwindow

for each object).

tauData A floating point scalar containing the length of the

data window.

biSpectra A GKVs2D object containing the biSpectrum of the

input data.

biCoherence A GKVs2D object containing the biCoherence

among the input data.

biCorr A GKVs2D object containing the bicorrelation

function of the input data

spect0 The spectral density of *Object*.

spect1` The Spectral density of *Arg1*.

spect2 The spectral density of *Arg2*.

corr0 The auto-correlation function of *Object*.

corr1 The auto-correlation function of *arg1*.

corr2 The auto-correlation function of *arg2*.

8. Analysis Protocols

While I am a great believer in interactive data analysis, it is often the case that you need to perform **exactly** the same analysis on data from many simulations runs — for example when comparing results of simulations from a parameter scan. This is facilitated by using *Analysis Protocols* — *GKV* scripts which perform a fixed suite of analysis routines, and store the result in an output structure. Several *Analysis Protocols* which I have found useful are described below.

8.1 Function TauCorrs

This Analysis Protocol is useful for analyzing 2-D plus time fluctuation data. Radial modes (zonal flows, etc) should be removed (see *delta* in §6.4) before applying this analysis protocol.

Usage:

```
result = Object -> TauCorrs( arg, keyword = values, ... )
```

This function performs a correlation analysis of *Object* (which must be a *GKVs3D* object), and returns the results of this analysis in as an anonymous structure (the contents of the output structure are described below). This analysis assumes that there is one inhomogeneous independent variable (even in flux-tube micro turbulence simulation codes the radial coordinate should be considered as *inhomogeneous* due to the radial variations in the zonal flows) which must be identified (either with the optional argument, *arg*, or via a keyword). If the system is truly homogeneous, it is ***MUCH*** more efficient to simply compute the correlation function with Xcorr (using no reference object).

Input Argument:

TauCorrs will accept any legal axis identifier (that is, an integer between 1 and 3, or a valid axis mnemonic) as an argument. If no argument is provided, then *TauCorrs* will expect the axis corresponding to the inhomogeneous coordinate to be identified by keywords (see below). (Optional)

Input Keywords:

Axis

If no argument is provided, then this keyword may be used to identify the inhomogeneous coordinate. Set axis equal to any legal axis identifier (see above). (optional)

'mnemonic'

Set the *mnemonic* of the selected axis equal to a two-element array, [min, max], to both identify the selected independent variable, and reset the signal window on this axis. This two-element array is interpreted as the desired *RANGE* in the independent variable (i.e., it is interpreted in the units of the corresponding independent variable), NOT the integer *'irange'* (that is, NOT as an integer index into the grid.values array). (optional)

irange

Set 'irange' to a two-element (integer) array to reset the signal window of the selected independent variable. The value of irange is interpreted as an index into the grid.values array. 'irange' defaults to the current signal window of 'self. (optional)

range

Set 'range' to a two-element (floating point) array to set the range in the independent variable. (optional)

skip

The sampling interval for the specified inhomogeneous independent variable. Defaults to 1 (Optional).

localNorm

Set this keyword (i.e., put '/LocalNorm' on the command line) to normalize the data from 'self' (but not 'self' itself, whose data remains unaltered) such that the rms fluctuation at each value of the specified inhomogeneous independent variable is the same BEFORE computing the correlation time. (Optional)

debug

Set this keyword (i.e., put '/debug' on the command line) to print out intermediate information, allowing the user to keep track of the progress (or lack thereof...) of this function. (optional)

fraction

Normally *TauCorrs* returns the full width at half maximum of the correlation function vs. the specified axis. If this keyword is set, *TauCorrs* will instead compute the full width at 'fraction' of maximum vs. time. Defaults to 0.5 (Optional).

Output:

TauCorrs returns a structure with the following tags. Additional tags can be included by setting

(optional) output keywords (see "Output Keywords" below).

TauCorr

A *GKVs1D* object containing the correlation time (full-width at half-maximum measured along the maximum of the local correlation function) vs. the specified inhomogeneous independent variable.

vPhase

A *GKVs1D* object containing the phase velocity (slope of the maximum in the local correlation function) vs. the inhomogeneous independent variable.

yCorr

A *GKVs1D* object containing the correlation length in the remaining independent variable (full-width at half maximum of the Hilbert-transform 'envelope' of the oscillatory local correlation function evaluated at zero time lag) vs. the inhomogeneous variable.

kAvg

A *GKVs1D* object containing the power-weighted average wave number in the remaining (presumably homogeneous) independent variable vs. the inhomogeneous variable. The error bars on kAvg represent the power-weighted standard deviation about this mean wave number.

kSpect

A *GKVs1D* object containing the average (over the inhomogeneous variable) of the local frequency-integrated spectrum vs. the wave number associated with the remaining independent variable. If the */LocalNorm* keyword is set, then this is a volume average, while if it is not set, then this is a power-weighted volume average.

CorrFcn

A *GKVs1D* object containing the (volume or power-weighted volume as with kSpect above) average over the inhomogeneous coordinate of the maximum of the local correlation function vs. the time lag.

yCorrFcn

A *GKVs1D* object containing the (volume or power-weighted volume as with *kSpect* above) average over the inhomogeneous coordinate of the local correlation function vs. the remaining independent variable evaluated at zero time lag.

Output Keywords:

CorrFcns Set this keyword (i.e., put "/CorrFcns" on the

command line) to add the tag "TauCorrArr" to the output structure. The corresponding value is an array of GKVs1D objects containing the local correlation function vs. tau for each location at which the correlation time is computed. (Ontional)

which the correlation time is computed. (Optional)

yCorrFcns Set this keyword (i.e., put "/yCorrFcns" on the

command line) to add the tag "yCorrArr" to the output structure. The corresponding value is an array of GKVs1D objects containing the local correlation function vs. the homogeneous spatial coordinate at each radial location at which the

correlation function in computed. (Optional)

kSpects Set this keyword (i.e., put "/kSpects" on the

command line) to add the tag "kSpectArr" to the output structure. The corresponding value is an array of GKVs1D objects containing the local k-spectrum (integrated over frequency) vs. the homogeneous spatial coordinate at each radial location at which the correlation function in

computed. (Optional)

Side Effects: Resets the signal window of *Object* to specified

'range' or 'irange' if one is provided with any of the

keywords 'mnemonic', irange, or range.

8.2 AnalysisProtocol

This analysis protocol was designed for the analysis of TEM parameter scans from GS2. It assumes that there is a user present (and paying attention. It performs the analysis described in *TauCorrs* above (see §8.1) and also analyzes the radial modes (zonal flows and GAMs).

Usage:

Result = AnalysisProtocol(keyword = value, ...)

In addition to all the keywords described in *TauCorrs* above, *AnalysisProtocol* accepts the following

Keywords

Data Set this keyword to a structure containing the GS2

data (as returned by *NetCDF_DATA*). If this keyword is not present (or, does not point to a structure), then *NetCDF_DATA* will be initialized, and the user must choose the appropriate NetCDF

file. (Optional)

Path Set this keyword to a string variable containing the

Path where NetCDF_DATA should begin its search for the appropriate GS2 data file. If not present, then the search will start at the current working

directory. (Optional)

File Set this keyword to a string variable containing the

full specification of the NetCDF file containing the GS2 data. If not present, a widget will pop up so that the user can select the appropriate file.

(Optional)

RunID Set this keyword to a string variable containing an

appropriate RunID for the NeteCDF data file to be

read. (Optional)

TRange Set this keyword to a two-element floating-point

array containing the time interval over which the data is to be analyzed. If not present, a widget will pop up, allowing the user to select an appropriate

time interval. (Optional)

Save Set this keyword (i.e., put '/Save' on the command

line) to save the output of this Analysis Protocol to disk using GKV_SaveStructure (see §11.8 below).

8.3 LinearModes

This routine is useful for performing linear analysis from of data with one homogeneous variable (which will be Fourier transformed over) and one inhomogeneous variable. It expects data from the linear phase of the simulation in the input (GKVs3D) object. It returns a structure containing real frequency and growth rate of the of fastest growing mode for each Fourier harmonic, together with an object array containing the (best effort) at extracting the corresponding linear mode structures.

Usage:

result = Object -> LinearModes(argument, keyword = value, ...)

Argument: The argument is any legal axis identifier. It should

identify the axis which is to be fourier transformed over to separate spatial structure of the linear

eigenmodes. Defaults to axis 2.

Keywords:

xRef Set this keyword to an appropriate reference value

of the inhomogeneous variable. This should be a location where the linear eigenmodes are expected to have a significant value. Defaults to 0.

(Optional)

'mnemonic' Alternatively, this reference location can be set by

using the syntax 'mnemonic'=value, where 'mnemonic' is the mnemonic for the inhomogeneous axis, and value is the desired

reference value.

9. Outputting Results

9.1 View

Usage:

object -> view, arg0, arg1, ..., keyword = value, ...

VIEW is GKV'S basic tool for viewing objects and outputting results. Upon invoking VIEW a resizable graphics widget will pop up displaying a plot of "object". The menu allows the user to change the color table, or output the plot in a variety of graphics formats.

Arguments; VIEW only accepts arguments (as opposed to keywords)

when *obj* is a *GKVs2D* object (that is, a 2-D *GKVsd* object). In this case, the a line drawing of a curve is displayed. Any arguments provided should be either *GKVs2D* objects or arrays of *GKVs2D* objects which will be displayed on the same frame as *obj* (but in different

colors).

Keywords: Any of the keywords described under "DRAW" below, or

any valid IDL graphics keyword can be employed with

VIEW. In addition, the user may employ the keyword:

Shade Surf For GKVs2D or GKVs3D objects the default plot is an

image with colors chosen according the local data values (in *GKVs3D* objects only one time slice is shown at a time). If this keyword is set (i.e., */Shade_Surf* is put on the command line), then a surface plot is displayed instead of

an *image* (essentially, a color contour plot).

9.2 GKVs1D::Draw

Usage:

object -> Draw, keywords

Where *object* is a valid GKVs1D object. "Draws" *object* in the currently open window, producing a line plot for 1-D objects.

Keywords:

In addition to the usual IDL graphics keywords (see IDL Reference manual for a discussion of IDL graphics keywords), there are the following:

Pretty Set this keyword (i.e., put /Pretty on the command line) to use

Hershey vector fonts to make 'pretty' titles and labels. Default is

to just use ascii characters.

Log Set this keyword (i.e., put /Log on the command line) to make a

plot which is logarithmic in the dependent variable.

Indx1 When *Drawing* a GKVsd object of dimensionality greater than

two set this keyword (and its companion, Indx2) to set values at

which the remaining independent variables should be 'sliced'.

Runtime Keywords:

mnemonic Set this keyword to a two-element floating point array (IDL will

automatically convert integer arrays) to specify the plotting range

in the specified independent variable.

9. 3 PRO GKVs1D::oPlot

Usage:

Object -> oplot, keywords

Where *Object* is a valid GKVs1D objects. Plots *Object* over the image on the currently open graphics window.

Keywords:

In addition to any IDL graphics keywords that are accepted by the IDL routine OPLOT, the following keyword is available.

RealOnly Set this keyword (i.e., put /RealOnly on the command line) to plot

only the real part of a complex object. Default is to plot the real part as a solid line and the imaginary part as a dashed line.

(Optional)

9.4 Pro GKVs2D::Draw

Usage:

Object -> Draw, keywords

Where *Object* is a valid GKVsd object of two or more dimensions. Produces an "image" plot (essentially a color contour plot) in the currently open graphics window.

Keywords:

In addition to the usual IDL graphics keywords (see IDL Reference manual for a discussion of IDL graphics keywords), there are the following:

Pretty Set this keyword (i.e., put /*Pretty* on the command line) to use Hershey vector fonts to make 'pretty' titles and labels. Default is

to just use ascii characters. (Optional)

Polar Set this keyword (i.e., put /Polar on the command line) to make a

polar plot. The first independent variable will be interpreted as the

radius, while the second will be interpreted as the angle.

VRange Set this keyword to a two-element floating point array (IDL will

automatically convert integer arrays) to set the axis range for the

dependent variable. (Optional)

Log Set this keyword (i.e., put /Log on the command line) to make a

plot which is logarithmic in the dependent variable. (Optional)

Grid1 Set to any valid GKV axis identifier (an integer or an axis

mnemonic) to specify the first ('x') axis for this plot. Defaults to

the first independent variable. (Optional)

Grid2 Set to any valid GKV axis identifier (an integer or an axis

mnemonic) to specify the second ('y') axis for this plot. Note that if Grid2 is specified, it MUST correspond to an axis whose (integer) identifier is greater than that of Grid1 (user the INFO method to determine integer axis identifiers). Defaults to the

second independent variable. (Optional)

Indx1 Set this keyword (and its companion, Indx2) to set values at which

the remaining independent variables to determine where the

dependent variable should be 'sliced'. (Optional)

Runtime Keywords:

mnemonic

Set this keyword to a two-element floating point array (IDL will automatically convert integer arrays) to specify the plotting range in the specified independent variable. (Optional)

OR

Set this keyword to a scalar to specify the value at which the third (or fourth) independent variable should be 'sliced' for this plot. (Optional)

9.5 Pro Shade Surf

Usage:

Object ->Shade_Surf, keywords

Where *Object* is a valid *GKVsd* object of two or more dimensions. Produces a surface plot of the dependent variable in the currently open graphics window.

Keywords:

In addition to the usual IDL graphics keywords (see IDL Reference manual for a discussion of IDL graphics keywords), there are the following:

Pretty Set this keyword (i.e., put /Pretty on the command line) to use

Hershey vector fonts to make 'pretty' titles and labels. Default is

to just use ascii characters. (Optional)

Polar Set this keyword (i.e., put /Polar on the command line) to make a

polar plot. The first independent variable will be interpreted as the

radius, while the second will be interpreted as the angle.

PhaseShading For surface plots of complex data, unset this keyword (i.e., put PhaseShading=0 on the command line) to turn off "phase shading" (the default for complex data). With phase shading off

the surface is colored according to a scheme relating to the 'lighting', while the height is proportional to the real part of the dependent variable. When phase shading is turned on, the surface color is chosen according to the cosine of the phase of the complex

dependent variable, while the height of the surface is proportional

to its absolute value.

VRange Set this keyword to a two-element floating point array (IDL will

automatically convert integer arrays) to set the axis range for the

dependent variable. (Optional)

Log Set this keyword (i.e., put /Log on the command line) to make a

plot which is logarithmic in the dependent variable. (Optional)

Grid1 Set to any valid GKV axis identifier (an integer or an axis

mnemonic) to specify the first ('x') axis for this plot. Defaults to

the first independent variable. (Optional)

Grid2 Set to any valid GKV axis identifier (an integer or an axis

mnemonic) to specify the second ('y') axis for this plot. Note that if Grid2 is specified, it MUST correspond to an axis whose (integer) identifier is greater than that of Grid1 (user the INFO method to determine integer axis identifiers). Defaults to the

second independent variable. (Optional)

Indx1 Set this keyword (and its companion, Indx2) to set values at which

the remaining independent variables to determine where the

dependent variable should be 'sliced'. (Optional)

Runtime Keywords:

mnemonic Set this keyword to a two-element floating point array (IDL will

automatically convert integer arrays) to specify the plotting range

in the specified independent variable. (Optional)

OR

Set this keyword to a scalar to specify the value at which the third

(or fourth) independent variable should be 'sliced' for this plot.

(Optional)

9.6 Outputting Objects to a TIFF file

Many objects can be written into a TIFF file using the proceedure GKV_TiffOut.

Usage:

 $GKV_TiffOut, arg0, arg1, arg2, ..., keyword = value, ...$

This routine accepts GKV objects, GKV object arrays, or structures containing GKV objects as input. It produces a Tiff output file which displays each of these GKV objects.

Arguments: GKV_TiffOut accepts up to 10 arguments, each of which is

either a GKVsd object, an array of GKVsd objects, or a structure (any GKVsd objects in these structure will be displayed in the TIFF file produced by this command).

Keywords:

Pack Setting this keyword (i.e., putting '/pack/ on the command line)

will result in 4 plots per page in the output TIFF file. Default is one frame per page. (Optional) **NOT YET IMPLEMENTED**

FileName Set this keyword to an ascii string containing the name of the

desired output file. (Optional). Defaults:

If the argument is a single GKV object, then the fileName defaults to 'mnemonic'.tif, where 'mnemonic' is the mnemonic of the GKV object

mnemonic of the GKV object.

If the argument is a structure which includes the tag "Name", then the outfile name defaults to 'Name'.tif, where 'Name' is the (casii) contents of the tag "Name"

'Name' is the (ascii) contents of the tag "Name".

If no "fileName keyword is supplied, and the structure argument does not have a tag "Name", then the FileName

defaults to "GKV.tif".

Path Set this keyword to the path to the directory where the TIFF file is

to be stored. Defaults to the current working directory. (Optional)

Append Set this keyword (i.e., put "/Append" on the command line) when

calling GKV_TIffOut recursively to indicate that frames are to be

added to an existing TIFF file.

xSize x-dimension (in pixels) of resulting image. Defaults to 400.

(Optional)

ySize y-dimension (in pixels) of resulting image. Defaults to 400.

(Optional)

10. Producing Animations

A convenient and rapid way of producing an animation is to use:

10.1 Movie

Usage:

```
obj \rightarrow Movie, arg1, arg2, ..., keywords = value, ...
```

This procedure creates and displays an animation of the data contained in *obj* using the *XINTERANIMATE* tool provided as part of *IDL*. This tool also optionally allows you to produce and save MPEG files containing this animation (NOTE: you must request the MPEG license from RSI when you upgrade to *IDL* Version 5.4. This license doesn't seem to cost extra, but only appears on request ...).

Arguments: MOVIE only accepts arguments (as opposed to keywords)

when *obj* is a *GKVs2D* object (that is, a 2-D *GKVsd* object). In this case, the animation is a line drawing of a curve which will evolve in time. Any arguments provided should be either *GKVs2D* objects or arrays of *GKVs2D* objects which will be displayed (and evolve) on the same

frame as *obj*.

KeyWords:

imin Index within 'self' to the first frame of the animation.

Defaults to the first time-slice of 'self'. (Optional)

imax Index within 'self' to the final frame of the animation.

Defaults to the final time-slice of 'self'. (Optional)

'Mnemonic' Alternatively, you can specify the time-interval for the

animation in the format "Mnemonic = [start, end]", where "Mnemonic" is the mnemonic for the time-like (third) axis, while 'start' and 'end' are the values of the time-like

coordinate at the stare and end of the animation.

skip The animation uses only "iskip"th time-slice. Defaults to

the smallest integer such that the total number of frames in the animation is 128. NOTE: on many (but not LINUX) platforms IDL appears to limit the total number of PIXMAP windows (one PIXMAP window is required for each frame of the animation) to 128, so the user's choice of

iskip is overridden if it would result in more than 128 frame in the animation. (Optional)

npixels

The number of pixels to be used in each frame of the animation. If npixels is set to a scalar, a square window of (npixels x npixels) is produced. If npixels is set to a two-element array, then the a (generally) rectangular window of (nPixels[0] x nPixels[1]) is produced. Defaults to 400x400. (Optional)

Shade_Surf

The default plot is an *image* with colors chosen according the local data values. If this keyword is set (i.e., /Shade_Surf is put on the command line), then a surface plot is animated instead of an *image* (essentially, a color contour plot).

Graphics Keywords:

Any additional keywords specified on the command line will forwarded to the plotting routines, allowing the user to customize his animation.

The *XINTERANIMATE* tool is limited on many platforms as to the maximum number of frames, and provides little control of the quality of the animation. Hence, there is a need of alternative means of producing animations.

10.2 MPeg,

Usage:

```
Object \rightarrow MPEG, keyword = value, ...
```

This method makes an MPeg animation from a sequence of images from slices of 'self' at sequence of values the independent variable stored in self.Grid3 (this is generally the *unlimited*, or *time* variable). It creates an image of every iSkipth time slice of 'self', and stores the result into a file selected by the user. This can take awhile, so probably you'll want to get a nice cup of coffee while you're waiting for *IDL* to finish making the MGPEG animation. NOTE, this procedure will ONLY work with *IDL* Version 5.4 (or higher).

Input KeyWords:

iSkip Interval between timeslices to be animated. Defaults to 1 (Optional).

GKV User's Manual

-56-

trange	A two-element array	specifying the	first and last time-slices
6 -			

of this animation. Defaults to self.Grid3.range (Optional).

'mnemonic' The mnemonic of self.Grid3 can be used in place of the

keyword 'trange' with the same effect. Defaults to

self.Grid3.range (Optional).

Shade_Surf Set this KeyWord (i.e., '/Shade_Surf') to make a surface

plot instead of an image. Defaults to making 'image' plots

(Optional)

Path Set to path to folder where the MPeg animation is to stored.

Defaults to the current working directory (Optional).

FileName Name of the file containing the MPeg animation. Defaults

to 'self.mnemonic'.mpg. (Optional)

Xsize, Ysize The size of the frame in 'device' pixels. Defaults to xsize =

500, ysize = 500. (Optional)

Quality Set this keyword to an integer value between 0 (low

quality) and 100 (high quality) inclusive to specify the quality at which the MPEG stream is to be stored. Higher quality values result in lower rates of time compression and less motion prediction which provide higher quality MPEGs but with substantially larger file size. Lower quality factors may result in longer MPEG generation

times. The default is 50. (Optional)

ShowLoad Set this keyword to view images as they are loaded into the

MPeg file. Default is not to show images. (Optional)

10.3 Jpegs

Usage:

 $Object \rightarrow JPEGS$, keyword = value, ...

Utilities are available which can convert a sequency of images contained in separate files (this works MUCH better than trying to put all the images in the same file — believe me, as I tried that!) into animations. You are responsible for finding such a utility (e.g., the shareware utility GraphicCoverter for MACs). I've contented my self with providing convenient means within *GKV* of producing a directory full of image files.

Input KeyWords:

;iSkip Interval between timeslices to be animated. Defaults to 1

(Optional).

trange A two-element array specifying the first and last time-slices

of this animation. Defaults to self.Grid3.range (Optional).

'mnemonic' The mnemonic of self.Grid3 can be used in place of the

keyword 'trange' with the same effect. Defaults to

self.Grid3.range. (Optional).

Shade_Surf Set this KeyWord (i.e., '/Shade_Surf') to make a surface

plot instead of an image. Defaults to making 'image' plots

(Optional)

Path Set to path to folder where a new folder containing the

sequence of JPEG files is to be stored. Defaults to the

current working directory (Optional).

DirectoryName Name of the new folder to be created to contain the

sequence of JPEG files. Defaults to

"'Self.mnemonic'_Animation". (Optional)

FileRoot Sequence of JPEG files will have the names

FileRoot00000.jpg, FILERoot00001.jpg, ... Defaults to

self.mnemonic. (Optional)

Xsize, Ysize The size of the frame in 'device' pixels. Defaults to xsize =

600, ysize = 700. (Optional)

Quality Sets the quality index in the range of 0 ("terrible") to 100

("excellent") of the JPEG images to be produced. The default is 80 to produce "pretty good" quality. Lower values of "Quality" produce higher compression ratios and

smaller files. Default is Quality = 80. (Optional).

true This keyword specifies the index, starting at 1, of the

dimension over which the color is interleaved. For example, for an image that is pixel interleaved and has dimensions of (3, m, n), set TRUE to 1. Specify 2 for row-interleaved images (m, 3, n); and 3 for band-interleaved images (m, n, 3). If this keyword is not set, then WRITE_JPEG is called with true=1. You probably won't have to worry about this, as I believe *true* defaults to an

appropriate value. (Optional)

ShowLoad Set this keyword to view images as they are loaded into the

jpeg file. Default is not to show images. (Optional)

10.4 TIFFs

Usage:

 $Object \rightarrow TIFFs$, keyword = value, ...

This routine is used to provide a sequence of TIFF images for an animation of 'self' over the independent variable stored in self.Grid3. It creates a TIFF image of every iSkipth timeslice of 'self', and stores the result into a sequence of files in a directory selected by the user. These files can be used to produce animations as described in *GKVs3D::JPEGS* above.

Input KeyWords:

iSkip Interval between timeslices to be animated. Defaults to 1

(Optional).

trange A two-element array specifying the first and last time-slices

of this animation. Defaults to self.Grid3.range (Optional).

'mnemonic' The mnemonic of self.Grid3 can be used in place of the

keyword 'trange' with the same effect. Defaults to

self.Grid3.range. (Optional).

Shade_Surf Set this KeyWord (i.e., '/Shade_Surf') to make a surface

plot instead of an image. Defaults to making 'image' plots

(Optional)

Path Set to path to folder where a new folder containing the

sequence of TIFF files is to be stored. Defaults to the

current working directory (Optional).

DirectoryName Name of the new folder to be created to contain the

sequence of TIFF files. Defaults to "TIFF_Animation".

(Optional)

FileRoot Sequence of TIFF files will have the names

FileRoot00000.tif, FILERoot00001.tif, ... Defaults to

self.mnemonic. (Optional)

Xsize, Ysize The size of the frame in 'device' pixels. Defaults to xsize =

500, ysize = 500. (Optional)

ShowLoad Set this keyword to view images as they are loaded into the

TIFF file. Default is not to show images. (Optional)

11. Memory Management

11.1 FUNCTION MakeCopy

Usage:

result = object -> MakeCopy

Makes a 'deep copy' of *object* and places it into *result*. This differs from a simple assignment statement (*result* = *object*), which only gives a second name (*result*) to the data stored in *object*. Any action taken on *result* also modifies *object* because they both point to the **same** data. *MakeCopy* is an implementation of a 'deep copy' in which *result* points to an additional copy of the *object* data which has been created in memory. This allows you to act on *result* without acting on *object*.

11.2 PRO Trash

Usage:

object -> Trash

Deletes all data associated with *object*, thereby freeing up memory. Note that *Trash* does **not** remove *object* from IDL's symbol table (that is, from IDL's Variable Watch window). Once an object's data has been deleted with *Trash*, it can be removed from the symbol table with the IDL procedure **DELVAR** (Usage: *DELVAR*, *object*. See the IDL Reference manual for more info on DELVAR). Simply using DELVAR to remove an object from IDL's symbol table (without using *trash*) does not free up any of IDL's memory.

11.3 PRO GKVdelete, arg

Usage:

GKVdelete, arg

where *arg* is a variable, array (including arrays of GKVsd objects), or a structure (including structures which contain GKVsd objects). *GKVdelete* deletes all data associated with *arg* freeing up the memory. Like *Trash*, this will not remove *arg* from IDL's symbol table (which must be done with **DELVAR**).

11.4 Pro GKVsd::Save

Keywords:

FileName The name of the file in which the GKVsd object is to be saved.

Defaults to mnemonic.gkv, where mnemonic is the mnemonic of

the GKVsd object being saved. (Optional)

Usage:

```
object -> Save, FileName=filename
```

Saves a GKVsd object to disk using IDL's XDR format (see **SAVE** in the IDL Reference manual for more information on XDR, but note that IDL's save routine is NOT a method on GKVsd objects and you cannot expect the keywords of IDL's save routine to work in this context).

11.5 FUNCTION GKV_RESTORE

Usage:

```
result = GKV_Restore(FileName=filename)
```

This procedure restores a GKVsd object which has previously been *Save*d (with *GKVsd::Save*) into *filename*. The restored GKVsd object is stored in *result*.

Keywords:

FileName The name of the file in which a GKVsd was saved. If FileName is

not provide, DIALOGUE_PICKFILE will allow the user to select

an appropriate file. (Optional)

11.6 Procedure GKV_SaveArray

Usage:

```
GKV_SaveArray, ObjArr
```

This procedure saves the array of *GKVsd* objects specified by , *ObjArr* to disk. It does this by first creating a new directory ("Directoryname_arr") and then writing separate .gkv file (see *GKVsd::Save*) with names FamilyName.index.gkv, where 'index' is the

zero-based array index into *ObjArr*. Unfortunately, this procedure will only work with *IDL* Version 5.4 (or greater).

Input Argument: The (required) input argument, *ObjArr* must be an

array of GKVsd objects, which will be saved to disk

by this procedure.

Input Keywords

Path to working directory in which the new

directory, "DirectoryName_arr", containing the '.gkv' save files will be created. Defaults to current

working directory. (Optional)

DirectoryName Name of the new directory to be created within the

directory specified by "Path". Defaults to the mnemonic of ObjArr[0] (or, "GKVsd_arr", if

ObjArr[0] has no mnemonic). (Optional)

Family Name Family name of the sequence of .gkv files. Defaults

to the mnemonic of ObjArr[0] (or, "GKVsd", if

ObjArr[0] has no mnemonic). (Optional)

Debug Set this keyword (i.e., put "/Debug" on the

commandline) to print out intermediate information which may be useful in debugging this procedure

11.7 Function GKV_RestoreArray

Usage:

 $ObjArr = GKV_RestoreArray(keyword = value, ...)$

This function returns an array of GKVsd objects which have previously been saved to disk using GKV SaveArray (see §11.6 above).

Input Keywords

Path to working directory in which the new

directory, "DirectoryName", containing the '.gkv' save files were created. Defaults to current working

DirectoryName Name of the directory (within the working directory

specified by 'Path') containing the '.gkv' save files.

If not specified the user will pick DirectoryName

with "Dialog_Pickfile". (Optional)

FamilyName The Save files should have a name of the form

'FamilyName'.'index'.gkv. If not specified *GKV* will extract 'FamilyName' from the first file

returned by "FINDFILE". (Optional)

Debug Set this keyword (i.e., put "/Debug" on the

commandline) to print out intermediate information which may be useful in debugging this procedure

11.8 Procedure GKV_SaveStructure

Usage:

GKV_SaveStructure, structure

;This procedure save a structure (possibly containing *GKVsd* objects) onto to disk. It does this by first creating a new directory ("Directoryname_str") and then writing separate SAVE files using *GKVsd::Save*, *GKV_SaveArray*, and the native *IDL* SAVE routine as appropriate

;Input Argument: The (required) input argument, *structure* must bean

anonymous structure which may contain GKVsd

objects and/or GKVsd object arrays

Input Keywords

Path to working directory in which the new

directory, "DirectoryName_str", containing the '.gkv' save files will be created. Defaults to current

working directory. (Optional)

DirectoryName Name of the new directory to be created within the

directory specified by "Path". Defaults to the contents of *structure.name* with "_*str*" appended if such a tag exists within *structure*, If no such tag

exists, then default is *GKVsd_str*. (Optional)

Debug Set this keyword (i.e., put "/Debug" on the

commandline) to print out intermediate information which may be useful in debugging this procedure

11.9 FUNCTION GKV_RestoreStructure

Usage:

```
structure = GKV RestoreStructure( keyword = values, ... )
```

This function returns a structure (possibly containing *GKVsd* objects or arrays of *GKVsd* objects) which has previously been saved to disk using *GKV_SaveStructure* (see §11.8 above)

Input Keywords

Path to working directory in which the new

directory, "DirectoryName", containing the various save files and subdirectories was created. Defaults

to current working directory. (Optional)

DirectoryName Name of the directory within the working directory

specified by 'Path' containing the various save files and subdirectories. If not specified, the user will pick DirectoryName with "Dialog_Pickfile".

(Optional)

Debug Set this keyword (i.e., put "/Debug" on the

commandline) to print out intermediate information which may be useful in debugging this procedure

11. Basic GKVsd Object Management

11.1 Procedure Info

Usage:

Prints out information about *object* to the IDL log window. This includes the object's mnemonic, title, indices, units, range of values, CodeName, CodePI, RunID, and FileID. For each of the object's independent variables the corresponding mnemonic, title, units, boundary condition, uniformity (of the grid), range, and signal window (irange) are printed out. All this can be helpful if you don't recall current state of a particular GKVsd object.

11.2 Function Cat

Usage:

```
result = Object \rightarrow CAT(arg1, arg2, arg3, ...)
```

This function, which accepts up to 10 arguments, concatenates its argument(s) with *Object* and returns the result. *Object* is left unaltered. It returns a *GKVsd* object of the same dimensionality as *Object* in which the data and grid (independent variable) values from 'arg1' & Co. have been concatenated behind those of 'self'. Concatenation is done *ONLY* in the last (generally, time-like) argument.

Input Arguments:

Cat is generally called with at least one argument, which must be a *GKVsd* object of the same dimensionality as *Object*. If *CAT* is called with no argument, or with inappropriate arguments, then CAT returns a (deep) copy of *Object*.

11.3 FUNCTION SubSample

Usage:

```
Result = Object -> SubSample(Arg, keyword = value, ...)
```

This function returns a GKVsd object of the same dimensionality as *Object* in which the data of *Object* has been 'subSampled' onto a uniform grid of 'nSteps' (see keyword descriptions below) over the selected independent variable.

Argument:

Arg The (optional) argument is any legal axis identifier.

That is, either an integer between 1 and nDims, or a

STRING containing an axis mnemonic.

Keywords:

Axis If no argument is provided, then this keyword may

be used to identify independent variable to be subsampled. Set axis equal to any legal axis

identifier (see above).

mnemonic Set the mnemonic of the selected axis equal to a

two-element array, [min, max], to both identify the independent variable to be subsampled, and to reset the signal window on this axis (before subsampling). This two-element array is interpreted as the desired RANGE in the independent variable.

NOT the integer 'irange'

irange Set 'irange' to a two-element (integer) array to reset

the signal window before subsampling on the

selected independent variable.

range Set 'range' to a two-element (floating point) array to

set the range in the independent variable over

subsampling is performed

nSteps The desired number of gridpoint for the selected

axis. Defaults to no change in number of grid

points over Object's SignalWindow. (Optional).

DownBy Decrease number of grid points by a factor of

'Downby'. Defaults to no change in number of grid

points in Object' SignalWindow. (Optional).

Dt Desired size of the uniform sampling interval in the

output grid. Defaults to no change in number of

grid points in Object's SignalWindow. (Optional).

11.4 GKVs1D::Squash

Usage:

result = Object -> Squash(arg)

This function method returns a *GKVs1D* object with the data of *Object* as the dependent variable, and the data of *arg* as the independent variable. Plots of *result* can be used to check for relationships between data objects.

Argument; arg must be a GKVsd object of the same

dimensionality as Object, with the same

independent variables.

Input Keywords

Title Should be set equal to a *String*, which becomes the

Title for output object. Defaults to title of Object.

(Optional)

Mnemonic Should be set equal to a *String*, which becomes the

Mnemonic for output object. Defaults to mnemonic

of *Object*. (Optional)

11.5 PRO SignalWindow,

Keywords:

Axis Set to any legal axis identifier—either an integer between 1 and the

dimensionality of the object to be acted on, or the mnemonic of

one of the independent variables.

range Set to a two-element floating point array (IDL will automatically

convert integer arrays) to set the range of the signal window for the

selected independent variable in its proper units.

irange Set to a two-element integer array to set the range of grid-indices

of the selected independent variable corresponding to its signal

window.

RunTime Keywords:

mnemonic

Set *mnemonic* to a two-element floating point array (IDL will automatically convert integer arrays) to set the range of the signal window for the independent variable identified by *mnemonic* in its proper units.

Usage:

object -> SignalWindow, keywords

The signal window is used to select a portion of the data for analysis. GKV analysis routines act only on data within the current signal window. For example, if you are interested in examining the linear phase from a non-linear simulation run you would set the signal window in time such that it covered just the initial transients before non-linear effects become important. Conversely, if you are interested in fully developed turbulence, set the signal window to exclude initial transients from further analysis.

11.6 PRO GET

Usage:

object -> GET, keyword=value, ...

If you find that you are frustrated with the dictum "Only an object's methods can access an object's data", use this "GET" (and the corresponding "SET") to work around it.

Keywords:

mnemonic Mnemonic associated with GKVsd object

Title of GKVsd object (used on 'pretty' plots)

Indices An array used to properly label GKVsd plots...

units Units of dependent variable

values a POINTER to the GKVsd object's values

vrange Range of dependent variable values for plots

ErrorBars a POINTER to ErrorBars (of provided)

Code Name Code in which data was created

CodePI Additional info on this code

RunID Information on particular code run

FileID Additional information on code run

11.7 PRO SET

Keywords: See discussion under GKVsd

Usage:

```
Object -> Set, keyword=value
```

If you find that you are frustrated with the dictum "Only an object's methods can access an object's data", use this "SET" (and the corresponding "GET") to work around it.

11.8 FUNCTION GetValues

Usage:

```
result = object -> GetValues
```

Returns a POINTER to an array containing those values of the dependent variable which lie within the object's SignalWindow. For 0-D GKVsd objects ONLY, it returns the (scalar) value rather than a pointer to this value.

11.9 FUNCTION GKVsND_Gen

Usage:

```
result = GKVs1D(keywords)

result = GKVs2D(keywords)
```

Output is a valid GKVsd object of the specified dimensionality containing sample data with requested Fourier spectrum (and no correlations between Fourier modes), where N is an integer between 1 and 4 specifying the dimensionality of the object to be generated. The corresponding independent variables are (x, y, z, t).

Keywords:

Nx, Ny, Nz, Nt Number of grid points in specified variable.

(Optional)

Amplitude The amplitude of the signal to be generated.

(Optional)

kx, ky, kz, omega The central wavenumber (frequency) in the specified

independent variable of the signal to be generated.

(Optional)

Del_k=bandwidth The bandwidth of the signal to be generated.

(Optional)