Boot to a virtual hard disk: Add a VHDX or VHD to the boot menu

10/05/2021

Native Boot allows you to create a virtual hard disk (VHDX), install Windows to it, and then boot it up, either on your PC side-by-side with your existing installation, or on a new device.

A native-boot VHDX can be used as the running operating system on designated hardware without any other parent operating system. This differs from a scenario where a VHDX is connected to a virtual machine on a computer that has a parent operating system.

Native boot for Windows 10 or later requires the .vhdx format, not the .vhd format.

VHDXs can be applied to PCs or devices that have no other installations of Windows, without a virtual machine or hypervisor. (A hypervisor is a layer of software under the operating system that runs virtual computers.) This enables greater flexibility in workload distribution because a single set of tools can be used to manage images for virtual machines and designated hardware.

You can also deploy the VHDX to a PC that already has Windows installed on it, and use a boot menu to select between the existing version of Windows, or the version on the VHD.

To learn more about using VHDXs in an enterprise environment, see Understanding Virtual Hard Disks with Native Boot.

Prerequisites

- A technician PC with the Windows Assessment and Deployment Kit (Windows ADK) tools installed on it.
- A generalized Windows image (.WIM file). To learn more, see Sysprep (Generalize) a Windows installation.
- A bootable Windows PE drive. To learn more, see WinPE: Create USB Bootable drive.
- A destination PC or device on which to install the VHDX. This device requires 30 gigabytes (GB) or more of free disk space. You can install the VHDX to a device already running other operating system installations, or as the only operating system on a device.

Step 1: Create a VHDX from diskpart

On the technician PC:

1. From the Command Prompt, open Diskpart.

Windows Command Prompt

diskpart

2. Create and prepare a new VHDX. In this example, we create a 25 GB fixed-type VHDX.

Windows Command Prompt

create vdisk file=C:\windows.vhdx maximum=25600 type=fixed

3. Attach the VHDX. This adds the VHDX as a disk to the storage controller on the host.

Windows Command Prompt

attach vdisk

4. Create a partition for the Windows files, format it, and assign it a drive letter. This drive letter will appear in File Explorer.

Windows Command Prompt

create partition primary
format quick label=vhdx
assign letter=v

1 of 4 8/2/25, 07:23

5. Exit Diskpart

```
Windows Command Prompt

exit
```

Step 2: Apply a Windows image to the VHD

On your technician PC, apply a generalized Windows image to the primary partition of the VHDX that you created and attached in Step 1.

```
Windows Command Prompt

Dism /Apply-Image /ImageFile:install.wim /index:1 /ApplyDir:V:\
```

Step 3: Detach the VHD, copy it to a new device, and attach it (optional)

You can deploy the VHDX to a device that already has a copy of Windows installed on it, or you can clean and prepare the destination PC's hard drive to use the VHD.

Detach the VHDX and save it to a network share or storage drive

1. Use diskpart to detach the virtual disk from your technician PC.

```
Windows Command Prompt

diskpart
select vdisk file=C:\windows.vhdx
detach vdisk
exit
```

2. Copy the VHDX to a network share or removable storage drive. The following maps a drive letter to a network share, creates a directory for the VHD, and then copies the VHD.

```
Windows Command Prompt

net use n: \\server\share\
md N:\VHDs
copy C:\windows.VHDX n:\VHDs\
```

Clean and prepare a new device for native boot

On your destination PC:

- 1. Use your bootable WinPE key to boot the destination PC to WinPE.
- 2. Clean and prepare the destination PC's hard drive. Create a system partition (S), and a main partition (M) where the VHDX will be stored.

UEFI:

2 of 4 8/2/25, 07:23

BIOS:

3. Connect to the network drive or storage location where you copied the VHDX in step 3.2.

```
Windows Command Prompt

net use N: \\server\share
```

4. Copy the VHDX from the network drive or storage location to the destination PC's main partition.

```
copy N:\VHDs\Windows.vhdx M:
```

Attach the VHDX

1. While still booted into WinPE, attach your VHDX to the destination PC.

```
Windows Command Prompt

diskpart
select vdisk file=M:\windows.vhdx
attach vdisk
```

2. Identify the attached VHDX's volume letter. (Optional: Change it to another letter that makes more sense, for example V, and leave the diskpart command line open for the next step).

```
Windows Command Prompt

list volume
select volume 3
assign letter=v
```

Step 4: Add a boot entry

1. From your destination PC, open Diskpart (if necessary) and identify the drive letters of the VHDX and the system partition, for example, V and S.

```
Windows Command Prompt

diskpart
```

3 of 4 8/2/25, 07:23

```
list volume
exit
```

2. Add a boot entry to the device. You can add multiple VHDX files using this method.

UEFI:

```
V:\
cd v:\windows\system32
bcdboot v:\windows /s S: /f UEFI
```

BIOS:

```
V:
cd v:\windows\system32
bcdboot v:\windows /s S: /f BIOS
```

- 3. Remove the WinPE USB key.
- 4. Restart the destination PC.

If there's only one boot entry, the device immediately boots to Windows. If there's more than one boot entry, you'll see a boot menu where you can choose between the available versions of Windows on the device.

Related topics

Understanding Virtual Hard Disks with Native Boot

BCDboot Command-Line Options

4 of 4