## TeX 主题选讲

TeX 技术员手册

Victor Eijkhout 翻译:LiYanrui, zoho, Liam0205

 $document\ revision\ 1.4,\ December\ 2013$ 

Copyright © 1991-2013 Victor Eijkhout.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

This document is based on the book TEX by Topic, copyright 1991-2008 Victor Eijkhout. This book was printed in 1991 by Addison-Wesley UK, ISBN 0-201-56882-9, reprinted in 1993, pdf version first made freely available in 2001.

Cover design (lulu.com version): Joanna K. Wozniak (jokwoz@gmail.com)

# 目录

	许可证	•	٠	•	•	•	٠	•	٠	•	٠	٠	•	٠	. 4
	前言						•				•				· 13
1	TEX 处理器的	的结构	勾.			•					•	•			· 15
2	分类码与内部	8状态	<u>,</u>			•					•	•			. 22
3	字符・・・		•			•					•	•			. 39
4	Fonts ·		•			•					•	•			. 48
5	Boxes ·														. 54
6	Horizontal a	nd V	ertic	al M	ode										· 73
7	Numbers ·		•			•					•	•			· 81
8	Dimensions	and	Glue			•					•	•			. 91
9	Rules and L	eadeı	rs			•					•	•			· 105
10	编组		•								•				· 113
11	宏定义		•			•					•	•			· 117
12	Expansion		•			•					•	•			· 133
13	Conditionals	· ·	•			•					•	•			· 151
14	Token Lists		•			•					•	•			· 166
15	基线距离														· 171
16	Paragraph S	tart													. 176
17	Paragraph E	nd													. 182

<u>目录</u> 3

18	段落形状		•	•					•					187
19	Line Breakin	g												193
20	Spacing ·				•	•		•		•	•	•		205
21	Characters in	n Mat	th M	lode	·	•	•	•	•	•	·	·		211
22	Fonts in For	mulas	ş.	•	·	•	•	•	•	•	·	·		218
23	Mathematics	<b>Тур</b>	eset	ting	·	•	•	•	•	•	·	·		223
24	Display Matl	h·	•	•	·	•	•	•	•	•	·	·		236
25	Alignment		•	•		•			•	•				242
26	Page Shape				•	•		•		•	•	•		253
27	分页·		•	•		•			•	•				256
28	Output Rout	ines				•				•				264
29	Insertions													271
30	File Input an	ıd Ou	tput			•				•				277
31	Allocation													284
32	Running TEX					•								287
33	T <sub>E</sub> X and the	Outs	side '	Worl	ld	•								290
34	Tracing					•								302
35	Errors, Catas	stropl	nes,	and	Help									307
36	The Gramma	ar of	T <sub>E</sub> X			•				•				313
37	Glossary of T	Γ <u>E</u> X P	Primi	tives	; ·									318
38	编码表格					•								338
	索引					•								353
	参考文献									•				353
	版本历史													353

Version 1.2, November 2002

Copyright © 2000,2001,2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

#### 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for in-

put to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

#### 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced

in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission. B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement. C. State on the Title page the name of the publisher of the Modified Version, as the publisher. D. Preserve all the copyright notices of the Document. E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices. F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below. G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice. H. Include an unaltered copy of this License. I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence. J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission. K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given

therein. L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles. M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version. N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section. O. Preserve any Warranty Disclaimers. If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

#### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are

multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements."

#### 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

#### 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

#### 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

#### 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

#### 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## 前言

对于偶然了解到 **TeX** 的人来说,它并不是时下最先进的排版系统。它没有时髦的多级菜单,也没有对文本图片交互式的操作方式。然而,在更深层次,**TeX** 是一个精致的程序:首先是因为,**TeX** 内置的断行算法和数学公式排版算法十分精巧;其次是因为,它几乎是完备程序性的。这些因素使得 **TeX** 可以高度自动化地实现几乎所有能想到的排版布局。

不幸的是,这也意味着 **T<sub>E</sub>X** 有非常多的命令和参数;因此进行 **T<sub>E</sub>X** 编程远谈不上简单。每一个想要进行 **T<sub>E</sub>X** 编程的人,大概都得看两本书:一本新手引导,介绍 **T<sub>E</sub>X** 的基本内容;以及一本系统而完全的手册。本书属于后者。入门后的 **T<sub>E</sub>X** 用户(无论阅读了市面上多少本入门书)即可阅读本书。

本书将 **T<sub>E</sub>X** 划分为大约 **40** 个主题,每个主题一章。在每章开头,本书会列出和 当前章节有关的控制序列。大多数章节都有内容介绍和示例参考。

大体上说,本书的结构如下。首先讲解基本机制,而后介绍有关文本和数学处理的内容,最后会有几章介绍 TeX 与外界的联系。借助示例、控制序列和主题,本书也包含了有关 TeX 命令、表格、索引的术语表。根据主题,大多数概念可以索引至具体一页;在这一页上,读者能找到有关该主题的大部分内容,也能了解去何处查阅相关信息。

本书没有涵盖任何具体的 TeX 宏包。有关 plainTeX 格式的内容,本书也只介绍其中最核心的部分:它们 LATeX 等格式的一部分。因此,大多数关于 plainTeX 格式的内容对于 LATeX 和其他格式也仍然适用。特别地,如果文中明确指出相关段落是对plainTeX 的介绍,那么这些内容是有关纯 IniTeX 的,而与 LATeX 无关。为方便讲述,本书偶尔也会介绍一些 plainTeX 的非核心宏。

#### 致谢

承蒙 Barbara Beeton、Karl Berry 以及 Nico Poppelier 阅读本书初稿。在他们的帮助下,本书的陈述有所提高。同时感谢以下讨论列表中的参与者: TpXhax、TpX-nl以及 comp.text.tex。他们提出的问题和给出的回答给予我思考之食粮。最后,任何一本有关 TpX 的书,都应向 TpX 的发明者 Donald Knuth 致敬。本书也不例外。

Victor Eijkhout

14 前言

厄巴纳, 伊利诺伊州, 1991 年 8 月 诺克斯维尔, 田纳西州, 2001 年 5 月 奥斯汀, 德克萨斯州, 2013 年 12 月

## 第1章 TEX 处理器的结构

本书涵盖了 **TeX** 诸多方面的内容;其中每一章都讲述一个相对较小且易于描述的主题。本章将简介 **TeX** 处理文档的基本流程。当然,本章会忽略很多细节,留待后续章节继续讨论。相应的,为了说明问题,本章会给出一些例子;这些例子在后续的这些章节中会继续讨论。

## 1.1 TEX 的 4 个处理器

**TeX** 处理输入的过程可分为 **4** 个阶段。你可以认为 **TeX** 处理器 (也称 **TeX** 引擎)有 **4** 个独立的单元,每个单元接收前序步骤的输出,并将输出作为后续单元的输入。第一阶段的输入是.tex 文件,最后一个阶段的输出是.dvi 文件<sup>1</sup>。

4 个阶段列举如下(按 Knuth 最初的叫法,分别是「眼睛」、「嘴巴」、「胃」和「肠道」):

- 1. 输入处理器(input processor):负责从运行 TeX 的计算机的文件系统中读入输入,并处理为记号。记号是两种 TeX 内部对象的统称:构成排版文本的字符记号、待后续两个阶段作为命令处理的控制序列记号。
- 2. 展开处理器 (expansion processor): 负责展开输入处理器输出的部分记号: 宏、条件式、以及部分 TeX 原语。记号展开的过程会将一些(连续的)记号删除或替换为其它记号。
- **3.** 执行处理器(execution processor): 不可展开的控制序列即是可执行的; 执行处理器负责执行这些可执行的控制序列。

执行处理器的部分活动涉及到 **TpX** 的内部状态之变化:赋值(包括宏定义)是其中典型。除此之外,执行处理器负责构造水平列表、垂直列表和数学列表。

 $<sup>^1</sup>$ 译注(Liam0205):此处讨论的 TpX 是 Knuth TpX。后续扩展的 pdfTpX 等不一定输出 .dvi 文件。

<sup>&</sup>lt;sup>2</sup>译注(Liam0205):流式处理,上一阶段处理完多少,下一个阶段就接着继续处理这部分。

4. 可视化处理器 (visual processor): TeX 的最后一个阶段负责排版内容的可视化。可视化处理器将水平列表分行成段,将垂直列表分割成页,将数学列表构建成数学公式; 最终输出 .dvi 文件<sup>3</sup>。可视化处理器的内部算法对于用户是不可见的;不过用户可以通过一系列参数来控制。

## 1.2 输入处理器

输入处理器是 TeX 的一部分,负责将 TeX 从输入文件中读入的内容翻译成记号。它的输出是记号流(stream of tokens):记号组成的列表。大部分记号属于以下两类:字符记号和控制序列记号。还有一类记号是参数记号,留待后续章节讨论。

#### 1.2.1 字符的输入

对于简单的输入文本,其中的字符被输入处理器翻译为字符记号。在某些情况下,**T<sub>E</sub>X** 会忽略一些输入字符;例如,连续空格通常等价于单个空格。此外,**T<sub>E</sub>X** 也会向记号流中插入一些与输入字符无关的记号。例如在每一行的末尾插入一个空格,以及在每一个空行末尾插入一个\par 记号。

并非所有的字符记号都会被最终排版出来。事实上,在  $T_EX$  中,字符被分类为 16 类 —— 每一类都有特定的功能 ——而只有两类最终会被排版出来。其它字符类,像  $\{\cdot\}\cdot$ & 和 #,都不会被排版出来。也就是说,在  $T_EX$  中,字符记号的含义由字符编码(通常是 ASCII 编码)和分类码这一对数字共同决定。而具体某一编码的字符对应的分类码是可以修改的。

当输入处理器遇到转义字符时(默认是\),它会将转义字符之后的若干连续个字符拼在一起,形成一个控制序列记号。

在分类码的影响下, $T_{E}X$  输入处理器的行为可视作是一个在三种内部状态 (N, 新行;M,行内;S,忽略空格)中切换的机器。第 2 章将讨论这些状态及其切换。

## 1.2.2 输入处理器的两个阶段

TeX 的输入处理器本身也可分为两个阶段。因为一些限制(来自终端、编辑器或者操作系统),某些字符可能很难输入。为此,TeX 设计了一套机制来表达这些字符:以两个连续的上标字符来获取所有可用字符。这套机制可视作输入处理器中相对独立的阶段;它运行于上述三状态机之前。

例如,由于 k 和 + 的 ASCII 码之差为 64, 所以 ^^+ 会被输入处理器等价地转换为 k。由于这种替换机制发生在形成记号之前,所以输入 \vs^^+ip 5cm 与输入 \vskip 5cm 是等价的。某些情况下,这种用法是很有用的。

³译注(zoho):对于现代 TrX 处理器而言,还可以是 pdf 和 xml 等文件。

1.3 展开处理器 17

注意,这是 **TeX** 输入处理器的第一阶段,它不考虑分类码,而只是一个从字符到字符的变换。分类码只在输入处理器的第二阶段才起作用:字符的编码和分类码组合在一起,变成一个字符记号。

## 1.3 展开处理器

**TeX** 的展开处理器接受记号流,并将记号流里的记号逐一展开,直到再无可展开记号为止。宏展开即是其中一例:如果一个控制序列是一个宏名,则根据定义,它将(和可能的参数记号一起)被替换。

展开处理器的输入主要来自输入处理器。自输入处理器而来的记号流被展开处理器展开成仅含有不可展开记号的记号流,最终流向执行处理器。

此外,在处理类似 \edef 及 \write 命令时,展开处理器也会参与工作。这些命令的参数记号会被直接展开,变成顶层的替换文本,而不是这些命令的参数。

#### 1.3.1 记号的展开过程

记号展开的步骤如下:

- 1. 确认当前待处理的记号是否可展开。
- 2. 若当前待处理的记号不可展开,则直接将其加入正在构建的记号列表中,并读入下一个记号。
- 3. 若当前待处理记号可展开,则将其替换为其展开。对不带参数的宏以及一些 TeX 原语(例如 \jobname),该过程只需简单地进行记号替换即可。不过,通常 TeX 需要从输入流中读取一些参数记号,以便构造当前待处理记号的替换形式。举 例说,对于带参数的宏,TeX 将读取足够的参数(parameters)记号,而后将这些 参数记号作为宏的参数(arguments)。
- 4. 将展开结果的第一个记号作为待处理记号,继续展开。

宏的可展开性之判断很简单:所有的宏、活动字符、条件式以及部分 **TeX** 原语(见第 **134** 页的列表)是可展开的,其他记号都不可展开。因此,展开处理器会负责诸如将宏替换为其展开、对条件是求值而后忽略条件为假的部分的任务;诸如 \vskip、字符记号(包括美元符号和花括号)则原封不动地传到输出流。

## 1.3.2 几个特例:\expandafter\noexpand 及 \the

如前所述,记号被展开后, $T_{PX}$ 会继续展开其展开后得到的记号<sup>4</sup>。

<sup>&</sup>lt;sup>4</sup>译注(Liam0205):展开处理器负责「展开到底」,但展开结果中可能存在需要继续展开的记号。

\expandafter 是一个特例。初看之下,它只做一步展开,因而破坏了这个规则。 例如说,

 $\ensuremath{\mbox{\sc version}} \ensuremath{\mbox{\sc versio$ 

会被替换为

 $\langle token_1 \rangle \langle expansion \ of \ token_2 \rangle$ 

但实际上,这个替换结果还会被展开处理器再次处理5。

\noexpand 是另一个特例。当 TeX 遇到 \noexpand,则其下一个记号会被展开处理器当做是不可展开的。因此,展开处理器会把 \noexpand 的下一个记号当做是 \relax 那样,直接将其加入正在构建的记号列表。

举例说,以下宏定义中,其替换文本 \noexpand\b 会在宏定义时被展开:

\edef\a{\noexpand\b}

\noexpand 展开后,其后的记号暂时会被当做是\relax 的意思。于是,当展开处理器处理下一个记号\b时,认为它是不可展开的,并将其直接加入正在构建的记号列表中。因此\b就是这个宏的替换文本。

\the 也是一个特例。在 \edef 宏定义中, \the \token variable \} 的展开结果不会被继续展开。

#### 1.3.3 展开处理器中的花括号

之前提到,展开处理器将花括号视为不可展开的字符记号。通常而言,这没错。例如说 TpX 在展开下列 \romannumeral 控制序列时,会一直展开,直到遇见花括号:

\romannumeral1\number\count2 3{4 ...

因此,如果 \count2 的值是 0,那么这个控制序列的展开结果是 103 的罗马数字表示。又例如说,展开处理器对待

\iftrue {\else }\fi

的方式与对待

\iftrue a\else b\fi

的方式完全一致;即:此时 { 只是一个字符记号,与它的分类码无关。

不过,在宏展开的上下文中,展开处理器会识别和处理花括号。首先,配对的花括号内可用于将其内的一组记号标记为宏的参数。例如,下面定义的单参数宏:

\def\macro#1{ ... }

你可以单传一个参数来调用它:

\macro 1 \macro \\$

<sup>5</sup>译注(Liam0205):因而不算完全破坏了规则。

1.4 执行处理器 19

也可以使用配对的花括号包裹一组记号作为宏的参数:

```
\macro {abc} \macro {d{ef}g}
```

其次,对于带参数的宏,其参数中不得包含未配对的花括号。例如,如下定义的 \a 带有一个参数:包含从 \a 之后开始,直到遇见第一个花括号外的 \stop 位置的全部记号。

```
\def\a#1\stop{ ... }
```

对于以下用法, \a 的参数应当是 bc{d\stop}e; 因为宏的参数中花括号必须是配对的。

\a bc{d\stop}e\stop

## 1.4 执行处理器

执行处理器构建水平列表、竖直列表和数学列表。与之相应,执行处理器有三种工作模式:水平模式、竖直模式、数学模式。这三种模式又分别有「内部」和「外部」两种类型。除了构建列表,执行处理器还需要处理一些与模式无关的操作,例如赋值。

执行处理器的输入是展开处理器输出的不可展开记号组成的流。在执行处理器 看来,这条记号流中有两种类型的记号:

- 触发赋值操作(包括宏定义)的记号,以及触发与模式无关的其他操作的记号(例如 \show 和 \aftergroup)。
- 构建列表的记号:字符、盒子、粘连。执行处理器对它们的处理方式根据所处模式的不同而改变。

有些记号在所有模式下都可用;比如盒子可用于水平、竖直、数学三种模式。当然,这些记号的作用与效果,根据所处的模式不同而不同。也有记号只在特定模式下可用。例如说,字符记号(确切说是分类码为 11 和 12 的字符记号)则与水平模式密切相关:当执行处理器在竖直模式中遇到字符记号时,会切换到水平模式继续工作。

并非所有字符记号都是可排版的。执行处理器可能遇到数学模式切换标志(默认是\$)、分组起止符(默认是{和})。当执行处理器遇到数学模式切换标志时,它会进入或退出数学模式;而分组起止符则让执行处理器进入或退出新的一层分组。

控制序列 \relax 有些特别:该控制序列是不可展开的,同时执行时啥也不做。 为说明 \relax 的作用,可与 \empty 进行比较。\empty 的定义如下:

\def\empty{}

使用 \relax 时, 因其不可展开, 故而下例中计数寄存器被赋值为 1:

\count0=1\relax 2

使用 \empty 时, 因 \empty 的展开结果为空, 故而下例中计数寄存器被赋值为 12:

 $\count0=1\ensuremath{\count0}$ 

## 1.5 可视化处理器

TeX 的可视化处理器使用了若干用户不可直接控制的算法:断行、切齐、分页、数学排版以及 dvi 文件生成算法。尽管用户不可直接控制这些算法,但可通过一些参数,间接控制它们。

这些算法当中,部分算法的输出结果可被执行处理器继续处理。例如说,分段成行得到一系列行组成的列表;这些行会被加入主竖直列表当中;而每一行又是由若干水平盒子及其中的行间粘连和惩罚组成的。又例如说,分页算法将其结果保存在\box255当中;而后交由输出例程继续处理<sup>6</sup>。其余算法的输出结果则不然,例如数学公式不可以分解,又例如输出至 dvi 文件的盒子也是不可逆的。

#### 1.6 示例

#### 1.6.1 被忽略的空格

被忽略的空格可以反映数据在 TrX 各处理器之间的流动情况。例如:

```
\def \a{\penalty200}\a 0
```

展开的结果不是(设置惩罚项为200,并排版数字0)

```
\penalty200 0
```

而是

\penalty2000

这是由于输入处理器会忽略 \a 后的空格,因此展开处理器的输入流中的内容是:\a0

## 1.6.2 内部量值及其表示

**T<sub>E</sub>X** 使用了多种内部量,比如说整数和尺寸。这些内部量的外部表示是同一的:字符组成的字符串。例如 4711 和 91.44cm。

内部量与外部表示之间的转换发生在执行处理器或展开处理器中。具体来说,外部表示向内部量的转换发生在执行处理器中:

```
\pageno=12 \baselineskip=13pt
\vskip 5.71pt
```

内部量向外部表示的转换发生在展开处理器中:

<sup>&</sup>lt;sup>6</sup>译注(Liam0205):最简单的是 \output{\shipout\box255}。

1.6 示例 21

\number\pageno \romannumeral\year
\the\baselineskip

最后再举一例。假设\count2=45,则下列代码

\count0=1\number\count2 3

首先将 \number\count2 被展开为字符串 45, 注意 \count2 后的空格被用于界定 计数器编号而已被展开。因此,下一级处理时,执行处理器看到并执行的是:

\count0=1453

## 第2章 分类码与内部状态

读取字符时, $\mathbf{T}_{\mathbf{p}}\mathbf{X}$  的输入处理器会为字符分配分类码。根据读取到字符的分类码,输入处理器会在三种内部状态之间切换。本章讨论  $\mathbf{T}_{\mathbf{p}}\mathbf{X}$  是如何读取字符的,以及字符的分类码是如何影响读取行为的。本章还将讨论空格及行尾<sup>1</sup>的相关问题。

\endlinechar 该命令是输入处理器添加至输入行尾的行终止符的字符编码。在 IniTpX 中默认是 13。

\par 该命令结束当前自然段,并使 TeX 进入竖直模式。输入处理器会将(连续或单个的)空行转换成它。

\ignorespaces 该命令展开时读取连续的空格,直到遇见非空格记号(non-\space token\))后停止展开。

\catcode 该命令用于查询或者设置分类码。

\ifcat 该命令用于检测两个字符的分类码是否相同。

\L 控制空格。该命令插入一个空白,其宽度与\spacefactor = 1000 时空格记号之宽度相等。

**\obeylines** 该 plain T<sub>E</sub>X 宏将使源文件中的行尾符的换行效果体现在排版结果中。 **\obeyspaces** 该 plain T<sub>E</sub>X 宏将使源文件中(大多数)空格体现在排版结果中。

## 2.1 概述

TeX 的输入处理器从文件或终端扫描输入行,而后将读取到的字符转换成记号。输入处理器可视作一简单的有限状态自动机,其具有三种内部状态;根据输入处理器所处内部状态的不同,其扫描行为有所不同。本章将分别从内部状态和控制内部状态转换的分类码两个角度来考察该自动机。

 $<sup>^1</sup>$ 译注(Liam0205): 在本文的翻译中: 行尾(line ends) 是一行末尾及相关问题的统称, 行终止符(endof-line character) 是  $T_EX$  的输入处理器主动添加在输入行末尾的字符, 行尾符是操作系统中用于标识一行结尾的字符, 例如: 回车符(carriage return)与换行符(line feed)。

2.2 初始化处理 23

## 2.2 初始化处理

**TeX** 逐行处理来自文件的输入(也可能是来自终端的输入,但实际甚少使用,故不再提及)。此处首先讨论在 **TeX** 语境下,到底什么是「输入行」。

不同计算机系统对输入行的具体定义有所不同。最常见的方式是用回车符(carriage return) 紧跟换行符(line feed) 作为行尾符,有些系统单用换行符作为行尾符,一些有定长存储(块存储)的系统则根本不使用行尾符。因此,**T<sub>E</sub>X** 在结束一行输入时有自己特定的处理方式。

- 1. 从输入文件读取一行输入行(不包含可能的行尾符)。
- 2. 移除行尾空格(这是针对块存储系统设计的,同时避免了因行为空格不可见而导致的混乱)。
- 3. 将编码为 \endlinechar 的行终止符(默认是 ASCII 编码为 13 的 \(return\))添加在行尾。若 \endlinechar 的值为负或大于 255(在低于 TEX3 的版本中则是 127; 316 页介绍了更多差异),则输入处理器不会添加任何行终止符;在输入行 尾添加注释字符也有相同的作用。

不同计算机在字符编码方面也存在差异(最常见的是 ASCII 和 EBCDIC)。因此, TeX 有必要将从文件读入的字符转换为其内部编码。这些编码仅在 TeX 内适用,因此 TeX 在任何操作系统上的行为都保持一致。更多内容详见第 3 章。

## 2.3 分类码

256 个字符编码 (0-255) 中的每一个都关联了一个不尽相同的分类码。 $T_{E}X$  的分类码共有 16 个,从 0 开始编号至 15。在扫描输入流的过程中, $T_{E}X$  会生成由字符编码和分类码组成的字符编码-分类码配对 (character-code-category-code pairs);而后,基于这些配对,输入处理器将它们处理成字符记号、控制序列记号和参数记号。这些记号随后被传给  $T_{E}X$  的展开处理器和执行处理器。

字符记号是简单的字符编码-分类码配对,它们会直接被传给展开处理器。控制序列记号则由转义字符引导,后接一个或多个字符组成。关于控制序列记号和参数记号的介绍详见下文。

以下就这些分类做简单说明,详细的阐述则散布在本章其他位置及后续章节当中。

- 0. 转义字符;用于标记控制序列的开始。IniT<sub>E</sub>X 默认使用反斜线\作为转义字符(ASCII 码为 92)。
- 1. 分组开始符; TeX 遇到此类字符时,会进入新的一层分组。在 plain TeX 中,默认的分组开始符是左花括号 {。

- 2. 分组结束符; **T<sub>E</sub>X** 遇到此类字符时, 会关闭并从当前分组中退出。在 **plain T<sub>E</sub>X** 中,默认的分组开始符是左花括号 **}**。
- 3. 数学切换符; 此类字符是数学公式的左右定界符。在 plain T<sub>E</sub>X 中, 默认的数学 切换符是美元符号 \$。
- 4. 制表符;在 \halign(\valign)制作的表格中,作为列(行)间分隔符。在 plain TpX 中,默认的制表符是与符号 &。
- 5. 行终止符; TeX 用来表达输入行结束的字符。IniTeX 将回车符 〈return〉 (ASCII 编码为 13)作为默认的行终止符。这就是为什么 IniTeX 中, \endlinechar 的值是 13(详见前文)。
- 6. 参数符;用于表示宏的参数。在 plain TpX 中,默认的参数符是井号 #。
- 7. 上标符;在数学模式中表示上标;也可用于在输入文件中表示无法直接输入的字符(详见后文)。在 plain TpX 中,默认的上标符即是 ^。
- 8. 下标符;在数学模式中表示下标。在 plain TpX 中,默认的下标符是下划线\_。
- 9. 被忽略字符; 此类字符将被 TeX 自输入流中清除, 因此不会影响后续处理。在 plain TeX 中, 默认将空字符 (null)(AscII 编码为 0)设置为被忽略字符。
- 10. 空格符;T<sub>E</sub>X 对待空格符的方式较为特殊。IniT<sub>E</sub>X 将空格 ⟨space⟩(ASCII 编码为 32)作为默认的空格符。
- **11**. 字母;  $IniT_EX$  默认只将 a . . . z 和 A . . . Z 分为此类。在宏包中,某些「隐秘」字符(例如 ②)会被暂时分为此类<sup>2</sup>。
- 12. 其他字符; IniT<sub>E</sub>X 将所有未归于其他类的字符归于此类。因此, 数字和标点都属于此类。
- 13. 活动字符;活动字符相当于一个无需转义字符前导的 T<sub>E</sub>X 控制序列。在 plain T<sub>E</sub>X 中,只有带子~是活动字符,表示不可断行的空格(参见第 207 页)。
- 14. 注释符; T<sub>E</sub>X 遇见注释符后,会将从注释符开始到输入行尾的所有内容视作注释 而忽略。在 IniT<sub>E</sub>X 中,默认的注释符是百分号 %。
- 15. 无效字符; 该分类包含了不应在  $T_EX$  中出现的字符。 $IniT_EX$  将退格字符(Ascii 编码为 127)(delete) 归于此类。

用户可使用 \catcode 命令修改字符编码到分类码的映射(见第 36 章对诸如 ⟨equals⟩ 等概念的解释):

 $\colored{catcode} \langle number \rangle \langle equals \rangle \langle number \rangle.$ 

该语句中,第一个参数可用如下方式给出:

`\character\ 或 `\\character\

 $<sup>^2</sup>$ 译注(Liam0205): 此类字符的分类码在普通用户文档中和在宏包中会有不同。在宏包中暂时分为此类,以起到「提示当前控制序列是内部的」这样的作用。

2.4 从字符到记号 25

两种写法都表示该字符的字符编码(见第39页和82页)。

plain T<sub>E</sub>X 格式使用 \chardef 命令(将在第 41 页和 84 页介绍)将 \active 定义为:

\chardef\active=13

因此上述语句可写成这样:

\catcode`\{=\active

LATEX 格式定义了如下两个控制序列,用于开启或关闭「隐秘字符」@(详见下文):

\def\makeatletter{\catcode`@=11 }
\def\makeatother{\catcode`@=12 }

使用 \catcode 命令查询字符编码对应的分类码,可得到一个数字:

\count255=\catcode`\{

在例中, {的分类码被保存在第255号\count寄存器中。

下列语句可用于检测两个记号的分类码是否相等:

 $\ \langle token_1 \rangle \langle token_2 \rangle$ 

无论 \ifcat 后有什么, TeX 都会将其展开, 直至发现两个不可展开的记号; 而后, TeX 将比较这两个记号的分类码。控制序列的分类码被视为 16; 因此, 所有控制序列的分类码都是相等的, 而与所有字符记号的分类码都不相等。条件式的详细介绍见第 13 章。

## 2.4 从字符到记号

从文件或用户终端扫描输入行后, $T_{EX}$ 的输入处理器会将其中的字符转换为记号。记号共有三种。

- 字符记号:字符记号会被打上相应的分类码,而后直接传给 TrX 的后续处理器。
- 控制序列记号: 严格来说, 控制序列记号分为两种。其一是控制词 —— 分类码为 0 的字符后紧跟一串字母(分类码是 11)。其二是控制字符 —— 转义字符后紧跟单个非字母字符(分类码不是 11)。在无需区分控制词和控制字符的场合,它们统称为控制序列。

由转义字符与一个空格字符 \□构成的控制序列,称为控制空格。

• 参数记号:由一个参数符 —— 分类码为 6,默认为 # ——和一个紧跟着的 1..9 中的数字构成。参数记号只能在宏(见第 11 章)的上下文中出现。 连续两个参数符(字符编码不一定相同)会被替换为单个字符记号。该字符记号 的分类码是 6(参数符),字符编码则与上述连续两个参数符中后者的字符编码相同。最常见的情形是 ## 会被替换为 #6。此处下标表示分类码。

## 2.5 输入处理器是有限状态自动机

**TeX** 的输入处理器有三种内部状态,可看做是一个有限状态自动机。这也就是说,在任意瞬间,**TeX** 的输入处理器都处于并且只能处于三种状态的一种;并且在状态切换完成后,**TeX** 的输入处理器对先前的状态没有任何记忆。

#### 2.5.1 状态 N:新行


当且仅当遇到新的输入行时, $T_{\mathbf{p}}$ X 会进入状态 N。在该状态下, $T_{\mathbf{p}}$ X 遇到空格记号(分类码为 10 的字符)即会将之忽略;遇到行终止符则会将之替换为  $\mathsf{par}$  记号;遇到其它记号,则会切换到状态 M。

#### 2.5.2 状态 S: 忽略空格

在状态 M 下遇到空格记号,或在任意状态下遇到控制词或控制空格之后(注意其他控制字符不在此列), $T_{\mathbf{p}}\mathbf{X}$  会进入状态 S。在该状态下, $T_{\mathbf{p}}\mathbf{X}$  遇到空格记号或行终止符都会忽略。

#### 2.5.3 状态 M:行内

显然,状态 M 是输入处理器最常见的状态,它表示「处理到输入行的中间」(middle of line)。当输入处理器遇到分类码为 1-4、6-8 以及 11-13 的字符或者控制字符 (不包括控制空格)之后,就会进入该状态。在该状态下, $T_EX$  会将行终止符替换为空格记号。



## 2.6 访问整个字符集

大体上,**T<sub>E</sub>X**的输入处理器可以认为是一个有限状态自动机,但严格来说它并不是。输入处理器在扫描输入行期间,为了让用户能够输入一些特殊字符,而设计了这

2.7 内部状态切换 27

样的机制:两个相同的上标符(分类码为7)以及一个字符编码小于128的字符(暂称原字符)组成的三元组会被替换为一个新的字符。该字符的编码位于0-127之间,并且与原字符的编码相差64。

这种机制可用于访问字体中难以输入的字符。例如 ASCII 中的控制符号〈return〉(ASCII 编码为 13)和〈delete〉(ASCII 编码为 127)可分别使用 ^^M 和 ^^? 进行访问。 当然,由于 ^^? 是无效字符(分类码是 15),故而在访问前需要先修改其分类码。

在  $T_EX3$  中,该机制被扩展为可以访问 256 个字符:四元组  $^xy$  会被替换为一个编码在 0-255 之间的字符;其中 x 和 y 是小写十六进制数字 0-9, a-f, m xy 正是该字符编码的十六进制表示。这一扩展也给先前的机制带来了一些限制:例如  $^x$ 0 会被输入处理器替换为 x1,而不是 x2。

这种机制一方面使得 **TeX** 的输入处理器在某种意义上比真正的有限状态自动 机更为强大,另一方面还不会影响其余的扫描过程。因此,在概念上,可以简单地假 装认为这种对 ^^ 引导的三元组或四元组的替换是提前进行的。不过,在实践中这样 做是不可能的。这是因为,在处理输入行的过程中,用户可能将其他字符分类为第 7 类,从而影响后续处理<sup>4</sup>。

## 2.7 内部状态切换

现在我们来讨论特定分类码的字符对TpX输入处理器内部状态的影响。

## 2.7.1 0:转义字符

遇到转义字符后,**TeX** 开始构建控制序列记号。取决于转义字符后面的字符之分类码,所得的控制序列记号有三种类型。

- 若转义字符后的字符之分类码为 11,即字母,则  $T_{EX}$  将转义字符和之后连续的分类码为 11 的字符构建成一个控制词,而后进入状态 S。
- 若转义字符后的字符之分类码为 10,即空格,则  $T_{EX}$  将它们构建成名为控制空格的控制字符,而后进入状态 S。
- 若转义字符后的字符之分类码不是 10 也不是 11,那么  $T_{EX}$  将它们构建成控制字符,而后进入状态 M。

控制序列名字的所有字符必须在同一输入行之中; 控制序列的名字不能跨行, 即使当前行以注释符结尾或者没有行终止符(通过将  $\endlinechar$  设置为 0-255 之外的值)。

 $<sup>^3</sup>$ 译注(Liam0205): w 和 7 的 ASCII 编码之差为 64。由于 7a 可被理解为是一个十六进制数,所以  $T_EX$  贪婪地将四元组看做一个整体替换为 z。

<sup>&</sup>lt;sup>4</sup>译注(Liam0205):也就是说,如果没有其他字符被分类为第7类,则这个假设在实践中也是可行的。

#### 2.7.2 1-4, 7-8, 11-13:非空字符

分类为 1-4、7-8 及 11-13 的字符会被转换为字符记号,而后  $T_{PX}$  进入状态 M。

#### 2.7.3 5: 行终止符

遇到行终止符时, $T_{\mathbf{E}}\mathbf{X}$  的行为取决于输入处理器当前的状态。但不论处于何种状态, $T_{\mathbf{E}}\mathbf{X}$  会忽略当前行 $^{5}$ ,而后进入状态 N 并开始处理下一行。

- 处于状态 N, 即当前行在此前只有空格,  $T_PX$  将插入 \par 记号;
- 处于状态 M,  $T_{PX}$  将插入一个空格记号;
- 处于状态 S,  $T_{PX}$  将不插入任何记号。

此处「行终止符」指得是分类码为 5 的字符。因此,它的字符编码不一定是\endlinechar,也不一定非得出现在行尾。详见后文。

#### 2.7.4 6:参数符

在宏定义的上下文中,参数符 —— 通常为 # —— 可跟 1..9 中的数字或另一个参数符。前者产生参数记号,而后者产生单个参数字符记号待后续处理。在这两种情形中, $T_{P}X$  都会进入状态 M。

单独出现的参数符也被用于阵列的模板行(见第25章)。

## 2.7.5 7: 上标符

**TeX** 对上标符的处理和大多数非空字符一样,仅在上述替换机制中有所不同:连续两个字符编码相同的上标符及其后字符组成的三元组或四元组会按规则被替换为其它字符。

#### 2.7.6 9:被忽略符

分类码为9的字符会被忽略,且不会影响TrX的状态。

## 2.7.7 10:空格符

在状态 N 和状态 S 中,不论字符编码是多少,空格记号 —— 分类码为 10 的记号 —— 都会被忽略;同时  $T_{PX}$  的状态保持不变。在状态 M 中, $T_{PX}$  会向正在构建

<sup>&</sup>lt;sup>5</sup>译注(Liam0205):指源文件中的当前行。

的记号序列中插入  $_{110}$ (ASCII 编码中的空格,编码为 32),并进入状态 S。这意味着空格记号的字符编码可能与输入字符的编码不同 $^6$ 。

#### 2.7.8 14:注释符

 $T_{E}X$  遇到注释符后,会忽略当前行之后包括注释符本身在内的所有内容。特别地, $T_{E}X$  会忽略行终止符。因此,哪怕是在状态 M 下, $T_{E}X$  也不会插入额外的空格记号。

#### 2.7.9 15: 无效字符

 $T_{E}X$  遇到无效字符时会报错,而  $T_{E}X$  自身会停留在之前的状态。不过,在控制字符的上下文中,无效字符是合法的。因此,```? 不会触发报错。

## 2.8 分类码中的字母与其他字符

大部分编程语言的标识符可由字母与数字构成(还可能包含其他诸如下划线之类的字符)。但是,在 **TeX** 中,控制序列的名字只能由第 **11** 类字符(即字母)组成。而通常,数字和标点的分类码是 **12**,即其他字符。

此外,TeX 可以产生一些由第 12 类字符组成的字符串,哪怕其中的字符原本并非都是第 12 类字符。此类字符串可由\string、\number、\romannumeral、\jobname、\fontname、\meaning 以及 \the 等命令生成。若这些命令产生的字符串包含空格字符(ASCII 编码为 32)<sup>7</sup>,则在输出的字符串中,该字符的分类码为 10。

在极个别情况下,控制序列的展开中可能会包含十六进制数字;因此,除了通常表示字母的  $A_{11} - F_{11}$ 之外, $T_{PX}$ 中还有表示十六进制数字的  $A_{12} - F_{12}$ 。

举例来说,

\string\end 得到四个字符记号 \12e12n12d12

注意,此处输出中有转义字符\12 的原因是宏\escapechar 的值是反斜线的字符编码。而若将\escapechar 的值改为其它字符的编码,则\string 将输出另一个字符。有关\string 命令的详细内容参见第3章。

通过一些特殊技巧,空格也可以出现在控制序列的名字当中:

\csname a b\endcsname

 $<sup>^{6}</sup>$ 译注(Liam0205):不论输入的是哪一个分类码为  $^{10}$  的字符,输入处理器都会将其替换为字符编码为  $^{32}$  的  $^{48}$ CU 空格.

 $<sup>^{7}</sup>$ 译注(Liam0205): 注意, 此处说的是空格字符, 而非是  $^{T}_{P}X$  的空格记号。前者讨论的是字符编码, 而后者讨论的是分类码。

是一个控制序列记号,其名称由三个字符组成,并且其中之一是空格符。将这个控制序列转化为字符串

\expandafter\string\csname a b\endcsname

可得 \12a12110b12。

举个更加实用的例子。假设有一系列输入文件:file1.tex、file2.tex,而我们希望写一个宏来输出当前正在处理的文件的序号。第一种解法是:

```
\newcount\filenumber
\def\getfilenumber file#1.{\filenumber=#1 }
\expandafter\getfilenumber\jobname.
```

宏定义中,参数文本中的 file(见第 11.5 节)会吸走 \jobname 中的 file 部分,从而留下文件编号作为宏的参数。

但这段代码有些小问题。\jobname 输出的 file 四个字符,其分类码为 12。但在 \getfilenumber 的定义中, file 四个字符的分类码是 11。为此,需要对上述代码进行以下修正:

```
{\escapechar=-1
  \expandafter\gdef\expandafter\getfilenumber
    \string\file#1.{\filenumber=#1 }
}
```

此处,\escapechar=-1 让 \string 忽略反斜线; 因此 \string\file 的结果会是  $f_{12}i_{12}l_{12}e_{12}$  四个字符。为了在宏定义是得到分类码为 12 的四个字符,我们使用 \expandafter 命令让 \string\file 在宏定义之前先行展开;而由于 \escapechar 的设定被放在分组内部,所以我们需要使用 \gdef 进行宏定义。

## 2.9 \par 记号

在遇到室行之后,也就是在状态 N 遇到行终止符 (分类码为 5)之后  $^8$ ,  $T_{\rm E}X$  会向输入中插入一个 \par 记号。具体来说,由于  $T_{\rm E}X$  遇到任何非空格字符,都会从状态 N 转移走,因此空行只能包含分类码为 10 的字符。特别地,空行不能以注释符结尾  $^9$ 。因此,若输入文件中因格式美观需要保留空行,则可以在该行中放一个注释符。这算是  $T_{\rm E}X$  这一特性的常见用法。

两个连续的空行产生两个连续的 \par 记号,而实际上它们等同于一个 \par 记号:在遇见第一个 \par 记号之后,**TpX** 会进入竖直模式,而在竖直模式中,\par 只是充当 **TpX** 页面构建器,起到清空段落形状参数的作用。

TeX 于非受限水平模式(unrestricted horizontal mode)遇到竖直命令(⟨vertical

<sup>&</sup>lt;sup>8</sup>译注(**Liam0205**): 此处说的是 **T<sub>E</sub>X** 添加的行终止符, 而不是输入文件中的行尾符。输入文件中的行尾符已在初始化处理中被移除并替换成了行终止符。

 $<sup>^{9}</sup>$ 译注(Liam0205):此时, $T_{P}X$ 添加的行终止符位于注释之后,故而该行终止符会被 $T_{P}X$ 忽略。

2.10 空格 31

command》)时,也会向输入插入一个 \par 记号。当该 \par 被读取和展开后,上述 竖直命令会被重新处理(详见第 6 章和 17 章)。

\end 命令 $^{10}$ 也会向输入插入 \par 记号,而后结束  $T_{PX}$  的运行;见第 28 章。

值得注意的是,遇到空行时 **TpX** 通常的行为(结束当前自然段)完全取决于 \par 记号的默认定义。重定义 \par 后,空行和竖直命令的行为可能就完全两样了;因此,我们可以借此实现一些特别的效果。在这种情况下,为了使用正常的 \par 的功能,plain **TpX** 提供了其同义词 \endgraf。详见第 **17** 章。

除非宏被声明为 \long 的,不然 \par 记号不能出现在宏的参数当中。对于非 \long 声明的宏,若其参数中包含 \par 记号,则 TeX 会给出「runaway argument」的报错。不过,使用 \let 定义的与 \par 同义的控制序列(例如 \endgraf)是允许出现在这些宏的参数之中的。

## 2.10 空格

这一节讨论输入处理器中有关**空格字**符和**空格记号**的一些内容。有关文本排版中的空格,留待第 **20** 章讨论。

#### 2.10.1 被忽略的空格

在上述有关输入处理器内部状态的讨论中,我们不难发现,有些空格在输入处理器中就被抛弃了,因此永远不会被输出:输入行开头的空格以及在让  $T_{E}X$  进入状态 S 的字符之后的空格。另一方面,行终止符尽管不在输入中(而是由  $T_{E}X$  添加的),但能产生可输出的空格。除此之外,还有第三种空格:它们可以通过输入处理器,甚至干脆由输入处理器产生,但也不会被输出。那便是非强制空格( $\langle optional\ spaces \rangle$ )。在  $T_{E}X$  的语法中,很多地方都会出现此类空格。

## 2.10.2 非强制空格

TpX 语法中有所谓非强制空格与单个非强制空格的概念:

 $\langle \text{one optional space} \rangle \longrightarrow \langle \text{space token} \rangle \mid \langle \text{empty} \rangle$  $\langle \text{optional spaces} \rangle \longrightarrow \langle \text{empty} \rangle \mid \langle \text{space token} \rangle \langle \text{optional spaces} \rangle$ 

通常单个非强制空格( $\langle$ one optional space $\rangle$ )允许出现在数字和粘连说明之后;而非强制空格( $\langle$ optional spaces $\rangle$ )允许出现在数字或粘连中任意允许出现空格的地方(比如负号与数字之间,又比如 plus 和 1fil 之间)。此外,根据  $\langle$ equals $\rangle$ 的定义,非强制空格允许出现在 = 之前。

 $<sup>^{10}</sup>$ 译注(Liam0205):注意这里说的不是 LATeX 中结束环境的 \end{\( env-name \)} 命令,而就是 \end 这个 plain TeX 命令。

以下是有关非强制空格的一些例子:

- ⟨one optional space⟩ 可用于界定数字的范围。这有助于避免一些意外情况(见第7章),同时能加速 TeX 的处理过程——这是因为借助单个非强制空格,TeX 能更容易地界定当前正在读入的 ⟨number⟩ 于何时结束。注意,并非每个「数值」都是 ⟨number⟩。例如说, \magstep2 中的 2 就不是数字,而是作为 \magstep 的参数的单独的字符记号。因此,在其后加上空格或行终止符是有意义的。此外,宏参数中的数字,例如 #1:因为一个宏最多允许有 9 个参数,故而只需在参数符后扫描一位数字即可<sup>11</sup>。
- 根据 TeX 的语法,关键字 fill 及 fill1 由 fil 与若干单独的 1 字符记号组成 (详见第 314 页);因此此处允许非强制空格。据此,例如fil L 是合法的关键 字<sup>12</sup>。这里有一些潜在的问题,可能导致莫名其妙的情况。大多数情况下,在关键字后面加上一个 \relax 即可避免此类问题。
- **T<sub>E</sub>X** 原语 \ignorespaces 会吃掉其后的非强制空格; 故此可将其插入宏定义的 末尾, 以避免将参量右花括号后的空格无意带入输出当中。例如说:

```
\def\item#1{\par\leavevmode
   \llap{#1\enspace}\ignorespaces}
\item{a/}one line \item{b/} another line \item{c/}
yet another
```

此处,\ignorespaces 吃掉了第二、第三两次调用之后的空格,而这些空格是不希望被排版输出的。不过,在\ignorespaces 之后的空行仍然会插入\par 记号。

#### 2.10.3 被忽略和被保留的空格

 $T_{E}X$  会忽略控制词之后的空格。不过这不是因为控制词之后的空格是非强制空格,而是因为  $T_{E}X$  在遇到控制词之后会进入状态 S,从而忽略空格。类似地,控制词之后的行终止符也会被忽略。

数字由单个非强制空格界定,但是

a\count0=3 b

的输出是'ab'。这是因为  $T_{pX}$  在第一个空格记号<sup>13</sup>之后会进入状态 S,从而第二个空格会被  $T_{pX}$  的输入处理器忽略,永远不会变成空格记号。

当  $\mathbf{T}_{\mathbf{E}}\mathbf{X}$  处于新行状态 N 时,空格也会被忽略。另一方面,当  $\mathbf{T}_{\mathbf{E}}\mathbf{X}$  处于竖直模式工作时,空格记号(也就是在一开始未被忽略的空格)会被忽略。例如说,下例第一个盒子之后由行终止符生成的空格记号会被忽略<sup>14</sup>。

<sup>11</sup>译注(Liam0205):而不需要单个非强制空格来辅助界定数字的范围。

 $<sup>^{12}</sup>$ 译注(Liam0205): $T_PX$ 的关键字不区分大小写,并且在关键字前允许有非强制空格。

<sup>13</sup>译注(Liam0205):第一个空格记号是单个非强制空格,界定了单个数字。

<sup>&</sup>lt;sup>14</sup>译注(Liam0205): 此处 \hbox{〈 内容物 〉} 并不会使 TrX 从由 \par 记号引入的竖直模式中切换回

2.10 空格 33

```
\par
\hbox{a}
\hbox{b}
```

plain TeX 和 LATeX 格式都定义了名为 \obeyspaces 的宏。该宏能使每个空格都是有意义的:在一个空格之后,连续的空格会被保留。两种格式中,\obeyspaces的基本形式是一致的。

```
\catcode`\ =13 \def {\space}
```

不过,对于\space的定义,两种格式有所区别。在 plain TeX 中,\space 的定义如下\def\space{}

在 图形 中, 同名的宏则定义为

```
\def\space{\leavevmode{} }
```

在 \obeylines 的上下文中,比较容易看出这两种定义的区别。使用 \obeylines 后,每个行终止符都会被转换成一个 \par 命令。因此 TpX 开始处理每一行时,都处于竖直模式。在 plain TpX 中,活动空格被展开为空格记号,因此在垂直模式中会被忽略。但在 IMpX 中,首先会离开竖直模式并进入水平模式,因此每个空格就都是有意义的了。

#### 2.10.4 空格被忽略的其他情形

还有三种情形下, TrX 会忽略空格记号:

- 1. 在寻找未被花括号定界的宏参数时,**T<sub>E</sub>X** 会忽略所有空格记号,而将第一个非空记号(或分组)作为参数。详见第 **11** 章。
- 2. 在数学模式中,所有的空格记号会被忽略(详见第23章)。
- 3. 在阵列制表符之后,空格记号会被忽略(见第25章)。

## 2.10.5 空格记号:(space token)

在  $T_{EX}$  中,空格总是表现得与众不同。举例来说,\string 会将所有字符的分类码设置为 12,唯独空格的分类码是 10。此外,如前文所述,在状态 M 中, $T_{EX}$  的输入处理器会将所有分类码为 10 的字符转换为真正的空格:字符编码会被设置为 32。于是,任何分类码为 10 的字符记号称为室格记号( $\langle space\ token \rangle$ )。字符编码不是 32 的空格记号称为滑稽室格。

例子: 将字符 Q 的分类码设置为空格字符之后, 如下定义

\catcode Q=10 \def \q{aQb}

可得

\show\q macro:-> a b

这是因为输入处理器改变了宏定义中滑稽空格的字符编码。

字符编码不为 32 的空格记号可以用 \uppercase 等命令生成。不过,「由于字符编码不同的空格记号的行为是一致的,所以纠缠于这类细节是没有意义的」。详见 [?] 第 377 页。

#### 2.10.6 控制空格

控制空格命令 \u 给出一个与 \spacefactor 等于 1000 时空格记号宽度一样的 空格。控制空格不能被当做是空格记号,也不能理解为会展开成一个空格记号的宏 (例如 plain T<sub>E</sub>X 中的 \space)。举例来说,T<sub>E</sub>X 会忽略所有输入行开头的空格,但 是控制空格是一个水平命令(〈horizontal command〉),故而 T<sub>E</sub>X 在遇到它之后会从 竖直模式切换到水平模式(并插入一个缩进盒子)。有关 \spacefactor 的介绍,详见第 20 章;有关水平模式和竖直模式的介绍,详见第 6 章。

#### 2.10.7 可见空格:,,

在 Computer Modern 的打字机字体中,字符编码为 32 的字符是显式空格符号'1'。不过,简单地使用 \tt 命令<sup>15</sup>是无法将其打印出来的。这是因为空格在输入处理器中有特别的处理。

使空格字符 」显形的一种方法是将空格字符的分类码设置为 12:

 $\catcode' = 12$ 

此时, $T_{E}X$  会将空格字符作为编码为 32 的字符排版出来。此外,连续的空格不会被忽略。这是因为状态 S 只是在遇到分类码为 10 的字符后才会进入。类似地,控制序列之后的空格也会因分类码的改变而显形。

## 2.11 有关行尾的更多知识

TeX 从输入文件中获取文本行,但不包括输入行中的行尾符。因此,TeX 的行为不依赖操作系统以及行尾符究竟是什么(CR-LF、LF 抑或是在块存储系统里根本就不存在行尾符)。而后,TeX 会移除输入行末尾的空格。这样处理是有历史原因的:TeX 必须能够适应 IBM 大型计算机的块存储模式有关。对于由计算机的不同而造成的有关行尾符的问题,详见[?]。

此后,字符编码为 \endlinechar 的行终止符会被追加在文本行的末尾;除非 \endlinechar 中保存的数值为负数或大于 255。注意,改行终止符的分类码不一定

<sup>15</sup>译注(Liam0205):在LATEX 中是 \ttfamily 命令。

非得是5。

## 2.11.1 保持各行

有时候会期望会希望输入文本中的行尾符能与排版输出的行尾——对应。下面的代码可以可以解决这一问题:

```
\catcode`\^^M=13 %
\def^^M{\par}%
```

这里,\endlinechar 成为活动符,其含义变为\par。上述代码中的注释符用于阻止 TrX 看到代码末尾的行终止符,以防它将其作为活动字符而展开。

需要注意的是,在将上述代码嵌入宏的展开文本中需要特别小心。例如说下列 代码会让 **TrX** 误解:

具体来说, $T_{E}X$  将丢弃第二个  $^{n}M$  之后的所有字符。这是因为,在宏展开的过程中,  $^{n}M$  分类码为  $^{n}M$  分类码为  $^{n}M$  力类码为  $^{n}M$  也就是说,这一行实际上变成了:

```
\def\obeylines{\catcode`\^^M=13 \def
```

要修正上述问题,需要为 ^~M 营造一个可作为活动字符使用的环境:

```
{\catcode`\^^M=13 %
  \gdef\obeylines{\catcode`\^^M=13 \def^^M{\par}}%
}
```

这样解决了上面提到的问题,但仍有缺陷。这是因为,该\obeylines 仍然不能保留输入文本中的空行——连续两个\par 记号会被当成是一个。为此,我们需要对上述定义稍作改进:

```
\def^^M{\par\leavevmode}
```

这样,输入文本中的每一行都会开启一个新段落,空行则开启一个空段落。

#### 2.11.2 改变 \endlinechar

某些情况下,你会希望改变 \endlinechar 的值或者 ^M 的分类码,以达成一些特殊效果。例如说,可以用行终止符作为宏的参数的定界符。具体可参考第 130 页给出的例子。

在这些常识中,通常会有一些陷阱。我们来看以下写法:

```
{\catcode`\^^M=12 \endlinechar=`\^^J \catcode`\^^J=5
...
... }
```

这段代码的输出不符合预期:由于第一行和最后一行的行终止符,TrX 将输出字符码

为 **13**(^^M)和 **10**(^^J)的字符。<sup>16</sup>

在第一行和最后一行末尾加上注释符可以解决此问题,但还有另一种方法是将 第一行拆成下面两行<sup>17</sup>:

```
{\endlinechar=`\^^J \catcode`\^^J=5 \catcode`\^^M=12
```

当然,在多数情况下没必要将行终止符替换为另一个字符;设置

\endlinechar=-1

就等同于各行都以注释符结尾。

## 2.11.3 行终止符的更多注记

**TeX** 对所有字符一视同仁,包括追加到输入行末尾的行终止符。考虑到它特别的分类码,通常大家都不会注意行终止符。但是有一些方法可以特别地处理行终止符。

例子:如果\^^M有定义,此时可称为「控制换行」。则在输入行中用反斜线结尾将执行此控制换行命令。例如,在 plain TeX 中定义

 $\left( \frac{^{M}}{ } \right)$ 

将使得控制换行与控制空格等价。

# 2.12 输入处理器的更多知识

# 2.12.1 输入处理器作为独立过程

**T<sub>E</sub>X** 处理器的各个阶段都是同时运行的,但是在概念上它们常被视为依次独立运行,前者的输出是后者的输入。关于空格的小戏法很好地展现了这一点。

考虑以下宏定义:

\def\DoAssign{\count42=800}

及其调用:

 $<sup>^{16}</sup>$ 译注(Liam0205): 在第一行执行之前,输入处理器的初始化处理将会添加 ^^M 作为行终止符,但由于其分类码被修改为  $^{12}$ ,即其他字符,故而会被输出。最后一行执行之前,输入处理器的初始化处理将会添加 ^^J 作为行终止符,因为此时 \endlinechar 的值是它的字符码。但由于分组结束,^^J 的分类码已恢复,故此时添加在输入行尾的行终止符 ^^J 也会输出。

<sup>&</sup>lt;sup>17</sup>译注(Liam0205): 这样可以避免第一行的行终止符带来的问题, 但无法避免最后一行的行终止符带来的问题。

#### \DoAssign 0

作为构建记号的部分,**TeX**的输入处理器在扫描此次调用时,会忽略控制序列之后和零之前的所有空格。因此,此次调用的展开为:

\count42=8000

不要认为:「\DoAssign 首先被读入,而后展开,而后空格作为分隔符分割了 800,于 是 800 被赋值给计数器,并打印出数字零。」不过,需要注意的是,如果数字零出现在下一行,情况就不一样了。

再举一个让非强制空格出现在忽略空格阶段之后的例子:

\def\c.{\relax}

 $a\c. b$ 

会被展开为:

a\relax b

其输出是:

'a b'

这是因为,「输入处理器忽略控制序列\relax之后的空格」这一现象仅出现在该行被首次读取之时,而非在其被展开之时。另一方面,这个例子:

\def\c.{\ignorespaces}

a\c. b

则会被展开为:

a\ignorespaces<sub>□</sub>b

执行\ignorespaces 时会删除所有接续其后的连续空格记号。因此,输出是:

'ab'.

在上述两个例子中, \c 之后的西文句号均为定界符, 用于保护控制序列之后的空格不被输入处理器吃掉。

# 2.12.2 输入处理器不作为独立过程

将  $T_EX$  的记号化的过程视作独立过程是一个便利的做法,但有时这种做法会引起困惑。例如

 $\color= \color= 13{}$ 

将行终止符设为活动字符;因此,该行自身的行终止符将报错:「未定义的控制序列 (undefined control sequence)」。这表明,执行行内的命令有时会影响对同一行的扫描过程。

另一方面,下面例子则不会报错:

#### $\color= \color= 13$

这是因为,在 **TpX** 扫描数字 **13** 时就读入了行终止符,此时,分类码的赋值过程尚未执行;而此时,行终止符被转换成了非强制空格,作为数字的定界符。

## 2.12.3 输入处理器的递归调用

前文中,将参数符和数字替换为参数记号的过程被描述得与将字母捆绑成控制序列记号类似。但实际情况要复杂得多。**TrX** 的记号扫描机制不仅在扫描文件输入时起作用,在扫描记号列表输入时同样会起作用:例如在处理宏定义时。前文提到的内部状态变化的机制,仅仅适用于前一种情况。

在两种情况下,输入处理器对参数符的处理方式都是相同的。否则 **T<sub>E</sub>X** 便无法处理下面这样的宏定义:

\def\a{\def\b{\def\c###1{####1}}}

见第 123 页对这种嵌套定义的解释。

# 2.13 @ 约定

读过 plain TeX 或是 LATeX 格式的源码就会发现其中有很多包含符号 @ 的控制序列。这种包含 @ 的控制序列不能被普通用户直接使用。

格式文件的起始处附近有命令

\catcode`@=11

它将 @ 的分类从「其他字符」变为「字母」,从而可以用于组成控制序列。而在格式文件的末尾处附近有命令

\catcode`@=12

它将@的分类恢复为其他字符。

那么,为什么用户不能直接调用带有 @ 字符的控制序列,却能调用定义中包含此类控制序列的宏呢?原因在于,在宏定义时,带有 @ 的控制序列已被 TpX 内部处理过了,此后,这些控制序列就变成了记号而不是字符串了。在宏展开的过程中, TpX 只需要操作记号,因此,彼时记号内字符的分类码就不影响宏展开的过程了。

# 第3章 字符

TrX 在其内部使用字符编码来表示字符;本章讨论字符编码及相关命令。

\char 显式指定所要排版的字符。

\chardef 将一个控制序列定义为一个字符编码的同义词。

\accent 放置重音符号的命令。

\if 测试字符编码是否相等。

\ifx 测试字符编码与分类码是否都相等。

\let 将一个控制序列定义为一个记号的同义词。

\uccode 对于给定的字符编码,查询或设置其对应的大写变体的编码。

\lccode 对于给定的字符编码, 查询或设置其对应的小写变体的编码。

\uppercase 将普通文本(\(\frac{general text}\))转换为大写形式。

\lowercase 将普通文本(\(\langle\)eneral text\))转换为小写形式。

\string 将一个记号转换为一个字符串。

\escapechar 将控制序列转换为一串字符记号时,用作转义字符的字符之编码。在  $IniT_EX$  中默认为  $92(\)$ 。

# 3.1 字符编码

在概念上说,认为 **T<sub>E</sub>X** 内部直接对字符进行处理是最简单的;但是实际上 **T<sub>E</sub>X** 内部处理的是整数,即字符编码。

不同系统中,字符的编码方式可能不同。因此, $T_{EX}$ 使用其自身定义的字符编码方案。任何从文件或用户终端读入的字符,都会依据编码表转换成字符编码。之后, $T_{EX}$ 会根据这一字符编码为它们分配分类码(见第 2 章)。编码表基于 7-位 ASCII 编码表,可编码 128 个字符(见第 38.1 节)。

反引号(`,或称左引号)可将字符(准确说是字符记号)转换为其字符编码。在 TpX中,所有需要(number)的地方,都可以通过这种方式将一个字符记号的编码传 40 第 3 章 字符

给  $T_EX$ : 反引号加字符或是反引号加单字符控制序列。例如 \count`a 和 \count`\a 都表示 \count97。详见第 7 章。

第二种方式在某些情况下是有必要的,例如在下例中,若去掉\,就会让  $T_EX$  产生误解。

\catcode`\%=11 or \def\CommentSign{\char`\%}

例如在下例中,=11 会被认为是注释。

\catcode \%=11

单字符的控制序列可以由任何分类码的字符组成。1

当字符记号被转换为字符编码后,字符编码就与字符的形状没有关联了。当然,对于大多数字符来说,在视觉上,其排版输出与输入是一致的。例如输入 a 会排版输出字符「a」。不过,即使在常见的符号中,也有例外情况。在 Computer Modern Roman 字体中,就没有小于号和大于号。输入 '<>' 得到的输出是 ';;'。

为了使  $T_{EX}$  在输出端也不依赖具体的机器,dvi 文件格式也是用这种字符编码:操作码  $n=0\dots127$  表示:「从当前字体中取出第 n 个字符。」在 [?] 中可以找到 dvi 文件的操作码的完整定义。

# 3.2 字符相关的控制序列

有许多种方式可以用控制序列来表示字符。例如说,\char 命令可以指定一个用于打印的字符;\let 命令可引入一个与指定字符记号同义的控制序列——包括其字符编码和其分类码。

# 3.2.1 表示要排版的字符:\char

字符可以通过数值来表示,比如 \char98。该命令会将当前字体中编码为 98 的字符添加到正在构建的水平列表中。

相较而言,用八进制或十六进制表示字符编码可能比用十进制更方便。在数值前加上单引号,即可使用八进制数:\char'142;在数值前使用双引号,即可使用十六进制数:\char'62。注意,连续使用两个单引号,比如\char'62是错误的写法——将两个单引号替换为一个双引号的工作是由可视化处理器承担的,而不是数字扫描操作(执行处理器)。

由于可用反引号获取字符的编码,在当前字体的编码与ASCII兼容时,用\char`b或\char`\b也可以得到'b'这个字符。

表面上看,\char 命令与 ^^ 替换机制(第 2 章)类似:两种机制都是通过间接的方式来访问字符。但是, ^^ 替换机制发生的非常早——在 **TrX** 的输入处理器为字符

<sup>1</sup>译注(Liam0205):特别地,可以是无效字符。

分配分类码之前;而 \char 命令则在可视化处理器中起作用。从效果上看,\char 是告诉  $T_{P}X$ :「排版字体中第 n 个字符。」

\chardef 命令可定义一个控制序列定义作为一个字符编码的代替品。它的用法是

此处的〈number〉可以是显式给出的数字,也可以是计数器值,也可以是用反引号提取得到的字符编码(见上文;关于〈number〉的完整定义,参见第7章)。在 plain TeX中,就有类似下面的用法:

```
\chardef\%=`\%
```

它等价于下面的定义方式:

```
\chardef\%=37
```

如此定义之后,控制字符 \% 就变成了 \char37 的同义词。也就是说,它可以用于排版第 37 个字符(通常是百分号)。

用 \chardef 命令定义的控制序列可作为 \( number \) 使用。在诸如 \newbox 的分配类命令中,就用到了这一特性。(见第 7 章和第 31 章)用 \mathchardef 命令定义的记号同样可以这样使用。

## 3.2.2 隐式字符记号:\let

另一种定义表示字符的控制序列的方式是使用 \let 命令,并且将字符记号置于可选等号的右边:

如此,得到的控制序列称为隐式字符记号。(见第 125 页对 \let 的进一步讨论。)

在 plain TpX 中有对左右花括号定义同义控制序列:

```
\let\bgroup={ \let\egroup=}
```

如此,得到的控制序列被称为「隐式花括号」(见第 10 章)。

通过 \let 和 \chardef 将字符赋值给控制序列是有区别的。被 \let 定义的控制序列是字符编码与分类码这一组合的替代品。

例如在下例中, $\begin{cases} \begin{cases} \begin$ 

```
\catcode`|=2 % make the bar an end of group
\let\b=| % make \b a bar character
{\def\m{...}\b \m
```

又例如在下例中, \b 的定义在分类码修改之前, 因此它无法承担分组结束符的作用, 只能表示一条竖线(或是其他任何在当前字体中编号为 124 的字符)。因此, 这里构

第3章字符

造的是一个不闭合的分组。

42

```
\let\b=| % make \b a bar character
\catcode`|=2 % make the bar character end of group
{\def\m{...}\b \m
```

前一个例子表明,即是花括号本身被重定义了(例如在排版 C 语言代码时被定义成活动字符),分组开始和结束的功能依然可以由控制序列 \bgroup 和 \egroup 来承担。

隐式字符记号的行为与真实字符记号非常相似。举例来说,在如此定义之后,

```
\catcode`|=2 \let\b=|
```

以下两个真值测试均为真。

\if\b|

\ifcat\b}

再举一例。在 plain TpX 中,有如下对上标和下标符号的定义:

```
\let\sp=^ \let\sb=_
```

如此一来,即使键盘上没有这两个符号,也可以通过这两个控制序列得到数学环境的上标和下标。

```
x\sp2\sb{ij} gives x_{ij}^2
```

若是编写格式的人的键盘上也没有这些键,那么就要用更深的技巧了:

```
{\lccode`,=94 \lccode`.=95 \catcode`,=7 \catcode`.=8 \lowercase{\global\let\sp=, \global\let\sb=.}}
```

至于它为什么能起作用,可详见后文关于 \lowercase 的介绍。由于我们无法键入  $^{\circ}$ , 因此  $T_{E}X2$  中的  $^{\circ}$  表示法无法在此解决问题。(见第 26 页) 考虑到上标和下标的字符编码以十六进制表示分别是 5e 和 5f,利用  $T_{E}X3$  中扩展的表示法可以依照如下方式解决问题:

```
{\catcode`\,=7
\global\let\sp=,,5e \global\let\sb=,,5f}
```

使用 \meaning 命令可以查看使用 \let 定义的命令究竟代表哪个字符。例如下列代码将给出 'the character 3'。

```
\let\x=3 \meaning\x
```

# 3.3 重音

重音符号可用水平命令(〈horizontal command〉)\accent 给出。

```
\accent\langle 8-bit number\langle \optional assignments\langle \character\langle
```

其中、〈character〉是分类码为 11 或 12 的字符,或是形如 \char〈8-bit number〉的

3.4 字符真值测试 43

命令,抑或是一个由\chardef 定义的记号。此时,重音符号会被放置在该字符的上方。若 \character\ 不是上述四种情况之中的任意一种,则重音符号会被\char 命令直接处理,从而给出一个「悬在半空」的重音符号。可选的 \optional assignments\ 可用于改变重音和字符的字体。

\accent 命令后必须紧跟 \( \text{character} \))。这一规定避免了将重音符号置于连字之上或是置于另一个重音符号之上。在诸如印度语及越南语的少数语言中,确实存在双重音符号的情况;因此这种规定有时可能会令人不爽。不过,将重音符号置于另一个之上可以在数学模式中实现。

添加重音符号不会改变字符的宽度。对于重音符号摆放的位置, $T_{P}X$  假设字体文件中,重音符号摆放的高度与字母 x 的高度相适应;对于其他高度的字母, $T_{P}X$  则可以通过向上或向下移动恰当的高度来调整重音符号的位置。

在  $T_EX$  中没有真正的下重音,而是将它们视作位置较低的上重音实现的。更准确的做法是:编写一个宏,测量紧跟着的字符的尺寸,而后相应地升高或降低重音符号的位置。 $plain\ T_EX$  中的变音宏 \c就是这样做的。不过,对于有下伸部分的字母,它不会降低重音符号的位置。 $^2$ 

重音符号的水平位置由 \fontdimen1(每点倾斜, slant per point) 控制。为此, TeX 会引入铅空以校正重音符号的水平位置。<sup>3</sup>注意, 尽管这些铅空是自动插入的, 但 这些铅空隶属显式铅空。因此, 它们会抑制铅空前后的连字符。

以下代码能将水平列表转储出来,作为铅空和重音符号的示例。

```
\setbox0=\hbox{\it \`1}
\showbox0
```

#### 其结果是

```
\hbox(9.58334+0.0)x2.55554
.\kern -0.61803 (for accent)
.\hbox(6.94444+0.0)x5.11108, shifted -2.6389
.\tenit ^R
.\kern -4.49306 (for accent)
.\tenit 1
```

注意,TrX 首先放置重音符号,以保证最后一个字符的倾斜校正仍然有效。

# 3.4 字符真值测试

使用 \if 可检测两个字符记号的字符编码是否相等:

```
\inf \langle token_1 \rangle \langle token_2 \rangle
```

 $<sup>^2</sup>$ 译注(Liam0205):所谓下伸部分,指的是个别小写字母比其它小写字母更低的部分。比如「p」、「q」的「小尾巴」。

<sup>&</sup>lt;sup>3</sup>译注(Liam0205): 铅空是活字印刷排版时代,排版工人用于调整字符水平位置而使用的空白铅块。

第3章 字符

 $T_{PX}$  遇到 \if 后,会对其后的记号持续展开,直至遇见两个不可展开的记号。而后,不管分类码如何,若这两个记号的字符编码相等,则真值测试为真。

对于 TeX 来说,不可展开的控制序列的字符码是 256 而分类码为 16(因此控制序列的字符编码只与控制序列的字符编码相等),除非控制序列被 \let 定义成一个非活动字符记号——如前所述,此时该控制序列的字符编码和分类码与相应的字符相同。

第?? 章提到了用于检验分类码的 \ifcat 命令; 真值测试

 $\inf \langle token_1 \rangle \langle token_2 \rangle$ 

则检验字符编码和分类码是否均相等。特别注意的是,**TpX** 不会展开 \ifx 之后的记号。不过,若它们是宏,则 **TpX** 会检验它们的展开是否相等。

对于 \chardef 定义的数量,则可以用 \ifnum 来检验。

\chardef\a=`x \chardef\b=`v \ifnum\a=\b % is false

这是因为由 \chardef 定义的记号可被当做是数字来使用(见第 7 章)。 另见第 13.2 节。

# 3.5 大写和小写

# 3.5.1 大写和小写的编码

每个字符编码都有对应的大写编码和小写编码。(更多代码见下文)它们可分别用

 $\ \colored$   $\colored$   $\colore$ 

和

 $\verb|\locode| \langle number \rangle \langle equals \rangle \langle number \rangle$ 

来指定。在  $IniT_{P}X$ 中,'a...'z及'A...'Z的大写编码为'A...'Z而小写编码为'a...'z。 其余所有的字符的大写编码和小写编码均为零。

# 3.5.2 大写和小写命令

\uppercase{...} 和 \lowercase{...} 命令会遍历参数记号列表,而后将所有对应大写编码或小写编码不为零的显式字符替换成相应的大写编码或小写编码,分类码则维持不变。

\uppercase 和 \lowercase 命令的参数是普通文本(⟨general text⟩),其定义如下(其中 ⟨filler⟩ 的定义见第 36 章):

 $\langle general \ text \rangle \longrightarrow \langle filler \rangle \{\langle balanced \ text \rangle \langle right \ brace \rangle$ 

3.5 大写和小写 45

此处,左花括号可以是隐式字符记号,但右花括号必须是分类码为2的显式字符记号。在寻找左花括号时, $T_{P}X$ 会进行宏展开。

与 \number 和 \string 不同,大小写转换不是宏展开,而是在执行处理器中执行的。下列尝试得到 \A 的代码会因 \uppercase 不可展开而报错——TeX 将在 \uppercase 之前插入 \endcsname。<sup>4</sup>

\expandafter\csname\uppercase{a}\endcsname

正确的写法如下:

\uppercase{\csname a\endcsname}

下例对 \uppercase 的使用是正确的,它可用于检测一个字符是否为大写:

\def\ifIsUppercase#1{\uppercase{\if#1}#1}

大写检测也可以这样做:\ifnum`#1=\uccode`#1。

首字母大写(首字母的字符编码与其 \lccode 不同)的单词是否允许截断连字取决于 \uchyph 参数。若改参数为正数,则允许对首字母大写的单词进行截断连字。另见第 19 章。

## 3.5.3 关键字的大写与小写形式

# 3.5.4 巧用 \uppercase 和 \lowercase

利用 \uppercase 和 \lowercase 不会改变分类码的特性,可以构造出一些其它方式难以构造的字符编码-分类码配对; 比如第 13 章中对宏 \newif 的讲解; 又比如第 42 页上的例子。

再将一个稍有些不同的例子。考虑这一问题(已由 Rainer Schöpf 解决):给定一个计数器 \newcount\mycount,如何将其值作为字符编号输出到终端? 解法如下。

\lccode`a=\mycount \chardef\terminal=16

\lowercase{\write\terminal{a}}

此处,\lowercase 命令有效地将\write 命令的参数,从「a」转换成目标值。

<sup>&</sup>lt;sup>4</sup>译注(Liam0205): 这里的表述比较奇怪。事实上, TeX 要求\csname 和\endcsname 之间的内容展开到底后不能有不可展开的原语; 而\uppercase 正式一个不可展开的原语, 故而报错。这里提出 TeX 在\uppercase 之前插入\endcsname, 原因可能是 TeX 在发现问题「尝试修复的过程中」, 会做这样的操作。

46 第 3 章 字符

# 3.6 字符相关编码

每个字符编码都有一系列与之相关的〈codename〉。这些整数的取值范围各不相同;它们决定了在不同场合下, $T_{EX}$  会如何处理该字符,或是决定了在不同场合下,该字符会如何影响  $T_{FX}$  自身。

这些编码的名字罗列如下:

\catcode 4 位数字(\(\lambda\)-bit number\\,0-15);字符的分类码。见第 2 章。

\mathcode 15 位数字( $\langle 15\text{-bit number} \rangle$ ,0-"7FFF 或 "8000);它决定  $T_{E}X$  在数学环境下如何处理该字符。见第 21 章。

\delcode 27 位数字(\\(\frac{27\text{-bit number}}{0}\), 0-"7 FFF FFF); 它决定 TeX 在数学环境下 如何处理出现在 \left 和 \right 之后的该字符。见第 213 页。

\sfcode 整数;它决定 TrX 如何处理位于该字符之后的空距。见第 20 章。

**\lccode \uccode 8** 位数字 ( $\langle 8$ -bit number $\rangle$ , 0–255); 如前所述, 这是字符的小写及大写的编码。

# 3.7 将记号转换为字符串

\string 命令能将其下一个记号展开为由若干字符组成的字符串。例如,下例将输出\control。

\tt\string\control

又例如下例将输出 \$。

#### \tt\string\$

注意,字符串操作位于记号化之后。因此下例不能输出注释符号%,因为早在输入处理器中,注释符号就被删除了。于是,下例中的\string会将下一行的第一个记号转换为字符串。

#### \tt\string%

\string 命令由展开处理器执行。因此,除非显式地禁止,它必然会被展开。详见第 12 章。

# 3.7.1 输出控制序列

上例使用了打字机字族 $^5$ 。这是因为,在 Computer Modern Roman 字体中没有反斜线这一字符。不过, $\mathbf{T}_{\mathbf{P}}\mathbf{X}$  也可以使用其它字符来打印控制序列: 具体来说, $\mathbf{T}_{\mathbf{P}}\mathbf{X}$ 

 $<sup>^5</sup>$ 译注 (Liam0205) : \tt 是 plain TeX 风格的字体选择命令。在 LATeX 中, 应当使用 \ttfamily 或者 \texttt 代替。

使用 \escapechar 保存的字符编码对应的字符来打印控制序列。在使用下列命令时,也会用到 \escapechar 这个宏保存的值: \write、\message、\errmessage、\show、\showthe 以及 \meaning。若 \escapechar 的值为负或者大于 255,则转义字符不会显示出来;此外,在 IniTeX 中 \escapechar 的默认值是 92,即反斜线的字符编码。

在\write 语句中,有时可用\noexpand 代替\string。详见第 145 页。

# 3.7.2 \string 输出输出字符串的分类码

\string 命令输出的字符串中,各个字符的分类码均为 12,唯独被字符串化的控制序列中的空格,其分类码是 10。由于控制序列内部不存在分类码的说法,\string 输出的所有空格必定只是空格字符,也就是说,它的字符编码是 32。由于 TeX 的输入处理器会将所有空格记号的字符编码设置为 32,「滑稽空格」出现在控制序列中的机会相当渺茫。

在分类码方面,其他命令的行为与\string表现一致:\number\romannumeral、\jobname\fontname\meaning以及\the。

# 第4章 Fonts

In text mode TEX takes characters from a 'current font'. This chapter describes how *fonts* are identified to TEX, and what attributes a font can have.

\font Declare the identifying control sequence of a font.

\fontname The external name of a font.

\nullfont Name of an empty font that TFX uses in emergencies.

\hyphenchar Number of the hyphen character of a font.

\defaulthyphenchar Value of \hyphenchar when a font is loaded. Plain TEX default: `\-.

\fontdimen Access various parameters of fonts.

\char47 Italic correction.

\noboundary Omit implicit boundary character.

#### 4.1 Fonts

In TEX terminology a font is the set of characters that is contained in one external font file. During processing, TEX decides from what font a character should be taken. This decision is taken separately for text mode and math mode.

When TEX is processing ordinary text, characters are taken from the 'current font'. External font file names are coupled to control sequences by statements such as

```
\font\MyFont=myfont10
```

which makes TEX load the file myfont10.tfm. Switching the current font to the font described in that file is then done by

\MyFont

The status of the current font can be queried: the sequence

4.2 Font declaration 49

#### \the\font

produces the control sequence for the current font.

Math mode completely ignores the current font. Instead it looks at the 'current family', which can contain three fonts: one for text style, one for script style, and one for scriptscript style. This is treated in Chapter 21.

See [?] for a consistent terminology of fonts and typefaces.

With 'virtual fonts' (see [?]) it is possible that what looks like one font to TFX resides in more than one physical font file. See further page 298.

## 4.2 Font declaration

Somewhere during a run of TeX or IniTeX the coupling between an internal identifying control sequence and the external file name of a font has to be made. The syntax of the command for this is

```
\font(control sequence)(equals)(file name)(at clause)
```

where

```
\langle at clause \rangle \longrightarrow at \langle dimen \rangle \mid scaled \langle number \rangle \mid \langle optional spaces \rangle
```

Font declarations are local to a group.

By the  $\langle {\rm at\ clause} \rangle$  the user specifies that some magnified version of the font is wanted. The  $\langle {\rm at\ clause} \rangle$  comes in two forms: if the font is given scaled f TeX multiplies all its font dimensions for that font by f/1000; if the font has a design size dpt and the  $\langle {\rm at\ clause} \rangle$  is at ppt TeX multiplies all font data by p/d. The presence of an  $\langle {\rm at\ clause} \rangle$  makes no difference for the external font file (the .tfm file) that TeX reads for the font; it just multiplies the font dimensions by a constant.

After such a font declaration, using the defined control sequence will set the current font to the font of the control sequence.

#### 4.2.1 Fonts and tfm files

The external file needed for the font is a tfm (TEX font metrics) file, which is taken independent of any (at clause) in the \font declaration. If the tfm file has been loaded already (for instance by IniTEX when it constructed the format), an assignment of that font file can be reexecuted without needing recourse to the tfm file.

Font design sizes are given in the font metrics files. The cmr10 font, for

50 第 4 章 Fonts

instance, has a design size of 10 point. However, there is not much in the font that actually has a size of 10 points: the opening and closing parentheses are two examples, but capital letters are considerably smaller.

## 4.2.2 Querying the current font and font names

It was already mentioned above that the control sequence which set the current font can be retrieved by the command \the\font. This is a special case of

A  $\langle$ fontdef token $\rangle$  is a control sequence defined by  $\backslash$ font, or the predefined control sequence  $\backslash$ nullfont. The concept of  $\langle$ family member $\rangle$  is only relevant in math mode.

Also, the external name of fonts can be retrieved:

```
\forall fontname\langle font\rangle
```

gives a sequence of character tokens of category 12 (but space characters get category 10) that spells the font file name, plus an  $\langle$ at clause $\rangle$  if applicable.

```
例子:After
\font\tenroman=cmr10 \tenroman
```

the calls \the\font and \the\tenroman both give \tenroman. The call \fontname\tenroman gives cmr10.

### 4.2.3 \nullfont

TEX always knows a font that has no characters: the \nullfont. If no font has been specified, or if in math mode a family member is needed that has not been specified, TEX will take its characters from the nullfont. This control sequence qualifies as a \( \forall \) fontdef token \( \right) : it acts like any other control sequence that stands for a font; it just does not have an associated tfm file.

4.3 Font information 51

## 4.3 Font information

During a run of TEX the main information needed about the font consists of the dimensions of the characters. TEX finds these in the font metrics files, which usually have extension .tfm. Such files contain

- global information: the \fontdimen parameters, and some other information,
- · dimensions and the italic corrections of characters, and
- ligature and kerning programs for characters.

Also, the design size of a font is specified in the tfm file; see above. The definition of the tfm format can be found in [?].

#### 4.3.1 Font dimensions

Text fonts need to have at least seven \fontdimen parameters to describe *font dimensions* (but TeX will take zero for unspecified parameters); math symbol and math extension fonts have more (see page 233). For text fonts the minimal set of seven comprises the following:

- 1. the slant per point; this dimension is used for the proper horizontal positioning of accents;
- 2. the interword space: this is used unless the user specifies an explicit \spaceskip; see Chapter 20;
- 3. interword stretch: the stretch component of the interword space;
- 4. interword shrink: the shrink component of the interword space;
- 5. the x-height: the value of the (internal unit) ex, which is usually about the height of the lowercase letter 'x';
- 6. the quad width: the value of the (internal unit) em, which is approximately the width of the capital letter 'M'; and
- 7. the extra space: the space added to the interword space at the end of sentences (that is, when  $\spacefactor \ge 2000$ ) unless the user specifies an explicit  $\spacefactor$ .

Parameters 1 and 5 are purely information about the font and there is no point in varying them. The values of other parameters can be changed in order to adjust spacing; see Chapter 20 for examples of changing parameters 2, 3, 4, and 7.

52 第 4 章 Fonts

Font dimensions can be altered in a  $\langle font \ assignment \rangle$ , which is a  $\langle global \ assignment \rangle$  (see page 114):

```
\fontdimen\langle number\rangle\langle font\rangle\langle equals\rangle\langle dimen\rangle
```

See above for the definition of  $\langle font \rangle$ .

### 4.3.2 Kerning

Some combinations of characters should be moved closer together than would be the case if their bounding boxes were to be just abutted. This fine spacing is called *kerning*, and a proper kerning is as essential to a font as the design of the letter shapes.

Consider as an example

'Vo' versus the unkerned variant 'Vo'

Kerning in TEX is controlled by information in the tfm file, and is therefore outside the influence of the user. The tfm file can be edited, however (see Chapter 33).

The \kern command has (almost) nothing to do with the phenomenon of kerning; it is explained in Chapter 8.

#### 4.3.3 Italic correction

The primitive control symbol \/ inserts the *italic correction* of the previous character or ligature. Such a correction may be necessary owing to the definition of the *bounding box* of a character. This box always has vertical sides, and the width of the character as TEX perceives it is the distance between these sides. However, in order to achieve proper spacing for slanted or italic type-faces, characters may very well project outside their bounding boxes. The italic correction is then needed if such an overhanging character is followed by a character from a non-slanting typeface.

Compare for instance

 $T_{E}X$  has' to  $T_{E}X$  has',

where the second version was typed as

```
{\tilde X}
```

The size of the italic correction of each character is determined by font information in the font metrics file; for the Computer Modern fonts it is approximately half the 'overhang' of the characters; see [?]. Italic correction is not

4.3 Font information 53

the same as \fontdimen1, slant per point. That font dimension is used only for positioning accents on top of characters.

An italic correction can only be inserted if the previous item processed by TEX was a character or ligature. Thus the following solution for roman text inside an italic passage does not work:

```
{\italic Some text {\/\roman not} emphasized}
```

The italic correction has no effect here, because the previous item is glue.

## 4.3.4 Ligatures

Replacement of character sequences by *ligatures* is controlled by information in the tfm file of a font. Ligatures are formed from ⟨character⟩ commands: sequences such as fi are replaced by 'fi' in some fonts.

Other ligatures traditionally in use are between ff, ffi, fl, and ffl; in some older works ft and st can be found, and similarly to the fl ligature fk and fb can also occur.

Ligatures in TeX can be formed between explicit character tokens, \char commands, and \chardef token\s. For example, the sequence \char`f\char`i is replaced by the 'fi' ligature, if such a ligature is part of the font.

Unwanted ligatures can be suppressed in a number of ways: the unwanted ligature 'halflife' can for instance be prevented by

```
half{}life, half{l}ife, half\/life, or half\hbox{}life
```

but the solution using italic correction is not equivalent to the others.

## 4.3.5 Boundary ligatures

Each word is surrounded by a left and a right boundary character (TEX3 only). This makes phenomena possible such as the two different sigmas in Greek: one at the end of a word, and one for every other position. This can be realized through a ligature with the boundary character. A \noboundary command immediately before or after a word suppresses the boundary character at that place.

In general, the ligature mechanism has become more complicated with the transition to TrX version 3; see [?].

# 第5章 Boxes

The horizontal and vertical boxes of TEX are containers for pieces of horizontal and vertical lists. Boxes can be stored in box registers. This chapter treats box registers and such aspects of boxes as their dimensions, and the way their components are placed relative to each other.

\hbox Construct a horizontal box.

\vbox Construct a vertical box with reference point of the last item.

\vtop Construct a vertical box with reference point of the first item.

\vcenter Construct a vertical box vertically centred on the math axis; this command can only be used in math mode.

\vsplit Split off the top part of a vertical box.

\box Use a box register, emptying it.

\setbox Assign a box to a box register.

\copy Use a box register, but retain the contents.

\ifhbox \ifvbox Test whether a box register contains a horizontal/vertical box.

\ifvoid Test whether a box register is empty.

\newbox Allocate a new box register.

\unhbox \unvbox Unpack a box register containing a horizontal/vertical box, adding the contents to the current horizontal/vertical list, and emptying the register.

\unhcopy \unvcopy The same as \unhbox/\unvbox, but do not empty the register.

\ht \dp \wd Height/depth/width of the box in a box register.

\boxmaxdepth Maximum allowed depth of boxes. Plain TEX default: \maxdimen.

\splitmaxdepth Maximum allowed depth of boxes generated by \vsplit.

5.1 Boxes 55

\badness Badness of the most recently constructed box.

\hfuzz \vfuzz Excess size that TeX tolerates before it considers a horizontal/vertical box overfull.

\hbadness \vbadness Amount of tolerance before TeX reports an underfull or overfull horizontal/vertical box.

\overfullrule Width of the rule that is printed to indicate overfull horizontal boxes.

\hsize Line width used for text typesetting inside a vertical box.

\vsize Height of the page box.

\lastbox Register containing the last item added to the current list, if this was a box.

\raise \lower Adjust vertical positioning of a box in horizontal mode.

\moveleft \moveright Adjust horizontal positioning of a box in vertical mode.

\everybox \everyvbox Token list inserted at the start of a horizontal/vertical box.

# 5.1 Boxes

In this chapter we shall look at boxes. Boxes are containers for pieces of horizontal or vertical lists. Boxes that are needed more than once can be stored in box registers.

When TFX expects a  $\langle box \rangle$ , any of the following forms is admissible:

- \hbox\box specification\{\( \text{horizontal material} \) \}
- \vbox\box specification\{\langle vertical material\}
- \vtop\box specification\{\langle vertical material\}
- \box\8-bit number\
- \copy(8-bit number)
- $\vert \langle 8-bit\ number \rangle to \langle dimen \rangle$
- \lastbox

A (box specification) is defined as

```
\langle box\ specification \rangle \longrightarrow \langle filler \rangle
| to \langle dimen \rangle \langle filler \rangle | spread \langle dimen \rangle \langle filler \rangle
```

An  $\langle 8\text{-bit number} \rangle$  is a number in the range 0–255.

The braces surrounding box material define a group; they can be explicit characters of categories 1 and 2 respectively, or control sequences \let to such characters; see also below.

 $A \langle box \rangle$  can in general be used in horizontal, vertical, and math mode, but see below for the \lastbox. The connection between boxes and modes is explored further in Chapter 6.

The box produced by  $\ensuremath{\text{vcenter}}$  — a command that is allowed only in math mode — is not a  $\langle box \rangle$ . For instance, it can not be assigned with  $\ensuremath{\text{setbox}}$ ; see further Chapter 23.

The \vsplit operation is treated in Chapter 27.

# 5.2 Box registers

There are 256 box registers, numbered 0–255. Either a box register is empty ('void'), or it contains a horizontal or vertical box. This section discusses specifically box *registers*; the sizes of boxes, and the way material is arranged inside them, is treated below.

#### 5.2.1 Allocation: \newbox

The plain TFX \newbox macro allocates an unused box register:

\newbox\MyBox

after which one can say

```
\setbox\MyBox=...
```

or

\box\MyBox

and so on. Subsequent calls to this macro give subsequent box numbers; this way macro collections can allocate their own boxes without fear of collision with other macros.

The number of the box is assigned by \chardef (see Chapter 31). This implies that \MyBox is equivalent to, and can be used as, a  $\langle number \rangle$ . The control sequence \newbox is an \outer macro. Newly allocated box registers are initially empty.

5.2 Box registers 57

## 5.2.2 Usage: \setbox, \box, \copy

A register is filled by assigning a  $\langle box \rangle$  to it:

```
\star{box}\langle number \rangle \langle equals \rangle \langle box \rangle
```

For example, the  $\langle box \rangle$  can be explicit

```
\stbox37=\hbox{...} or \stbox37=\vbox{...}
```

or it can be a box register:

```
\setbox37=\box38
```

Usually, box numbers will have been assigned by a \newbox command.

The box in a box register is appended by the commands \box and \copy to whatever list TrX is building: the call

```
\box38
```

appends box 38. To save memory space, box registers become empty by using them:  $T_EX$  assumes that after you have inserted a box by calling  $\begin{subarray}{l} \begin{subarray}{l} \be$ 

It is possible to unwrap the contents of a box register by 'unboxing' it using the commands \unbox and \unvbox, and their copying versions \unbcopy and \unvcopy. Whereas a box can be used in any mode, the unboxing operations can only be used in the appropriate mode, since in effect they contribute a partial horizontal or vertical list (see also Chapter 6). See below for more information on unboxing registers.

# 5.2.3 Testing: \ifvoid, \ifhbox, \ifvbox

Box registers can be tested for their contents:

```
\ifvoid(number)
```

is true if the box register is empty. Note that an empty, or 'void', box register is not the same as a register containing an empty box. An empty box is still either a horizontal or a vertical box; a void register can be used as both.

The test

```
\ifhbox(number)
```

is true if the box register contains a horizontal box;

\ifvbox(number)

is true if the box register contains a vertical box. Both tests are false for void registers.

#### 5.2.4 The \lastbox

When TeX has built a partial list, the last box in this list is accessible as the \lastbox. This behaves like a box register, so you can remove the last box from the list by assigning the \lastbox to some box register. If the last item on the current list is not a box, the \lastbox acts like a void box register. It is not possible to get hold of the last box in the case of the main vertical list. The \lastbox is then always void.

As an example, the statement

```
{\setbox0=\lastbox}
```

removes the last box from the current list, assigning it to box register 0. Since this assignment occurs inside a group, the register is cleared at the end of the group. At the start of a paragraph this can be used to remove the indentation box (see Chapter 16). Another example of \lastbox can be found on page 71.

Because the \lastbox is always empty in external vertical mode, it is not possible to get hold of boxes that have been added to the page. However, it is possible to dissect the page once it is in \box255, for instance doing

```
\vbox{\unvbox255{\setbox0=\lastbox}}
```

inside the output routine.

If boxes in vertical mode have been shifted by \moveright or \moveleft, or if boxes in horizontal mode have been raised by \raise or lowered by \lower, any information about this displacement due to such a command is lost when the \lastbox is taken from the list.

## 5.3 Natural dimensions of boxes

#### 5.3.1 Dimensions of created horizontal boxes

Inside an hoox all constituents are lined up next to each other, with their reference points on the baseline of the box, unless they are moved explicitly in the vertical direction by lower or house.

The resulting width of the box is the sum of the widths of the components.

```
Thus the width of

\hbox{\hskip1cm}

is positive, and the width of

\hbox{\hskip-1cm}

is negative. By way of example,

a\hbox{\kern-1em b}--

gives as output

ba-
```

which shows that a horizontal box can have negative width.

The height and depth of an hoox are the maximum amount that constituent boxes project above and below the baseline of the box. They are nonnegative when the box is created.

The commands \lower and \raise are the only possibilities for vertical movement inside an \hbox (other than including a \vbox inside the \hbox, of course); a \( \nabla vertical \) command \( \nabla vertical \) command \( \nabla vertical \) such as \\nabla vertical \( \nabla vertical \) is not allowed in a horizontal box, and \\nabla par, although allowed, does not do anything inside a horizontal box.

#### 5.3.2 Dimensions of created vertical boxes

Inside a \vbox vertical material is lined up with the reference points on the vertical line through the reference point of the box, unless components are moved explicitly in the horizontal direction by \moveleft or \moveright.

The reference point of a vertical box is always located at the left boundary of the box. The width of a vertical box is then the maximal amount that any material in the box sticks to the right of the reference point. Material to the left of the reference point is not taken into account in the width. Thus the result of

```
a\vbox{\hbox{\kern-1em b}}--
is
ba-
```

This should be contrasted with the above example.

The calculation of height and depth is different for vertical boxes constructed by \vbox and \vtop. The ground rule is that a \vbox has a reference point that lies on the baseline of its last component, and a \vtop has its reference point on the baseline of the first component. In general, the depth (height) of a \vbox

(\vtop) can be non-zero if the last (first) item is a box or rule.

The height of a \vbox is then the sum of the heights and depths of all components except the last, plus the height of that last component; the depth of the \vbox is the depth of its last component. The depth of a \vtop is the sum of the depth of the first component and the heights and depths of all subsequent material; its height is the height of the first component.

However, the actual rules are a bit more complicated when the first component of a \vtop or the last component of a \vbox is not a box or rule. If the last component of a \vbox is a kern or a glue, the depth of that box is zero; a \vtop's height is zero unless its first component is a box or rule. (Note the asymmetry in these definitions; see below for an example illustrating this.) The depth of a \vtop, then, is equal to the total height plus depth of all enclosed material minus the height of the \vtop.

There is a limit on the depth of vertical boxes: if the depth of a \vbox or \vtop calculated by the above rules would exceed, the reference point of the box is moved down by the excess amount. More precisely, the excess depth is added to the natural height of the box. If the box had a to or spread specification, any glue is set anew to take the new height into account.

Ordinarily, \boxmaxdepth is set to the maximum dimension possible in TEX. It is for instance reduced during some of the calculations in the plain TEX output routine; see Chapter 28.

## 5.3.3 Examples

Horizontal boxes are relatively straightforward. Their width is the distance between the 'beginning' and the 'end' of the box, and consequently the width is not necessarily positive. With

```
\setbox0=\hbox{aa} \setbox1=\hbox{\copy0 \hskip-\wd0}

the \box1 has width zero;

/\box1/ gives '/aa'
```

The height and depth of a horizontal box cannot be negative: in

```
\setbox0=\hbox{\vrule height 5pt depth 5pt}
\setbox1=\hbox{\raise 10pt \box0}
```

the \box1 has depth 0pt and height 15pt

Vertical boxes are more troublesome than horizontal boxes. Let us first treat their width. After

```
\setbox0=\hbox{\hskip 10pt}
```

the box in the \box0 register has a width of 10pt. Defining

```
\setbox1=\vbox{\moveleft 5pt \copy0}
```

the \box1 will have width 5pt; material to the left of the reference point is not accounted for in the width of a vertical box. With

```
\setbox2=\vbox{\moveright 5pt \copy0}
```

the \box2 will have width 15pt.

The depth of a \vbox is the depth of the last item if that is a box, so

```
\vbox{\vskip 5pt \hbox{\vrule height 5pt depth 5pt}}
```

has height 10pt and depth 5pt, and

```
\vbox{\vskip -5pt \hbox{\vrule height 5pt depth 5pt}}
```

has height Opt and depth 5pt. With a glue or kern as the last item in the box, the resulting depth is zero, so

```
\vbox{\hbox{\vrule height 5pt depth 5pt}\vskip 5pt}
```

has height 15pt and depth 0pt;

```
\vbox{\hbox{\vrule height 5pt depth 5pt}\vskip -5pt}
```

has height 5pt and depth 0pt.

The height of a \vtop behaves (almost) the same with respect to the first item of the box, as the depth of a \vtox does with respect to the last item. Repeating the above examples with a \vtop gives the following:

```
\vtop{\vskip 5pt \hbox{\vrule height 5pt depth 5pt}}
```

has height Opt and depth 15pt, and

```
\vtop{\vskip -5pt \hbox{\vrule height 5pt depth 5pt}}
```

has height Opt and depth 5pt;

```
\vtop{\hbox{\vrule height 5pt depth 5pt} \vskip 5pt}
```

has height 5pt and depth 10pt, and

```
\vtop{\hbox{\vrule height 5pt depth 5pt} \vskip -5pt}
```

has height 5pt and depth 0pt.

#### 5.4 More about box dimensions

#### 5.4.1 Predetermined dimensions

The size of a box can be specified in advance with a \( box \) specification\\( ); see above for the syntax. Any glue in the box is then set in order to reach the required size. Prescribing the size of the box is done by

```
\hbox to \langle dimen \rangle \{ \ldots \}, \vbox to \langle dimen \rangle \{ \ldots \}
```

If stretchable or shrinkable glue is present in the box, it is stretched or shrunk in order to give the box the specified size. Associated with this glue setting is a badness value (see Chapter 8). If no stretch or shrink —— whichever is necessary —— is present, the resulting box will be underfull or overfull respectively. Error reporting for over/underfull boxes is treated below.

Another command to let a box have a size other than the natural size is

```
\hbox spread \langle dimen \rangle {...}, \vbox spread \langle dimen \rangle {...}
```

which tells T<sub>E</sub>X to set the glue in such a way that the size of the box is a specified amount more than the natural size.

Box specifications for \vtop vertical boxes are somewhat difficult to interpret. TEX constructs a \vtop by first making a \vbox, including glue settings induced by a \doox specification\); then it computes the height and depth by the above rules. Glue setting is described in Chapter 8.

## 5.4.2 Changes to box dimensions

The dimensions of a box register are accessible by the commands \ht, \dp, and \wd; for instance \dp13 gives the depth of box 13. However, not only can boxes be measured this way; by assigning values to these dimensions TEX can even be fooled into thinking that a box has a size different from its actual. However, changing the dimensions of a box does not change anything about the contents; in particular it does not change the way the glue is set.

```
Various formats use this in 'smash' macros: the macro defined by \def\smash#1{{\setbox0=\hbox{#1}\dp0=0pt \ht0=0pt \box0\relax}}
```

places its argument but annihilates its height and depth; that is, the output does show the whole box, but further calculations by TEX act as if the height and depth were zero.

Box dimensions can be changed only by setting them. They are  $\langle box\ dimen \rangle s$ , which can only be set in a  $\langle box\ size\ assignment \rangle$ , and not, for instance changed with  $\land advance$ .

Note that a \langle box size assignment \rangle is a \langle global assignment \rangle its effect transcends any groups in which it occurs (see Chapter 10). Thus the output of

$$\sc \box{0=\hbox{---} {\wd0=0pt} a\box{0b}}$$

is 'ab-'.

The limits that hold on the dimensions with which a box can be created (see above) do not hold for explicit changes to the size of a box: the assignment \dp0=-2pt for a horizontal box is perfectly admissible.

## 5.4.3 Moving boxes around

In a horizontal box all constituent elements are lined up with their reference points at the same height as the reference point of the box. Any box inside a horizontal box can be lifted or dropped using the macros \raise and \lower.

Similarly, in a vertical box all constituent elements are lined up with their reference points underneath one another, in line with the reference point of the box. Boxes can now be moved sideways by the macros \moveleft and \moveright.

Only boxes can be shifted thus; these operations cannot be applied to, for instance, characters or rules.

## 5.4.4 Box dimensions and box placement

TEX places the components of horizontal and vertical lists by maintaining a reference line and a current position on that line. For horizontal lists the reference line is the baseline of the surrounding \hbox; for vertical lists it is the vertical line through the reference point of the surrounding \vbox.

In horizontal mode a component is placed as follows. The current position coincides initially with the reference point of the surrounding box. After that, the following actions are carried out.

- 1. If the component has been shifted by \raise or \lower, shift the current position correspondingly.
- 2. If the component is a horizontal box, use this algorithm recursively for its contents; if it is a vertical box, go up by the height of this box, putting a new current position for the enclosed vertical list there, and place its components using the algorithm for vertical lists below.
- 3. Move the current position (on the reference line) to the right by the width of the component.

For the list in a vertical box TeX's current position is initially at the upper

left corner of that box, as explained above, and the reference line is the vertical line through that point; it also runs through the reference point of the box. Enclosed components are then placed as follows.

- 1. If a component has been shifted using \moveleft or \moveright, shift the current position accordingly.
- 2. Put the component with its upper left corner at the current position.
- 3. If the component is a vertical box, use this algorithm recursively for its contents; if it is a horizontal box, its reference point can be found below the current position by the height of the box. Put the current position for that box there, and use the above algorithm for horizontal lists.
- 4. Go down by the height plus depth of the box (that is, starting at the upper left corner of the box) on the reference line, and continue processing vertically.

Note that the above processes do not describe the construction of boxes. That would (for instance) involve for vertical boxes the insertion of baselineskip glue. Rather, it describes the way the components of a finished box are arranged in the output.

## 5.4.5 Boxes and negative glue

Sometimes it is useful to have boxes overlapping instead of line up. An easy way to do this is to use negative glue. In horizontal mode

```
{\dimen0=\wd8 \box8 \kern-\dimen0}
```

places box 8 without moving the current location.

More versatile are the macros \llap and \rlap, defined as

```
\def\llap#1{\hbox to Opt{\hss #1}}
```

and

```
\def\rlap#1{\hbox to Opt{#1\hss}}
```

that allow material to protrude left or right from the current location. The \hss glue is equivalent to \hskip Opt plus 1fil minus 1fil, which absorbs any positive or negative width of the argument of \lap or \rlap.

```
例子:The sequence
\llap{\hbox to 10pt{a\hfil}}
is effectively the same as
\hbox{\hskip-10pt \hbox to 10pt{a\hfil}}
```

which has a total width of Opt.

## 5.5 Overfull and underfull boxes

If a box has a size specification T<sub>E</sub>X will stretch or shrink glue in the box. For glue with only finite stretch or shrink components the *badness* (see Chapter 19) of stretching or shrinking is computed. In T<sub>E</sub>X version 3 the badness of the box most recently constructed is available for inspection by the user through the \badness parameter. Values for badness range 0–10000, but if the box is overfull it is 1000000.

When TEX considers the badness too large, it gives a diagnostic message. Let us first consider error reporting for horizontal boxes.

Horizontal boxes of which the glue has to stretch are never reported if  $\hbadness \geq 10\,000$ ; otherwise TEX reports them as 'underfull' if their badness is more than  $\hbadness$ .

Glue shrinking can lead to 'overfull' boxes: a box is called overfull if the available shrink is less than the shrink necessary to meet the box specification. An overfull box is only reported if the difference in shrink is more than  $\hfuzz$ , or if  $\hfuzs$  or if  $\hfuzs$  out that using all available shrinkability has badness 100).

例子: Setting \hfuzz=1pt will let TEX ignore boxes that can not shrink enough if they lack less than 1pt. In

```
\hbox to 1pt{\hskip3pt minus .5pt}
\hbox to 1pt{\hskip3pt minus 1.5pt}
```

Also, boxes that shrink but that are not overfull can be reported: if a box is 'tight', that is, if it uses at least half its shrinkability, TEX reports this fact if the computed badness (which is between 13 and 100) is more than \hbadness.

For horizontal and vertical boxes this error reporting is almost the same, with parameters \vbadness and \vfuzz. The difference is that for horizontal overfull boxes TeX will draw a rule to the right of the box that has the same height as the box, and width \overfullrule. No overfull rule ensues if the \tabskip glue in an \halign cannot be shrunk enough.

# 5.6 Opening and closing boxes

The opening and closing braces of a box can be either explicit, that is, character tokens of category 1 and 2, or implicit, a control sequence \let to such a character. After the opening brace the \everybox or \everyvbox tokens are inserted. If this box appeared in a \setbox assignment any \afterassignment token is inserted even before the 'everybox' tokens.

```
例子:
    \everyhbox{b}
    \afterassignment a
    \setbox0=\hbox{c}
    \showbox0

gives

    \box0=
    \hbox(6.94444+0.0)x15.27782
    .\tenrm a
    .\tenrm b
    .\kern0.27779
    .\tenrm c
```

Implicit braces can be used to let a box be opened or closed by a macro, for example:

```
\def\openbox#1{\setbox#1=\hbox\bgroup}
\def\closebox#1{\egroup\DoSomethingWithBox#1}
\openbox0 ... \closebox0
```

This mechanism can be used to scoop up paragraphs:

```
\everypar{\setbox\parbox=
   \vbox\bgroup
   \everypar{}
   \def\par{\egroup\UseBox\parbox}}
```

Here the \everypar opens the box and lets the text be set in the box: starting for instance

```
Begin a text ...
gives the equivalent of
  \setbox\parbox=\vbox{Begin a text ...
Inside the box \par has been redefined, so
    ... a text ends.\par
is equivalent to
```

5.7 Unboxing 67

```
... a text ends.}\Usebox\parbox
```

In this example, the \UseBox command can only treat the box as a whole; if the elements of the box should somehow be treated separately another approach is necessary. In

the macro \HandleLines can have access to successive elements from the vertical list of the paragraph. See also the example on page 71.

# 5.7 Unboxing

Boxes can be unwrapped by the commands \unbox and \unvbox, and by their copying versions \unbcopy and \unvcopy. These are horizontal and vertical commands (see Chapter 6), considering that in effect they contribute a partial horizontal or vertical list. It is not possible to \unbbox a register containing a \vbox or vice versa, but a void box register can both be \unbboxed and \unvboxed.

Unboxing takes the contents of a box in a box register and appends them to the surrounding list; any glue can then be set anew. Thus

```
\setbox0=\hbox to 1cm{\hfil} \hbox to 2cm{\unhbox0}
is completely equivalent to
   \hbox to 2cm{\hfil}
and not to
   \hbox to 2cm{\kern1cm}
The intrinsically horizontal nature of \unhbox is used to define
   \def\leavevmode{\unhbox\voidb@x}
```

This command switches from vertical mode to horizontal without adding anything to the horizontal list. However, the subsequent \indent caused by this transition adds an indentation box. In horizontal mode the \leavevmode command has no effect. Note that here it is not necessary to use \unhcopy, because the register is empty anyhow.

Beware of the following subtlety: unboxing in vertical mode does not add interline glue between the box contents and any preceding item. Also, the value

of \prevdepth is not changed, so glue between the box contents and any following item will occur only if there was something preceding the box; interline glue will be based on the depth of that preceding item. Similarly, unboxing in horizontal mode does not influence the \spacefactor.

## 5.8 Text in boxes

Both horizontal and vertical boxes can contain text. However, the way text is treated differs. In horizontal boxes the text is placed in one straight line, and the width of the box is in principle the natural width of the text (and other items) contained in it. No  $\langle \text{vertical command} \rangle$ s are allowed inside a horizontal box, and par does nothing in this case.

For vertical boxes the situation is radically different. As soon as a character, or any other  $\langle horizontal\ command \rangle$  (see page 75), is encountered in a vertical box, TEX starts building a paragraph in unrestricted horizontal mode, that is, just as if the paragraph were directly part of the page. At the occurrence of a  $\langle vertical\ command \rangle$  (see page 75), or at the end of the box, the paragraph is broken into lines using the current values of parameters such as \hsize.

Thus

```
\hbox to 3cm{\vbox{some reasonably long text}}
```

will *not* give a paragraph of width 3 centimetres (it gives an overfull horizontal box if \hsize > 3cm). However,

```
\vbox{\hsize=3cm some reasonably long text}
```

will be 3 centimetres wide.

A paragraph of text inside a vertical box is broken into lines, which are packed in horizontal boxes. These boxes are then stacked in internal vertical mode, possibly with \baselineskip and \lineskip separating them (this is treated in Chapter 15). This process is also used for text on the page; the boxes are then stacked in outer vertical mode.

If the internal vertical list is empty, no \parskip glue is added at the start of a paragraph.

Because text in a horizontal box is not broken into lines, there is a further difference between text in restricted and unrestricted horizontal mode. In restricted horizontal mode no discretionary nodes and whatsit items changing the value of the current language are inserted. This may give problems if the text is subsequently unboxed to form part of a paragraph.

5.9 Assorted remarks 69

See Chapter 19 for an explanation of these items, and [?] for a way around this problem.

## 5.9 Assorted remarks

## 5.9.1 Forgetting the \box

After \newcount\foo, one can use \foo on its own to get the \foo counter. For boxes, however, one has to use \box\foo to get the \foo box. The reason for this is that there exists no separate \boxdef command, so \chardef is used (see Chapter 31).

例子: Suppose \newbox\foo allocates box register 25; then typing \foo is equivalent to typing \char25.

## 5.9.2 Special-purpose boxes

Some box registers have a special purpose:

- \box255 is by used TeX internally to give the page to the output routine.
- \voidb@x is the number of a box register allocated in plain.tex; it is supposed to be empty always. It is used in the macro \leavevmode and others.
- when a new \insert is created with the plain TEX \newinsert macro, a \count, \dimen, \skip, and \box all with the same number are reserved for that insert. The numbers for these registers count down from 254.

# 5.9.3 The height of a vertical box in horizontal mode

In horizontal mode a vertical box is placed with its reference point aligned vertically with the reference point of the surrounding box. TeX then traverses its contents starting at the left upper corner; that is, the point that lies above the reference point by a distance of the height of the box. Changing the height of the box implies then that the contents of the box are placed at a different height.

```
Consider as an example
\hbox{a\setbox0=\vbox{\hbox{b}}\box0 c}
which gives
abc
```

and

```
\label{local} $$ \as etbox0=\vbox{\hbox{b}}\ht0=0cm \box0 c} $$ which gives
```

a<sub>h</sub>c

By contrast, changing the width of a box placed in vertical mode has no effect on its placement.

#### 5.9.4 More subtleties with vertical boxes

Since there are two kinds of vertical boxes, the \vbox and the \vtop, using these two kinds nested may lead to confusing results. For instance,

```
\vtop{\vbox{...}}
```

is completely equivalent to just

```
\vbox{...}
```

It was stated above that the depth of a \vbox is zero if the last item is a kern or glue, and the height of a \vtop is zero unless the first item in it is a box. The above examples used a kern for that first or last item, but if, in the case of a \vtop, this item is not a glue or kern, one is apt to overlook the effect that it has on the surrounding box. For instance,

```
\vtop{\write16{...}...}
```

has zero height, because the write instruction is packed into a 'whatsit' item that is placed on the current, that is, the vertical, list. The remedy here is

```
\vtop{\leavevmode\write16{...}...}
```

which puts the whatsit in the beginning of the paragraph, instead of above it.

Placement of items in a vertical list is sometimes a bit tricky. There is for instance a difference between how vertical and horizontal boxes are treated in a vertical list. Consider the following examples. After \offinterlineskip the first example

5.9 Assorted remarks 71

The difference is caused by the fact that horizontal boxes are placed with respect to their reference point, but vertical boxes with respect to their upper left corner.

## 5.9.5 Hanging the \lastbox back in the list

You can pick the last box off a vertical list that has been compiled in (internal) vertical mode. However, if you try to hang it back in the list the vertical spacing may go haywire. If you just hang it back,

```
\setbox\tmpbox=\lastbox
\usethetmpbox \box\tmpbox
```

baselineskip glue is added a second time. If you 'unskip' prior to hanging the box back,

```
\setbox\tmpbox=\lastbox \unskip
\usethetmpbox \box\tmpbox
```

things go wrong in a more subtle way. The <code>(internal dimen) \prevdepth (which controls interline glue; see Chapter 15)</code> will have a value based on the last box, but what you need for the proper interline glue is a depth based on one box earlier. The solution is not to unskip, but to specify <code>\nointerlineskip</code>:

```
\setbox\tmpbox=\lastbox
\usethetmpbox \nointerlineskip \box\tmpbox
```

# 5.9.6 Dissecting paragraphs with \lastbox

Repeatedly applying \last... and \un... macros can be used to take a paragraph apart. Here is an example of that.

In typesetting advertisement copy, a way of justifying paragraphs has become popular in recent years that is somewhere between flushright and raggedright setting. Lines that would stretch beyond certain limits are set with their glue at natural width. This single paragraph is but an example of this procedure; the macros are given next.

72 第 5 章 Boxes

```
\newbox\linebox \newbox\snapbox
\def\eatlines{
    \setbox\linebox\lastbox % check the last line
   \ifvoid\linebox
   \else
                               % if it's not empty
   \unskip\unpenalty
                               % take whatever is
   {\eatlines}
                               % above it;
                               % collapse the line
   \setbox\snapbox\hbox{\unhcopy\linebox}
                       % depending on the difference
   \ifdim\wd\snapbox<.98\wd\linebox
          \box\snapbox % take the one or the other,
   \else \box\linebox \fi
   \fi}
```

This macro can be called as

```
\vbox{ ... some text ... \par\eatlines}
```

or it can be inserted automatically with \everypar; see [?].

In the macro \eatlines, the \lastbox is taken from a vertical list. If the list is empty the last box will test true on \ifvoid. These boxes containing lines from a paragraph are actually horizontal boxes: the test \ifhbox applied to them would give a true result.

# 第 6 章 Horizontal and Vertical Mode

At any point in its processing TeX is in some *mode*. There are six modes, divided in three categories:

- 1. horizontal mode and restricted horizontal mode,
- 2. vertical mode and internal vertical mode, and
- 3. math mode and display math mode.

The math modes will be treated elsewhere (see page 225). Here we shall look at the horizontal and vertical modes, the kinds of objects that can occur in the corresponding lists, and the commands that are exclusive for one mode or the other.

\ifhmode Test whether the current mode is (possibly restricted) horizontal mode.

\ifvmode Test whether the current mode is (possibly internal) vertical mode.

\ifinner Test whether the current mode is an internal mode.

\vadjust Specify vertical material for the enclosing vertical list while in horizontal mode.

\showlists Write to the log file the contents of the partial lists currently being built in all modes.

### 6.1 Horizontal and vertical mode

When not typesetting mathematics, TEX is in horizontal or vertical mode, building horizontal or vertical lists respectively. Horizontal mode is typically used to make lines of text; vertical mode is typically used to stack the lines of a paragraph on top of each other. Note that these modes are different from the internal states of TEX's input processor (see page 26).

## 6.1.1 Horizontal mode

The main activity in *horizontal mode* is building lines of text. Text on the page and text in a \vbox or \vtop is built in horizontal mode (this might be called 'paragraph mode'); if the text is in an \hbox there is only one line of text, and the corresponding mode is the restricted horizontal mode.

In horizontal mode all material is added to a horizontal list. If this list is built in unrestricted horizontal mode, it will later be broken into lines and added to the surrounding vertical list.

Each element of a *horizontal list* is one of the following:

- a box (a character, ligature, \vrule, or a \langle box \rangle),
- a discretionary break,
- a whatsit (see Chapter 30),
- vertical material enclosed in \mark, \vadjust, or \insert,
- glue or leaders, a kern, a penalty, or a math-on/off item.

The items in the last point are all discardable. *Discardable items* are called that, because they disappear in a break. Breaking of horizontal lists is discussed in Chapter 19.

#### 6.1.2 Vertical mode

*Vertical mode* can be used to stack items on top of one another. Most of the time, these items are boxes containing the lines of paragraphs.

Stacking material can take place inside a vertical box, but the items that are stacked can also appear by themselves on the page. In the latter case TEX is in vertical mode; in the former case, inside a vertical box, TEX operates in internal vertical mode.

In vertical mode all material is added to a vertical list. If this list is built in external vertical mode, it will later be broken when pages are formed.

Each element of a *vertical list* is one of the following:

- a box (a horizontal or vertical box or an \hrule),
- a whatsit,
- · a mark.
- glue or leaders, a kern, or a penalty.

The items in the last point are all discardable. Breaking of vertical lists is

discussed in Chapter 27.

There are a few exceptional conditions at the beginning of a vertical list: the value of \prevdepth is set to -1000pt. Furthermore, no \parskip glue is added at the top of an internal vertical list; at the top of the main vertical list (the top of the 'current page') no glue or other discardable items are added, and \topskip glue is added when the first box is placed on this list (see Chapters 26 and 27).

# 6.2 Horizontal and vertical commands

Some commands are so intrinsically horizontal or vertical in nature that they force  $T_E X$  to go into that mode, if possible. A command that forces  $T_E X$  into horizontal mode is called a  $\langle horizontal \ command \rangle$ ; similarly a command that forces  $T_E X$  into vertical mode is called a  $\langle vertical \ command \rangle$ .

However, not all transitions are possible: TEX can switch from both vertical modes to (unrestricted) horizontal mode and back through horizontal and vertical commands, but no transitions to or from restricted horizontal mode are possible (other than by enclosing horizontal boxes in vertical boxes or the other way around). A vertical command in restricted horizontal mode thus gives an error; the \par command in restricted horizontal mode has no effect.

The *horizontal commands* are the following:

- any (letter), (otherchar), \char, a control sequence defined by \chardef, or \noboundary;
- \accent, \discretionary, the discretionary hyphen \- and control space \;
- \unhbox and \unhcopy;
- \vrule and the \(\lambda\) commands \\hskip, \\hfill, \\hss, and \\hfilneg;
- \valign;
- math shift (\$).

The *vertical commands* are the following:

- \unvbox and \unvcopy;
- \hrule and the \(\forall \) vertical skip\(\) commands \\vskip\(\) vfil\(\), \\\vsi\(\) and \\\\vfilneg\(\);
- \halign;
- \end and \dump.

Note that the vertical commands do not include \par; nor are \indent and \noindent horizontal commands.

The connection between boxes and modes is explored below; see Chapter 9 for more on the connection between rules and modes.

## 6.3 The internal modes

The restricted horizontal mode and internal vertical mode are those variants of horizontal mode and vertical mode that hold inside an \hbox and \vbox (or \vtop or \vcenter) respectively. However, restricted horizontal mode is rather more restricted in nature than internal vertical mode. The third internal mode is non-display math mode (see Chapter 23).

#### 6.3.1 Restricted horizontal mode

The main difference between restricted horizontal mode, the mode in an  $\hbox$ , and unrestricted horizontal mode, the mode in which paragraphs in vertical boxes and on the page are built, is that you cannot break out of restricted horizontal mode:  $\par$  does nothing in this mode. Furthermore, a  $\par$  vertical command $\par$  in restricted horizontal mode gives an error. In unrestricted horizontal mode it would cause a  $\par$  token to be inserted and vertical mode to be entered (see also Chapter 17).

### 6.3.2 Internal vertical mode

Internal vertical mode, the vertical mode inside a  $\begin{tabular}{l} \begin{tabular}{l} \begin{tabular}{l$ 

One difference is that the commands \unskip and \unkern have no effect in external vertical mode, and \lastbox is always empty in external vertical mode. See further pages 58 and 102.

The entries of alignments (see Chapter 25) are processed in internal modes: restricted horizontal mode for the entries of an halign, and internal vertical mode for the entries of a valign. The material in vadjust and hinsert items is also processed in internal vertical mode; furthermore, TeX enters this mode when processing the houtput token list.

6.4 Boxes and modes 77

The commands \end and \dump (the latter exists only in IniTeX) are not allowed in internal vertical mode; furthermore, \dump is not allowed inside a group (see Chapter 33).

## 6.4 Boxes and modes

There are horizontal and vertical boxes, and there is horizontal and vertical mode. Not surprisingly, there is a connection between the boxes and the modes. One can ask about this connection in two ways.

## 6.4.1 What box do you use in what mode?

This is the wrong question. Both horizontal and vertical boxes can be used in both horizontal and vertical mode. Their placement is determined by the prevailing mode at that moment.

## 6.4.2 What mode holds in what box?

This is the right question. When an \hbox starts, TeX is in restricted horizontal mode. Thus everything in a horizontal box is lined up horizontally.

When a \vbox is started, TeX is in internal vertical mode. Boxes of both kinds and other items are then stacked on top of each other.

# 6.4.3 Mode-dependent behaviour of boxes

Any \langle box \rangle (see Chapter 5 for the full definition) can be used in horizontal, vertical, and math mode. Unboxing commands, however, are specific for horizontal or vertical mode. Both \unbox and \unbcopy are \langle horizontal command\rangles, so they can make TeX switch from vertical to horizontal mode; both \unvbox and \unvcopy are \langle vertical command\rangles, so they can make TeX switch from horizontal to vertical mode.

In horizontal mode the \spacefactor is set to 1000 after a box has been placed. In vertical mode the \prevdepth is set to the depth of the box placed. Neither statement holds for unboxing commands: after an \unbox or \unbox or \unbox opy the spacefactor is not altered, and after \unvbox or \unvcopy the \prevdepth remains unchanged. After all, these commands do not add a box, but a piece of a (horizontal or vertical) list.

The operations \raise and \lower can only be applied to a box in horizontal mode; similarly, \moveleft and \moveright can only be applied in vertical mode.

# 6.5 Modes and glue

Both in horizontal and vertical mode TeX can insert glue items the size of which is determined by the preceding object in the list.

For horizontal mode the amount of glue that is inserted for a space token depends on the \spacefactor of the previous object in the list. This is treated in Chapter 20.

In vertical mode TEX inserts glue to keep boxes at a certain distance from each other. This glue is influenced by the height of the current item and the depth of the previous one. The depth of items is recorded in the \prevdepth parameter (see Chapter 15).

The two quantities \prevdepth and \spacefactor use the same internal register of TEX. Thus the \prevdepth can be used or asked only in vertical mode, and the \spacefactor only in horizontal mode.

# 6.6 Migrating material

The three control sequences \insert, \mark, and \vadjust can be given in a paragraph (the first two can also occur in vertical mode) to specify *migrating material*: material that will wind up on the surrounding vertical list rather than on the current list. Note that this need not be the main vertical list: it can be a vertical box containing a paragraph of text. In this case a \mark or \insert command will not reach the page breaking algorithm.

When several migrating items are specified in a certain line of text, their left-to-right order is preserved when they are placed on the surrounding vertical list. These items are placed directly after the horizontal box containing the line of text in which they were specified: they come before any penalty or glue items that are automatically inserted (see page 198).

# 6.6.1 \vadjust

The command

is only allowed in horizontal and math modes (but it is not a \( \)horizontal command\( \)). Vertical mode material specified by \( \)vadjust is moved from the horizontal list in which the command is given to the surrounding vertical list, directly after the box in which it occurred.

 In the current line a \vadjust item was placed to put the bullet in the margin.

Any vertical material in a \vadjust item is processed in internal vertical mode, even though it will wind up on the main vertical list. For instance, the \ifinner test is true in a \vadjust, and at the start of the vertical material \prevdepth=-1000pt.

# 6.7 Testing modes

The three conditionals \ifhmode, \ifvmode, and \ifinner can distinguish between the four modes of TEX that are not math modes. The \ifinner test is true if TEX is in restricted horizontal mode or internal vertical mode (or in non-display math mode). Exceptional condition: during a \write TEX is in a 'no mode' state. The tests \ifhmode, \ifvmode, and \iffmode are then all false.

Inspection of all current lists, including the 'recent contributions' (see Chapter 27), is possible through the command \showlists. This command writes to the log file the contents of all lists that are being built at the moment the command is given.

Consider the example

```
a\hfil\break b\par
c\hfill\break d
\hbox{e\vbox{f\showlists}
```

Here the first paragraph has been broken into two lines, and these have been added to the current page. The second paragraph has not been concluded or broken into lines.

The log file shows the following. TEX was busy building a paragraph (starting with an indentation box 20pt wide):

```
### horizontal mode entered at line 3
\hbox(0.0+0.0)x20.0
\tenrm f
spacefactor 1000
```

This paragraph was inside a vertical box:

```
### internal vertical mode entered at line 3
```

```
prevdepth ignored
```

The vertical box was in a horizontal box,

```
### restricted horizontal mode entered at line 3
\tenrm e
spacefactor 1000
```

which was part of an as-yet unfinished paragraph:

```
### horizontal mode entered at line 2
\hbox(0.0+0.0)x20.0
\tenrm c
\glue 0.0 plus 1.0fill
\penalty -10000
\tenrm d
etc.
spacefactor 1000
```

Note how the infinite glue and the \break penalty are still part of the horizontal list.

Finally, the first paragraph has been broken into lines and added to the current page:

```
### vertical mode entered at line 0
### current page:
\glue(\topskip) 5.69446
\hbox(4.30554+0.0)x469.75499, glue set 444.75497fil
.\hbox(0.0+0.0)x20.0
.\tenrm a
.\glue 0.0 plus 1.0fil
.\penalty -10000
.\glue(\rightskip) 0.0
\penalty 300
\glue(\baselineskip) 5.05556
\hbox(6.94444+0.0)x469.75499, glue set 464.19943fil
.\tenrm b
.\penalty 10000
.\glue(\parfillskip) 0.0 plus 1.0fil
.\glue(\rightskip) 0.0
etc.
total height 22.0 plus 1.0
 goal height 643.20255
prevdepth 0.0
```

# 第7章 Numbers

In this chapter integers and their denotations will be treated, the conversions that are possible either way, allocation and use of \count registers, and arithmetic with integers.

\number Convert a \( \number \) to decimal representation.

\ifnum Test relations between numbers.

\ifodd Test whether a number is odd.

\ifcase Enumerated case statement.

\count Prefix for count registers.

\countdef Define a control sequence to be a synonym for a \count register.

\newcount Allocate an unused \count register.

\advance Arithmetic command to add to or subtract from a \( \numeric \) variable \( \).

\multiply Arithmetic command to multiply a \( \)numeric variable \\.

\divide Arithmetic command to divide a \( \numeric variable \).

# 7.1 Numbers and $\langle number \rangle s$

An important part of the grammar of TeX is the rigorous definition of a \( \text{number} \), the syntactic entity that TeX expects when semantically an *integer* is expected. This definition will take the largest part of this chapter. Towards the end, \count registers, arithmetic, and tests for numbers are discussed.

For clarity of discussion a distinction will be made here between integers and numbers, but note that a (number) can be both an 'integer' and a 'number'.

82 第 7 章 Numbers

'Integer' will be taken to denote a mathematical number: a quantity that can be added or multiplied. 'Number' will be taken to refer to the printed representation of an integer: a string of digits, in other words.

# 7.2 Integers

Quite a few different sorts of objects can function as integers in TeX. In this section they will all be treated, accompanied by the relevant lines from the grammar of TeX.

First of all, an integer can be positive or negative:

```
\langle number \rangle \longrightarrow \langle optional\ signs \rangle \langle unsigned\ number \rangle
\langle optional\ signs \rangle \longrightarrow \langle optional\ spaces \rangle
|\langle optional\ signs \rangle \langle plus\ or\ minus \rangle \langle optional\ spaces \rangle
```

A first possibility for an unsigned integer is a string of digits in decimal, octal, or hexadecimal notation. Together with the alphabetic constants these will be named here  $\langle \text{integer denotation} \rangle$ . Another possibility for an integer is an internal integer quantity, an  $\langle \text{internal integer} \rangle$ ; together with the denotations these form the  $\langle \text{normal integer} \rangle$ s. Lastly an integer can be a  $\langle \text{coerced integer} \rangle$ : an internal  $\langle \text{dimen} \rangle$  or  $\langle \text{glue} \rangle$  quantity that is converted to an integer value.

```
\begin{split} &\langle unsigned\ number \rangle \longrightarrow \langle normal\ integer \rangle \mid \langle coerced\ integer \rangle \\ &\langle normal\ integer \rangle \longrightarrow \langle integer\ denotation \rangle \mid \langle internal\ integer \rangle \\ &\langle coerced\ integer \rangle \longrightarrow \langle internal\ dimen \rangle \mid \langle internal\ glue \rangle \end{split}
```

All of these possibilities will be treated in sequence.

## 7.2.1 Denotations: integers

Anything that looks like a number can be used as a  $\langle number \rangle$ : thus 42 is a number. However, bases other than decimal can also be used:

```
'123 is the octal notation for 1 \times 8^2 + 2 \times 8^1 + 3 \times 8^0 = 83, and "123 is the hexadecimal notation for 1 \times 16^2 + 2 \times 16^1 + 3 \times 16^0 = 291. \langle \text{integer denotation} \rangle \longrightarrow \langle \text{integer constant} \rangle \langle \text{one optional space} \rangle | '\langle \text{octal constant} \rangle \langle \text{one optional space} \rangle | "\langle \text{hexadecimal constant} \rangle \langle \text{one optional space} \rangle
```

7.2 Integers 83

The octal digits are 0-7; a digit 8 or 9 following an octal denotation is not part of the number: after

```
\count0='078
```

the \count0 will have the value 7, and the digit 8 is typeset.

The hexadecimal digits are 0–9, A–F, where the A–F can have category code 11 or 12. The latter has a somewhat far-fetched justification: the characters resulting from a \string operation have category code 12. Lowercase a–f are not hexadecimal digits, although (in TEX3) they are used for hexadecimal notation in the 'circumflex method' for accessing all character codes (see Chapter 3).

### 7.2.2 Denotations: characters

A character token is a pair consisting of a character code, which is a number in the range 0–255, and a category code. Both of these codes are accessible, and can be used as a  $\langle number \rangle$ .

The character code of a character token, or of a single letter control sequence, is accessible through the left quote command: both `a and `\a denote the character code of a, which can be used as an integer.

In order to emphasize that accessing the character code is in a sense using a denotation, the syntax of TeX allows an optional space after such a 'character constant'. The left quote must have category 12.

# 7.2.3 Internal integers

The class of  $\langle$  internal integers $\rangle$  can be split into five parts. The  $\langle$  codename $\rangle$ s and  $\langle$  special integer $\rangle$ s will be treated separately below; furthermore, there are the following.

 The contents of \count registers; either explicitly used by writing for instance \count23, or by referring to such a register by means of a control sequence that was defined by \countdef: after

```
\countdef\MyCount=23
```

\MyCount is called a \(\countdef \text{token}\), and it is fully equivalent to \\count23.

• All parameters of TEX that hold integer values; this includes obvious ones such as \linepenalty, but also parameters such as \hyphenchar\(\rangle \text{font}\) and \parshape (if a paragraph shape has been defined for n lines, using \parshape in the context of a \(\rangle \text{number}\) will yield this value of n).

84 第 7 章 Numbers

• Tokens defined by \chardef or \mathchardef. After

```
\chardef\foo=74
```

the control sequence  $\setminus$ foo can be used on its own to mean  $\setminus$ char74, but in a context where a  $\langle$ number $\rangle$  is wanted it can be used to denote 74:

```
\count\foo
```

is equivalent to \count74. This fact is exploited in the allocation routines for registers (see Chapter 31).

A control sequence thus defined by  $\c$  is called a  $\c$  if it is defined by  $\a$  if it is defined by  $\a$  if it is called a  $\a$  if it is called a  $\a$  if it is called a  $\a$  if it is defined by  $\a$  if it is called a  $\a$  in the called a

#### Here is the full list:

```
\langle internal\ integer \rangle \longrightarrow \langle integer\ parameter \rangle
| \langle special integer \rangle | \lastpenalty
| \langle countdef token \rangle | \count \langle 8-bit number \rangle
| \langle chardef token \rangle | \langle mathchardef token \rangle |
|\langle codename \rangle \langle 8-bit number \rangle
| \hyphenchar \langle font \rangle | \skewchar \langle font \rangle | \parshape
|\inputlineno|\badness
\langle \text{integer parameter} \rangle \longrightarrow | \land \text{adjdemerits} | \land \text{binoppenalty}
| \brokenpenalty | \clubpenalty | \day
| \defaulthyphenchar | \defaultskewchar
| \delimiterfactor | \displaywidowpenalty
|\doublehyphendemerits|\endlinechar|\escapechar
|\exhypenpenalty|\fam|\finalhyphendemerits
|\floatingpenalty|\globaldefs|\hangafter
| \hbadness | \hyphenpenalty | \interlinepenalty
|\linepenalty|\looseness|\mag
|\maxdeadcycles|\month
| \newlinechar | \outputpenalty | \pausing
|\postdisplaypenalty|\predisplaypenalty
| \pretolerance | \relpenalty | \showboxbreadth
|\showboxdepth|\time|\tolerance
| \tracingcommands | \tracinglostchars | \tracingmacros
| \tracingonline | \tracingoutput | \tracingpages
| \tracingparagraphs | \tracingrestores | \tracingstats
| \uchyph | \vbadness | \widowpenalty | \year
```

Any internal integer can function as an (internal unit), which —— preceded by (optional spaces) —— can serve as a (unit of measure). Examples of

7.2 Integers 85

this are given in Chapter 8.

## 7.2.4 Internal integers: other codes of a character

The \catcode command (which was described in Chapter 2) is a  $\langle$  codename $\rangle$ , and like the other code names it can be used as an integer.

```
\label{location} $$ \langle codename \rangle \longrightarrow \catcode \mid \code \mid \code\mid
```

A (codename) has to be followed by an (8-bit number).

Uppercase and lowercase codes were treated in Chapter 3; the \sfcode is treated in Chapter 20; the \mathcode and \delcode are treated in Chapter 21.

# 7.2.5 (special integer)

One of the subclasses of the internal integers is that of the special integers.

```
\langle special\ integer \rangle \longrightarrow \langle spacefactor \mid \langle prevgraf \mid \langle deadcycles \mid \langle insertpenalties \rangle
```

An assignment to any of these is called an  $\langle intimate assignment \rangle$ , and is automatically global (see Chapter 10).

## 7.2.6 Other internal quantities: coersion to integer

TeX provides a conversion between dimensions and integers: if an integer is expected, a  $\langle dimen \rangle$  or  $\langle glue \rangle$  used in that context is converted by taking its (natural) size in scaled points. However, only  $\langle internal\ dimen \rangle s$  and  $\langle internal\ glue \rangle$  can be used this way: no dimension or glue denotations can be coerced to integers.

# 7.2.7 Trailing spaces

The syntax of  $T_EX$  defines integer denotations (decimal, octal, and hexadecimal) and 'back-quoted' character tokens to be followed by (one optional space). This means that  $T_EX$  reads the token after the number, absorbing it if it was a space token, and backing up if it was not.

Because TEX's input processor goes into the state 'skipping spaces' after it has seen one space token, this scanning behaviour implies that integer denotations can be followed by arbitrarily many space characters in the input. Also, a

86 第 7 章 Numbers

line end is admissible. However, only one space token is allowed.

# 7.3 Numbers

TEX can perform an implicit *number conversion* from a string of digits to an integer. Conversion from a representation in decimal, octal, or hexadecimal notation was treated above. The conversion the other way, from an \integer\ to a printed representation, has to be performed explicitly. TEX provides two conversion routines, \number, to decimal, and \romannumeral to *roman numerals*. The command \number is equivalent to \the when followed by an internal integer. These commands are performed in the expansion processor of TEX, that is, they are expanded whenever expansion has not been inhibited.

Both commands yield a string of tokens with category code 12; their argument is a \( number \). Thus \( romannumeral51, \) romannumeral\( year, and \) number\( linepenalty \) are valid, and so is \( number13. Applying \) number to a denotation has some uses: it removes leading zeros and superfluous plus and minus signs.

A roman numeral is a string of lowercase 'roman digits', which are characters of category code 12. The sequence

```
\uppercase\expandafter{\romannumeral ...}
```

gives uppercase roman numerals. This works because TEX expands tokens in order to find the opening brace of the argument of \uppercase. If \romannumeral is applied to a negative number, the result is simply empty.

# 7.4 Integer registers

Integers can be stored in \count registers:

```
\count \langle 8-bit number \rangle
```

is an  $\langle integer\ variable \rangle$  and an  $\langle internal\ integer \rangle$ . As an integer variable it can be used in a  $\langle variable\ assignment \rangle$ :

```
\langle variable \ assignment \rangle \longrightarrow \langle integer \ variable \rangle \langle equals \rangle \langle number \rangle \mid \dots
```

As an internal integer it can be used as a (number):

```
\langle number \rangle \rightarrow \langle optional \ signs \rangle \langle internal \ integer \rangle \mid ...
```

Synonyms for \count registers can be introduced by the \countdef command in a  $\langle$ shorthand definition $\rangle$ :

```
\countdef(\control sequence)(\control sequence)
```

7.5 Arithmetic 87

A control sequence defined this way is called a  $\langle countdef \ token \rangle$ , and it serves as an  $\langle internal \ integer \rangle$ .

The plain TEX macro \newcount (which is declared \outer) uses the \countdef command to allocate an unused \count register. Counters 0–9 are scratch registers, like all registers with numbers 0–9. However, counters 0–9 are used for page identification in the dvi file (see Chapter 33), so they should be used as scratch registers only inside a group. Counters 10–22 are used for plain TEX's bookkeeping of allocation of registers. Counter 255 is also scratch.

## 7.5 Arithmetic

The user can perform some *arithmetic* in TEX, and TEX also performs arithmetic internally. User arithmetic is concerned only with integers; the internal arithmetic is mostly on fixed-point quantities, and only in the case of glue setting on floating-point numbers.

#### 7.5.1 Arithmetic statements

 $T_{E\!X}$  allows the user to perform some arithmetic on integers. The statement

 $\advance\langle integer\ variable \rangle \langle optional\ by \rangle \langle number \rangle$ 

adds the value of the  $\langle number \rangle$  —— which may be negative —— to the  $\langle integer variable \rangle$ . Similarly,

 $\mbox{\mbox{\tt multiply}} \mbox{\mbox{\tt integer variable}} \mbox{\mbox{\tt optional by}} \mbox{\mbox{\tt number}}$ 

multiplies the value of the (integer variable), and

\divide\(\)integer variable\(\)\(\)\(\)optional by\(\)\(\)\(\)

divides an (integer variable).

Multiplication and division are also available for any so-called  $\langle numeric\ variable \rangle$ : their most general form is

\multiply \numeric variable \langle optional by \langle number \rangle

where

```
\begin{split} &\langle numeric\ variable \rangle \longrightarrow \langle integer\ variable \rangle \ |\ \langle dimen\ variable \rangle \\ &|\ \langle glue\ variable \rangle \ |\ \langle muglue\ variable \rangle \end{split}
```

The result of an arithmetic operation should not exceed  $2^{30}$  in absolute value.

Division of integers yields an integer; that is, the remainder is discarded.

88 第 7 章 Numbers

This raises the question of how rounding is performed when either operand is negative. In such cases TEX performs the division with the absolute values of the operands, and takes the negative of the result if exactly one operand was negative.

# 7.5.2 Floating-point arithmetic

Internally some *floating-point arithmetic* is performed, namely in the calculation of glue set ratios. However, machine-dependent aspects of rounding cannot influence the decision process of TEX, so machine independence of TEX is guaranteed in this respect (sufficient accuracy of rounding is enforced by the Trip test of [?]).

# 7.5.3 Fixed-point arithmetic

All fractional arithmetic in  $T_EX$  is performed in *fixed-point arithmetic* of 'scaled integers': multiples of  $2^{-16}$ . This ensures the machine independence of  $T_EX$ . Printed representations of scaled integers are rounded to 5 decimal digits.

In ordinary 32-bit implementations of TEX the largest integers are  $2^{31}-1$  in absolute size. The user is not allowed to specify dimensions larger in absolute size than  $2^{30}-1$ : two such dimensions can be added or subtracted without overflow on a 32-bit system.

# 7.6 Number testing

The most general test for integers in TFX is

```
\  \langle num \langle number_1 \rangle \langle relation \rangle \langle number_2 \rangle
```

where  $\langle \text{relation} \rangle$  is a <, >, or = character, all of category 12.

Distinguishing between odd and even numbers is done by

\ifodd(number)

A numeric case statement is provided by

where the  $\ensuremath{\verb||else-part|}$  is optional. The tokens for  $\langle case_i \rangle$  are processed if the number turns out to be i; other cases are skipped, similarly to what ordinarily happens in conditionals (see Chapter 13).

7.7 Remarks 89

## 7.7 Remarks

#### 7.7.1 Character constants

In formats and macro collections numeric constants are often needed. There are several ways to implement these in  $T_EX$ .

Firstly,

```
\newcount\SomeConstant \SomeConstant=42
```

This is wasteful, as it uses up a \count register.

Secondly,

```
\def\SomeConstant{42}
```

Better but accident prone: TEX has to expand to find the number — which in itself is a slight overhead — and may inadvertently expand some tokens that should have been left alone.

Thirdly,

```
\chardef\SomeConstant=42
```

This one is fine. A  $\langle chardef\ token \rangle$  has the same status as a  $\backslash count\ register$ : both are  $\langle internal\ integer \rangle s$ . Therefore a number defined this way can be used everywhere that a  $\backslash count\ register$  is feasible. For large numbers the  $\backslash chardef$  can be replaced by  $\backslash chardef$ , which runs to "7FFF =  $32\,767$ . Note that a  $\langle mathchardef\ token \rangle$  can usually only appear in math mode, but in the context of a number it can appear anywhere.

# 7.7.2 Expanding too far / how far

It is a common mistake to write pieces of TEX code where TEX will inadvertently expand something because it is trying to compose a number. For example:

```
\def\par{\endgraf\penalty200}
...\par \number\pageno
```

Here the page number will be absorbed into the value of the penalty.

Now consider

```
\newcount\midpenalty \midpenalty=200
\def\par{\endgraf\penalty\midpenalty}
...\par \number\pageno
```

Here the page number is not scooped up by mistake:  $T_EX$  is trying to locate a  $\langle number \rangle$  after the  $\langle penalty \rangle$ , and it finds a  $\langle countdef$  token $\rangle$ . This is *not* con-

90 第7章 Numbers

verted to a representation in digits, so there is never any danger of the page number being touched.

It is possible to convert a  $\langle countdef\ token \rangle$  first to a representation in digits before assigning it:

\penalty\number\midpenalty

and this brings back again all previous problems of expansion.

# 第8章 Dimensions and Glue

In TEX vertical and horizontal white space can have a possibility to adjust itself through 'stretching' or 'shrinking'. An adjustable white space is called *glue*. This chapter treats all technical concepts related to dimensions and glue, and it explains how the badness of stretching or shrinking a certain amount is calculated.

\dimen Dimension register prefix.

\dimendef Define a control sequence to be a synonym for a \dimen register.

\newdimen Allocate an unused dimen register.

\skip Skip register prefix.

\skipdef Define a control sequence to be a synonym for a \skip register.

\newskip Allocate an unused skip register.

\ifdim Compare two dimensions.

\hskip Insert in horizontal mode a glue item.

\hfil Equivalent to \hskip Ocm plus 1fil.

\hfilneg Equivalent to \hskip Ocm minus 1fil.

\hfill Equivalent to \hskip Ocm plus 1fill.

\hss Equivalent to \hskip Ocm plus 1fil minus 1fil.

\vskip Insert in vertical mode a glue item.

\vfil Equivalent to \vskip 0cm plus 1fil.

\vfill Equivalent to \vskip Ocm plus 1fill.

\vfilneg Equivalent to \vskip Ocm minus 1fil.

\vss Equivalent to \vskip Ocm plus 1fil minus 1fil.

\kern Add a kern item to the current horizontal or vertical list.

\lastkern If the last item on the current list was a kern, the size of it.

\lastskip If the last item on the current list was a glue, the size of it.

\unkern If the last item of the current list was a kern, remove it.

\unskip If the last item of the current list was a glue, remove it.

\removelastskip Macro to append the negative of the \lastskip.

\advance Arithmetic command to add to or subtract from a  $\langle numeric variable \rangle$ .

\multiply Arithmetic command to multiply a \( \numeric variable \).

\divide Arithmetic command to divide a \( \numeric variable \).

# 8.1 Definition of \( \text{glue} \) and \( \text{dimen} \)

This section gives the syntax of the quantities  $\langle dimen \rangle$  and  $\langle glue \rangle$ . In the next section the practical aspects of glue are treated.

Unfortunately the terminology for glue is slightly confusing. The syntactical quantity  $\langle glue \rangle$  is a dimension (a distance) with possibly a stretch and/or shrink component. In order to add a glob of 'glue' (a white space) to a list one has to let a  $\langle glue \rangle$  be preceded by commands such as  $\langle glue \rangle$ .

#### 8.1.1 Definition of dimensions

A  $\langle dimen \rangle$  is what TeX expects to see when it needs to indicate a dimension; it can be positive or negative.

```
\langle dimen \rangle \longrightarrow \langle optional signs \rangle \langle unsigned dimen \rangle
```

The unsigned part of a (dimen) can be

```
\begin{split} &\langle unsigned\ dimen \rangle \longrightarrow \langle normal\ dimen \rangle \mid \langle coerced\ dimen \rangle \\ &\langle normal\ dimen \rangle \longrightarrow \langle internal\ dimen \rangle \mid \langle factor \rangle \langle unit\ of\ measure \rangle \\ &\langle coerced\ dimen \rangle \longrightarrow \langle internal\ glue \rangle \end{split}
```

That is, we have the following three cases:

 an (internal dimen); this is any register or parameter of TEX that has a (dimen) value:

```
\begin{split} &\langle \text{internal dimen} \rangle \longrightarrow \langle \text{dimen parameter} \rangle \\ &| \langle \text{special dimen} \rangle \mid \text{\scalebox{lastkern}} \\ &| \langle \text{dimendef token} \rangle \mid \text{\scalebox{lamen}} \langle \text{8-bit number} \rangle \\ &| \langle \text{box dimension} \rangle \langle \text{8-bit number} \rangle \end{split}
```

```
⟨dimen parameter⟩ → \boxmaxdepth
| \delimitershortfall | \displayindent
| \displaywidth | \hangindent
| \hfuzz | \hoffset | \hsize
| \lineskiplimit | \mathsurround
| \maxdepth | \nulldelimiterspace
| \overfullrule | \parindent
| \predisplaysize | \scriptspace
| \splitmaxdepth | \vfuzz
| \voffset | \vsize
```

- a dimension denotation, consisting of \( \frac{factor}{\text{unit of measure}} \), for example
   0.7\vsize; or
- an (internal glue) (see below) coerced to a dimension by omitting the stretch and shrink components, for example \parfillskip.

A dimension denotation is a somewhat complicated entity:

• a \( \factor \rangle \) is an integer denotation, a decimal constant denotation (a number with an integral and a fractional part), or an \( \langle \) integral integer \( \rangle \)

```
\begin{split} &\langle factor \rangle \longrightarrow \langle normal\ integer \rangle \mid \langle decimal\ constant \rangle \\ &\langle normal\ integer \rangle \longrightarrow \langle integer\ denotation \rangle \\ &|\ \langle internal\ integer \rangle \\ &|\ \langle decimal\ constant \rangle \longrightarrow ._{12} \mid ,_{12} \\ &|\ \langle digit \rangle \langle decimal\ constant \rangle \\ &|\ \langle decimal\ constant \rangle \langle digit \rangle \end{split}
```

An internal integer is a parameter that is 'really' an integer (for instance, \count0), and not coerced from a dimension or glue. See Chapter 7 for the definition of various kinds of integers.

• a \( \)unit of measure\( \) can be a \( \)physical unit\( \), that is, an ordinary unit such as cm (possibly preceded by true), an internal unit such as em, but also an \( \)internal integer\( \) (by conversion to scaled points), an \( \)internal dimen\( \), or an \( \)internal glue\( \).

```
\begin{split} &\langle \text{unit of measure} \rangle \longrightarrow \langle \text{optional spaces} \rangle \langle \text{internal unit} \rangle \\ &| \langle \text{optional true} \rangle \langle \text{physical unit} \rangle \langle \text{one optional space} \rangle \\ &\langle \text{internal unit} \rangle \longrightarrow \text{em} \langle \text{one optional space} \rangle \\ &| \text{ex} \langle \text{one optional space} \rangle \mid \langle \text{internal integer} \rangle \\ &| \langle \text{internal dimen} \rangle \mid \langle \text{internal glue} \rangle \end{split}
```

Some \( \dimen \) s are called \( \special \dimen \) s:

```
⟨special dimen⟩ → \prevdepth
| \pagegoal | \pagetotal | \pagestretch
| \pagefilstretch | \pagefillstretch
| \pagefillstretch | \pageshrink | \pagedepth
```

An assignment to any of these is called an (intimate assignment), and it is automatically global (see Chapter 10). The meaning of these dimensions is explained in Chapter 27, with the exception of \prevdepth which is treated in Chapter 15.

## 8.1.2 Definition of glue

A  $\langle glue \rangle$  is either some form of glue variable, or a glue denotation with explicitly indicated stretch and shrink. Specifically,

```
\label{eq:continuous} $$\langle glue \rangle \longrightarrow \langle glue \ parameter \rangle \ | \ dimen \rangle \langle shrink \rangle \langle internal \ glue \rangle \longrightarrow \langle glue \ parameter \rangle \ | \ lastskip \rangle \langle skipdef \ token \rangle \ | \ lastskip \rangle \langle glue \ parameter \rangle \longrightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \longrightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \longrightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \longrightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \longrightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \longrightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \rightarrow \ labovedisplayshortskip \rangle \langle glue \ parameter \rangle \langle glue \ parameter
```

The stretch and shrink components in a glue denotation are optional, but when both are specified they have to be given in sequence; they are defined as

```
\langle stretch \rangle \longrightarrow plus \langle dimen \rangle \mid plus \langle fil \ dimen \rangle \mid \langle optional \ spaces \rangle \\ \langle shrink \rangle \longrightarrow minus \langle dimen \rangle \mid minus \langle fil \ dimen \rangle \mid \langle optional \ spaces \rangle \\ \langle fil \ dimen \rangle \longrightarrow \langle optional \ signs \rangle \langle factor \rangle \langle fil \ unit \rangle \langle optional \ spaces \rangle \\ \langle fil \ unit \rangle \longrightarrow \mid fil \mid fill \mid fill |
```

The actual definition of  $\langle \text{fil unit} \rangle$  is recursive (see Chapter 36), but these are the only valid possibilities.

# 8.1.3 Conversion of $\langle glue \rangle$ to $\langle dimen \rangle$

```
The grammar rule
```

```
\langle dimen \rangle \longrightarrow \langle factor \rangle \langle unit of measure \rangle
```

has some noteworthy consequences, caused by the fact that a (unit of measure) need not look like a 'unit of measure' at all (see the list above).

For instance, from this definition we conclude that the statement

```
\dimenO=\lastpenalty\lastpenalty
```

is syntactically correct because \lastpenalty can function both as an integer and as \( \)unit of measure\( \) by taking its value in scaled points. After \( \)penalty8 the \( \)dimen0 thus defined will have a size of 64sp.

More importantly, consider the case where the  $\langle unit \text{ of measure} \rangle$  is an  $\langle internal glue \rangle$ , that is, any sort of glue parameter. Prefixing such a glue with a number (the  $\langle factor \rangle$ ) makes it a valid  $\langle dimen \rangle$  specification. Thus

```
\skip0=\skip1
```

is very different from

```
\skip0=1\skip1
```

The first statement makes \skip0 equal to \skip1, the second converts the \skip1 to a \dimen\ before assigning it. In other words, the \skip0 defined by the second statement has no stretch or shrink.

## 8.1.4 Registers for \dimen and \skip

TeX has registers for storing  $\langle dimen \rangle$  and  $\langle glue \rangle$  values: the \dimen and \skip registers respectively. These are accessible by the expressions

```
\dimen(number)
```

and

```
\skip \number \
```

As with all registers of T<sub>F</sub>X, these registers are numbered 0–255.

Synonyms for registers can be made with the  $\dim$  and  $\sinh$  are is

```
\dimendef(control sequence)(equals)(8-bit number)
```

and

For example, after \skipdef\foo=13 using \foo is equivalent to using \skip13.

Macros \newdimen and \newskip exist in plain TEXfor allocating an unused dimen or skip register. These macros are defined to be \outer in the plain format.

### 8.1.5 Arithmetic: addition

As for integer variables, arithmetic operations exist for *arithmetic on glue*: dimen, glue, and muglue (mathematical glue; see page 229) variables.

The expressions

```
\label{lem:continuous} $$ \advance \langle dimen\ variable \rangle \langle optional\ by \rangle \langle dimen \rangle $$ \advance \langle glue\ variable \rangle \langle optional\ by \rangle \langle glue \rangle $$ \advance \langle muglue\ variable \rangle \langle optional\ by \rangle \langle muglue \rangle $$
```

add to the size of a dimen, glue, or muglue.

Advancing a  $\langle glue\ variable \rangle$  by  $\langle glue \rangle$  is done by adding the natural sizes, and the stretch and shrink components. Because TeX converts between  $\langle glue \rangle$  and  $\langle dimen \rangle$ , it is possible to write for instance

```
\advance\skip1 by \dimen1
or
\advance\dimen1 by \skip1
```

In the first case  $\dimen1$  is coerced to  $\dimen2$  without stretch or shrink; in the second case the  $\ship1$  is coerced to a  $\dimen2$  by taking its natural size.

# 8.1.6 Arithmetic: multiplication and division

Multiplication and division operations exist for glue and dimensions. One may for instance write

```
\multiply\skip1 by 2
```

which multiplies the natural size, and the stretch and shrink components of \skip1 by 2.

The second operand of a \multiply or \divide operation can only be a  $\langle number \rangle$ , that is, an integer. Introducing the notion of  $\langle numeric \ variable \rangle$ :

```
\begin{split} &\langle numeric\ variable \rangle \longrightarrow \langle integer\ variable \rangle \ | \ \langle dimen\ variable \rangle \\ &| \ \langle glue\ variable \rangle \ | \ \langle muglue\ variable \rangle \end{split}
```

these operations take the form

```
\verb|\multiply| \langle numeric\ variable \rangle \langle optional\ by \rangle \langle number \rangle
```

and

```
\divide\langle numeric\ variable\rangle\langle optional\ by\rangle\langle number\rangle
```

Glue and dimen can be multiplied by non-integer quantities:

```
\sin 1=2.5 \sin 2
```

\dimen1=.78\dimen2

However, in the first line the  $\sin 2$  is first coerced to a  $\langle dimen \rangle$  value by omitting its stretch and shrink.

## 8.2 More about dimensions

#### 8.2.1 Units of measurement

In TeX dimensions can be indicated in the following *units of measurement*:

centimetre denoted cm or

**millimetre** denoted mm; these are SI units (*Système International d'Unités*, the international system of standard units of measurements).

inch in; more common in the Anglo-American world. One inch is 2.54 centimetres.

pica denoted pc; one pica is 12 points.

**point** denoted pt; the common system for Anglo-American printers. One inch is 72.27 points.

**didot point** denoted dd; the common system for continental European printers. Furthermore, 1157 didot points are 1238 points.

cicero denoted cc; one cicero is 12 didot points.

**big point** denoted bp; one inch is 72 big points.

scaled point denoted sp; this is the smallest unit in TEX, and all measurements are integral multiples of one scaled point. There are 65 536 scaled points in a point.

Decimal fractions can be written using both the Anglo-American system with the decimal point (for example, 1in=72.27pt) and the continental European system with a decimal comma; 1in=72,27pt.

Internally TeX works with multiples of a smallest dimension: the scaled point. Dimensions larger (in absolute value) than  $2^{30} - 1$ sp, which is about 5.75 metres or 18.9 feet, are illegal.

Both the pica system and the didot system are of French origin: in 1737 the type founder Pierre Simon Fournier introduced typographical points based on the French foot. Although at first he introduced a system based on lines and points, he later took the point as unit: there are 72 points in an inch, which is one-twelfth of a foot. About 1770 another founder, François Ambroise Didot,

introduced points based on the more common, and slightly longer, 'pied du roi'.

## 8.2.2 Dimension testing

Dimensions and natural sizes of glue can be compared with the \ifdim test. This takes the form

where the relation can be an >, <, or = token, all of category 12.

### 8.2.3 Defined dimensions

\z@ 0pt

\maxdimen 16383.99999pt; the largest legal dimension.

These  $\langle dimen \rangle s$  are predefined in the plain format; for instance

\newdimen\z@ \z@=Opt

Using such abbreviations for commonly used dimensions has at least two advantages. First of all it saves main memory if such a dimension occurs in a macro: a control sequence is one token, whereas a string such as Opt takes three. Secondly, it saves time in processing, as TeX does not need to perform conversions to arrive at the correct type of object.

Control sequences such as \z0 are only available to a user who changes the category code of the 'at' sign. Ordinarily, these control sequences appear only in the macros defined in packages such as the plain format.

# 8.3 More about glue

Glue items can be added to a vertical list with one of the commands  $\$  \vskip\(glue\), \vfill, \vsi or \vfilneg; glue items can be added to a horizontal list with one of the commands \hskip\(glue\), \hfill, \hfill, \hss or \hfilneg. We will now treat the properties of glue.

#### 8.3.1 Stretch and shrink

In the syntax given above, (glue) was defined as having

- a 'natural size', which is a \( \dimen \), and optionally
- a *stretch* and *shrink* components*tretchshrink* built out of a (fil dimen).

Each list that TEX builds has amounts of stretch and shrink (possibly zero), which are the sum of the stretch and shrink components of individual pieces of glue in the list. Stretch and shrink are used if the context in which the list appears requires it to assume a size that is different from its natural size.

There is an important difference in behaviour between stretch and shrink components when they are finite —— that is, when the  $\langle$  fildimen $\rangle$  is not fil(1(1)). A finite amount of shrink is indeed the maximum shrink that TeX will take: the amount of glue specified as

```
5pt minus 3pt
```

can shrink to 2pt, but not further. In contrast to this, a finite amount of stretch can be stretched arbitrarily far. Such arbitrary stretching has a large 'badness', however. Badness calculation is treated below.

例子: The sequence with natural size 20pt

```
\hskip 10pt plus 2pt \hskip 10pt plus 3pt
```

has 5pt of stretch, but it has no shrink. In

```
\hskip 10pt minus 2pt \hskip 10pt plus 3pt
```

there is 3pt of stretch, and 2pt of shrink, so its minimal size is 18pt.

Positive shrink is not the same as negative stretch:

```
\hskip 10pt plus -2pt \hskip 10pt plus 3pt
```

looks a lot like the previous example, but it cannot be shrunk as there are no minus  $\langle dimen \rangle$  specifications. It does have 1pt of stretch, however.

This is another example of negative amounts of shrink and stretch. It is not possible to stretch glue (in the informal sense) by shrinking it (in the technical sense):

```
\hbox to 5cm{a\hskip 0cm minus -1fil}
```

is an underfull box, because  $T_EX$  looks for a plus  $\langle dimen \rangle$  specification when it needs to stretch the contents.

Finally,

```
\hskip 10pt plus -3pt \hskip 10pt plus 3pt
```

can neither stretch nor shrink. The fact that there is only stretch available means that the sequence cannot shrink. However, the stretch components cancel out: the total stretch is zero. Another way of looking at this is to consider that for each point that the second glue item would stretch, the first one would 'stretch back' one point.

Any amount of infinite stretch or shrink overpowers all finite stretch or shrink available:

```
\hbox to 5cm{\hskip 0cm plus 16384pt text\hskip 0cm plus 0.0001fil}
```

has the text at the extreme left of the box. There are three orders of 'infinity', each one infinitely stronger than the previous one:

both have the text at the left end of the box.

# 8.3.2 Glue setting

In the process of *glue setting*, the desired width (or height) of a box is compared with the natural dimension of its contents, which is the sum of all natural dimensions of boxes and globs of glue. If the two differ, any available stretchability or shrinkability is used to bridge the gap. To attain the desired dimension of the box only the glue of the highest available order is set: each piece of glue of that order is stretched or shrunk by the same ratio.

```
For example, in
\hbox to 6pt{\hskip 0pt plus 3pt \hskip 0pt plus 9pt}
```

the natural size of the box is 0pt, and the total stretch is 12pt. In order to obtain a box of 6pt each glue item is set with a stretch ratio of 1/2. Thus the result is equivalent to

```
\hbox {\hskip 1.5pt \hskip 4.5pt}
```

Only the highest order of stretch or shrink is used: in

```
\hbox to 6pt{\hskip 0pt plus 1fil \hskip 0pt plus 9pt}
```

the second glue will assume its natural size of Opt, and only the first glue will be stretched.

TEX will never exceed the maximum value of a finite amount of shrink. A box that cannot be shrunk enough is called 'overfull'. Finite stretchability can be exceeded to provide an escape in difficult situations; however, TEX is likely to give an Underfull \hbox message about this (see page 65). For an example of infinite shrink see page 64.

## 8.3.3 Badness

When stretching or shrinking a list TEX calculates *badness* badness based on the ratio between actual stretch and the amount of stretch present in the line. See Chapter 19 for the application of badness to the paragraph algorithm.

The formula for badness of a list that is stretched (shrunk) is

$$b = \min \left(10\,000, 100 \times \left(\frac{\text{actual amount stretched (shrunk)}}{\text{possible amount of stretch (shrink)}}\right)^3\right)$$

In reality TEX uses a slightly different formula that is easier to calculate, but behaves the same. Since glue setting is one of the main activities of TEX, this must be performed as efficiently as possible.

This formula lets the badness be a reasonably small number if the glue set ratio (the fraction in the above expression) is reasonably small, but will let it grow rapidly once the ratio is more than 1. Badness is infinite if the glue would have to shrink more than the allotted amount; stretching glue beyond its maximum is possible, so this provides an escape for very difficult lines of text or pages.

In TEX3, the \badness parameter records the badness of the most recently formed box.

# 8.3.4 Glue and breaking

TEX can break lines and pages in several kinds of places. One of these places is before a glue item. The glue is then discarded. For line breaks this is treated in Chapter 19, for page breaks see Chapter 27.

There are two macros in plain  $T_EX$ , \hglue and \vglue, that give non-disappearing glue in horizontal and vertical mode respectively. For the horizontal case this is accomplished by placing:

```
\vrule width Opt \nobreak \hskip ...
```

Because TEX breaks at the front end of glue, this glue will always stay attached to the rule, and will therefore never disappear. The actual macro definitions are somewhat more complicated, because they take care to preserve the \spacefactor and the \prevdepth.

## 8.3.5 \kern

The \kern command specifies a kern item in whatever mode TEX is currently in. A kern item is much like a glue item without stretch or shrink. It

differs from glue in that it is in general not a legal breakpoint. Thus in

```
.. text .. \hbox{a}\kernOpt\hbox{b}
```

TFX will not break lines in between the boxes; in

```
.. text .. \hbox{a}\hskip0pt\hbox{b}
```

a line can be broken in between the boxes.

However, if a kern is followed by glue, TeX can break at the kern (provided that it is not in math mode). In horizontal mode both the kern and the glue then disappear in the break. In vertical mode they are discarded when they are moved to the (empty) current page after the material before the break has been disposed of by the output routine (see Chapter 27).

#### 8.3.6 Glue and modes

All horizontal skip commands are \( \horizontal \) command\( \)s and all vertical skip commands are \( \vertical \) commands\( \)s. This means that, for instance, an \( \hskip \) command makes TEX start a paragraph if it is given in vertical mode. The \( \kern \) command can be given in both modes.

# 8.3.7 The last glue item in a list: backspacing

The last glue item in a list can be measured, and it can be removed in all modes but external vertical mode. The internal variables \lastskip and \lastkern can be used to measure the last glob of glue in all modes; if the last glue was not a skip or kern respectively they give Opt. In math mode the \lastskip functions as \(\(\)internal muglue\), but in general it classifies as \(\)internal glue\). The \lastskip and \lastkern are also Opt if that was the size of the last glue or kern item on the list.

The operations \unskip and \unkern remove the last item of a list, if this is a glue or kern respectively. They have no effect in external vertical mode; in that case the best substitute is \vskip-\lastskip and \kern-\lastkern.

In the process of paragraph building TEX itself performs an important \unskip: a paragraph ending with a white line will have a space token inserted by TEX's input processor. This is removed by an \unskip before the \parfillskip glue (see Chapter 17) is inserted.

Glue is treated by TEX as a special case of leaders, which becomes apparent when \unskip is applied to leaders: they are removed.

## 8.3.8 Examples of backspacing

```
The plain TEX macro \removelastskip is defined as \ifdim\lastskip=0pt \else \vskip-\lastskip \fi
```

If the last item on the list was a glue, this macro will backspace by its value, provided its natural size was not zero. In all other cases, nothing is added to the list.

Sometimes an intelligent version of commands such as \vskip is necessary, in the sense that two subsequent skip commands should result only in the larger of the two glue amounts. On page 180 such a macro is used:

```
\newskip\tempskipa
\def\vspace#1{\tempskipa=#1\relax
   \ifvmode \ifdim\tempskipa<\lastskip
        \else \vskip-\lastskip \vskip\tempskipa
   \fi
   \else \vskip\tempskipa \fi}</pre>
```

First of all, this tests whether the mode is vertical; if not, the argument can safely be placed. Copying the argument into a skip register is necessary because \vspace{2pt plus 3pt} would lead to problems in an \ifdim#1<\lastskip test.

If the surrounding mode was vertical, the argument should only be placed if it is not less than what is already there. The macro would be incorrect if the test read

```
\ifdim\tempskipa>\lastskip
  \vskip-\lastskip \vskip\tempskipa
\fi
```

In this case the sequence

```
... last word.\par \vspace{0pt plus 1fil}
```

would not place any glue, because after the \par we are in vertical mode and \lastskip has a value of Opt.

## 8.3.9 Glue in trace output

If the workings of TeX are traced by setting \tracingoutput positive, or if TeX writes a box to the log file (because of a \showbox command, or because it is overfull or underfull), glue is denoted by the control sequence \glue. This is not a TeX command; it merely indicates the presence of glue in the current list.

The box representation that TeX generated from, for instance, \showbox inserts a space after every explicit \kern, but no space is inserted after an im-

plicit kern that was inserted by the kerning information in the font tfm file. Thus \kern 2.0pt denotes a kern that was inserted by the user or by a macro, and \kern2.0pt denotes an implicit kern.

Glue that is inserted automatically (\topskip, \baselineskip, et cetera) is denoted by name in TEX's trace output. For example, the box

```
\vbox{\hbox{Vo}\hbox{b}}
```

#### looks like

```
\vbox(18.83331+0.0)x11.66669
.\hbox(6.83331+0.0)x11.66669
.\tenrm V
.\kern-0.83334
.\tenrm o
.\glue(\baselineskip) 5.05556
.\hbox(6.94444+0.0)x5.55557
..\tenrm b
```

Note the implicit kern inserted between 'V' and 'o'.

# 第 9 章 Rules and Leaders

Rules and leaders are two ways of getting TEX to draw a line. Leaders are more general than rules: they can also fill available space with copies of a certain box. This chapter explain how rules and leaders work, and how they interact with modes.

\hrule Rule that spreads in horizontal direction.

\vrule Rule that spreads in vertical direction.

\leaders Fill a specified amount of space with a rule or copies of box.

\cleaders Like \leaders, but with box leaders any excess space is split equally before and after the leaders.

\xleaders Like \leaders, but with box leaders any excess space is spread equally before, after, and between the boxes.

## 9.1 Rules

TEX's rule commands give *rules*: rectangular black patches with horizontal and vertical sides. Most of the times, a rule command will give output that looks like a rule, but a can also be produced by a rule.

TeX has both horizontal and vertical rules, but the names do not necessarily imply anything about the shape. They do, however, imply something about modes: an  $\$  and a  $\$  in horizontal mode. In fact, an  $\$  is a  $\$  derivative command, and a  $\$  is a  $\$  horizontal command, so TeX may change modes when encountering these commands.

Why then is a \vrule called a *vertical* rule? The reason is that a \vrule can expand arbitrarily far in the vertical direction: if its height and depth are not specified explicitly it will take as much room as its surroundings allow.

For the \hrule command a similar statement is true: a horizontal rule can spread to assume the width of its surroundings. Thus

```
\vbox{\hbox{One line of text}\hrule}
```

looks like

One line of text

#### 9.1.1 Rule dimensions

Horizontal and vertical rules have a default thickness:

```
\ is the same as \ hrule height.4pt depth0pt and
```

```
\vrule is the same as \vrule width.4pt
```

and if the remaining dimension remains unspecified, the rule extends in that direction to fill the enclosing box.

Here is the formal specification of how to indicate rule sizes:

```
\label{eq:contaction} $$ \ \operatorname{vrule} \ \to \operatorname{vrule} \ \operatorname{specification} $$ \ \operatorname{crule specification} $$ \ \operatorname{crule specification} $$ \ \operatorname{crule specification} $$ \to \operatorname{optional spaces} $$ \ | \ \operatorname{dimensions} \ \operatorname{crule dimension} $$ \to \operatorname{width} \ \operatorname{dimen} \ | \ \operatorname{height} \ \operatorname{dimen} \ | \ \operatorname{depth} \ \operatorname{dimen} $$ $$ $$ $$ $$
```

If a rule dimension is specified twice, the second instance takes precedence over the first. This makes it possible to override the default dimensions. For instance, after

```
\let\xhrule\hrule \def\hrule{\xhrule height .8pt}
```

9.2 Leaders 107

the macro \hrule gives a horizontal rule of double the original height, and it is still possible with

```
\hrule height 2pt
```

to specify other heights.

It is possible to specify all three dimensions; then

```
\vrule height1ex depth0pt width1ex
```

and

```
\hrule height1ex depth0pt width1ex
```

look the same. Still, each of them can be used only in the appropriate mode.

#### 9.2 Leaders

Rules are intimately connected to modes, which makes it easy to obtain some effects. For instance, a typical application of a vertical rule looks like

```
\hbox{\vrule width1pt\ Important text! \vrule width 1pt}
which gives
```

```
| Important text! |
```

However, one might want to have a horizontal rule in horizontal mode for effects such as

```
\leftarrow 5cm \rightarrow from here to there
```

An \hrule can not be used in horizontal mode, and a vertical rule will not spread automatically.

However, there is a way to use an \hrule command in horizontal mode and a \rule in vertical mode, and that is with *leaders*, so called because they lead your eye across the page. A leader command tells TEX to fill a specified space, in whatever mode it is in, with as many copies of some box or rule specification as are needed. For instance, the above example was given as

```
\hbox to 5cm{from here\leaders\hrule\hfil to there}
```

that is, with an \hrule that was allowed to stretch along an \hfil. Note that the leader was given a horizontal skip, corresponding to the horizontal mode in which it appeared.

```
A general leader command looks like
```

```
⟨leaders⟩⟨box or rule⟩⟨vertical/horizontal/mathematical skip⟩
```

where  $\langle leaders \rangle$  is  $\langle leaders \rangle$ ,  $\langle leaders \rangle$ , or  $\langle leaders \rangle$ , a  $\langle leaders \rangle$ , a  $\langle leaders \rangle$ , and the lists of horizontal and vertical skips appear in Chapter 6; a mathematical skip is either a horizontal skip or an  $\langle leaders \rangle$  Leaders can thus be used in all three modes. Of course, the appropriate kind of skip must be specified.

A horizontal (vertical) box containing leaders has at least the height and depth (width) of the  $\langle box \ or \ rule \rangle$  used in the leaders, even if, as can happen in the case of box leaders, no actual leaders are placed.

#### 9.2.1 Rule leaders

Rule leaders fill the specified amount of space with a rule extending in the direction of the skip specified. The other dimensions of the resulting rule leader are determined by the sort of rule that is used: either dimensions can be specified explicitly, or the default values can be used.

For instance,

```
\hbox{g\leaders\hrule\hskip20pt f}
```

gives

```
g___f
```

because a horizontal rule has a default height of .4pt. On the other hand,

```
\hbox{g\leaders\vrule\hskip20pt f}
```

gives



because the height and depth of a vertical rule by default fill the surrounding box.

Spurious rule dimensions are ignored: in horizontal mode

```
\leaders\hrule width 10pt \hskip 20pt
```

is equivalent to

```
\leaders\hrule \hskip 20pt
```

If the width or height-plus-depth of either the skip or the box is negative, TFX uses ordinary glue instead of leaders.

9.2 Leaders 109

#### 9.2.2 Box leaders

Box leaders fill the available spaces with copies of a given box, instead of with a rule.

For all of the following examples, assume that a box register has been allocated:

```
\newbox\centerdot \setbox\centerdot=\hbox{\hskip.7em.\hskip.7em}
Now the output of
   \hbox to 8cm {here\leaders\copy\centerdot\hfil there}
is
   here . . . . . . . . . . . there
```

That is, copies of the box register fill up the available space.

Dot leaders, as in the above example, are often used for tables of contents. In such applications it is desirable that dots on subsequent lines are vertically aligned. The \leaders command does this automatically:

```
\hbox to 8cm {here\leaders\copy\centerdot\hfil there}
\hbox to 8cm {over here\leaders\copy\centerdot\hfil over there}
gives
here . . . . . . . . . . . . there
over here . . . . . . . . over there
```

The mechanism behind this is the following: TEX acts as if an infinite row of boxes starts (invisibly) at the left edge of the surrounding box, and the row of copies actually placed is merely the part of this row that is not obscured by the other contents of the box.

Stated differently, box leaders are a window on an infinite row of boxes, and the row starts at the left edge of the surrounding box. Consider the following example:

The row of leaders boxes becomes visible as soon as it does not coincide with other material.

The above discussion only talked about leaders in horizontal mode. Leaders

can equally well be placed in vertical mode; for box leaders the 'infinite row' then starts at the top of the surrounding box.

#### 9.2.3 Evenly spaced leaders

Aligning subsequent box leaders in the way described above means that the white space before and after the leaders will in general be different. If vertical alignment is not an issue it may be aesthetically more pleasing to have the leaders evenly spaced. The \cleaders command is like \leaders, except that it splits excess space before and after the leaders into two equal parts, centring the row of boxes in the available space.

```
例子:
    \hbox to 7.8cm {here\cleaders\copy\centerdot\hfil there}
    \hbox to 7.8cm {here is\cleaders\copy\centerdot\hfil there}
gives
here is
                                       . there
The 'expanding leaders' \xleaders spread excess space evenly between
the boxes, with equal globs of glue before, after, and in between leader
boxes.
例平:
    \hbox to 7.8cm{here\hskip.7em
          \xleaders\copy\centerdot\hfil \hskip.7em there}
gives
here
                                         there
Note that the glue in the leader box is balanced here with explicit glue
before and after the leaders; leaving out these glue items, as in
    \hbox to 7.8cm {here\xleaders\copy\centerdot\hfil there}
gives
here
                                       . there
which is clearly not what was intended.
```

#### 9.3 Assorted remarks

9.3 Assorted remarks 111

#### 9.3.1 Rules and modes

Above it was explained how rules can only occur in the appropriate modes. Rules also influence mode-specific quantities: no baselineskip is added before rules in vertical mode. In order to prevent glue after rules, TEX sets \prevdepth to -1000pt (see Chapter 15). Similarly the \spacefactor is set to 1000 after a \vrule in horizontal mode (see Chapter 19).

## 9.3.2 Ending a paragraph with leaders

An attempt to simulate an \hrule at the end of a paragraph by \nobreak\leaders\hrule\hfill\par

does not work. The reason for this is that TEX performs an \unskip at the end of a paragraph, which removes the leaders. Normally this \unskip removes any space token inserted by the input processor after the last line. Remedy: stick an \hbox{} at the end of the leaders.

### 9.3.3 Leaders and box registers

In the above examples the leader box was inserted with \copy. The output of

is

```
here . . . . . . . . . . . . . . there over here
```

The box register is emptied after the first leader command, but more than one copy is placed in that first command.

## 9.3.4 Output in leader boxes

Any \write, \openout, or \closeout operation appearing in leader boxes is ignored. Otherwise such an operation would be executed once for every copy of the box that would be shipped out.

#### 9.3.5 Box leaders in trace output

The dumped box representation obtained from, for instance, \tracingoutput does not write out box leaders in full: only the total size and one copy of the box used are dumped. In particular, the surrounding white space before and after the leaders is not indicated.

#### 9.3.6 Leaders and shifted margins

If margins have been shifted, leaders may look different depending on how the shift has been realized. For an illustration of how \hangindent and \leftskip influence the look of leaders, consider the following examples, where

```
\setbox0=\hbox{K o }
```

The horizontal boxes above the leaders serve to indicate the starting point of the row of leaders.

```
First
```

```
\hbox{\leaders\copy0\hskip5cm}
\noindent\advance\leftskip 1em
\leaders\copy0\hskip5cm\hbox{}\par
```

gives

```
K o K o K o K o K o K o K o K o
```

Then

```
\hbox{\kern1em\hbox{\leaders\copy0\hskip5cm}}
\hangindent=1em \hangafter=-1 \noindent
    \leaders\copy0\hskip5cm\hbox{}\par
```

gives (note the shift with respect to the previous example)

```
K o K o K o K o K o K o K o
```

In the first paragraph the \leftskip glue only obscures the first leader box; in the second paragraph the hanging indentation actually shifts the orientation point for the row of leaders. Hanging indentation is performed in TeX by a \moveright of the boxes containing the lines of the paragraph.

# 第 10 章 编组

**T<sub>E</sub>X** 提供的编组机制可以将大多数改变限制在局部范围内。此章解释哪些操作 是局部的,以及编组是如何形成的。

\bgroup 隐式的编组开始符。

\egroup 隐式的编组结束符。

\begingroup 开始一个必须用 \endgroup 结束的编组。

\endgroup 结束一个用\begingroup 开始的编组。

\aftergroup 保存下一个记号,并在当前编组结束后插入它。

\global 使得赋值,宏定义和算术运算是全局的。

\globaldefs 用于覆盖 \global 前缀的参数。IniTpX 默认值:0。

## 10.1 编组机制

一个编组是一串记号,以'组开始'记号开头,以'组结束'记号结尾,而且这两种记号在其中是配对的。

**TeX** 的编组机制与普通编程语言的块作用域不同。大多数语言的块结构中只能有局部定义。**TeX** 的编组机制更加强大:编组中的大多数赋值是局部的,在离开该编组后旧的值将被还原,但可以显式指明全局赋值。

下面局部定义的例子

#### ${\left\{ def a\{b\} \right\} a}$

将给出 'undefined control sequence' 的错误,因为 \a 是在编组内部定义的,类似地,下列代码

\count0=1 {\count0=2 } \showthe\count0

显示的值为 1;编组内的赋值在该编组结束后将被撤销。

对编组结束时要还原的值的记录是通过保存堆栈的结构来实现的。保存堆栈的 溢出问题在第35章中介绍。这个保存堆栈还有另外几个用途:比如在调用\hbox to 100pt{...} 114 第 10 章 编组

时,在开始新层级的编组之前,所指定的to 100pt 将被放入保存堆栈中。

为避免给保存堆栈造成各种麻烦, $IniT_{EX}$ 不允许在编组内用  $\dump$  命令转储格式文件。 $\end$  命令可以出现在编组内,但  $T_{EX}$  将对此给出一个诊断信息。

控制系列 \aftergroup 保存一个记号,并在当前编组结束后插入它。此命令可以放置多个记号,这些记号将按出现的先后顺序被插入。此命令将在第 12 章中讨论.

## 10.2 局部和全局赋值

给赋值或宏定义加上 \global 前缀,通常可让它们成为全局的,但 \integer parameter \ \globaldefs 的非零值将覆盖 \global 指定: 如果 \globaldefs 为正数,每个赋值都被隐式地添加 \global 前缀,而如果 \globaldefs 为负数,\global 将会被忽略。通常这个参数的取值为零。

有些赋值总是全局的:所有的 (global assignment) 如下:

**(font assignment)** \fontdimen \hyphenchar 和 \skewchar 的赋值。

**(hyphenation assignment)** \hyphenation 和 \patterns 命令(见第 19 章)。

**(box size assignment)** 用 \ht \\dp 和 \wd 修改盒子尺寸(见第 5 章)。

(interaction mode assignment) TpX 任务的运行模式(见第 32 章)。

**⟨intimate assignment**⟩ 对 ⟨special integer⟩ 或 ⟨special dimen⟩ 的赋值; 见第 85 和 93 页。

## 10.3 编组定界符

编组定界符可以由类别码为 1 的 '组开始符' 和类别码为 2 的 '组结束符' 组成 (显式花括号),或者用 \let 等价到这两类字符的控制序列组成(隐式花括号),正如 plain T<sub>E</sub>X 中的 \bgroup 和 \egroup。隐式和显式花括号可以配对以定界一个编组;比如见第 12.3.4 节的例子。

编组也可以用 \begingroup 和 \endgroup 定界。这两个控制序列必须一起使用,它们不能与隐式或显式花括号配对,也不能像花括号那样用于围住盒内素材等。

用 \begingroup 和 \endgroup 定界可以提供一种有限的运行时错误检测。在这两个编组定界符之间一个多余的开或闭花括号将有

\begingroup ... \endgroup

或者

\begingroup ... \ endgroup

的形式。对这两种情形 **TrX** 都将给出括号不配对的错误信息。这里若改用 \bgroup 和 \egroup 将使得错误更加难以发现,因为出现了不正确的配对。这个想法在多种

10.4 花括号进阶 115

环境宏中用到。

TeX 并没有硬性规定花括号作为组开始和结束符。在 plain 格式中,它是类似这样编写的:

```
\catcode`\{=1 % left brace is begin-group character
\catcode`\}=2 % right brace is end-group character
```

隐式花括号也在 plain 格式中定义:

```
\let\bgroup={ \let\egroup=}
```

下面列出一些特殊情形:

- 宏的替换文本必须用显式组开始符和组结束符围住。
- 盒子、\vadjust 和 \insert 的开始和结束花括号可以是隐式的。这样就可能像 下面这样定义

```
\def\openbox#1{\setbox#1=\hbox\bgroup}
\def\closebox#1{\egroup\box#1}
\openbox{15}Foo bar\closebox{15}
```

• 记号列赋值的右边,以及命令 \write、\message、\errmessage、\uppercase、 \lowercase、\special 和 \mark 的参量是 \general text \, 定义为

```
\langle general \ text \rangle \longrightarrow \langle filler \rangle \{\langle balanced \ text \rangle \langle right \ brace \rangle
```

这意味着左花括号可以是隐式的,但右花括号必须是类别码2的显式字符记号。

在可以使用隐式花括号的情形中,如果展开没被显式禁止,**TpX** 将展开记号直到遇到一个左花括号。这是 \uppercase\expandafter{\romannumeral80} 这种写法的原理,在未展开之前这样的写法并不符合语法。如果第一个不可展开的记号不是一个左花括号,**TpX** 将给出一个错误信息。

在 TeX 的文法(见第 36 章)中,用  $\langle left brace \rangle$  和  $\langle right brace \rangle$  表示显式字符,即字符记号;而用 {和}表示可能为隐式的字符,即已经用  $\langle let$ 等价到这些显式字符的控制序列。

## 10.4 花括号讲阶

## 10.4.1 花括号计数器

TeX 有两个计数器用于记录编组的层级: 主计数器和平衡计数器。这两个计数器都是语法计数器:它们计算显式花括号记号的个数,但不受语义上与显式花括号等价的隐式花括号(比如 \bgroup)的影响。

平衡计数器处理除了阵列之外的所有情形。其工作原理直观而清晰:对每个左花括号增加一,对每个右花括号减少一,只要该花括号不被跳过。因此对于下面的语句

116 第 10 章 编组

#### \iffalse{\fi

在它仅仅被扫描时(比如它出现在宏定义文本中)将增加平衡计数器的值;而在它被执行时花括号将被跳过,从而不会改变平衡计数器的值。

主计数器更加复杂;在阵列中只使用主计数器,不使用平衡计数器。这个计数器记录所有花括号,即使在被跳过时,像\iffalse{\fi这种。对这个计数器,未计数的已跳过花括号还是可能的:当字母表常数`{和`}被执行处理器作为〈number〉使用时,不影响这个计数器;当它们被输入处理器查看(仅查看字符,不含上下文)时,确实会影响这个计数器。

#### 10.4.2 花括号作为记号

显式花扩号是字符记号,而作为字符记号它们是不可展开的。这表示它们直到 **TrX** 处理的最后一个阶段还是存在的。例如,

#### \count255=1{2}

将给 \count255 赋值 1,并排印 '2',因为左花括号充当了数字 1 的定界符。类似地, $f\{f\}$ 

将阻止 TrX 形成 'ff' 连写。

从花括号不可展开的事实,可以得知它们的嵌套与条件语句的嵌套相互独立。比如

#### \iftrue{\else}\fi

将给出左花括号,因为条件语句是在展开时处理的。右花括号作为〈 $false\ text$ 〉的一部分被直接跳过了;这对编组的影响在  $T_{PX}$  处理的后续阶段才显现出来。

非定界的宏参量或者是单个记号,或者是一个用显式花括号围住的编组。因此,显式的左或右花括号不能作为宏参量。然而,花括号可以用于 \let 赋值,就像这样

#### \let\bgroup={

这在 plain TrX 的 \footnote 宏(见第 138 页)中用到。

#### 10.4.3 花括号控制符号

控制序列 \{ 和 \} 并不属于这一章,也与编组无关。它们被用 \let 分别定义为 \lbrace 和 \rbrace 的别名,而这两个控制序列为 \delimiter 指令(见第 21 章)。

计算机现代罗马字体中不包含花括号,但打字机字体中包含;而对于数学公式, 在扩展字体中有不同尺寸的——且可伸展的——花括号。

# 第 11 章 宏定义

在  $T_{\mathbf{p}}\mathbf{X}$  中,宏是对一串需要多次用到的命令的缩写机制,它有点像普通编程语言的过程。然而  $T_{\mathbf{p}}\mathbf{X}$  的参数机制是与众不同的。这一章解释  $T_{\mathbf{p}}\mathbf{X}$  的宏如何运作,并介绍命令\let 和 \futurelet。

\def 开始一个宏定义。

\gdef 等同于 \global\def。

\edef 开始一个宏定义;在定义时替换文本被展开。此命令在下一章也会介绍。

\xdef 等同于 \global\edef。

\csname 开始生成一个控制序列的名称。

\endcsname 结束生成一个控制序列的名称。

\global 使得后面的定义、算术语句或赋值是全局的。

\outer 此前缀表示正在定义的宏只能用在'外部'层级中。

\long 此前缀表示正在定义的宏的参量可以包含 \par 记号。

\let 将一个控制序列定义为等价于下一个记号。

\futurelet 将一个控制序列定义为等价于下一个记号之后的记号。

## 11.1 介绍

基本上宏是缩写为一个控制序列的一串记号。以 \def 等开始的语句称为宏定 义,而语句

#### \def\abc{\de f\g}

就定义了以 \de f\g 为替换文本的宏 \abc。以这种方式, 宏可以用于缩写需要多次用到的一段文本或一串命令。在任何时候, 只要 TeX 的展开处理器遇到控制序列 \abc, 它就将这个宏用其替换文本代替。

如果想让宏依赖它被用到时的上下文,就可以将它定义为带参数的宏。像下面这样定义的 \PickTwo

118 第 11 章 宏定义

#### \def\PickTwo#1#2{(#1,#2)}

有两个参数。这个宏被用到时将取出两段文本,即对应的参量,并将它们排印在圆括号中。例如:

	macro	argument1	argument2		expansion	
definition	\def\PickTwo	#1	#2	{	(#1,#2)	}
use	\PickTwo	1	<b>2</b>		(1,2)	
use	\PickTwo	{ab}	{cd}		(ab,cd)	

将宏及其参量用替换文本代替的活动称为宏展开。

## 11.2 宏定义的结构

- 一个宏定义按照顺序包含下列各部分:
- 1. 任意多个 \global \long 和 \outer 前缀,
- 2. 一个 〈def〉 控制序列,或者任何用 \let 等价到此种控制序列的东西,
- 3. 一个将要定义的控制序列或活动字符,
- 4. 一个可能存在的 (parameter text) 用于指定宏参数的个数及其他东西,以及
- 5. 一个用类别码为 1 和 2 的显式字符记号包围的替换文本, 在 plain TpX 中这两 类字符默认为 { 和 }。

这些元素将在接下来各节中解释。

在宏定义完成之后,任何已保存的 \afterassignment 记号(见第 12.3.3 节)将被插入进来。

'展开的' 定义 \edef 和 \xdef 将在第 12 章讨论。

## 11.3 前缀

有三种前缀用于改变宏定义的状态:

\global 如果定义出现在编组内,此前缀将使得该定义成为全局的。除了宏定义之外,此前缀还能用于赋值;实际上,对于宏定义,可以用缩写形式而不用\global:

\gdef\foo... 等价于 \global\def\foo...

丽

\xdef\foo... 等价于 \global\edef\foo...

如果参数 \globaldefs 为正数,所有赋值都被视为全局的;而如果 \globaldefs 为负数,所有 \global 前缀都被忽略,而且 \gdef 和 \xdef 也生成局部的定义

11.4 定义的类型 119

( 见第 10 章)。

\outer 外部宏的定义机制用于帮助定位未配对花括号(及其他错误):\outer 宏只能出现在非嵌入语境中。更准确地说,它不可以出现

- 在宏的替换文本中(但如果将它放在 \noexpand 或 \meaning 之后,就可以 出现在 \edef 的替换文本中),
- 在参数文本中,
- 在跳过的条件文本中,
- 在阵列的导言中,以及
- 在 \message \write 等的 \langle balanced text \rangle 中。

然而,在特定应用中某些 plain 宏是外部的很不方便,特别是像 \newskip 这样的宏。有个补救方法是将它们重新定义为非外部的宏,这正是 LATEX 所做的,但还有更巧妙的做法。

\long 宏的参量通常不允许包含 \par 记号。这个限制在定位遗漏的右括号时很有用(比 \outer 定义有用得多)。例如,对于下面的输入 TeX 将抱怨 'runaway argument':

```
\def\a#1{ ... #1 ... }
\a {This sentence should be in braces.
```

And this is not supposed to be part of the argument 其中的空行生成一个 \par,这在多数时候意味着有个右花括号漏掉了。如果某个宏允许其参量包含 \par 记号,则这个宏应当定义为 \long 宏。在测试两个记号是否相等时(见第 13 章),\ifx 也会将前缀考虑在内。

## 11.4 定义的类型

在 TeX 中有四种 〈def〉 控制序列: \def、\gdef、\edef 和 \xdef。其中 \gdef 是 \global\def 的同义词,而 \xdef 是 \global\edef 的同义词。而 '展开的定义' \edef 在第 12 章中介绍。

各种宏定义仅在定义时有区别。在宏被调用时是无法知道它们是如何定义的。

## 11.5 参数文本

在所定义的控制序列或活动字符以及替换文本的左花括号之间,可以有 \(\rangle parameter text \),参数文本有点像普通编程语言的参量。它指定这个宏是否有参数,有多少个参数,以及各参数之间如何定界。\(\rangle parameter text \rangle \) 不能包含显式花括号。

一个宏最多可以有九个参数。参数用参数记号表示,参数记号由宏参数字符(即类别码为 6 的字符,在 plain  $T_{E}X$  中为 #)后跟一个 1–9 的数字组成。举个例子,#6 表示宏的第六个参数。参数记号不能出现在宏定义之外的其他地方。

在参数文本中,参数必须从 1 开始顺序编号。参数记号后的空格是有意义的,不管是在参数文本还是在替换文本中。

参数分为定界参数和非定界参数;它决定宏参量的范围。如果在〈parameter text〉中一个参数后面紧跟着另一个参数,就像 \def\foo#1#2 这样,则前面的参数就是非定界的。如果一个参数后面紧跟着替换文本的左花括号,就像 \def\foo#1{...}这样,则它也是非定界的。一个参数称为定界的,如果它后面紧跟着其他记号;比如\def\foo#1!#2{...}的第一个参数就是被感叹号定界的参数。

在宏展开(或'调用')时,用于替换参数的(零个或多个)记号称为该参数对应的'参量'。

## 11.5.1 非定界参数

在带有非定界参数的宏,比如单参数宏\foo

```
\def\foo#1{ ... #1 ...}
```

被展开时, $T_EX$  往前扫描(但不展开)直到遇到一个非空格记号。如果这个记号不是显式  $\langle left \ brace \rangle$ ,它就被取为对应于该参数的参量。否则,通过扫描直到找到匹配的显式  $\langle right \ brace \rangle$ , $T_EX$  得到一个  $\langle balanced \ text \rangle$ 。这个平衡文本就要找的参量。

这里是个带有三个非定界参数的宏的例子:对于

```
\def\foo#1#2#3{#1(#2)#3}
```

宏调用 \foo123 给出 '1(2)3'; 而\foo 1 2 3 给出同样的结果。在调用

```
\foo 1 2 3
```

中,第一个空格被  $T_{E}X$  的输入处理器跳过。从而对应于第一个参数的参量是 1。为找到第二个参量, $T_{E}X$  跳过所有空格(在此例子中跳过一个空格),最后找到的第二个参量是 2。类似的第三个参量是 3。

为了将多个记号作为一个非定界参量,你可以使用花括号。对于上述的 \foo 定义,调用 \foo a{bc}d 将给出 'a(bc)d'。当宏的参量是平衡文本而非单个记号时,在将参量插入替换文本时定界花括号会被去掉。例如:

```
\def\foo#1{\count0=1#1\relax} \\ foo{23}
```

将展开为 \count0=123\relax, 这将对计数器赋值 123。另一方面, 下面语句 \count0=1{23}

```
将赋值1并排印23。
```

11.5 参数文本 121

#### 11.5.2 定界参数

除了将它们括在花括号里面,还有另一种方式可将一串记号作为宏的一个参量,即使用**定界的参**数。

在〈parameter text〉中,出现在宏参数之后(即在紧跟参数字符的参数编号之后)的非参数记号被当作该参数的定界子。定界子可以包含空格记号:参数编号之后的空格是有意义的。定界记号同样出现在所定义的控制序列和它的第一个参数记号#1 之间。

对于在参数文本中充当定界子的字符记号,它们的字符码和类别码都被存储下来;实际参量的定界字符记号必须和两者都匹配。这些字符可以拥有一些通常只出现在特殊环境中的类别码;比如,在定义

```
\def\foo#1 #2^{...}
```

之后,宏\foo可以在数学模式之外使用。

在寻找对应于一个定界参数的参量时,**TpX** 吸收所有记号而不展开它们(但保持花括号配对),直到遇到(完全一致的)定界记号串。定界记号串不是参量的一部分;在宏调用时它们被从输入流中移除。

#### 11.5.3 定界参量举例

作为一个简单例子,我们定义一个宏\def\DoASentence#1#2.{{#1#2.}}

它的第一个参数是非定界的,而第二个参数是用句号定界的。像下面这样调用时

\DoASentence \bf This sentence is the argument.

它的两个参量分别是:

#1<-\bf

#2<-This sentence is the argument

注意结尾的句号不在参量中,但它已经被吸收了,不会再出现在输入流中。

常用的定界子是\par,例如:

\def\section#1. #2\par{\medskip\noindent {\bf#1. #2\par}}

这个宏第一个参数用'.'定界,而第二个参数用\par 定界。像下面调用此宏

\section 2.5. Some title

The text of the section...

将给出

#1<-2.5

#2<-Some title

注意在第二个由行尾符生成的参量的末尾有个空格。如果这个空格是多余的,你可以定义

```
\def\section#1. #2 \par{...}
```

从而用 \par 定界第二个参量。然而这种方法导致用户不可以显式写上 \par:

```
\section 2.5 Some title\par
```

解决这种两难选择的其中一种方法是,在需要去掉结尾空格时,在定义文本中写上#2\unskip。

充当定界子的控制序列不需要已经定义,因为它们只被吸收不会被展开。因此 \def\control#1\sequence{...}

是有效的定义,即使在\sequence 未定义时。

下面的例子展示了定界参量的类别码是至关重要的:

```
\def\a#1 #2.{ ... }
\catcode`\ =12
\a b c
d.

将给出
```

\a #1 #2.-> ... #1<- b c #2<-d

解释: 参数 1 和参数 2 之间的定界子是一个第 10 类的空格。在 a 和 b 之间有一个第 12 类的空格; 第一个第 10 类的空格是由行尾生成的空格。

在第 13 章对 \newif 的解释,以及在第 30 页的例子中,有类别码匹配的实际例子。

## 11.5.4 空参量

在 T<sub>E</sub>X 需要一个宏参量时,如果用户指定一个围在花括号中的 〈balanced text〉、则该文本就被用作参量。因此,指定 {} 给出的参量是一个空记号列;它称为'空参量'。

在使用定界参数时也可能得到空参量。例如,在下述定义

```
\def\mac#1\ro{ ... }
```

之后,这样调用

\mac\ro

将给出一个空参量。

11.5 参数文本 123

#### 11.5.5 宏参数字符

在 **TeX** 的输入处理器扫描宏定义文本时,它对后面跟着数字的每个宏参数字符插入一个参数记号。实际上,在替换文本中,参数记号表示'在这里插入某某编号的 参量'。连续两个参数字符被替换为一个。

后一个的事实可以用于嵌套的宏定义。下面的定义

```
\def\a{\def\b#1{...}}
```

给出一个错误信息,因为 \a 被定义为不带参数的宏,而在它的替换文本中有一个参数记号。

下面的语句

```
\def\a#1{\def\b#1{...}}
```

定义了宏 \a,这个宏又定义了另一个宏 \b。然而,\b 任然不带任何参数:这样调用 \a z

就定义了一个不带参数的宏 \b,其后必须跟着 z。注意这并不是在定义宏 \bz,因为 **TrX** 的输入处理器读取输入行时就已经形成了控制序列 \b。

最后,

```
\def\a{\def\b\#1{...}}
```

定义了带一个参数的宏 \b。

我们来仔细检查一下参数字符的处理过程。考虑下面定义

```
\def\a#1{ .. #1 .. \def\b##1{ ... }}
```

当这个语句作为输入被读取时,输入处理器

- 将字符串 #1 替换为 (parameter token<sub>1</sub>),并且
- 将字符串 ## 替换为 #

在调用宏 \a 时,输入处理器将扫描

```
\def\b#1{ ... }
```

并将其中两个字符的#1替换为一个参数记号。

## 11.5.6 花括号定界

在定义的〈parameter text〉中通常是不可能有左或右花括号的。然而,有一种特殊规定可以让宏的最后一个参数看似用左花括号定界的。

如果最后一个参数记号后面是一个参数字符(#),接着是替换文本的左花括号, TeX 将让最后一个参数以组开始符定界。此外,与参数文本的其他定界记号不同,这 个左花括号不会被从输入流中移除。

考虑一个例子。假设你想有个宏\every 宏用于像下面这样填充记号列:

第 11 章 宏定义

\every par{abc} \every display{def}

这个宏可以定义为

\def\every#1#{\csname every#1\endcsname}

在上面的第一个调用中,对应于参数的参量是 abc,因此该调用展开为

\csname everypar\endcsname{abc}

这就给出所要的结果。

## 11.6 构造控制序列

命令 \csname 和 \endcsname 可用于构造控制序列。例如 \csname hskip\endcsname 5pt

等价于 \hskip5pt。

在构造的过程中,介于\csname 和\endcsname之间的所有宏和其他可展开控制序列都如常展开,直到仅留下不可展开的字符记号。若将上面例子改写为

\csname \ifhmode h\else v\fi skip\endcsname 5pt

则它将依据当前模式执行 \hskip 或 \vskip。展开的最后结果必须只包含字符记号,但对它们的类别码却无限制。在碰到不可展开的控制序列时,**T<sub>E</sub>X** 将抛出一个错误,并在错误恢复时在该处之前插入一个 \endcsname。

利用 \csname, 我们可以构造通常无法写出的, 包含类别码不为 **11**(字母)的字符的控制序列。这个原理可用于对用户隐藏宏包内部的控制序列。

#### 例子:

```
\def\newcounter#1{\expandafter\newcount
    \csname #1:counter\endcsname}
\def\stepcounter#1{\expandafter\advance
    \csname #1:counter\endcsname 1\relax}
```

第二个定义中的 \expandafter 是多余的,但它没有坏处,且可以让代码更清楚。

\newcounter 创建的计数器的名称中包含一个冒号,因此写起来有点麻烦。好处是现在这个计数器对用户是隐藏的,它只能通过类似\stepcounter 的控制序列来访问。顺便说一下,在 plain 格式中 \newcount 被定义为 \outer 宏,因此在重新定义 \newcount 后才能写出上述定义。

如果用 \csname...\endcsname 生成的控制序列之前尚未定义,它就被定义为 \relax。因此如果 \xx 是一个未定义的控制序列,命令

\csname xx\endcsname

将不会导致错误信息,因为它等价于\relax。此外,在执行\csname...\endcsname

语句后, 控制序列 \xx 本身等价于 \relax, 因此它也不再导致 'undefined control sequence' 的错误(另见第 141 页)。

## 11.7 用 \let 和 \futurelet 给出记号赋值

在 TrX 中有两个 (let assignment)。它们的语法为

在\futurelet 赋值的语法中,不可以出现可选的等号。

#### 11.7.1 \let

原始命令 \let 将某个记号的当前含义赋予一个控制序列或活动字符。

例如,在 plain 格式中,\endgraf 定义为

\let\endgraf=\par

这使得宏的编写者可以重新定义 \par,而原始的 \par 命令的功能仍然可以使用。例如,

\everypar={\bgroup\it\def\par{\endgraf\egroup}}

在第3章中已经讨论了〈token〉不是控制序列而是字符记号的情形。

#### 11.7.2 \futurelet

如上所述,\let 系列

将  $\langle token_1 \rangle$  (的含义)赋予该控制序列,而剩下的输入流如下

 $\langle token_2 \rangle \langle token_3 \rangle \langle token \cdots \rangle$ 

即 〈token<sub>1</sub>〉 从输入流中消失了。

命令 \futurelet 的运作稍有不同:对于下面的输入流

 $\time \time \tim$ 

它将 (token<sub>2</sub>)(的含义)赋予该控制序列,而剩下的输入流如下

 $\langle token_1 \rangle \langle token_2 \rangle \langle token_3 \rangle \langle token \cdots \rangle$ 

也就是说,  $\langle token_1 \rangle$  和  $\langle token_2 \rangle$  都不会被从输入流中去掉。然而, 现在  $\langle token_1 \rangle$  无需将  $\langle token_2 \rangle$  取为宏参数就 '知道' 它是什么。见后面给出的例子。

第 11 章 宏定义

在字符记号已经被\futurelet 到一个控制序列时,它的类别码就已经确定了。随后的〈token<sub>1</sub>〉无法再改变它。

## 11.8 杂项注记

## 11.8.1 活动字符

类别码 **13** 的字符记号称为活动字符,我们可以像控制序列那样定义它。如果这种字符的定义出现在宏里面,在宏定义时这个字符必须是活动的。

以下面的定义为例(取自第2章):

```
\catcode`\^^M=13 \% $$ \gdef\obeylines{\catcode`\^^M=13 \def^^M{\pi}}
```

在定义 \obeylines 前必须先设定好  $^{\text{M}}$  字符的类别码, 否则  $T_{\text{EX}}$  会认为该行在 \def 之后结束。

## 11.8.2 宏与原始命令

相比其他编程语言,在TrX中原始命令与用户宏的区分并不大重要。

• 用户可以用别的名称使用原始命令:

\let\StopThisParagraph=\par

• 原始命令的名称可以给用户宏使用:

```
\def\par{\hfill$\bullet$\endgraf}
```

• 很多原始命令和用户宏一样都可以展开,比如所有条件句,以及类似 \number 和 \jobname 的命令。

## 11.8.3 尾递归

**TeX** 中的宏,与大多数现代编程语言一样,可以是递归的:即在宏定义中可以调用这个宏本身,或者另一个将调用这个宏的宏。如果同一个递归宏的'化身'在同一时间出现太多次,它容易弄乱 **TeX** 的内存。然而,对于尾递归这种常见的递归情形,**TeX** 能够避免出现混乱。

要理解这里发生的事情,需要一些背景知识。在开始执行一个宏时,**TpX** 抓取宏的参量,然后在输入栈上放置一个指向替换文本的项目,这样扫描器接着将转到替换文本中。一旦它处理完毕,输入栈中的这个项目将被移除。然而,如果宏的定义文本中包含另外的宏,这个过程将对它们重复进行:新的项目将被放在输入栈上,引导扫描器到其他宏中,甚至在第一个宏还未完成时,

11.9 宏的技巧 127

一般来说,这种'栈构建'不是很好但却是无可避免的;然而如果嵌套宏调用出现在宏的替换文本末尾的记号处,这是可以避免的。在末尾的记号后没有其他记号需要处理,因此我们可以在新的宏放进来之前清除输入栈顶部的项目。这正是 **TeX** 所做的事情。

Plain T<sub>F</sub>X 的 \loop 对这个原理给出很好的说明。它的定义是

```
\def\loop#1\repeat{\def\body{#1}\iterate}
\def\iterate{\body \let\next=\iterate
  \else \let\next=\relax\fi \next}
```

而这个宏可以用类似下面的例子来调用:

```
\loop \message{\number\MyCount}
   \advance\MyCount by 1
   \ifnum\MyCount<100 \repeat</pre>
```

宏 \iterate 可以调用它自己,而且当它这样做时,递归调用出现在列表的末尾记号。 也许可以将 \iterate 定义为

```
\def\iterate{\body \iterate\fi}
```

但这样 **TeX** 将无法消除这个递归,因为对 \iterate 的调用并不出现在 \iterate 的替换文本的末尾记号. 这里的赋值 \let\next=\iterate 就是一种让递归调用出现在列表的末尾记号的方法。

```
另一种消除尾递归的方法是使用 \expandafter(见第 160 页):在下面 \def\iterate{\body \expandafter\iterate\fi}
```

这种写法中,它去掉了 \fi 记号。如果列表的末尾记号是递归宏的参量,尾递归也将被消除。

```
顺便说一句:如果将 \iterate 定义为
\def\iterate{\let\next\relax
\body \let\next\iterate \fi \next}

就可以这些写
\loop ... \if... \else ... \repeat
```

## 11.9 宏的技巧

## 11.9.1 不确定个数的参量

在某些应用中,我们希望宏的参量个数不用先规定好。

考虑在国际象棋棋盘上转换位置的问题(全部宏和字体可以在[?]和[?]中找到),比如要将棋谱记法

```
\White(Ke1,Qd1,Na1,e2,f4)
```

第 11 章 宏定义

转换为一串排版好的走法

注意在位置列表中兵前面的 'P' 被省略掉了。

首要问题在于棋子列表是变长的,因此我们添加一个终止棋子:

```
\def\White(#1){\xWhite#1,xxx,}
\def\endpiece{xxx}
```

这样我们就可以检测到。接下来,\x\mite 从列表中读取一个位置,检测它是否为终止棋子;如果不是,依据它是否为一个兵分别处理。

```
\def\xWhite#1,{\def\temp{#1}%
  \ifx\temp\endpiece
  \else \WhitePieceOrPawn#1XY%
       \expandafter\xWhite
  \fi}
```

其中必须用 \expandafter 命令去掉 \fi(见第 160 页), 使得 \x\hite 以下一个位置而不是 \fi 为参量。

位置的长度为两个或三个字符长。在调用四参数宏 \WhitePieceOrPawn 时添加了一个终止字符串 XY。因此,对棋子为兵的情形,第 3 个参量为字符 X 而第 4 个参量为空;对其他棋子的情形,第 1 个参量是该棋子,而第 2 和 3 个参量为具体的位置,第 4 个参量为 X。

```
\def\WhitePieceOrPawn#1#2#3#4Y{
   \if#3X \WhitePiece{P}{#1#2}%
   \else \WhitePiece{#1}{#2#3}\fi}
```

## 11.9.2 检查参量

在有些时候。我们需要检查宏参量中是否包含某个元素。考虑下面的实际例子(另见第 241 页的 \DisplayEquation 的例子)。

假设文章的标题和作者为

```
\title{An angle trisector}
\author{A.B. Cee\footnote*{Research supported by the
Very Big Company of America}}
```

而有多个作者时为

```
\author{A.B. Cee\footnote*{Supported by NSF grant 1}
    \and
    X.Y. Zee\footnote{**}{Supported by NATO grant 2}}
```

另外假设 \title 和 \author 宏定义为

11.9 宏的技巧 129

这将会被这样使用

```
\def\ArticleHeading{ ... \TheTitle ... \TheAuthor ... }
  有些期刊要求文章的作者和标题全部大写。这种要求的实现方式可能是
   \def\ArticleCapitalHeading
     { ...
      \uppercase\expandafter{\TheTitle}
      \uppercase\expandafter{\TheAuthor}
     }
现在 \expandafter 命令将展开标题和作者为实际文本,接着 \uppercase 命令将把
它们变为大写。然而,对于这样写对作者名来说是错误的,因为 \uppercase 命令将
脚注文本也大写了。现在的问题在于如何仅将在脚注之间的文本变为大写。
   作为第一次尝试,让我们先考虑只有一个作者的情形,设基本调用为
   \expandafter\UCnoFootnote\TheAuthor
这将展开为
  \UCnoFootnote A.B. Cee\footnote*{Supported ... }
这个宏
  \def\UCnoFootnote#1\footnote#2#3{\uppercase{#1}\footnote{#2}{#3}}
将正确地分析它:
  #1<-A.B. Cee
   #2<-*
   #3<-Supported ...
然而,如果脚注不存在时,这个宏将是完全错误的。
   作为首个改进,我们自己添加脚注,以让它始终存在:
   \expandafter\UCnoFootnote\TheAuthor\footnote 00
```

现在我们得检测所找到的脚注的类型:

```
\def\stopper{0}
\def\UCnoFootnote#1\footnote#2#3{\uppercase{#1}\def\tester{#2}%
    \ifx\stopper\tester
   \else\footnote{#2}{#3}\fi}
```

我们用 \ifx 区分出定界脚注号和实际脚注号。注意如果改用

```
\int ifx0#2
```

将是错误的,因为脚注号可能包含多个记号,比如 {\*\*}。

到目前为止,如果没有脚注这个宏是正确的,但如果有个脚注它是错误的:这几 个终结记号还有待我们处理掉。在下面这个版本中它们会被小心处理好:

```
\def\stopper{0}
```

第 11 章 宏定义

```
\def\UCnoFootnote#1\footnote#2#3{\uppercase{#1}\def\tester{#2}%
\ifx\stopper\tester
\else\footnote{#2}{#3}\expandafter\UCnoFootnote
\fi}
```

重复调用 \UCnoFootnote 将去掉定界记号(\expandafter 先去掉了 \fi),而且作为额外收获,这个宏对于多个作者的情形也是正确的。

## 11.9.3 用 \futurelet 实现可选的宏参数

\futurelet 的其中一个标准用法就是实现宏的可选参数。一般做法如下:

```
\def\Com{\futurelet\testchar\MaybeOptArgCom}
\def\MaybeOptArgCom{\ifx[\testchar \let\next\OptArgCom \else \let\next\NoOptArgCom \fi \next}
\def\OptArgCom[#1]#2{ ... }\def\NoOptArgCom#1{ ... }
```

注意即便它测试的是个字符还是使用了\ifx。原因当然是,如果可选参量不存在,在\Com之后可能会是一个可展开的控制序列。

现在宏 \Com 有一个可选参量以及一个常规参量;我们可以这样 \Com{argument}

或者这样

\Com[optional]{argument}

调用它。通常不带可选参量的调用将插入默认值:

\def\NoOptArgCom#1{\OptArgCom[default]{#1}}

这种机制在类似 LATEX 和 LAMSTEX 的格式中广泛用到;另外可以参考 [?]。

#### 11.9.4 两步宏

用户经常会觉得某个宏事实上是一个两步的过程,其中第一个宏设定好条件,而 第二个宏将执行操作。

作为例子,这里有个 \PickToEo1 宏,它的参量以行尾符定界。首先我们写出第一个不带参量的宏,它改变行尾符的类别码,然后调用第二个宏。

```
\def\PickToEol{\begingroup\catcode`\^^M=12 \xPickToEol}
```

现在第二个宏将以直到行尾的所有内容作为它的参量:

```
\def\xPickToEol#1^^M{ ... #1 ... \endgroup}
```

这个定义有个问题: ^^M 符的类别码必须为 12。我们改进一下:

```
\def\PickToEol{\begingroup\catcode`\^^M=12 \xPickToEol}
{\catcode`\^^M=12 %
  \gdef\xPickToEol#1^^M{ ... #1 ... \endgroup}%
```

11.9 宏的技巧 131

}

其中为 \xPickToEo1 的定义改变了 ^^M 的类别码。注意 \PickToEo1 中的 ^^M 作为控制符号出现,此时它的类别码是无关紧要的。因此那个定义可以出现在重新定义 ^^M 的类别码的编组的外边。

## 11.9.5 注释环境

作为上述两步宏的想法的应用,也为了演示尾递归,这里是一个'注释'环境的宏。

我们经常需要临时删除部分 TrX 输入。为此我们想这样写

\comment

. . .

\endcomment

最简单的实现方式,

```
\def\comment#1\endcomment{}
```

有许多不足。比如,它无法妥善处理外部宏或者花括号不匹配的输入。然而,最大的不足是它将整个注释文本作为宏参量读取。这使得注释文本的长度不能超过 **TpX** 的输入缓冲区的大小。

将注释文本逐行取出会更好些。为此我们需要编写一个递归宏

```
\def\comment#1^^M{ ... \comment }
```

为使这个定义能写出来,行尾符的类别码必须改变。和上面一样我们将有

```
\def\comment{\begingroup \catcode`\^^M=12 \xcomment}
{\catcode`\^^M=12 \endlinechar=-1 %
  \gdef\xcomment#1^^M{ ... \xcomment}
}
```

改变 \endlinechar 只不过是为了避免在这个定义的每行末尾加上注释符。

当然,这个过程必须在某个地方停止。为此我们考察已被取为宏参量的文本行:

```
{\catcode`\^^M=12 \endlinechar=-1 %
  \gdef\xcomment#1^^M{\def\test{#1}
    \ifx\test\endcomment \let\next=\endgroup
    \else \let\next=\xcomment \fi
    \next}
}
```

而我们必须定义 \endcomment 如下:

```
\def\endcomment{\endcomment}
```

这个命令将永远不会被执行;它只是用于测试是否已经到达环境的结尾处。

我们也许想注释掉语法不正确的文本。因此在注释时我们切换到抄录模式。下

132 第 11 章 宏定义

面的宏是 plain TeX 给出的:

```
\label{localizero} $$\do^{do}\do^{\do}^A\do^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\do}^{\
```

我们把它用到 \comment 的定义中:

```
\def\makeinnocent#1{\catcode`#1=12 }
\def\comment{\begingroup
   \let\do=\makeinnocent \dospecials
   \endlinechar`\^^M \catcode`\^^M=12 \xcomment}
```

这种方法除了能注释掉语法错误比如花括号不匹配的文本外,还能处理外部宏。之前的\xcomment 实现在注释文本包含外部宏时将会产生 **TrX** 错误。

然而,使用抄录模式给结束环境造成了问题。注释的最后一行现在不是控制序列 \endcomment,而是由一串字符组成。这样我们就必须测试这个字符串:

```
{\escapechar=-1
  \xdef\endcomment{\string\\endcomment}
}
```

代码 \string\\ 给出一个反斜线。我们不能这样写

\edef\endcomment{\string\endcomment}

因为这样写单词 endcomment 各字母的类别码将为 12, 而与它们在注释最后一行中的类别码 11 不相等。

# 第 12 章 Expansion

Expansion in TEX is rather different from procedure calls in most programming languages. This chapter treats the commands connected with expansion, and gives a number of (non-trivial) examples.

\relax Do nothing.

\expandafter Take the next two tokens and place the expansion of the second after the first.

\noexpand Do not expand the next token.

\edef Start a macro definition; the replacement text is expanded at definition time.

\aftergroup Save the next token for insertion after the current group.

\afterassignment Save the next token for execution after the next assignment or macro definition.

\the Expand the value of various quantities in TeX into a string of character tokens.

#### 12.1 Introduction

TEX's expansion processor accepts a stream of tokens coming out of the input processor, and its result is again a stream of tokens, which it feeds to the execution processor. For the input processor there are two kinds of tokens: expandable and unexpandable ones. The latter category is passed untouched, and it contains largely assignments and typesettable material; the former category is expanded, and the result of that expansion is examined anew.

## 12.2 Ordinary expansion

The following list gives those constructs that are expanded, unless expansion is inhibited:

- macros
- conditionals
- \number, \romannumeral
- \string, \fontname, \jobname, \meaning, \the
- \csname ... \endcsname
- \expandafter, \noexpand
- \topmark, \botmark, \firstmark, \splitfirstmark, \splitbotmark
- \input, \endinput

This is the list of all instances where expansion is inhibited:

- when TFX is reading a token to be defined by
  - a (let assignment), that is, by \let or \futurelet,
  - a (shorthand definition), that is, by \chardef or \mathchardef, or a \( \text{register def} \), that is, \( \text{countdef}, \dimendef, \skipdef, \muskipdef, \) or \\toksdef,
  - a (definition), that is a macro definition with \def, \gdef, \edef, or \xdef,
  - the \(\simple assignment\)s \(\read \and \font;\)
- when a \(\parameter\) text\\) or macro arguments are being read; also when
  the replacement text of a control sequence being defined by \\def, \\gdef, or
  \\read is being read;
- when the token list for a \(\text{token variable}\) or \uppercase, \lowercase, or \uppercase, \upperc
- when tokens are being deleted during error recovery;
- when part of a conditional is being skipped;
- in two instances when TFX has to know what follows
  - after a left quote in a context where that is used to denote an integer (thus in \catcode`\a the \a is not expanded), or
  - after a math shift character that begins math mode to see whether another math shift character follows (in which case a display opens);

 when an alignment preamble is being scanned; however, in this case a token preceded by \span and the tokens in a \tabskip assignment are still expanded.

## 12.3 Reversing expansion order

Every once in a while you need to change the normal order of expansion of tokens. TEX provides several mechanisms for this. Some of the control sequences in this section are not strictly concerned with expansion.

## 12.3.1 One step expansion: \expandafter

The most obvious tool for reversed expansion order is  $\ensuremath{\char{\sc}}$  expandafter. The sequence

Note the following.

If \(\text{token}\_2\)\) is a macro, it is replaced by its replacement text, not by its final expansion. Thus, if

```
\def\tokentwo{\ifsomecondition this \else that \fi}
\def\tokenone#1{ ... }

the call
   \expandafter\tokenone\tokentwo

will give \ifsomecondition as the parameter to \tokenone:
   \tokenone #1-> ...
   #1<-\ifsomecondition</pre>
```

• If the \tokentwo is a macro with one or more parameters, sufficiently many subsequent tokens will be absorbed to form the replacement text.

#### 12.3.2 Total expansion: \edef

Macros are usually defined by \def, but for the cases where one wants the replacement text to reflect current conditions (as opposed to conditions at the time of the call), there is an 'expanding define', \edef, which expands everything in the replacement text, before assigning it to the control sequence.

例子:

```
\edef\modedef{This macro was defined in
  `\ifvmode vertical\else \ifmmode math
  \else horizontal\fi\fi' mode}
```

The mode tests will be executed at definition time, so the replacement text will be a single string.

As a more useful example, suppose that in a file that will be \input the category code of the @ will be changed. One could then write

```
\label{lem:catcode`@=\the\catcode`@} $$at\ the\ start,\ and
```

at the end. See page 148 for a fully worked-out version of this.

Contrary to the 'one step expansion' of \expandafter, the expansion inside an \edef is complete: it goes on until only unexpandable character and control sequence tokens remain. There are two exceptions to this total expansion:

- any control sequence preceded by \noexpand is not expanded, and,
- if \sometokenlist is a token list, the expression

```
\the\sometokenlist
```

\restorecat

is expanded to the contents of the list, but the contents are not expanded any further (see Chapter 14 for examples).

On certain occasions the \edef can conveniently be abused, in the sense that one is not interested in defining a control sequence, but only in the result of the expansion. For example, with the definitions

the call

\expandafter\somemacro\othermacro

gives the parameter assignment

```
#1<-\ifnum
```

This can be repaired by calling

```
\edef\next{\noexpand\somemacro\othermacro}\next
```

Conditionals are completely expanded inside an \edef, so the replacement text of \next will consist of the sequence

```
\somemacro{this}
```

and a subsequent call to \next executes this statement.

#### 12.3.3 \afterassignment

The \afterassignment command takes one token and sets it aside for insertion in the token stream after the next assignment or macro definition. If the first assignment is of a box to a box register, the token will be inserted right after the opening brace of the box (see page 66).

Only one token can be saved this way; a subsequent token saved by \afterassignment will override the first.

Let us consider an example of the use of \afterassignment. It is often desirable to have a macro that will

- assign the argument to some variable, and then
- do a little calculation, based on the new value of the variable.

The following example illustrates the straightforward approach:

```
\def\setfontsize#1{\thefontsize=#1pt\relax
   \baselineskip=1.2\thefontsize\relax}
\setfontsize{10}
```

A more elegant solution is possible using \afterassignment:

```
\def\setbaselineskip
   {\baselineskip=1.2\thefontsize\relax}
\def\fontsize{\afterassignment\setbaselineskip
   \thefontsize}
\fontsize=10pt
```

Now the macro looks like an assignment: the equals sign is even optional. In reality its expansion ends with a variable to be assigned to. The control sequence \setbaselineskip is saved for execution after the assignment to \thefontsize.

Examples of  $\arrange TEX$  are the  $\arrange$ 

## 12.3.4 \aftergroup

Several tokens can be saved for insertion after the current group with an  $\verb| aftergroup| \langle token \rangle|$ 

command. The tokens are inserted after the group in the sequence the \aftergroup commands were given in. The group can be delimited either by implicit or explicit braces, or by \begingroup and \endgroup.

```
例子:
{\aftergroup\a \aftergroup\b}
is equivalent to
\a \b
```

This command has many applications. One can be found in the \textvcenter macro on page 149; another one is provided by the footnote mechanism of plain TeX.

The footnote command of plain TEX has the layout

```
\footnote \langle footnote \ symbol \rangle \{\langle footnote \ text \rangle\}
```

which looks like a macro with two arguments. However, it is undesirable to scoop up the footnote text, since this precludes for instance category code changes in the footnote.

What happens in the plain footnote macro is (globally) the following.

• The \footnote command opens an insert,

```
\def\footnote#1{ ...#1... %treat the footnote sign
\insert\footins\bgroup
```

• In the insert box a group is opened, and an \aftergroup command is given to close off the insert properly:

```
\bgroup\aftergroup\@foot
```

This command is meant to wind up after the closing brace of the text that the user typed to end the footnote text; the opening brace of the user's footnote text must be removed by

```
\let\next=}%end of definition \footnote
```

which assigns the next token, the brace, to \next.

- The footnote text is set as ordinary text in this insert box.
- After the footnote the command \@foot defined by

```
\def\@foot{\strut\egroup}
```

will be executed.

## 12.4 Preventing expansion

Sometimes it is necessary to prevent expansion in a place where it normally occurs. For this purpose the control sequences \string and \noexpand are available.

The use of \string is rather limited, since it converts a control sequence token into a string of characters, with the value of \escapechar used for the character of category code 0. It is eminently suitable for use in a \write, in order to output a control sequence name (see also Chapter 30); for another application see the explanation of \newif in Chapter 13.

All characters resulting from \string have category code 12, 'other', except for space characters; they receive code 10. See also Chapter 3.

#### 12.4.1 \noexpand

The \noexpand command is expandable, and its expansion is the following token. The meaning of that token is made temporarily equal to \relax, so that it cannot be expanded further.

For \noexpand the most important application is probably in \edef commands (but in write statements it can often replace \string). Consider as an example

```
\edef\one{\def\noexpand\two{\the\prevdepth}}
```

Without the \noexpand, TEX would try to expand \two, thus giving an 'undefined control sequence' error.

A (rather pointless) illustration of the fact that \noexpand makes the following token effectively into a \relax is

```
\def\a{b}
\noexpand\a
```

This will not produce any output, because the effect of the \noexpand is to make the control sequence \a temporarily equal to \relax.

## 12.4.2 \noexpand and active characters

The combination  $\noexpand(token)$  is equivalent to  $\rowniant relax$ , even if the token is an active character. Thus,

```
\csname\noexpand~\endcsname
```

will not be the same as \char`\~. Instead it will give an error message, because unexpandable commands —— such as \relax —— are not allowed to appear in between \csname and \endcsname. The solution is to use \string instead; see page 148 for an example.

In another context, however, the sequence \noexpand(active character) is equivalent to the character, but in unexpandable form. This is when the condi-

tionals \if and \ifcat are used (for an explanation of these, see Chapter 13). Compare

```
\if\noexpand~\relax % is false
```

where the character code of the tilde is tested, with

```
\def\a{ ... } \if\noexpand\a\relax % is true
```

where two control sequences are tested.

## 12.5 \relax

The control sequence \relax cannot be expanded, but when it is executed nothing happens.

This statement sounds a bit paradoxical, so consider an example. Let counters

```
\newcount\MyCount
\newcount\MyOtherCount \MyOtherCount=2
```

be given. In the assignment

```
\MyCount=1\number\MyOtherCount3\relax4
```

the command \number is expandable, and \relax is not. When TeX constructs the number that is to be assigned it will expand all commands, either until a non-digit is found, or until an unexpandable command is encountered. Thus it reads the 1; it expands the sequence \number\MyOtherCount, which gives 2; it reads the 3; it sees the \relax, and as this is unexpandable it halts. The number to be assigned is then 123, and the whole call has been expanded into

```
\MyCount=123\relax4
```

Since the \relax token has no effect when it is executed, the result of this line is that 123 is assigned to \MyCount, and the digit 4 is printed.

Another example of how \relax can be used to indicate the end of a command is

```
\everypar{\hskip Ocm plus 1fil }
\indent Later that day, ...
```

This will be misunderstood: TFX will see

```
\hskip Ocm plus 1fil L
```

and fil L is a valid, if bizarre, way of writing fill (see Chapter 36). One remedy is to write

```
\everypar{\hskip 0cm plus 1fil\relax}
```

12.5 \relax 141

#### 12.5.1 \relax and \csname

If a \csname ... \endcsname command forms the name of a previously undefined control sequence, that control sequence is made equal to \relax, and the whole statement is also equivalent to \relax (see also page 124).

However, this assignment of \relax is only local:

```
{\xdef\test{\expandafter\noexpand\csname xx\endcsname}}
\test
```

gives an error message for an undefined control sequence \xx.

Consider as an example the LATEX environments, which are delimited by

```
\begin{...} ... \end{...}
```

The begin and end commands are (in essence) defined as follows:

```
\def
\begin#1{\begingroup\csname#1\endcsname}
\def\end#1{\csname end#1\endcsname \endgroup}
```

Thus, for the list environment the commands \list and \endlist are defined, but any command can be used as an environment name, even if no corresponding \end... has been defined. For instance,

```
\begin{it} ... \end{it}
is equivalent to
  \begingroup\it ... \relax\endgroup
```

See page 114 for the rationale behind using \begingroup and \endgroup instead of \bgroup and \egroup.

## 12.5.2 Preventing expansion with \relax

Because \relax cannot be expanded, a control sequence can be prevented from being expanded (for instance in an \edef or a \write) by making it temporarily equal to \relax:

```
{\let\somemacro=\relax \write\outfile{\somemacro}}
```

will write the string '\somemacro' to an output file. It would write the expansion of the macro \somemacro (or give an error message if the macro is undefined) if the \let statement had been omitted.

## 12.5.3 T<sub>F</sub>X inserts a \relax

 $T_EX$  itself inserts \relax on some occasions. For instance, \relax is inserted if  $T_EX$  encounters an \or, \else, or \fi while still determining the extent of the test.

```
例子:
    \ifvoid1\else ... \fi

is changed into
    \ifvoid1\relax \else ...\fi

internally.

Similarly, if one of the tests \if, \ifcat is given only one comparand, as in \if1\else ...

a \relax token is inserted. Thus this test is equivalent to \iff1\relax\else ...
```

Another place where \relax is used is the following. While a control sequence is being defined in a \shorthand definition\ —— that is, a \registerdef\ or \chardef or \mathchardef —— its meaning is temporarily made equal to \relax. This makes it possible to write \chardef\foo=123\foo.

#### 12.5.4 The value of non-macros; \the

Expansion is a precisely defined activity in TeX. The full list of tokens that can be expanded was given above. Other tokens than those in the above list may have an 'expansion' in an informal sense. For instance one may wish to 'expand' the \parindent into its value, say 20pt.

Converting the value of (among others) an  $\langle integer\ parameter \rangle$ , a  $\langle glue\ parameter \rangle$ ,  $\langle dimen\ parameter \rangle$  or a  $\langle token\ parameter \rangle$  into a string of character tokens is done by the expansion processor. The command \the is expanded whenever expansion is not inhibited, and it takes the value of various sorts of parameters. Its result (in most cases) is a string of tokens of category 12, except that spaces have category code 10.

Here is the list of everything that can be prefixed with \the.

⟨parameter⟩ or ⟨register⟩ If the parameter or register is of type integer, glue, dimen or muglue, its value is given as a string of character tokens; if it is of type token list (for instance \everypar or \toks5), the result is a string of tokens. Box registers are excluded here.

12.6 Examples 143

```
\langle \mathbf{codename} \rangle \langle \mathbf{8\text{-}bit\ number} \rangle See page 46.
```

⟨special register⟩ The integer registers \prevgraf, \deadcycles, \insertpenalties
\inputlineno, \badness, \parshape, \spacefactor (only in horizontal mode),
or \prevdepth (only in vertical mode). The dimension registers \pagetotal,
\pagegoal, \pagestretch,
\pagefilstretch, \pagefillstretch, \pagefillstretch, \pageshrink, or
\pagedepth.

Font properties:  $\fontdimen\langle parameter number \rangle \langle font \rangle$ ,  $\shortdimen\langle font \rangle$ ,  $\hy-phenchar\langle font \rangle$ .

Last quantities: \lastpenalty, \lastkern, \lastskip.

⟨defined character⟩ Any control sequence defined by \chardef or \mathchardef;
the result is the decimal value.

In some cases \the can give a control sequence token or list of such tokens.

**⟨font⟩** The result is the control sequence that stands for the font.

**(token variable)** Token list registers and ⟨token parameter⟩s can be prefixed with \the; the result is their contents.

Let us consider an example of the use of \the. If in a file that is to be \input the category code of a character, say the at sign, is changed, one could write

```
\edef\restorecat{\catcode`@=\the\catcode`@}
```

and call  $\$  at the end of the file. If the category code was 11,  $\$  is defined equivalent to

```
\catcode \@=11
```

See page 148 for more elaborate macros for saving and restoring catcodes.

# 12.6 Examples

## 12.6.1 Expanding after

The most obvious use of \expandafter is to reach over a control sequence:

```
\def\stepcounter
    #1{\expandafter\advance\csname
         #1:counter\endcsname 1\relax}
\stepcounter{foo}
```

Here the \expandafter lets the \csname command form the control sequence \foo:counter; after \expandafter is finished the statement has reduced to

```
\advance\foo:counter 1\relax
```

It is possible to reach over tokens other than control sequences: in

```
\uppercase\expandafter{\romannumeral \year}
```

it expands \romannumeral on the other side of the opening brace.

You can expand after two control sequences:

If you think of \expandafter as reversing the evaluation order of *two* control sequences, you can reverse *three* by

```
\expandafter\expandafter\expandafter\a\expandafter\b\c
```

which reaches across the three control sequences

```
\expandafter \a \b
```

to expand \c first.

There is even an unexpected use for \expandafter in conditionals; with

```
\def\bold#1{{\bf #1}}
```

the sequence

```
\ifnum1>0 \bold \fi {word}
```

will not give a boldface 'word', but

```
\ifnum1>0 \expandafter\bold \fi {word}
```

will. The \expandafter lets TeX see the \fi and remove it before it tackles the macro \bold (see also page 160).

#### 12.6.2 Defining inside an \edef

There is one  $T_EX$  command that is executed instead of expanded that is worth pointing out explicitly: the primitive command \def (and all other  $\langle def \rangle$  commands) is not expanded.

Thus the call

```
\edef\next{\def\thing{text}}
```

will give an 'undefined control sequence' for  $\land$ thing, even though after  $\land$ def expansion is ordinarily inhibited (see page 134). After

```
\edef\next{\def\noexpand\thing{text}}
```

the 'meaning' of \next will be

```
macro: \def \thing {text}
```

12.6 Examples 145

#### The definition

```
\edef\next{\def\noexpand\thing{text}\thing}
```

will again give an 'undefined control sequence' for \thing (this time on its second occurrence), as it will only be defined when \next is called, not when \next is defined.

## 12.6.3 Expansion and \write

The argument token list of \write is treated in much the same way as the replacement text of an \edef; that is, expandable control sequences and active characters are completely expanded. Unexpandable control sequences are treated by \write as if they are prefixed by \string.

Because of the expansion performed by \write, some care has to be taken when outputting control sequences with \write. Even more complications arise from the fact that the expansion of the argument of \write is only performed when it is shipped out. Here follows a worked-out example.

Suppose \somecs is a macro, and you want to write the string

\def\othercs{the expansion of \somecs}

to a file.

The first attempt is

```
\write\myfile{\def\othercs{\somecs}}
```

This gives an error 'undefined control sequence' for \othercs, because the \write will try to expand that token. Note that the \somecs is also expanded, so that part is right.

The next attempt is

```
\write\myfile{\def\noexpand\othercs{\somecs}}
```

This is almost right, but not quite. The statement written is

\def\othercs{expansion of \somecs}

which looks right.

However, writes — and the expansion of their argument — are not executed on the spot, but saved until the part of the page on which they occur is shipped out (see Chapter 30). So, in the meantime, the value of \somecs may have changed. In other words, the value written may not be the value at the time the \write command was given. Somehow, therefore, the current expansion must be inserted in the write command.

The following is an attempt at repair:

```
\edef\act{\write\myfile{\def\noexpand\othercs{\somecs}}}
\act
```

Now the write command will be

```
\write\myfile{\def\othercs{value of \somecs}}
```

The \noexpand prevented the \edef from expanding the \othercs, but after the definition it has disappeared, so that execution of the write will again give an undefined control sequence. The final solution is

In this case the write command caused by the expansion of \act will be

```
\write\myfile{\def\noexpand\othercs{current value of \somecs}
```

and the string actually written is

```
\def\othercs{current value of \somecs}
```

This mechanism is the basis for cross-referencing macros in several macro packages.

#### 12.6.4 Controlled expansion inside an \edef

Sometimes you may need an \edef to evaluate current conditions, but you want to expand something in the replacement text only to a certain level. Suppose that

```
\def\a{\b} \def\b{c} \def\d{\e} \def\e{\f}
```

is given, and you want to define  $\g$  as  $\a$  expanded one step, followed by  $\d$  fully expanded. The following works:

```
\edef\g{\expandafter\noexpand\a \d}
```

Explanation: the \expandafter reaches over the \noexpand to expand \a one step, after which the sequence \noexpand\b is left.

This trick comes in handy when you need to construct a control sequence with \csname inside an \edef. The following sequence inside an \edef

```
\expandafter\noexpand\csname name\endcsname
```

will expand exactly to \name, but not further. As an example, suppose

```
\def\condition{true}
```

has been given, then

12.6 Examples 147

will let \setmycondition expand to \mytesttrue.

### 12.6.5 Multiple prevention of expansion

As was pointed out above, prefixing a command with \noexpand prevents its expansion in commands such as \edef and \write. However, if a sequence of tokens passes through more than one expanding command stronger measures are needed.

The following trick can be used: in order to protect a command against expansion it can be prefixed with \protect. During the stages of processing where expansion is not desired the definition of \protect is

```
\def\protect{\noexpand\protect\noexpand}
```

Later on, when the command is actually needed, \protect is defined as

```
\def\protect{}
```

Why does this work? The expansion of

\protect\somecs

is at first

```
\noexpand\protect\noexpand\somecs
```

Inside an \edef this sequence is expanded further, and the subsequent expansion is

```
\protect\somecs
```

That is, the expansion is equal to the original sequence.

#### 12.6.6 More examples with \relax

Above, a first example was given in which  $\$  served to prevent  $\$ TeX from scanning too far. Here are some more examples, using  $\$  to bound numbers.

#### After

```
\countdef\pageno=0 \pageno=1
\def\Par{\par\penalty200}
```

#### the sequence

```
\Par\number\pageno
```

is misunderstood as

```
\par\penalty2001
```

In this case it is sufficient to define

```
\def\Par{\par\penalty200 }
```

as an (optional space) is allowed to follow a number.

Sometimes, however, such a simple escape is not possible. Consider the definition

```
\def\ifequal#1#2{\ifnum#1=#2 1\else 0\fi}
```

The question is whether the space after #2 is necessary, superfluous, or simply wrong. Calls such as \ifequal{27}{28} that compare two numbers (denotations) will correctly give 1 or 0, and the space is necessary to prevent misinterpretation.

However, \ifequal\somecounter\othercounter will give 1 if the counters are equal; in this case the space could have been dispensed with. The solution that works in both cases is

```
\def\ifequal #1#2{\ifnum#1=#2\relax 1\else 0\fi}
```

Note that \relax is not expanded, so

```
\edef\foo{1\ifequal\counta\countb}
```

will define \foo as either 1\relax1 or 10.

#### 12.6.7 Example: category code saving and restoring

In many applications it is necessary to change the category code of a certain character during the execution of some piece of code. If the writer of that code is also the writer of the surrounding code, s/he can simply change the category code back and forth. However, if the surrounding code is by another author, the value of the category code will have to be stored and restored.

Thus one would like to write

```
\storecat@
... some code ...
\restorecat@
```

or maybe

```
\storecat\%
```

for characters that are possibly a comment character (or ignored or invalid). The basic idea is to define

```
\def\storecat#1{%
   \expandafter\edef\csname restorecat#1\endcsname
```

12.6 Examples 149

```
{\catcode`#1=\the\catcode`#1}}
```

so that, for instance, \storecat\$ will define the single control sequence '\restorecat\$' (one control sequence) as

```
\catcode`$=3
```

The macro \restorecat can then be implemented as

```
\def\restorecat#1{%
   \csname restorecat#1\endcsname}
```

Unfortunately, things are not so simple.

The problems occur with active characters, because these are expanded inside the \csname . . . \endcsname pairs. One might be tempted to write \noexpand#1 everywhere, but this is wrong. As was explained above, this is essentially equal to \relax, which is unexpandable, and will therefore lead to an error message when it appears between \csname and \endcsname. The proper solution is then to use \string#1. For the case where the argument was given as a control symbol (for example \%), the escape character has to be switched off for a while.

Here are the complete macros. The \storecat macro gives its argument a default category code of 12.

# 12.6.8 Combining \aftergroup and boxes

At times, one wants to construct a box and immediately after it has been constructed to do something with it. The \aftergroup command can be used to put both the commands creating the box, and the ones handling it, in one macro.

As an example, here is a macro \textvcenter which defines a variant of the \vcenter box (see page 229) that can be used outside math mode.

```
\def\textvcenter
{\hbox \bgroup$\everyvbox{\everyvbox{}%
  \aftergroup$\aftergroup\egroup}\vcenter}
```

The idea is that the macro inserts \hbox {\$, and that the matching \$} gets inserted by the \aftergroup commands. In order to get the \aftergroup commands inside the box, an \everyvbox command is used.

This macro can even be used with a  $\langle box\ specification \rangle$  (see page 55), for example

```
\textvcenter spread 8pt{\hbox{a}\vfil\hbox{b}}
```

and because it is really just an \hbox, it can also be used in a \setbox assignment.

## 12.6.9 More expansion

There is a particular charm to macros that work purely by expansion. See the articles by [?], [?], and [?].

# 第 13 章 Conditionals

Conditionals are an indispensible tool for powerful macros. TEX has a large repertoire of conditionals for querying such things as category codes or processing modes. This chapter gives an inventory of the various conditionals, and it treats the evaluation of conditionals in detail.

\if Test equality of character codes.

\ifcat Test equality of category codes.

\ifx Test equality of macro expansion, or equality of character code and category code.

\ifcase Enumerated case statement.

\ifnum Test relations between numbers.

\ifodd Test whether a number is odd.

\ifhmode Test whether the current mode is (possibly restricted) horizontal mode.

\ifvmode Test whether the current mode is (possibly internal) vertical mode.

\ifmmode Test whether the current mode is (possibly display) math mode.

\ifinner Test whether the current mode is an internal mode.

\ifdim Compare two dimensions.

\ifvoid Test whether a box register is empty.

\ifhbox Test whether a box register contains a horizontal box.

\ifvbox Test whether a box register contains a vertical box.

\ifeof Test for end of input stream or non-existence of file.

\iftrue A test that is always true.

\iffalse A test that is always false.

\fi Closing delimiter for all conditionals.

\else Select \( \)false text\\ of a conditional or default case of \\ if case.

\or Separator for entries of an \ifcase.

\newif Create a new test.

# 13.1 The shape of conditionals

Conditionals in TFX have one of the following two forms

where the  $\langle \text{test tokens} \rangle$  are zero or more tokens, depending on the particular conditional; the  $\langle \text{true text} \rangle$  is a series of tokens to be processed if the test turns out true, and the  $\langle \text{false text} \rangle$  is a series of tokens to be processed if the test turns out false. Both the  $\langle \text{true text} \rangle$  and the  $\langle \text{false text} \rangle$  can be empty.

The exact process of how TeX expands conditionals is treated below.

# 13.2 Character and control sequence tests

Three tests exist for testing character tokens and control sequence tokens.

#### 13.2.1 \if

Equality of character codes can be tested by

```
\inf \langle token_1 \rangle \langle token_2 \rangle
```

In order to allow the tokens to be control sequences, TeX assigns character code 256 to control sequences, the lowest positive number that is not the character code of a character token (remember that the legal character codes are 0–255).

Thus all control sequences are equal as far as \if is concerned, and they are unequal to all character tokens. As an example, this fact can be used to define

```
\def\ifIsControlSequence#1{\if\noexpand#1\relax}
```

which tests whether a token is a control sequence token instead of a character token (its result is unpredictable if the argument is a  $\{\ldots\}$  group).

After \if TEX will expand until two unexpandable tokens are obtained, so it is necessary to prefix expandable control sequences and active characters with

\noexpand when testing them with \if.

```
例子:After
\catcode`\b=13 \catcode`\c=13 \def b{a} \def c{a} \let\d=a
we find that
\if bc is true, because both b and c expand to a,
\if\noexpand b\noexpand c is false, and
\if b\d is true because b expands to the character a, and \d is an implicit character token a.
```

#### 13.2.2 \ifcat

The \if test ignores category codes; these can be tested by

```
\ \left\langle token_{1}\right\rangle \left\langle token_{2}\right\rangle
```

This test is a lot like \if: TeX expands after it until unexpandable tokens remain. For this test control sequences are considered to have category code 16 (ordinarily, category codes are in the range 0–15), which makes them all equal to each other, and different from all character tokens.

#### 13.2.3 \ifx

Equality of tokens is tested in a stronger sense than the above by  $\label{eq:condition} $$ \ifx\langle token_1\rangle\langle token_2\rangle $$$ 

- Character tokens are equal for \ifx if they have the same character code and category code.
- Control sequence tokens are equal if they represent the same TEX primitive, or have been similarly defined by \font, \countdef, or some such. For example,

```
\let\boxhor=\hbox \ifx\boxhor\hbox %is true
\font\a=cmr10 \font\b=cmr10 \ifx\a\b %is true
```

Control sequences are also equal if they are macros with the same parameter text and replacement text, and the same status with respect to \outer and \long. For example,

```
\def\a{z} \def\b{z} \def\c1{z} \def\d{\a}
\ifx\a\b %is true
\ifx\a\c %is false
\ifx\a\d %is false
```

Tokens following this test are not expanded.

By way of example of the use of  $\in T_F X$  is as follows:

```
\def\ifEqString#1#2{\def\testa{#1}\def\testb{#2}%
\ifx\testa\testb}
```

The two strings are used as the replacement text of two macros, and equality of these macros is tested. This is about as efficient as string testing can get: TeX will traverse the definition texts of the macros \testa and \testb, which has precisely the right effect.

As another example, one can test whether a control sequence is defined by

```
\def\ifUnDefinedCs#1{\expandafter
   \ifx\csname#1\endcsname\relax}
\ifUnDefinedCs{parindent} %is not true
\ifUnDefinedCs{undefined} %is (one hopes) true
```

This uses the fact that a \csname...\endcsname command is equivalent to \relax if the control sequence has not been defined before. Unfortunately, this test also turns out true if a control sequence has been \let to \relax.

## 13.3 Mode tests

In order to determine in which of the six modes (see Chapter 6) TEX is currently operating, the tests \ifhmode, \ifhmode, \ifhmode, and \ifinner are available.

- \ifhmode is true if T<sub>F</sub>X is in horizontal mode or restricted horizontal mode.
- \ifvmode is true if TEX is in vertical mode or internal vertical mode.
- \ifmmode is true if TFX is in math mode or display math mode.

The \ifinner test is true if TEX is in any of the three internal modes: restricted horizontal mode, internal vertical mode, and non-display math mode.

See also chapter 6.

## 13.4 Numerical tests

```
Numerical relations between \langle number \rangle s can be tested with
```

```
\  \langle number_1 \rangle \langle relation \rangle \langle number_2 \rangle
```

where the relation is a character  $\langle , = , \text{ or } \rangle$ , of category 12.

13.5 Other tests 155

Quantities such as glue can be used as a number here through the conversion to scaled points, and  $T_E X$  will expand in order to arrive at the two  $\langle number \rangle s$ .

Testing for odd or even numbers can be done with \ifodd: the test

```
\ifodd(number)
```

is true if the (number) is odd.

## 13.5 Other tests

## 13.5.1 Dimension testing

Relations between  $\langle dimen \rangle$  values (Chapter 8) can be tested with  $\land$  using the same three relations as in  $\land$  if num.

#### 13.5.2 Box tests

Contents of box registers (Chapter 5) can be tested with

```
\ifvoid(8-bit number)
```

which is true if the register contains no box,

```
\ifhbox \langle 8-bit number \rangle
```

which is true if the register contains a horizontal box, and

```
\ifvbox(8-bit number)
```

which is true if the register contains a vertical box.

## 13.5.3 I/O tests

The status of input streams (Chapter 30) can be tested with the end-of-file test  $\ifootnote{1}{ifeof\langle number\rangle}$ , which is only false if the number is in the range 0–15, and the corresponding stream is open and not fully read. In particular, this test is true if the file name connected to this stream (through  $\ofontnote{1}{openin}$ ) does not correspond to an existing file. See the example on page 281.

#### 13.5.4 Case statement

The  $T_E X$  case statement is called  $\ightharpoonup$  its syntax is

```
\langle case_0 \rangle \cdot ... \langle case_n \rangle \cdot ...
```

where for n cases there are n-1 \or control sequences. Each of the  $\langle case_i \rangle$  parts can be empty, and the  $\langle case_i \rangle$  part is optional.

## 13.5.5 Special tests

The tests \iftrue and \iffalse are always true and false respectively. They are mainly useful as tools in macros.

For instance, the sequences

```
\iftrue{\else}\fi
```

and

```
\iffalse{\else}\fi
```

yield a left and right brace respectively, but they have balanced braces, so they can be used inside a macro replacement text.

The \newif macro, treated below, provides another use of \iftrue and \iffalse. On page 260 of the TeX book these control sequences are also used in an interesting manner.

# 13.6 The \newif macro

The plain format defines an (outer) macro \newif by which the user can define new conditionals. If the user defines

```
\newif\iffoo
```

TeX defines three new control sequences, \footrue and \foofalse with which the user can set the condition, and \iffoo which tests the 'foo' condition.

The macro call \newif\iffoo expands to

```
\def\footrue{\let\iffoo=\iffalse}
\foofalse
```

The actual definition, especially the part that ensures that the \iffoo indeed starts with \if, is a pretty hack. An explanation follows here. This uses concepts from Chapters 11 and 12.

The macro \newif starts as follows:

```
\outer\def\newif#1{\count@\escapechar \m@ne
```

This saves the current escape character in \count@, and sets the value of \escapechar to -1. The latter action has the effect that no escape character is used in the

output of \string\control sequence\.

An auxiliary macro \if@ is defined by

```
{\uccode`1=`i \uccode`2=`f \uppercase{\gdef\if@12{}}}
```

Since the uppercase command changes only character codes, and not category codes, the macro \if@ now has to be followed by the characters if of category 12. Ordinarily, these characters have category code 11. In effect this macro then eats these two characters, and TFX complains if they are not present.

Next there is a macro \@if defined by

```
\def\@if#1#2{\csname\expandafter\if@\string#1#2\endcsname}
```

which will be called like  $\c \$  and  $\c \$  and  $\c \$  and  $\c \$ .

Let us examine the call \@if\iffoo{true}.

- The \expandafter reaches over the \if@ to expand \string first. The part \string\iffoo expands to iffoo because the escape character is not printed, and all characters have category 12.
- The  $\ightharpoonup$  eats the first two characters  $i_{12}f_{12}$  of this.
- As a result, the final expansion of \@if\iffoo{true} is then

```
\csname footrue\endcsname
```

Now we can treat the relevant parts of \newif itself:

```
\expandafter\expandafter
\edef\@if#1{true}{\let\noexpand#1=\noexpand\iftrue}%
```

The three \expandafter commands may look intimidating, so let us take one step at a time.

• One \expandafter is necessary to reach over the \edef, such that \@if will expand:

```
\expandafter\edef\@if\iffoo{true}
gives
\edef\csname footrue\endcsname
```

• Then another \expandafter is necessary to activate the \csname:

```
\expandafter \expandafter \expandafter \edef \@if ...
% new old new
```

• This makes the final expansion

```
\edef\footrue{\let\noexpand\iffoo=\noexpand\iftrue}
```

After this follows a similar statement for the false case:

```
\expandafter\expandafter \expandafter \edef\@if#1{false}{\let\noexpand#1=\noexpand\iffalse}%
```

The conditional starts out false, and the escape character has to be reset:

\@if#1{false}\escapechar\count@}

#### 13.7 Evaluation of conditionals

TEX's conditionals behave differently from those in ordinary programming languages. In many instances one may not notice the difference, but in certain contexts it is important to know precisely the *evaluation of conditionals* proceeds.

When TEX evaluates a conditional, it first determines what is to be tested. This in itself may involve some expansion; as we saw in the previous chapter, only after an \ifx test does TEX not expand. After all other tests TEX will expand tokens until the extent of the test and the tokens to be tested have been determined. On the basis of the outcome of this test the  $\langle \text{true text} \rangle$  and the  $\langle \text{false text} \rangle$  are either expanded or skipped.

For the processing of the parts of the conditional let us consider some cases separately.

• \if... \fi and the result of the test is false. After the test TeX will start skipping material without expansion, without counting braces, but balancing nested conditionals, until a \fi token is encountered. If the \fi is not found an error message results at the end of the file:

```
Incomplete \if...; all text was ignored after line ...
```

where the line number indicated is that of the line where TEX started skipping, that is, where the conditional occurred.

• \if... \else ... \fi and the result of the test is false. Any material in between the condition and the \else is skipped without expansion, without counting braces, but balancing nested conditionals.

The \fi token can be the result of expansion; if it never turns up TeX will give a diagnostic message

```
\end occurred when \if... on line ... was incomplete
```

This sort of error is not visible in the output.

This point plus the previous may jointly be described as follows: after a false condition TEX skips until an \else or \fi is found; any material in between \else and \fi is processed.

• \if... \fi and the result of the test is true. TEX will start processing the material following the condition. As above, the \fi token may be

13.8 Assorted remarks 159

inserted by expansion of a macro.

• \if... \else ... \fi and the result of the test is true. Any material following the condition is processed until the \else is found; then TEX skips everything until the matching \fi is found.

This point plus the previous may be described as follows: after a true test TEX starts processing material until an \else or \fi is found; if an \else is found TEX skips until it finds the matching \fi.

## 13.8 Assorted remarks

#### 13.8.1 The test gobbles up tokens

A common mistake is to write the following:

```
\ifnum\x>0\someaction \else\anotheraction \fi
```

which has the effect that the \someaction is expanded, regardless of whether the test succeeds or not. The reason for this is that TeX evaluates the input stream until it is certain that it has found the arguments to be tested. In this case it is perfectly possible for the \someaction to yield a digit, so it is expanded. The remedy is to insert a space or a \relax control sequence after the last digit of the number to be tested.

#### 13.8.2 The test wants to gobble up the \else or \fi

The same mechanism that underlies the phenomenon in the previous point can lead to even more surprising effects if  $T_EX$  bumps into an  $\ensuremath{\mathtt{\fontfamily less}}$ , or  $\ensuremath{\mathtt{\fontfamily figure}}$  while still busy determining the extent of the test itself.

Recall that \pageno is a synomym for \count0, and consider the following examples:

```
\newcount\nct \nct=1\ifodd\count0\else 2\fi 1
```

The first example will assign either 11 or 121 to \nct, but the second one will assign 1 or 121. The explanation is that in cases like the second, where an \else is encountered while the test still has not been delimited, a \relax is inserted. In the case that \count0 is odd the result will thus be \relax, and the example will yield

```
\nct=1\relax2
```

which will assign 1 to \nct, and print 2.

## 13.8.3 Macros and conditionals; the use of \expandafter

Consider the following example:

```
\def\bold#1{{\bf #1}} \def\slant#1{{\sl #1}}
\ifnum1>0 \bold \else \slant \fi {some text} ...
```

This will make not only 'some text', but *all* subsequent text bold. Also, at the end of the job there will be a notice that 'end occurred inside a group at level 1'. Switching on \tracingmacros reveals that the argument of \bold was \else. This means that, after expansion of \bold, the input stream looked like

```
\ifnum1>0 {\bf \else }\fi {some text} rest of the text
```

so the closing brace was skipped as part of the  $\langle false\ text \rangle$ . Effectively, then, the resulting stream is

```
{\bf {some text} rest of the text
```

which is unbalanced.

One solution to this sort of problem would be to write

```
\ifnum1>0 \let\next=\bold \else \let\next=\slant \fi \next
```

but a solution using \expandafter is also possible:

```
\ifnum1>0 \expandafter \bold \else \expandafter \slant \fi
```

This works, because the \expandafter commands let  $T_EX$  determine the boundaries of the  $\langle true\ text \rangle$  and the  $\langle false\ text \rangle$ .

In fact, the second solution may be preferred over the first, since conditionals are handled by the expansion processor, and the \let statements are tackled only by the execution processor; that is, they are not expandable. Thus the second solution will (and the first will not) work, for instance, inside an \edef.

Another example with \expandafter is the sequence

```
\def\get#1\get{ ... }
  \expandafter \get \ifodd1 \ifodd3 5\fi \fi \get
This gives
  #1<- \ifodd3 5\fi \fi
and
  \expandafter \get \ifodd2 \ifodd3 5\fi\fi \get</pre>
```

gives

13.8 Assorted remarks 161

```
#1<-
```

This illustrates again that the result of evaluating a conditional is not the final expansion, but the start of the expansion of the  $\langle true\ text \rangle$  or  $\langle false\ text \rangle$ , depending on the outcome of the test.

A detail should be noted: with  $\ensuremath{\mathtt{expandafter}}$  it is possible that the  $\ensuremath{\mathtt{else}}$  is encountered before the  $\ensuremath{\mathtt{true}}$  text $\ensuremath{\mathtt{expandafter}}$  has been expanded completely. This raises the question as to the exact timing of expansion and skipping. In the example

```
\def\hello{\message{Hello!}}
\ifnum1>0 \expandafter \hello \else \message{goodbye} \bye
```

the error message caused by the missing \fi is given without \hello ever having been expanded. The conclusion must be that the  $\langle false\ text \rangle$  is skipped as soon as it has been located, even if this is at a time when the  $\langle true\ text \rangle$  has not been expanded completely.

#### 13.8.4 Incorrect matching

TEX's matching of \if, \else, and \fi is easily upset. For instance, the TEX book warns you that you should not say

```
\let\ifabc=\iftrue
```

inside a conditional, because if this text is skipped TEX sees at least one \if to be matched.

The reason for this is that when TEX is skipping it recognizes all \if..., \or, \else, and \fi tokens, and everything that has been declared a synonym of such a token by \let. In \let\ifabc=\iftrue TEX will therefore at least see the \iftrue as the opening of a conditional, and, if the current meaning of \ifabc was for instance \iffalse, it will also be considered as the opening of a conditional statement.

As another example, if

```
\csname if\sometest\endcsname \someaction \fi
```

is skipped as part of conditional text, the \fi will unintentionally close the outer conditional.

It does not help to enclose such potentially dangerous constructs inside a group, because grouping is independent of conditional structure. Burying such commands inside macros is the safest approach.

Sometimes another solution is possible, however. The  $\loop$  macro of plain  $T_FX$  (see page 127) is used as

```
\loop ... \if ... \repeat
```

where the \repeat is not an actually executable command, but is merely a delimiter:

```
\def\loop#1\repeat{ ... }
```

Therefore, by declaring

```
\let\repeat\fi
```

the \repeat balances the \if... that terminates the loop, and it becomes possible to have loops in skipped conditional text.

## 13.8.5 Conditionals and grouping

It has already been mentioned above that group nesting in TEX is independent of conditional nesting. The reason for this is that conditionals are handled by the expansion part of TEX; in that stage braces are just unexpandable tokens that require no special treatment. Grouping is only performed in the later stage of execution processing.

An example of this independence is now given. One may write a macro that yields part of a conditional:

```
\def\elsepart{\else \dosomething \fi}
```

The other way around, the following macros yield a left brace and a right brace respectively:

```
\def\leftbrace{\iftrue{\else}\fi}
\def\rightbrace{\iffalse{\else}\fi}
```

Note that braces in these definitions are properly nested.

#### 13.8.6 A trick

In some contexts it may be hard to get rid of \else or \fi tokens in a proper manner. The above approach with \expandafter works only if there is a limited number of tokens involved. In other cases the following trick may provide a way out:

```
\def\hop#1\fi{fi #1}
```

Using this as

```
\if... \hop \langle lots of tokens \\fi
```

will place the tokens outside the conditional. This is for instance used in [?].

As a further example of this sort of trick, consider the problem (suggested to

13.8 Assorted remarks 163

me and solved by Alan Jeffrey) of implementing a conditional \ifLessThan#1#2#3#4 such that the arguments corresponding to #3 or #4 result, depending on whether #1 is less than #2 or not.

The problem here is how to get rid of the \else and the \fi. The —— or at least, one —— solution is to scoop them up as delimiters for macros:

Note that \ifLessThan has only two parameters (the things to be tested); however, its result is a macro that chooses between the next two arguments.

#### 13.8.7 More examples of expansion in conditionals

Above, the macro \ifEqString was given that compares two strings:

```
\def\ifEqString#1#2%
{\def\csa{#1}\def\csb{#2}\ifx\csa\csb }
```

However, this macro relies on \def, which is not an expandable command. If we need a string tester that will work, for instance, inside an \edef, we need some more ingenuity (this solution was taken from [?]). The basic principle of this solution is to compare the strings one character at a time. Macro delimiting by \fi is used; this was explained above.

First of all, the \iffEqString call is replaced by a sequence \iffAllChars ...\Are ...\TheSa and both strings are delimited by a dollar sign, which is not supposed to appear in the strings themselves.

```
\def\ifEqString
#1#2f\ifAllChars#1$\Are#2$\TheSame}
```

The test for equality of characters first determines whether either string has ended. If both have ended, the original strings were equal; if only one has ended, they were of unequal length, hence unequal. If neither string has ended, we test whether the first characters are equal, and if so, we make a recursive call to test the remainder of the string.

The \say macro is supposed to give \iftrue for \say{true} and \iffalse for

\say{false}. Observing that all calls to this macro occur two conditionals deep, we use the 'hop' trick explained above as follows.

```
\def\say#1#2\fi\fi
{\fi\fi\csname if#1\endcsname}
```

Similar to the above example, let us write a macro that will test lexicographic ('dictionary') precedence of two strings:

```
\let\ex=\expandafter
\def\ifbefore
                      #1#2{\ifallchars#1$\are#2$\before}
\def\ifallchars#1#2\are#3#4\before
                 {\if#1$\say{true\ex}\else
                             \if#3$\say{false\ex\ex\ex}\else
                                  \ifnum\#1>\#3 \say{false%
                                                   \ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath{\ensuremath}\amb}\amb}\amb}}}}}}}}}}}}}}
                                        \ifnum`#1<`#3 \say{true%
                                                   \ex\ex\ex\ex\ex\ex
                                                   \ex\ex\ex\ex\ex\ex\ex\ex}\else
                                        \ifrest#2\before#4\fi\fi\fi\fi}
\def\ifrest#1\before#2\fi\fi\fi
                 {\fi\fi\fi\fi
                       \ifallchars#1\are#2\before}
\def\say#1{\csname if#1\endcsname}
```

In this macro a slightly different implementation of \say is used.

Simplified, a call to \ifbefore will eventually lead to a situation that looks (in the 'true' case) like

```
\ifbefore{...}{...}
    \if... %% some comparison that turns out true
    \csname iftrue\expandafter\endcsname
    \else ... \fi
    ... %% commands for the `before' case
\else
    ... %% commands for the `not-before' case
\fi
```

When the comparison has turned out true,  $T_EX$  will start processing the  $\langle true text \rangle$ , and make a mental note to remove any  $\langle else \dots \rangle$  fi part once an  $\langle else token is seen$ . Thus, the sequence

\csname iftrue\endcsname

Calls to \say occur inside nested conditionals, so the number of \expandafter

13.8 Assorted remarks 165

commands necessary may be larger than 1: for level two it is 3, for level three it is 7, and for level 4 it is 15. Slightly more compact implementations of this macro do exist.

# 第 14 章 Token Lists

TEX has only one type of data structure: the *token list* There are token list registers that are available to the user, and TEX has some special token lists: the \every... variables, \errhelp, and \output.

\toks Prefix for a token list register.

\toksdef Define a control sequence to be a synonym for a \toks register.

\newtoks Macro that allocates a token list register.

### 14.1 Token lists

Token lists are the only type of data structure that TEX knows. They can contain character tokens and control sequence tokens. Spaces in a token list are significant. The only operations on token lists are assignment and unpacking.

TEX has 256 token list registers \toksnnn that can be allocated using the macro \newtoks, or explicitly assigned by \toksdef; see below.

## 14.2 Use of token lists

Token lists are assigned by a  $\langle variable \ assignment \rangle$ , which is in this case takes one of the forms

```
\label{eq:condition} $$ \token variable \equals \equ
```

Here a  $\langle token\ variable \rangle$  is an explicit  $\langle toksnnn\ register,\ something\ that has been defined to such a register by <math>\langle toksdef\ (probably\ hidden\ in\ newtoks),\ or\ one\ of\ the\ special\ \langle token\ parameter \rangle\ lists\ below.\ A\ \langle general\ text \rangle\ has\ an\ explicit\ closing\ brace,\ but\ the\ open\ brace\ can\ be\ implicit.$ 

Examples of token lists are (the first two lines are equivalent):

```
\toks0=\bgroup \a \b cd}
\toks0={\a \b cd}
\toks1=\toks2
```

Unpacking a token list is done by the command  $\text{ the expansion of } \text{ token variable} \ is the sequence of tokens that was in the token list. }$ 

Token lists have a special behaviour in \edef: when prefixed by \the they are unpacked, but the resulting tokens are not evaluated further. Thus

```
\toks0={\a \b} \edef\SomeCs{\the\toks0}
gives
\SomeCs: macro:-> \a \b
```

This is in contrast to what happens ordinarily in an \edef; see page 135.

# 14.3 (token parameter)

There are in  $T_EX$  a number of token lists that are automatically inserted at certain points. These  $\langle token\ parameter \rangle s$  are the following:

\output this token list is inserted whenever TeX decides it has sufficient material for a page, or when the user forces activation by a penalty  $\leq -10\,000$  in vertical mode (see Chapter 28);

\everypar is inserted when TeX switches from external or internal vertical mode to unrestricted horizontal mode (see Chapter 16);

\everymath is inserted after a single math-shift character that starts a formula;

\everydisplay is inserted after a double math-shift character that starts a display formula;

\everypbox is inserted when an \hbox begins (see Chapter 5);

\everyvbox is inserted when a vertical box begins (see Chapter 5);

\everyjob is inserted when a job begins (see Chapter 32);

\everycr is inserted in alignments after \cr or a non-redundant \crcr (see Chapter 25);

\errhelp contains tokens to supplement an \errmessage (see Chapter 35).

A  $\langle token\ parameter \rangle$  behaves the same as an explicit  $\backslash toksnnn\ list,$  or a quantity defined by  $\backslash toksdef.$ 

168 第 14 章 Token Lists

# 14.4 Token list registers

Token lists can be stored in \toks registers:

```
\toks(8-bit number)
```

which is a \(\tau\) token variable\\. Synonyms for token list registers can be made by the \(\tau\) registerdef\(\tau\) command \(\tau\) toksdef in a \(\tau\) shorthand definition\(\tau\):

```
\toksdef\langle control\ sequence\rangle\langle equals\rangle\langle 8-bit\ number\rangle
```

A control sequence defined this way is called a  $\langle toksdef\ token \rangle$ , and this is also a token variable (the remaining third kind of token variable is the  $\langle token\ parameter \rangle$ ).

The plain TEX macro \newtoks uses \toksdef to allocate unused token list registers. This macro is \outer.

# 14.5 Examples

Token lists are probably among the least obvious components of TEX: most TEX users will never find occasion for their use, but format designers and other macro writers can find interesting applications. Following are some examples of the sorts of things that can be done with token lists.

#### 14.5.1 Operations on token lists: stack macros

The number of primitive operations available for token lists is rather limited: assignment and unpacking. However, these are sufficient to implement other operations such as appending.

```
Let us say we have allocated a token register
```

```
\newtoks\list \list={\c}
```

and we want to add tokens to it, using the syntax

```
\Prepend \a \b (to:)\list
```

such that

\showthe\list

gives

```
> \a \b \c .
```

For this the original list has to be unpacked, and the new tokens followed by the old contents have to assigned again to the register. Unpacking can be done 14.5 Examples 169

with \the inside an \edef, so we arrive at the following macro:

```
\def\Prepend#1(to:)#2{\toks0={#1}%
  \edef\act{\noexpand#2={\the\toks0 \the#2}}%
  \act}
```

Note that the tokens that are to be added are first packed into a temporary token list, which is then again unpacked inside the \edef. Including them directly would have led to their expansion.

Next we want to use token lists as a sort of stack: we want a 'pop' operation that removes the first element from the list. Specifically,

```
> \b \c .
```

Here we make creative use of delimited and undelimited parameters. With an \edef we unpack the list, and the auxiliary macro \SplitOff scoops up the elements as one undelimited argument, the first element, and one delimited argument, the rest of the elements.

## 14.5.2 Executing token lists

The \the operation for unpacking token lists was used above only inside an \edef. Used on its own it has the effect of feeding the tokens of the list to TeX's expansion mechanism. If the tokens have been added to the list in a uniform syntax, this gives rise to some interesting possibilities.

Imagine that we are implementing the bookkeeping of external files for a format. Such external files can be used for table of contents, list of figures, et cetera. If the presence of such objects is under the control of the user, we need some general routines for opening and closing files, and keeping track of what files we have opened at the user's request.

Here only some routines for bookkeeping will be described. Let us say there is a list of auxiliary files, and an auxiliary counter:

```
\newtoks\auxlist \newcount\auxcount
```

First of all there must be an operation to add auxiliary files:

```
\def\NewAuxFile#1{\AddToAuxList{#1}%
   % plus other actions
   }
\def\AddToAuxList#1{\let\\=\relax
   \edef\act{\noexpand\auxlist={\the\auxlist \\{#1}}}%
   \act}
```

This adds the name to the list in a uniform format:

```
\NewAuxFile{toc} \NewAuxFile{lof}
\showthe\auxlist
> \\{toc}\\{lof}.
```

using the control sequence \\ which is left undefined.

Now this control sequence can be used for instance to count the number of elements in the list:

```
\def\ComputeLengthOfAuxList{\auxcount=0
    \def\\##1{\advance\auxcount1\relax}%
    \the\auxlist}
\ComputeLengthOfAuxList \showthe\auxcount
> 2.
```

Another use of this structure is the following: at the end of the job we can now close all auxiliary files at once, by

which gives the output

```
closing file: toc. closing file: lof.
```

# 第 15 章 基线距离

文本行的高度和深度多半不会是相等的。因此 **T<sub>E</sub>X** 添加行间粘连,以保证各行基线有一致的距离。这一章处理行间粘连的计算。

\baselineskip 竖直列中相邻盒子基线距离的'理想值'。Plain TpX 默认为 12pt。

\lineskiplimit 竖直列中相邻盒子的底部和顶部需要保持的距离。Plain TeX 默 认为 Opt。

\lineskip 在相邻盒子的底部和顶部的距离小于 \lineskiplimit 时添加的粘连。 Plain TFX 默认为 1pt。

\prevdepth 上一个被 TpX 添加到竖直列的盒子的深度。

\nointerlineskip 用于阻止一次行间粘连插入的宏。


\offinterlineskip 用于全局地阻止此后所有行间粘连的宏。

\openup 给\baselineskip、\lineskip和\lineskiplimit增加指定的量。

# 15.1 行间粘连

通过插入行间粘连,TeX 试图让竖直列的盒子的基准点保持一定的距离。特别地,它试图让普通文本的各行保持恒定的基线距离。实际上,\baselineskip 是一个 \( \text{glue} \),因此行距是可以伸缩的。然而,它的自然尺寸以及伸长量和收缩量,在各行之间是一致的。

当添加盒子——不管是段落文本行还是显式盒子——到竖直列时,**T<sub>E</sub>X** 通常会添加粘连,使得它与前面盒子深度和当前盒子高度之和等于 \baselineskip。这样能让各行的基准点保持相同的距离。



注意这通常会导致盒子的基线距离超过 \baselineskip。

确切的处理过程如下:

- 如果 \prevdepth 小于或等于 -1000pt,不会添加任何粘连,否则
- TeX 计算出上一个盒子底部和当前盒子顶部的距离: 它用 \baselineskip 减去 \prevdepth(上一个盒子的深度)再减去当前盒子的高度;
- 如果这个距离小于 \lineskiplimit, TeX 添加一个粘连,这个粘连的自然尺寸等于该距离,伸长量和收缩量等于 \baselineskip 的伸长量和收缩量。
- 否则,TeX 改为添加 \lineskip 粘连。
- TeX 将 \prevdepth 设为当前项目的深度。

这里有两个例外情形: 在标尺前后不添加行间粘连, 而 \unvbox 或 \unvcopy 命

15.1 行间粘连 173

令不改变 \prevdepth 值。在标线之后行间粘连是由于 \prevdepth 等于 -1000pt 而被阻止。

上面的处理过程不考虑盒子间另外插入的粘连。因此竖直模式中添加的盒子间 距不会影响从基线距离算出的结果,从而不影响行间粘连的大小。这个规则也适用 于在段落中用 \vadjust 添加的粘连。

```
例子:
```

```
\baselineskip=10pt \lineskiplimit=2pt \lineskip=2pt
   \setbox0=\vbox{\hbox{\vrule depth4pt}}
                   \hbox{\vrule height 3pt}}
    \showbox0
将绘出
   \log 0 =
   \forall x = (10.0+0.0)x0.4
    .\hbox(0.0+4.0)x0.4
    ..\rule(*+4.0)x0.4
    .\glue(\baselineskip) 3.0
    .\hbox(3.0+0.0)x0.4
    ...rule(3.0+*)x0
将盒子的距离减少到 \lineskiplimit 以内,即
   \setbox0\vbox{\hbox{\vrule depth4pt}
                  \hbox{\vrule height 5pt}}
    \showbox0
将给出
   \ln 0 =
   \forall x = (11.0+0.0)x0.4
    .\hbox(0.0+4.0)x0.4
    ..\rule(*+4.0)x0.4
    .\glue(\lineskip) 2.0
    .\hbox(5.0+0.0)x0.4
    ...rule(5.0+*)x0.4
```

其中插入的是 \lineskip 粘连,而不是通常的 \baselineskip 粘连。

Plain TFX 中的默认值为

```
\lineskiplimit=Opt lineskip=1pt
```

因此, 当两个盒子开始碰到时, 它们被拉开一个点的距离。

# 15.2 盒子深度

在确定行间粘连时,\prevdepth 代表竖直列中前一个盒子的深度。\prevdepth 参数只能在竖直模式中使用。

\prevdepth 被设定为添加到竖直列的盒子的深度,但它不受\unvbox或\unvcopy影响。在\hrule之后它被设为-1000pt 以阻止在下个盒子前生成行间粘连。

在竖直列的开头,\prevdepth 被设为 -1000pt,除非在 \halign 和 \noalign 中,此时使用的是外层列表的 \prevdepth 值。在阵列的结尾,阵列末尾行设定的 \prevdepth 的值被送到外层列表中。

为阻止一次行间粘连,只需要修改\prevdepth。

\def\nointerlineskip{\prevdepth=-1000pt}

\offinterlineskip 宏要彻底得多: 它使得所有行间粘连都为零,从调用它的时刻算起,或者,倘若在段落中间使用它,从段落开头处算起。它的定义为

```
\baselineskip=-1000pt \lineskip=0pt \lineskiplimit\maxdimen
```

其中第二行是关键之处:它使得 **T<sub>E</sub>X** 添加的 \lineskip 粘连始终等于零。这样 \baselineskip 的设置将不再重要。

\offinterlineskip 宏在阵列中能派上用场(见第25章)。

通过设置

\lineskiplimit=-\maxdimen

你可以强制  $T_EX$  始终使用 \baselineskip, 而不管是否将导致盒子靠得太近, 或者导致它们重叠。

# 15.3 术语

在铅字排版时代,一个字体的所有字母都印在相同大小的'字身'上。因此排版的每行都有相同的高度和深度,从而基线的距离将有合适的大小。若由于某原因需要增加此距离(见[?]对此问题的讨论),则需要插入一个铅条(strips of lead)。这个额外的距离就称为'leading'(发音同'ledding')。

在照相排版时代,基线距离有时候被称为 'film transport',而 'leading' 这个术语变得模糊,有时也被用于表示基线距离。这种混乱同样出现在 TeX 中:参数 \baselineskip 指定基线距离,但是在追踪输出中(见上面的例子),为保证基线距离等于\baselineskip 而插入的粘连也被称为 \baselineskip。

15.4 补充说明 175

# 15.4 补充说明

一般地,对于超过一页的文档,自始至终保持相同的基线距离比较合适。然而,对于单页文档,你可以添加伸长度到 \baselineskip,这样可以让文本在底部对齐。

若仅仅想增加某两行的距离,你可以使用\vadjust命令。这个命令的参量是竖直素材,它们将被插入到竖直列并放在这个命令所在的行之后。比如这个段落的第二行就包含命令\vadjust{\kern2pt}。

行间距的大小可以在段落中间修改,这是因为在分段为行并添加到主竖直列时才会用到 \baselineskip 的当前值。\lineskip 和 \lineskiplimit 类似。

Plain TeX 宏 \openup 给 \baselineskip \lineskip 和 \lineskiplimit 增加 宏参量所指定的大小。其效果是给行间距增加所指定的大小,无论它是由 \baselineskip 还是由 \lineskip 给出。

# 第 16 章 Paragraph Start

At the start of a paragraph TEX inserts a vertical skip as a separation from the preceding paragraph, and a horizontal skip as an indentation for the current paragraph. This chapter explains the exact sequence of actions, and it discusses how TEX's decisions can be altered.

\indent Switch to horizontal mode and insert a box of width \parindent.

\noindent Switch to horizontal mode with an empty horizontal list.

\parskip Amount of glue added to the surrounding vertical list when a paragraph starts. Plain TeX default: Opt plus 1pt.

\parindent Size of the indentation box added in front of a paragraph. Plain TrX default: 20pt.

\everypar Token list inserted in front of paragraph text;

\leavevmode Macro to switch to horizontal mode if necessary.

# 16.1 When does a paragraph start

TEX starts a paragraph whenever it switches from vertical mode to (unrestricted) horizontal mode. This switch can be effected by one of the commands \indent and \noindent, for example

```
{\bf And now~\dots}
\vskip3pt
\noindent It's~\dots
```

or by any  $\langle horizontal\ command \rangle$ . Horizontal commands include characters, inline formulas, and horizontal skips, but not boxes. Consider the following examples. The character 'I' is a horizontal command:

```
\vskip3pt
It's~\dots
```

A single \$ is a horizontal command:

```
$x$ is supposed~\dots
```

The control sequence \hskip is a horizontal command:

```
\hskip .5\hsize Long indentation~\dots
```

The full list of horizontal commands is given on page 75.

Upon recognizing a horizontal command in vertical mode, TEX will perform an \indent command (and all the actions associated with it; see below), and after that it will reexamine the horizontal command, this time executing it.

# 16.2 What happens when a paragraph starts

The \indent and \noindent commands cause a paragraph to be started. An \indent command can either be placed explicitly by the user or a macro, or it can be inserted by  $T_EX$  when a \horizontal command occurs in vertical mode; a \noindent command can only be placed explicitly.

After either command is encountered, \parskip glue is appended to the surrounding vertical list unless TEX is in internal vertical mode and that list is empty (for example, at the start of a \vbox or \vtop). TEX then switches to unrestricted horizontal mode with an empty horizontal list. In the case of \indent (which may be inserted implicitly) an empty \hbox of width \parindent is placed at the start of the horizontal list; after \noindent no indentation box is inserted.

The contents of the \everypar \langle token parameter \rangle are then inserted into the input (see some applications below). After that, the page builder is exercised (see Chapter 27). Note that this happens in horizontal mode: this is to move the \parskip glue to the current page.

If an \indent command is given while TEX is already in horizontal mode, the indentation box is inserted just the same. This is not very useful.

### 16.3 Assorted remarks

## 16.3.1 Starting a paragraph with a box

An \hbox does not imply horizontal mode, so an attempt to start a paragraph with a box, for instance

```
\hbox to Ocm{\hss$\bullet$\hskip1em}Text ....
```

will make the text following the box wind up one line below the box. It is necessary to switch to horizontal mode explicitly, using for instance \noindent or \leavevmode. The latter is defined using \unbbox, which is a horizontal command.

## 16.3.2 Starting a paragraph with a group

If the first (horizontal command) of a paragraph is enclosed in braces, the \everypar is evaluated inside the group. This may give unexpected results. Consider this example:

```
\everypar={\setbox0=\vbox\bgroup\def\par{\egroup}}
{\bf Start} a paragraph ... \par
```

The \(\lambda\) horizontal command\(\rangle\) starting the paragraph is the character 'S', so when \(\lambda\) everypar has been inserted the input is essentially

```
{\bf \indent\setbox0=\vbox\bgroup
    \def\par{\egroup}Start} a paragraph ... \par
```

which is equivalent to

```
{\bf \setbox0=\vbox{Start} a paragraph ... \par
```

The effect of this is rather different from what was intended. Also, TeX will probably end the job inside a group.

# 16.4 Examples

#### 16.4.1 Stretchable indentation

Considering that  $\parindent$  is a  $\dimen\$ , not a  $\glue\$ , it is not possible to declare

```
\parindent=1cm plus 1fil
```

in order to get a variable indentation at the start of a paragraph. This problem may be solved by putting

```
\everypar={\nobreak\hskip 1cm plus 1fil\relax}
```

The \nobreak serves to prevent (in rare cases) a line break at the stretchable glue.

16.4 Examples 179

# 16.4.2 Suppressing indentation

Inserting {\setbox0=\lastbox} in the horizontal list at the beginning of the paragraph removes the indentation: indentation consists of a box, which is available through \lastbox. Assigning it effectively removes it from the list.

However, this command sequence has to be inserted at a moment when  $T_E X$  has already switched to horizontal mode, so explicit insertion of these commands in front of the first  $\langle horizontal \ command \rangle$  of the paragraph does not work. The moment of insertion of the  $\langle horizontal \ command \rangle$  tokens is a better candidate: specifying

```
\everypar={{\setbox0=\lastbox}}
```

leads to unindented paragraphs, even if \parindent is not zero.

#### 16.4.3 An indentation scheme

The above idea of letting the indentation box be removed by \everypar can be put to use in a systematic approach to indentation, where two conditionals

```
\newif\ifNeedIndent %as a rule
\newif\ifneedindent %special cases
```

control whether paragraphs should indent as a rule, and whether in special cases indentation is needed. This section is taken from [?].

```
We take a fixed \everypar:
```

```
\everypar={\ControlledIndentation}
```

which executes in some cases the macro \RemoveIndentation

```
\def\RemoveIndentation{{\setbox0=\lastbox}}
```

The implementation of \ControlledIndentation is:

In order to regulate indentation for a whole document, the user now once specifies, for instance,

```
\NeedIndenttrue
```

to indicate that, in principle, all paragraphs should indent. Macros such as \section can then prevent indentation in individual cases:

```
\def\section#1{ ... \needindentfalse}
```

## 16.4.4 A paragraph skip scheme

The use of \everypar to control indentation, as was sketched above, can be extended to the paragraph skip.

A visible white space between paragraphs can be created by the \parskip parameter, but, once this parameter has been set to some value, it is difficult to prevent paragraph skip in certain places elegantly. Usually, white space above and below environments and section headings should be specifiable independently of the paragraph skip. This section sketches an approach where \parskip is set to zero directly above and below certain constructs, while the \everypar is used to restore former values. This section is taken from [?].

First of all, here are two tools. The control sequence \csarg will be used only inside other macros; a typical call will look like

```
\csarg\vskip{#1Parskip}
```

Here is the definition:

```
\def\csarg#1#2{\expandafter#1\csname#2\endcsname}
```

Next follows a generalization of \vskip: the macro \vspace will not place its argument if the previous glue item is larger; otherwise it will eliminate the preceding glue, and place its argument.

Now assume that any construct foo with surrounding white space starts and ends with macro calls \StartEnvironment{foo} and \EndEnvironment{foo} respectively. Furthermore, assume that to this environment there correspond three glue registers: the \fooStartskip (glue above the environment), \fooParskip (the paragraph skip inside the environment), and the \fooEndskip (glue below the environment).

For restoring the value of the paragraph skip a conditional and a glue register are needed:

```
\newskip\TempParskip \newif\ifParskipNeedsRestoring
```

The basic sequence for the starting and ending macros for the environments is then

16.4 Examples 181

```
\TempParskip=\parskip\parskip=0cm\relax
\ParskipNeedsRestoringtrue

The implementations can now be given as:
\def\StartEnvironment#1{\csarg\vspace{#1Startskip}}
\begingroup % make changes local
  \csarg\TempParskip{#1Parskip} \parskip=0cm\relax
  \ParskipNeedsRestoringtrue}
\def\EndEnvironment#1{\csarg\vspace{#1Endskip}
  \endgroup % restore global values
  \ifParskipNeedsRestoring
  \else \TempParskip=\parskip \parskip=0cm\relax
  \ParskipNeedsRestoringtrue
\fi}
```

The \EndEnvironment macro needs a little comment: if an environment is used inside another one, and it occurs before the first paragraph in that environment, the value of the paragraph skip for the outer environment has already been saved. Therefore no further actions are required in that case.

Note that both macros start with a vertical skip. This prevents the \begingroup and \endgroup statements from occurring in a paragraph.

We now come to the main point: if necessary, the \everypar will restore the value of the paragraph skip.

```
\everypar={\ControlledIndentation\ControlledParskip}
\def\ControlledParskip
    {\ifParskipNeedsRestoring
        \parskip=\TempParskip \ParskipNeedsRestoringfalse
    \fi}
```

# 第 17 章 Paragraph End

TEX's mechanism for ending a paragraph is ingenious and effective. This chapter explains the mechanism, the role of \par in it, and it gives a number of practical remarks.

\par Finish off a paragraph and go into vertical mode.

```
\endgraf Synonym for \par: \let\endgraf=\par
```

\parfillskip Glue that is placed between the last element of the paragraph and the line end. Plain TpX default: Opt plus 1fil.

# 17.1 The way paragraphs end

A paragraph is terminated by the primitive \par command, which can be explicitly typed by the user (or inserted by a macro expansion):

```
... last words.\par
A new paragraph ...
```

It can be implicitly generated in the input processor of TEX by an empty line (see Chapter 2):

```
... last words.

A new paragraph ...
```

The  $\protect\$  can be inserted because a  $\protect\$  command $\protect\$  occurred in unrestricted horizontal mode:

```
... last words.\vskip6pt
A new paragraph ...
```

Also, a paragraph ends if a closing brace is found in horizontal mode inside \vbox, \insert, or \output.

After the \par command TFX goes into vertical mode and exercises the page

builder (see page 263). If the \par was inserted because a vertical command occurred in horizontal mode, the vertical command is then examined anew. The \par does not insert any vertical glue or penalties itself. A \par command also clears the paragraph shape parameters (see Chapter 18).

## 17.1.1 The \par command and the \par token

It is important to distinguish between the \par token and the primitive \par command that is the initial meaning of that token. The \par token is inserted when the input processor sees an empty line, or when the execution processor finds a \( \text{vertical command} \) in horizontal mode; the \par command is what actually closes off a paragraph. Decoupling the token and the command is an important tool for special effects in paragraphs (see some examples in Chapters 5 and 9).

## 17.1.2 Paragraph filling: \parfillskip

After the last element of the paragraph  $T_{\overline{E}}X$  implicitly inserts the equivalent of

```
\unskip \penalty10000 \hskip\parfillskip
```

The \unskip serves to remove any spurious glue at the paragraph end, such as the space generated by the line end if the \par was inserted by the input processor. For example:

```
end.
```

```
\noindent Begin
```

results in the tokens

```
end. \par Begin
```

With the sequence inserted by the \par this becomes

```
end. \unskip\penalty10000\hskip ...
```

which in turn gives

```
end.\penalty ...
```

The \parfillskip is in plain TEX first-order infinite (Opt plus 1fil), so ending a paragraph with \hfil\bullet\par will give a bullet halfway between the last word and the line end; with \hfill\bullet\par it will be flush right.

### 17.2 Assorted remarks

## 17.2.1 Ending a paragraph and a group at the same time

If a paragraph is set in a group, it may be necessary to ensure that the \par ending the paragraph occurs inside the group. The parameters influencing the typesetting of the paragraph, such as the \leftskip and the \baselineskip, are only looked at when the paragraph is finished. Thus finishing off a paragraph with

```
... last words.}\par
```

causes the values to be used that prevail outside the group, instead of those inside.

Better ways to end the paragraph are

```
... last words.\par}
or
... last words.\medskip}
```

In the second example the vertical command \medskip causes the \par token to be inserted.

## 17.2.2 Ending a paragraph with \hfill\break

The sequence \hfill\break is a way to force a 'newline' inside a paragraph. If you end a paragraph with this, however, you will probably get an Underfull \hbox error. Surprisingly, the underfull box is not the broken line —— after all, that one was filled —— but a completely empty box following it (actually, it does contain the \leftskip and \rightskip).

What happens? The paragraph ends with

```
\hfill\break\par
```

which turns into

```
\hfill\break\unskip\nobreak\hskip\parfillskip
```

The \unskip finds no preceding glue, so the \break is followed by a penalty item and a glue item, both of which disappear after the line break has been chosen at the \break. However, TEX has already decided that there should be an extra line, that is, an \hbox to \hsize. And there is nothing to fill it with, so an underfull box results.

17.2 Assorted remarks 185

## 17.2.3 Ending a paragraph with a rule

See page 111 for paragraphs ending with rule leaders instead of the default \parfillskip white space.

## 17.2.4 No page breaks in between paragraphs

The \par command does not insert any glue in the vertical list, so in the sequence

```
... last words.\par \nobreak \medskip \noindent First words ...
```

no page breaks will occur between the paragraphs. The vertical list generated is

```
\hbox(6.94444+0.0)x ... % last line of paragraph \penalty 10000 % \nobreak \glue 6.0 plus 2.0 minus 2.0 % \medskip \glue(\parskip) 0.0 plus 1.0 % \parskip \glue(\baselineskip) 5.05556 % interline glue \hbox(6.94444+0.0)x ... % first line of paragraph
```

TeX will not break this vertical list above the \medskip, because the penalty value prohibits it; it will not break at any other place, because it can only break at glue if that glue is preceded by a non-discardable item.

# 17.2.5 Finite \parfillskip

In plain TEX, \parfillskip has a (first-order) infinite stretch component. All other glue in the last line of a paragraph will then be set at natural width. If the \parfillskip has only finite (or possibly zero) stretch, other glue will be stretched or shrunk. A display formula in a paragraph with such a last line will be surrounded by \abovedisplayskip and \belowdisplayskip, even if \abovedisplayshortskip glue would be in order.

The reason for this is that glue setting is slightly machine-dependent, and any such processes should be kept out of TeX's global decisions.

# 17.2.6 A precaution for paragraphs that do not indent

If you are setting a text with both the paragraph indentation and the white space between paragraphs zero, you run the risk that the start of a new paragraph may be indiscernible when the last line of the previous paragraph ends almost or completely flush right. A sensible precaution for this is to set the  $\protect\operatorname{parfillskip}$  to, for instance

```
\parfillskip=1cm plus 1fil
```

instead of the usual Ocm plus 1fil.

On the other hand, you may let yourself be convinced by [?] that paragraphs should always indent.

# 第 18 章 段落形状

本章讨论影响段落形状的参数和命令。

\parindent 在段落开头添加的缩进盒子的宽度。 $Plain T_{E}X$  默认为 20pt。

\hsize 段落排版所用的行宽。Plain TeX 默认为 6.5in。


\leftskip 放在段落各行左侧的粘连。

\rightskip 放在段落各行右侧的粘连。

\hangindent 若大于零,表示左侧的缩进量;若小于零,表示右侧缩进量的负值。

\hangafter 若大于零,表示仅不缩进段落的前面多少行;若小于零,其绝对值表示 仅缩进段落的前面多少行。默认值为 1。

\parshape 用于设定段落形状的一般命令。



# 18.1 文本行的宽度

在吸收完一个段落后, TeX 形成了一个以缩进盒子开头, 以 \parfillskip 粘连结尾的水平列, 然后将此列表分为长度相等的多行。段落各行的宽度等于 \hsize, 其中包括两侧填充的 \leftskip 和 \rightskip 粘连。

TeX 的断行算法将 \leftskip 和 \rightskip 的值考虑在内。而 plain TeX 的 \raggedright 宏与 LaTeX 的 'flushleft' 环境的要点就在于,将 \rightskip 设定为零加上某些伸长量。

命令 \parshape 和 \hangindent 也影响行宽。它们通过改变 \hsize 然后移动 文本行所在盒子来实现。

# 18.2 段落形状参数

# 18.2.1 悬挂缩进

有种简单而常见的段落形状是开头或结尾若干行缩进。**TEX** 用 \hangafter 和 \hangindent 这两个参数实现这种形状。这两者都可以设定为正值或负值。

\hangindent 控制缩进量的大小:

- \hangindent > 0: 段落根据它的大小在左侧缩进。
- \hangindent < 0: 段落根据它的绝对值的大小在右侧缩进。

举个例子(假设\parindent=0pt),

\hangindent 的默认值为 Opt。

\hangafter 参数确定需要缩进的行的数目:

- \hangafter  $\geq 0$ : 这么多行除外的其他行都被缩进; 也就是说, 段落开头的这么 多行将不会被缩进。
- \hangafter < 0:它的绝对值就是段落开头将被缩进的行的数目。

18.3 杂项注记 189

举个例子,

\hangafter 的默认值为 1。

这两个参数都可正可负,总共有四种悬挂缩进结果。下面还将介绍探出边界的 悬挂缩进('outdent')。

悬挂缩进是这样实现的: 先从缩进行的 \hsize 中减去缩进量,接着将段落分段 为行,然后往右移动那些左侧缩进行。

正常的 \parindent 缩进不受悬挂缩进影响。如果不想要这个多余缩进,你应该在悬挂缩进段落开头使用 \noindent。

在每个 \par 命令之后 \hangindent 和 \hangafter 被还原为它们的默认值。

# 18.2.2 一般形状

用 \parshape 可以实现很一般的段落形状。这个命令可以指定段落前 n 行的缩 讲量和行宽,因此它有 2n+1 个参数: 先是行数 n,接着是 n 对缩进量和行宽。

```
\protect\ n \ i_1 \ \ell_1 \ \dots \ i_n \ \ell_n
```

如果段落超过n行,剩下的各行将重复第n行的指定。如果段落少于n行,多余的指定将被忽略。默认值(当然)是 \parshape = 0。

如果两者同时给出,那么 TeX 执行 \parshape 命令而忽略掉 \hangindent。在 \parshape 生效时,原本的 \parindent、\leftskip 和 \rightskip 仍然有效。

如同 \hangindent、\hangafter 和 \looseness 命令, \parshape 参数也会在 \par 命令后被重置(见第 19 章)。由于每个空行生成一个 \par 记号,在段落形状(或悬挂缩进)定义和段落内容之间你不应该留下空行。

控制序列 \parshape 是一个  $\langle internal\ integer \rangle$ : 它的值等于所设定的行数 n.

# 18.3 杂项注记

## 18.3.1 末尾行居中

给 \leftskip 和 \rightskip 设定相等的伸长量和收缩量将给出居中文本,在各行都居中的意义上。要让段落首行和尾行真正地居中,必须将 \parindent 和 \parfillskip 都设定为零。然而,两侧边界是不对齐的。

出人意料地,\leftskip 和 \rightskip 可以让段落两侧对齐而末尾行居中:

```
\leftskip=0cm plus 0.5fil \rightskip=0cm plus -0.5fil
\parfillskip=0cm plus 1fil
```

在段落的非末尾行,伸长量加起来等于零,所以插入的 \leftskip 和 \rightskip 等于零。而在末尾行, \parfillskip 添加了plus 1fil 的伸长量; 因此左右两边的总伸长量都是plus 0.5fil。

如果这样写将会是错误的:

```
\leftskip=0cm plus 0.5fil \rightskip=0cm minus 0.5fil
```

对此 TpX 将给出一个错误: 它抱怨 'infinite shrinkage'。

```
要让首行和尾行一样居中,可以用下面的参数设定:
```

```
\parindent=Opt \everypar{\hskip Opt plus -1fil}
\leftskip=Opt plus .5fil
\rightskip=Opt plus -.5fil
```

此时用 \everypar 插入的水平间距和 \leftskip 间距合起来将使得段落首行两侧的伸展能力相同。

# 18.3.2 凸出边界

假设你想要的悬挂缩进是让段落第二行以后各行凸出左边界 1cm。设定 \hangindent=-1cm 将得到在右边界缩进 1cm 的悬挂缩进, 所以需要另想办法。下面的方法可以完成此任务:

```
\leftskip=-1cm \hangindent=1cm \hangafter=-2
```

此方法的唯一问题在于段落结束后需要重设 \leftskip。我们可以通过重定义 \par 解决此问题:

```
\def\hangintomargin{\bgroup
  \leftskip=-1cm \hangindent=1cm \hangafter=-2
  \def\par{\endgraf\egroup}}
```

这里对\par 的重定义是局部的,只对需要凸出的段落生效。

还有一种更简洁的做法是利用 \parshape:

18.3 杂项注记 191

-1cm\dimen0 % third line specification

## 18.3.3 悬挂在对象上

LATEX 格式有一个 \@hangfrom 宏,用于将整个段落的文本悬挂在某个对象上,此对象通常是盒子或短文本。

悬挂例子 这个段落是下面定义的 \hangfrom 宏的一个例子。在 LATeX 文档类中,有一个 \@hangfrom 宏(与这里定义的类似)用于排版多行节标题。

现在来看 \hangfrom 宏的定义:

```
\def\hangfrom#1{\def\hangobject{#1}\setbox0=\hbox{\hangobject}%
   \hangindent \wd0 \noindent \hangobject \ignorespaces}
```

由于默认情形 \hangafter=1,这将使得段落首行的宽度为 \hsize,而后面各行按照 \hangobject 的宽度左缩进。

# 18.3.4 另一种悬挂缩进方法

将移动边界和凸出边界结合起来也可以得到悬挂缩进。比如逐项列表就可以用 这种方式实现:

```
\newdimen\listindent
\def\itemize{\begingroup
    \advance\leftskip by \listindent
    \parindent=-\listindent}
\def\stopitemize{\par\endgroup}
\def\item#1{\par\leavevmode
    \hbox to \listindent{#1\hfil}\ignorespaces
}
```

若想让列表项包含多个段落,可以这样实现:

```
\itemize\item{1.}First item\par Is two paragraphs long. \item{2.}Second item.\stopitemize
```

给出

#### 1. First item

Is two paragraphs long.

2. Second item.

# 18.3.5 悬挂缩进对比边界移动

上面的例子似乎表明悬挂缩进与修改 \leftskip 和 \rightskip 是可互换的。它们确实可以,但只在一定程度上。

将段落的 \leftskip 设为某个正值意味着 \hsize 保持不变, 但各行都以一个粘连项开始。另一方面, 悬挂缩进是通过减少缩进行的 \hsize 值, 然后在竖直列中移动水平盒子实现的。

这两种方法的区别可以从这个事实中看到:改变 \leftskip 并不会移动陈列公式。见第 9 章中展示的指引线如何受边界移动影响的例子。

# 18.3.6 更多例子

段落形状(用各种方式修改)的更多例子可以在[**?**]中找到。第 **71** 页的一个例子就取自该文章。

# 第 19 章 Line Breaking

This chapter treats line breaking and the concept of 'badness' that TEX uses to decide how to break a paragraph into lines, or where to break a page. The various penalties contributing to the cost of line breaking are treated here, as is hyphenation. Page breaking is treated in Chapter 27.

- \penalty Specify desirability of not breaking at this point.
- \linepenalty Penalty value associated with each line break. Plain TeX default: 10.
- \hyphenpenalty Penalty associated with break at a discretionary item in the general case. Plain TeX default: 50.
- \exhyphenpenalty Penalty for breaking a horizontal line at a discretionary item in the special case where the prebreak text is empty. Plain TEX default: 50.
- \adjdemerits Penalty for adjacent visually incompatible lines. Plain TeX default: 10 000.
- \doublehyphendemerits Penalty for consecutive lines ending with a hyphen. Plain TeX default: 10 000.
- \finalhyphendemerits Penalty added when the penultimate line of a paragraph ends with a hyphen. Plain TEX default: 5000.
- \allowbreak Macro for creating a breakpoint by inserting a \penalty0.
- \pretolerance Tolerance value for a paragraph without hyphenation. Plain TeX default: 100.
- \tolerance Tolerance value for lines in a paragraph with hyphenation. Plain TEX default: 200.
- \emergencystretch (TEX3 only) Assumed extra stretchability in lines of a paragraph.
- \looseness Number of lines by which this paragraph has to be made longer

than it would be ideally.

\prevgraf The number of lines in the paragraph last added to the vertical list.

\discretionary Specify the way a character sequence is split up at a line break.

\- Discretionary hyphen; this is equivalent to \discretionary{-}{}{}.

\hyphenchar Number of the hyphen character of a font.

\defaulthyphenchar Value of \hyphenchar when a font is loaded. Plain TEX default: `\-.

\uchyph Positive to allow hyphenation of words starting with a capital letter. Plain TFX default: 1.

\lefthyphenmin (TEX3 only) Minimal number of characters before a hyphenation. Plain TEX default: 2.

\righthyphenmin (TEX3 only) Minimum number of characters after a hyphenation. Plain TEX default: 3.

\patterns Define a list of hyphenation patterns for the current value of \language; allowed only in IniTeX.

\hyphenation Define hyphenation exceptions for the current value of \language.

\language Choose a set of hyphenation patterns and exceptions.

\setlanguage Reset the current language.

# 19.1 Paragraph break cost calculation

A paragraph is broken such that the amount d of demerits associated with breaking it is minimized. The total amount of demerits for a paragraph is the sum of those for the individual lines, plus possibly some extra penalties. Considering a paragraph as a whole instead of breaking it on a line-by-line basis can lead to better line breaking:  $T_EX$  can choose to take a slightly less beautiful line in the beginning of the paragraph in order to avoid bigger trouble later on.

For each line demerits are calculated from the *badness* b of stretching or shrinking the line to the break, and the *penalty* p associated with the break. The badness is not allowed to exceed a certain prescribed tolerance.

In addition to the demerits for breaking individual lines, TEX assigns demerits for the way lines combine; see below.

The implementation of TeX's paragraphbreaking algorithm is explained

in [?].

#### 19.1.1 Badness

From the ratio between the stretch or shrink present in a line, and the actual stretch or shrink taken, the *badness* of breaking a line at a certain point is calculated. This badness is an important factor in the process of line breaking. See page 101 for the formula for badness.

In this chapter badness will only be discussed in the context of line breaking. Badness is also computed when a vertical list is stretched or shrunk (see Chapter 27).

The following terminology is used to describe badness:

**tight (3)** is any line that has shrunk with a badness  $b \ge 13$ , that is, by using at least one-half of its amount of shrink (see page 101 for the computation).

**decent (2)** is any line with a badness  $b \le 12$ .

**loose** (1) is any line that has stretched with a badness  $b \ge 13$ , that is, by using at least one-half of its amount of stretch.

**very loose (0)** is any line that has stretched with a badness  $b \ge 100$ , that is, by using its full amount of stretch or more. Recall that glue can stretch, but not shrink more than its allowed amount.

The numbering is used in trace output (Chapter 34), and it is also used in the following definition: if the classifications of two adjacent lines differ by more than 1, the lines are said to be *visually incompatible*. See below for the \adjdemerits parameter associated with this.

Overfull horizontal and vertical boxes are passed unnoticed if their excess width or height is less than \hfuzz or \vfuzz respectively; they are not reported if the badness is less than \hbadness or \vbadness (see Chapter 5).

## 19.1.2 Penalties and other break locations

breaking.

Line breaks can occur at the following *breakpoints* in horizontal lists:

1. At a penalty. The penalty value is the 'aesthetic cost' of breaking the line at that place. Negative penalties are considered as bonuses. A penalty of  $10\,000$  or more inhibits, and a penalty of  $-10\,000$  or less forces, a break. Putting more than one penalty in a row is equivalent to putting just the one with the minimal value, because that one is the best candidate for line

Penalties in horizontal mode are inserted by the user (or a user macro). The only exception is the \nobreak inserted before the \parfillskip glue.

2. At a glue, if it is not part of a math formula, and if it is preceded by a non-discardable item (see Chapter 6). There is no penalty associated with breaking at glue.

The condition about the non-discardable precursor is necessary, because otherwise breaking in between two pieces of glue would be possible, which would cause ragged edges to the paragraph.

- 3. At a kern, if it is not part of a math formula and if it is followed by glue. There is no penalty associated with breaking at a kern.
- 4. At a math-off, if that is followed by glue. Since math-off (and math-on) act as kerns (see Chapter 23), this is very much like the previous case. There is no penalty associated with breaking at a math-off.
- 5. At a discretionary break. The penalty is the \hyphenpenalty or the \exhyphenpenalty. This is treated below.

Any discardable material following the break —— glue, kerns, math-on/off and penalties —— is discarded. If one considers a line break at glue (kern, math-on/off) to occur at the front end of the glue item, this implies that that piece of glue disappears in the break.

#### 19.1.3 Demerits

From the badness of a line and the penalty, if any, the demerits of the line are calculated. Let l be the value of \linepenalty, b the badness of the line, p the penalty at the break; then the *demerits* d are given by

$$d = \begin{cases} (l+b)^2 + p^2 & \text{if } 0 \le p < 10\,000 \\ (l+b)^2 - p^2 & \text{if } -10\,000 < p < 0 \\ (l+b)^2 & \text{if } p \le -10\,000 \end{cases}$$

Both this formula and the one for the badness are described in [?] as 'quite arbitrary', but they have been shown to lead to good results in practice.

The demerits for a paragraph are the sum of the demerits for the lines, plus

- the \adjdemerits for any two adjacent lines that are not visually compatible (see above),
- \doublehyphendemerits for any two consecutive lines ending with a hyphen, and the
- \finalhyphendemerits if the penultimate line of a paragraph ends with a

hyphen.

At the start of a paragraph TeX acts as if there was a preceding line which was 'decent'. Therefore \adjdemerits will be added if the first line is 'very loose'. Also, the last line of a paragraph is ordinarily also 'decent' —— all spaces are set at natural width owing to the infinite stretch in the \parfillskip —— so \adjdemerits are added if the preceding line is 'very loose'.

Note that the penalties at which a line break is chosen weigh about as heavily as the badness of the line, so they can be relatively small. However, the three extra demerit parameters have to be of the order of the square of penalties and badnesses to weigh equally heavily.

## 19.1.4 The number of lines of a paragraph

After a paragraph has been completed (or partially completed prior to a display), the variable  $\prevgraf$  records the number of lines in the paragraph. By assigning to this variable —— and because this is a  $\prevgraf$  such an assignment is automatically global ——  $\prevgraf$  TEX's decision processes can be influenced. This may be useful in combination with hanging indentation or  $\prevgraf$  specifications (see Chapter 18).

Some direct influence of the linebreaking process on the resulting number of lines exists. One factor is the \linepenalty which is included in the demerits of each line. By increasing the line penalty TeX can be made to minimize the number of lines in a paragraph.

Deviations from the optimal number of lines, that is, the number of lines stemming from the optimal way of breaking a paragraph into lines, can be forced by the user by means of the \looseness parameter. This parameter, which is reset every time the shape parameters are cleared (see Chapter 18), indicates by how many lines the current paragraph should be made longer than is optimal. A negative value of \looseness will attempt to make the paragraph shorter by a number of lines that is the absolute value of the parameter.

TEX will still observe the values of \pretolerance and \tolerance (see below) when lengthening or shortening a paragraph under influence of \looseness. Therefore, TEX will only lengthen or shorten a paragraph for as far as is possible without exceeding these parameters.

#### 19.1.5 Between the lines

TEX's paragraph mechanism packages lines into horizontal boxes that are appended to the surrounding vertical list. The resulting sequence of vertical items is then a repeating sequence of

- a box containing a line of text,
- possibly migrated vertical material (see page 78),
- a penalty item reflecting the cost of a page break at that point, which is normally the \interlinepenalty (see Chapter 27), and
- interline glue, which is calculated automatically on basis of the \prevdepth (see Chapter 15).

# 19.2 The process of breaking

TEX tries to break paragraphs in such a way that the badness of each line does not exceed a certain tolerance. If there exists more than one solution to this, the one with the fewest demerits is taken.

By setting \tracingparagraphs to a positive value, TeX can be made to report the calculations of the paragraph mechanism in the log file. Some implementations of TeX may have this option disabled to make TeX run faster.

# 19.2.1 Three passes

First an attempt is made to split the paragraph into lines without hyphenating, that is, without inserting discretionary hyphens. This attempt succeeds if none of the lines has a badness exceeding \pretolerance.

Otherwise, a second pass is made, inserting discretionaries and using \tolerance. If \pretolerance is negative, the first pass is omitted.

TEX can be made to make a third pass if the first and second pass fail. If \emergencystretch is a positive dimension, TEX will assume this much extra stretchability in each line when badness and demerits are calculated. Thus solutions that only slightly exceeded the given tolerances will now become feasible. However, no glue of size \emergencystretch is actually present, so underfull box messages may still occur.

19.3 Discretionaries 199

#### 19.2.2 Tolerance values

How much trouble TEX will have typesetting a piece of text depends partly on the tolerance value. Therefore it is sensible to have some idea of what badness values mean in visual terms.

For lines that are stretched, the badness is 100 times the cube of the stretch ratio. A badness of 800 thus means that the stretch ratio is 2. If the space is, as in the ten-point Computer Modern Font,

```
3.33pt plus 1.67pt minus 1.11pt
```

a badness of 800 means that spaces have been stretched to

```
3.33pt + 2 \times 1.67pt = 6.66pt
```

that is, to exactly double their natural size. It is up to you to decide whether this is too large.

#### 19.3 Discretionaries

A discretionary item \discretionary{...}{...} marks a place where a word can be broken. Each of the three arguments is a  $\langle general \ text \rangle$  (see Chapter 36): they are, in sequence,

- the *pre-break* text, which is appended to the part of the word before the break,
- the *post-break* text, which is prepended to the part of the word after the break, and
- the *no-break* text, which is used if the word is not broken at the discretionary item.

For example: ab\discretionary{g}{h}{cd}ef is the word abcdef, but it can be hyphenated with abg before the break and hef after. Note that there is no automatic hyphen character.

All three texts may contain any sorts of tokens, but any primitive commands and macros should expand to boxes, kerns, and characters.

# 19.3.1 Hyphens and discretionaries

Internally, T<sub>E</sub>X inserts the equivalent of
\discretionary{\char\hyphenchar\font}{}{}

at every place where a word can be broken. This causes a *hyphen character* to be placed before any break. No such discretionary is inserted if \hyphenchar\font is not in the range 0–255, or if its position in the font is not filled. When a font is loaded, its \hyphenchar value is set to \defaulthyphenchar. The \hyphenchar value can be changed after this.

In plain TeX the \defaulthyphenchar has the value `\-, so for all fonts character 45 (the Ascii hyphen character) is the hyphen sign, unless it is specified otherwise.

The primitive command  $\$  (called a 'discretionary hyphen')  $\$ -discretionary hyphen is equivalent to the above

\discretionary{\char\hyphenchar\font}{}{}. Breaking at such a discretionary, whether inserted implicitly by TeX or explicitly by the user, has a cost of \hyphenpenalty.

In unrestricted horizontal mode an empty discretionary \discretionary{}{} is automatically inserted after characters whose character code is the \hyphenchar value of the font, thus enabling hyphenation at that point. The penalty for breaking a line at such a discretionary with an empty pre-break text is \exhyphenpenalty, that is, the 'explicit hyphen' penalty.

If a word contains discretionary breaks, for instance because of explicit hyphen characters, TEX will not consider it for further hyphenation. People have solved the ensuing problems by tricks such as

```
\def\={\penalty10000 \hskip0pt -\penalty0 \hskip0pt\relax}
... integro\=differential equations...
```

The skips before and after the hyphen lead TeX into treating the first and second half of the compound expression as separate words; the penalty before the first skip inhibits breaking before the hyphen.

## 19.3.2 Examples of discretionaries

Languages such as German or Dutch have words that change spelling when hyphenated (German: 'backen' becomes 'bak-ken'; Dutch: 'autootje' becomes 'auto-tje'). This problem can be solved with TEX's discretionaries.

For instance, for German (this is inspired by [?]):

```
\catcode`\"=\active
\def"#1{\ifx#1k\discretionary{k-}{k}{ck}\fi}
```

which enables the user to write ba"ken.

In Dutch there is a further problem which allows a nice systematic solution. Umlaut characters ('trema' is the Dutch term) should often disappear in 19.4 Hyphenation 201

a break, for instance 'na"apen' hyphenates as 'na-apen', and 'onbe"invloedbaar' hyphenates as 'onbe-invloedbaar'. A solution (inspired by [?]) is

```
\catcode`\"=\active
\def"#1{\ifx#1i\discretionary{-}{i}{\"\i}%
   \else \discretionary{-}{#1}{\"#1}\fi}
```

which enables the user to type na "apen and onbe" invloedbaar.

# 19.4 Hyphenation

TEX's hyphenation algorithm uses a list of patterns to determine at what places a word that is a candidate for hyphenation can be broken. Those aspects of hyphenation connected with these patterns are treated in appendix H of the TEX book; the method of generating hyphenation patterns automatically is described in [?]. People have been known to generate lists of patterns by hand; see for instance [?]. Such hand-generated lists may be superior to automatically generated lists.

Here it will mainly be described how TEX declares a word to be a candidate for hyphenation. The problem here is how to cope with punctuation and things such as quotation marks that can be attached to a word. Also, *implicit kerns*, that is, kerns inserted because of font information, must be handled properly.

#### 19.4.1 Start of a word

TeX starts at glue items (if they are not in math mode) looking for a *starting letter* of a word: a character with non-zero \lccode, or a ligature starting with such a character (upper/lowercase codes are explained on page 44). Looking for this starting letter, TeX bypasses any implicit kerns, and characters with zero \lccode (this includes, for instance, punctuation and quotation marks), or ligatures starting with such a character.

If no suitable starting letter turns up, that is, if something is found that is not a character or ligature, TEX skips to the next glue, and starts this algorithm anew. Otherwise a trial word is collected consisting of all following characters with non-zero \lccode from the same font as the starting letter, or ligatures consisting completely of such characters. Implicit kerns are allowed between the characters and ligatures.

If the starting letter is from a font for which the value of \hyphenchar is invalid, or for which this character does not exist, hyphenation is abandoned

for this word. If the starting letter is an uppercase letter (that is, it is not equal to its own \lccode), TEX will abandon hyphenation unless \uchyph is positive. The default value for this parameter is 1 in plain TEX, implying that capitalized words are subject to hyphenation.

#### 19.4.2 End of a word

Following the trial word can be characters (from another font, or with zero \lccode), ligatures or implicit kerns. After these items, if any, must follow

- glue or an explicit kern,
- · a penalty,
- a whatsit, or
- a \mark, \insert, or \vadjust item.

In particular, the word will not be hyphenated if it is followed by a

- box,
- rule,
- math formula, or
- discretionary item.

Since discretionaries are inserted after the hyphenchar of the font, occurrence of this character inhibits further hyphenation. Also, placement of accents is implemented using explicit kerns (see Chapter 3), so any \accent command is considered to be the end of a word, and inhibits hyphenation of the word.

# 19.4.3 TEX2 versus TEX3

There is a noticeable difference in the treatment of hyphenated fragments between TEX2 and TEX3. TEX2 insists that the part before the break should be at least two characters, and the part after the break three characters, long. Typographically this is a sound decision: this way there are no two-character pieces of a word stranded at the end or beginning of the line. Both before and after the break there are at least three characters.

In TEX3 two integer parameters have been introduced to control the length of these fragments: \lefthyphenmin and \righthyphenmin. These are set to 2 and 3 respectively in the plain format for TEX3. If the sum of these two is 63 or more, all hyphenation is suppressed.

Another addition in TEX3, the possibility to have several sets of hyphen-

ation patterns, is treated below.

#### 19.4.4 Patterns and exceptions

The statements

are  $\langle hyphenation \, assignment \rangle s$ , which are  $\langle global \, assignment \rangle s$ . The \patterns command, which specifies a list of hyphenation patterns, is allowed only in IniTeX (see Chapter 33), and all patterns must be specified before the first paragraph is typeset.

Hyphenation exceptions can be specified at any time with statements such as

```
\hyphenation{oxy-mo-ron gar-goyle}
```

which specify locations where a word may be hyphenated. Subsequent \hyphenation statements are cumulative.

In TEX3 these statements are taken to hold for the language that is the current value of the \language parameter.

# 19.5 Switching hyphenation patterns

When typesetting paragraphs, TeX (version 3) can use several sets of patterns and hyphenation exceptions, for at most 256 *languages*.

If a \patterns or \hyphenation command is given (see above), TeX stores the patterns or exceptions under the current value of the \language parameter. The \patterns command is only allowed in IniTeX, and patterns must be specified before any typesetting is done. Hyphenation exceptions, however, can be specified cumulatively, and not only in IniTeX.

In addition to the \language parameter, which can be set by the user, TEX has internally a *current language*. This is set to zero at the start of every paragraph. For every character that is added to a paragraph the current language is compared with the value of \language, and if they differ a whatsit element is added to the horizontal list, resetting the current language to the value of \language.

At the start of a paragraph, this whatsit is inserted after the \everypar tokens, but \lastbox can still access the indentation box.

As an example, suppose that a format has been created such that language 0 is English, and language 1 is Dutch. English hyphenations will then be used if the user does not specify otherwise; if a job starts with

```
\language=1
```

the whole document will be set using Dutch hyphenations, because TEX will insert a command changing the current language at the start of every paragraph. For example:

The whatsit can be inserted explicitly, without changing the value of \language, by specifying

```
\sl number \rangle
```

However, this will hardly ever be needed. One case where it may be necessary is when the contents of a horizontal box are unboxed to a paragraph: inside the box no whatsits are added automatically, since inside such a box no hyphenation can take place. See page 68 for another problem with text in horizontal boxes.

# 第 20 章 Spacing

The usual interword space in TEX is specified in the font information, but the user can override this. This chapter explains the rules by which TEX calculates interword space.

\ Control space. Insert the same amount of space as a space token would if  $\spacefactor = 1000$ .

\spaceskip Interword glue if non-zero.

\xspaceskip Interword glue if non-zero and \spacefactor  $\geq 2000$ .

\spacefactor 1000 times the ratio by which the stretch (shrink) component of the interword glue should be multiplied (divided).

\sfcode Value for \spacefactor associated with a character.

\frenchspacing Macro to switch off extra space after punctuation.

\nonfrenchspacing Macro to switch on extra space after punctuation.

#### 20.1 Introduction

In between words in a text, TEX inserts space. This space has a natural component, plus stretch and shrink to make justified (right-aligned) text possible. Now, in certain styles of typesetting, there is more space after punctuation. This chapter discusses the mechanism that TEX uses to realize such effect.

Here is the general idea:

- After every character token, the \spacefactor quantity is updated with the space factor code of that character.
- When space is inserted, its natural size can be augmented (if \spacefactor  $\geq$  2000), and in general its stretch is multiplied, and its shrink divided, by \spacefactor/1000.

206 第 20 章 Spacing

• There are further rules, for instance so that in ...word.) And... the space is modified according to the period, not the closing parenthesis.

# 20.2 Automatic interword space

For every space token in horizontal mode the interword glue of the current font is inserted, with stretch and shrink components, all determined by \fontdimen parameters. To be specific, font dimension 2 is the normal interword space, dimension 3 is the amount of stretch of the interword space, and 4 is the amount of shrink. Font dimension 7 is called the 'extra space'; see below (the list of all the font dimensions appears on page 51).

Ordinarily all spaces between words (in one font) would be treated the same. To allow for differently sized spaces —— for instance a typeset equivalent of the double spacing after punctuation in typewritten documents —— TEX associates with each character a so-called *space factor*.

When a character is added to the current horizontal list, the space factor code (\sfcode) of that character is assigned to the space factor \spacefactor. There are two exceptions to this rule:

- When the space factor code is zero, the \spacefactor does not change. This
  mechanism allows space factors to persist through parentheses and such;
  see section 20.5.3.
- When the space factor code of the last character is >1000 and the current space factor is <1000, the space factor becomes 1000. This mechanism prevents elongated spaces after initials; see section 20.5.2.

The maximum space factor is 32 767.

The stretch component of the interword space is multiplied by the space factor divided by 1000; the shrink component is divided by this factor. The extra space (font dimension 7) is added to the natural component of the interword space when the space factor is  $\geq 2000$ .

# 20.3 User interword space

The user can override the interword space contained in the \fontdimen parameters by setting the \spaceskip and the \xspaceskip to non-zero values. If \spaceskip is non-zero, it is taken instead of the normal interword space (\fontdimen2 plus \fontdimen3 minus \fontdimen4), but a non-zero \xspaceskip

is used as interword space if the space factor is  $\geq 2000$ .

If the  $\spaceskip$  is used, its stretch and shrink components are multiplied and divided respectively by  $\spacefactor/1000$ .

Note that, if \spaceskip and \xspaceskip are defined in terms of em, they change with the font.

#### 例子:Let the following macros be given:

```
\def\a.{\vrule height10pt width4pt\spacefactor=1000\relax}
\def\b.{\vrule height10pt width4pt\spacefactor=3000\relax}
\def\c{\vrule height10pt width4pt\relax}
```

then

```
\vbox{
\fontdimen2\font=4pt % normal space
\fontdimen7\font=3pt % extra space
\a. \b. \c\par
% zero extra space
\fontdimen7\font=0pt
                                             \a. \b. \c\par
                                     gives
% set \spaceskip for normal space
\spaceskip=2\fontdimen2\font
\a. \b. \c\par
% set \xspaceskip
\xspaceskip=2pt
\a. \b. \c\par
}
```

In all of these lines the glue is set at natural width. In the first line the high space factor value after \b causes the extra space \fontdimen7 to be added. If this is zero (second line), the only difference between space factor values is the stretch/shrink ratio. In the third line the \spaceskip is taken for all space factor values. If the \xspaceskip is nonzero, it is taken (fourth line) instead of the \spaceskip for the high value of the space factor.

# 20.4 Control space and tie

The control character  $\setminus$  , *control space* is a horizontal command which inserts a space,  $\setminus$  acting as if the current space factor is 1000. However, it does not affect the value of  $\cdot$ 

第 20 章 Spacing

Control space has two main uses. First, it is convenient to use after a control sequence: \TeX\ is fun! Secondly, it can be used after abbreviations when \nonfrenchspacing (see below) is in effect. For example:

Such an active tilde is called a 'tie'; it inserts an ordinary amount of space, and prohibits breaking at this space.

# 20.5 More on the space factor

# 20.5.1 Space factor assignments

\def~{\penalty10000\ }

208

The space factor of a particular character is contained in its *spacefactor code* and can be assigned as

```
\scalebox{1.5} \code \langle 8-bit\ number \rangle \langle equals \rangle \langle number \rangle
```

IniTeX assigns a space factor code of 1000 to all characters except uppercase characters; they get a space factor code of 999. The plain format then assigns space factor codes greater than 1000 to various punctuation symbols, for instance  $\scalebox{sfcode}\\.=3000$ , which triples the stretch and shrink after a full stop. Also, for all space factor values  $\geq 2000$  the extra space is added; see above.

#### 20.5.2 Punctuation

Because the space factor cannot jump from a value below 1000 to one above, a punctuation symbol after an uppercase character will not have the effect on the interword space that punctuation after a lowercase character has.

```
例子:

a% \sfcode`a=1000, space factor becomes 1000
.% \sfcode`.=3000, spacefactor becomes 3000
% subsequent spaces will be increased.

A% \sfcode`A=999, space factor becomes 999
.% \sfcode`.=3000, space factor becomes 1000
% subsequent spaces will not be increased.
```

Thus, initials are not mistaken for sentence ends. If an uppercase character does end a sentence, for instance

```
... and NASA.
there are several solutions:
... NASA\spacefactor=1000.
or
... NASA\hbox{}.
```

which abuses the fact that after a box the space factor is set to 1000. The LATEX macro \@ is equivalent to the first possibility.

In the plain format two macros are defined that switch between uniform interword spacing, *frenchspacing*, and extra space after punctuation, which is more an American custom. The macro \frenchspacing sets the space factor code of all punctuation to 1000; the macro \nonfrenchspacing sets it to values greater than 1000.

Here are the actual definitions from plain.tex:

```
\def\frenchspacing{\sfcode`\.\@m \sfcode`\?\@m
\sfcode`\!\@m \sfcode`\.\@m}
\def\nonfrenchspacing{\sfcode`\.3000 \sfcode`\?3000
\sfcode`\!3000 \sfcode`\:2000
\sfcode`\;1500 \sfcode`\,1250 }
```

where

```
\mathchardef\@m=1000
```

is given in the plain format.

French spacing is a somewhat controversial issue: the TFX book acts as if

210 第 20 章 Spacing

non-French spacing is standard practice in printing, but for instance in [?] one finds 'The space of the line should be used after all points in normal text'. Extra space after punctuation may be considered a 'typewriter habit', but this is not entirely true. It used to be a lot more common than it is nowadays, and there are rational arguments against it: the full stop (point, period) at the end of a sentence, where extra punctuation is most visible, is rather small, so it carries some extra visual space of its own above it. This book does not use extra space after punctuation.

#### 20.5.3 Other non-letters

The zero value of the space factor code makes characters that are not a letter and not punctuation 'transparent' for the space factor.

```
例子:

a% \sfcode`a=1000, space factor becomes 1000
.% \sfcode`.=3000, spacefactor becomes 3000
% subsequent spaces will be increased.

a% \sfcode`a=1000, space factor becomes 1000
.% \sfcode`.=3000, space factor becomes 3000
)% \sfcode`)=0, space factor stays 3000
% subsequent spaces will be increased.
```

## 20.5.4 Other influences on the space factor

The space factor is 1000 when  $T_EX$  starts forming a horizontal list, in particular after \indent, \noindent, and directly after a display. It is also 1000 after a \vrule, an accent, or a  $\langle box \rangle$  (in horizontal mode), but it is not influenced by \unbox or \unbcopy commands.

In the first column of a \valign the space factor of the surrounding horizontal list is carried over; similarly, after a vertical alignment the space factor is set to the value reached in the last column.

# 第 21 章 Characters in Math Mode

In math mode every character specifies by its \mathcode what position of a font to access, among other things. For delimiters this story is a bit more complicated. This chapter explains the concept of math codes, and shows how TeX implements variable size delimiters.

\mathcode Code of a character determining its treatment in math mode.

\mathchar Explicit denotation of a mathematical character.

\mathchardef Define a control sequence to be a synonym for a math character code.

\delcode Code specifying how a character should be used as delimiter.

\delimiter Explicit denotation of a delimiter.

\delimiterfactor 1000 times the fraction of a delimited formula that should be covered by a delimiter. Plain T<sub>E</sub>X default: 901

\delimitershortfall Size of the part of a delimited formula that is allowed to go uncovered by a delimiter. Plain TeX default: 5pt

\nulldelimiterspace Width taken for empty delimiters. Plain TEX default: 1.2pt

\left Use the following character as an open delimiter.

\right Use the following character as a closing delimiter.

\big One line high delimiter.

\Big One and a half line high delimiter.

\bigg Two lines high delimiter.

\Bigg Two and a half lines high delimiter.

\bigl etc. Left delimiters.

\bigm etc. Delimiters used as binary relations.

\bigr etc. Right delimiters.

\radical Command for setting things such as root signs.

\mathaccent Place an accent in math mode.

\skewchar Font position of an after-placed accent.

\defaultskewchar Value of \skewchar when a font is loaded.

\skew Macro to shift accents on top of characters explicitly.

\widehat Hat accent that can accommodate wide expressions.

\widetilde Tilde accent that can accommodate wide expressions.

#### 21.1 Mathematical characters

Each of the 256 permissible character codes has an associated \mathcode, which can be assigned by

```
\mbox{\code}\langle 8\mbox{-bit number}\rangle\langle \mbox{\code}\rangle\langle 15\mbox{-bit number}\rangle
```

When processing in math mode, TeX replaces all characters of categories 11 and 12, and \char and \chardef characters, by their associated mathcode.

The 15-bit math code is most conveniently denoted hexadecimally as "xyzz, where

```
x \le 7 is the class (see page 227), y is the font family number (see Chapter 22), and zz is the position of the character in the font.
```

Math codes can also be specified directly by a  $\langle math \ character \rangle$ , which can be

- \mathchar\langle 15-bit number\rangle;
- $\langle mathchardef\ token \rangle$ , a control sequence that was defined by  $\mbox{\ \ } \langle mathchardef\ \langle control\ sequence \rangle \langle equals \rangle \langle 15\mbox{-bit\ number} \rangle$  or
- · a delimiter command

```
\delimiter \langle 27 - bit number \rangle
```

where the last 12 bits are discarded.

The commands \mathchar and \mathchardef are analogous to \char and \chardef in text mode. Delimiters are treated below. A  $\langle$  mathchardef token $\rangle$  can be used as a  $\langle$ number $\rangle$ , even outside math mode.

In IniTeX all letters receive \mathcode "71zz and all digits receive "70zz,

21.2 Delimiters 213

where "zz is the hexadecimal position of the character in the font. Thus, letters are initially from family 1 (math italic in plain TEX), and digits are from family 0 (roman). For all other characters, IniTEX assigns

```
\mathcode x = x,
```

thereby placing them also in family 0.

If the mathcode is "8000, the smallest integer that is not a  $\langle 15$ -bit number $\rangle$ , the character is treated as an active character with the original character code. Plain TFX assigns a \mathcode of "8000 to the space, underscore and prime.

# 21.2 Delimiters

After \left and \right commands TEX looks for a delimiter. A delimiter is either an explicit \delimiter command (or a macro abbreviation for it), or a character with a non-zero delimiter code.

The \left and \right commands implicitly delimit a group, which is considered as a subformula. Since the enclosed formula can be arbitrarily large, the quest for the proper delimiter is a complicated story of looking at variants in two different fonts, linked chains of variants in a font, and building extendable delimiters from repeatable pieces.

The fact that a group enclosed in \left...\right is treated as an independent subformula implies that a sub- or superscript at the start of this formula is not considered to belong to the delimiter. For example, TEX acts as if \left(\_2 is equivalent to \left({}\_2. (A subscript after a \right delimiter is positioned with respect to that delimiter.)

#### 21.2.1 Delimiter codes

To each character code there corresponds a *delimiter code*, assigned by  $\del{eq:code} \8-bit number \end{equals} \aligned 24-bit number \end{equals}$ 

A delimiter code thus consists of six hexadecimal digits "uvvxyy, where

uvv is the small variant of the delimiter, and xyy is the large variant;
u, x are the font families of the variants, and vv, yy are the locations in those fonts.

Delimiter codes are used after  $\left| \text{left} \right|$  and  $\left| \text{left} \right|$  sets all delimiter codes to -1, except  $\left| \text{delcode} \right|$ .=0, which makes the period an empty

delimiter. In plain  $T_EX$  delimiters have typically u = 2 and x = 3, that is, first family 2 is tried, and if no big enough delimiter turns up family 3 is tried.

### 21.2.2 Explicit \delimiter commands

Delimiters can also be denoted explicitly by a (27-bit number),

```
\delimiter"tuvvxyy
```

where uvvxyy are the small and large variant of the delimiter as above; the extra digit t (which is < 8) denotes the class (see page 227). For instance, the \langle macro is defined as

```
\def\langle{\delimiter "426830A }
```

which means it belongs to class 4, opening. Similarly, \rangle is of class 5, closing; and \uparrow is of class 3, relation.

After \left and \right — that is, when TEX is looking for a delimiter — the class digit is ignored; otherwise — when TEX is not looking for a delimiter — the rightmost three digits are ignored, and the four remaining digits are treated as a \mathchar; see above.

## 21.2.3 Finding a delimiter; successors

Typesetting a delimiter is a somewhat involved affair. First  $\operatorname{TpX}$  determines the size y of the formula to be covered, which is twice the maximum of the height and depth of the formula. Thus the formula may not look optimal if it is not centred itself.

The size of the delimiter should be at least  $\ensuremath{\backslash}$  delimiterfactor  $\ensuremath{\times} y/1000$  and at least y —  $\ensuremath{\backslash}$  delimitershortfall. TeX then tries first the small variant, and if that one is not satisfactory (or if the uvv part of the delimiter is 000) it tries the large variant. If trying the large variant does not meet with success, TeX takes the largest delimiter encountered in this search; if no delimiter at all was found (which can happen if the xyy part is also 000), an empty box of width  $\ensuremath{\backslash}$  nulldelimiterspace is taken.

Investigating a variant means, in sequence,

- if the current style (see page 225) is scriptscriptstyle, the \scriptscriptfont of the family is tried;
- if the current style is scriptstyle or smaller, the \scriptfont of the family is tried;
- otherwise the \textfont of the family is tried.

21.3 Radicals 215

The plain format puts the cmex10 font in all three styles of family 3.

Looking for a delimiter at a certain position in a certain font means

- if the character is large enough, accept it;
- if the character is *extendable*, accept it;
- otherwise, if the character has a *successor*, that is, it is part of a chain of increasingly bigger delimiters in the same font, try the successor.

Information about successors and extensibility of a delimiter is coded in the font metric file of the font. An extendable character has a top, a bottom, possibly a mid piece, and a piece which is repeated directly below the top piece, and directly above the bottom piece if there is a mid piece.

#### 21.2.4 \big, \Big, \bigg, and \Bigg delimiter macros

In order to be able to use a delimiter outside the \left...\right context, or to specify a delimiter of a different size than TeX would have chosen, four macros for 'big' delimiters exist: \big, \Big, \bigg, and \Bigg. These can be used with anything that can follow \left or \right.

Twelve further macros (for instance \big1, \bigm, and \bigr) force such delimiters in the context of an opening symbol, a binary relation, and a closing symbol respectively:

```
\def\bigl{\mathopen\big}
\def\bigm{\mathrel\big} \def\bigr{\mathclose\big}
```

The 'big' macros themselves put the requested delimiter and a null delimiter around an empty vertical box:

```
\def\big#1{{\nulldelimiterspace=0pt \mathsurround=0pt \hbox{$\left#1\vbox to 8.5pt{}\right.$}}}
```

As an approximate measure, the Big delimiters are one and a half times as large (11.5pt) as big delimiters; bigg ones are twice (14.5pt), and Bigg ones are two and a half times as large (17.5pt).

## 21.3 Radicals

A *radical* is a compound of a left delimiter and an overlined math expression. The overlined expression is set in the cramped version of the surrounding style (see page 225).

In the plain format and the Computer Modern math fonts there is only one

radical: the square root construct

```
\def\sqrt{\radical"270370 }
```

The control sequence  $\$  is followed by a  $\langle 24\text{-bit}$  number $\rangle$  which specifies a small and a large variant of the left delimiter as was explained above. Joining the delimiter and the rule is done by letting the delimiter have a large depth, and a height which is equal to the desired rule thickness. The rule can then be placed on the current baseline. After the delimiter and the ruled expression have been joined the whole is shifted vertically to achieve the usual vertical centring (see Chapter 23).

#### 21.4 Math accents

Accents in math mode are specified by

```
\mbox{\mbox{$\backslash$}} mathaccent\mbox{\mbox{$\langle$15$-bit number}\rangle\rangle} math field\mbox{\mbox{$\rangle$}}
```

Representing the 15-bit number as "xyzz, only the family y and the character position zz are used: an accented expression acts as \mathord expression (see Chapter 23).

In math mode whole expressions can be accented, whereas in text mode only characters can be accented. Thus in math mode accents can be stacked. However, the top accent may (or, more likely, will) not be properly positioned horizontally. Therefore the plain format has a macro \skew that effectively shifts the top accent. Its definition is

For the correct positioning of accents over single characters the symbol and extension font have a \skewchar: this is the largest accent that adds to the width of an accented character. Positioning of any accent is based on the width of the character to be accented, followed by the skew character.

The skew characters of the Computer Modern math italic and symbol fonts are character "7F, '', and "30, '0', respectively. The \defaultskewchar value is assigned to the \skewchar when a font is loaded. In plain TeX this is -1, so fonts ordinarily have no \skewchar.

Math accents can adapt themselves to the size of the accented expression:

21.4 Math accents 217

TEX will look for a successor of an accent in the same way that it looks for a successor of a delimiter. In the Computer Modern math fonts this mechanism is used in the \widehat and \widetilde macros. For example,

\widehat x, \widehat{xy}, \widehat{xyz} give 
$$\widehat{x}, \, \widehat{xy}, \, \widehat{xyz}$$

respectively.

## 第 22 章 Fonts in Formulas

For math typesetting a single current font is not sufficient, as it is for text typesetting. Instead TEX uses several font families, and each family can contain three fonts. This chapter explains how font families are organized, and how TEX determines from what families characters should be taken.

\fam The number of the current font family.

\newfam Allocate a new math font family.

\textfont Access the textstyle font of a family.

\scriptfont Access the scriptstyle font of a family.

\scriptscriptfont Access the scriptscriptstyle font of a family.

## 22.1 Determining the font of a character in math mode

The characters in math formulas can be taken from several different fonts (or better, font families) without any user commands. For instance, in plain  $T_E X$  math formulas use the roman font, the math italic font, the symbol font and the math extension font.

In order to determine from which font a character is to be taken, TEX considers for each character in a formula its \mathcode (this is treated in Chapter 21). A \mathcode is a 15-bit number of the form "xyzz, where the hex digits have the following meaning:

x: class, y: family,

zz: position in font.

In general only the family determines from what font a character is to be taken. The class of a math character is mostly used to control spacing and other aspects of typesetting. Typical classes include 'relation', 'operator', 'delimiter';

see section 23.3 for details.

Class 7 is special in this respect: it is called 'variable family'. If a character has a \mathcode of the form "7yzz it is taken from family y, unless the parameter \fam has a value in the range 0–15; then it is taken from family \fam.

## 22.2 Initial family settings

Both lowercase and uppercase letters are defined by IniTEX to have math codes "71zz, which means that they are of variable family, initially from family 1. As TEX sets fam=-1, that is, an invalid value, when a formula starts, characters are indeed taken from family 1, which in plain TEX is math italic.

Digits have math code "70zz so they are initially from family 0, in plain  $T_E X$  the roman font. All other character codes have a mathcode assigned by  $IniT_E X$  as

```
\mathcode x = x
```

which puts them in class 0, ordinary, and family 0, roman in plain TpX.

In plain TFX, commands such as \s1 then set both a font and a family:

```
\def\sl{\fam\slfam\tensl}
```

so putting \s1 in a formula will cause all letters, digits, and uppercase Greek characters, to change to slanted style.

In most cases, any font can be assigned to any family, but two families in TEX have a special meaning: these are families 2 and 3. For instance, their number of \fontdimen parameters is different from the usual 7. Family 2 needs 22 parameters, and family 3 needs 13. These parameters have all a very specialized meaning for positioning in math typesetting. Their meaning is explained below, but for the full story the reader is referred to appendix G of the TEX book.

## 22.3 Family definition

T<sub>E</sub>X can access 16 families of fonts in math mode; font families have numbers 0–15. The number of the current family is recorded in the parameter \fam.

The macro \newfam gives the number of an unused family. This number is assigned using \chardef to the control sequence.

Each font family can have a font meant for text style, script style, and scriptscript style. Below it is explained how TFX determines in what style a

(sub-) formula is to be typeset.

Fonts are assigned to a family as follows:

```
\newfam\MyFam
\textfont\MyFam=\tfont \scriptfont\MyFam=\sfont
\scriptscriptfont\MyFam=\ssfont
```

for the text, script, and scriptscript fonts of a family. In general it is not necessary to fill all three members of a family (but it is for family 3). If TeX needs a character from a family member that has not been filled, it uses the \nullfont instead, a primitive font that has no characters (nor a .tfm file).

## 22.4 Some specific font changes

#### 22.4.1 Change the font of ordinary characters and uppercase Greek

All letters and the uppercase Greek characters are by default in plain  $T_EX$  of class 7, variable family, so changing  $\dagger$  will change the font from which they are taken. For example

```
{\text{n=9 x}}
```

gives an x from family 9.

Uppercase Greek characters are defined by \mathchardef statements in the plain format as "70zz, that is, variable family, initially roman. Therefore, uppercase Greek character also change with the family.

## 22.4.2 Change uppercase Greek independent of text font

In the Computer Modern font layout, uppercase Greek letters are part of the roman font; see page 341. Therefore, introducing another text font (with another layout) will change the uppercase Greek characters (or even make them disappear). One way of remedying this is by introducing a new family in which the cmr font, which contains the uppercase Greek, resides. The control sequences accessing these characters then have to be redefined:

22.5 Assorted remarks 221

Note, by the way, the absence of a either a space or a \relax token after #1 in the definition of \hex. This implies that this macro can only be called with an argument that is a control sequence.

#### 22.4.3 Change the font of lowercase Greek and mathematical symbols

Lowercase Greek characters have math code "01zz, meaning they are always from the math italic family. In order to change this one might redefine them, for instance \mathchardef\alpha=10B, to make them variable family. This is not done in plain TeX, because the Computer Modern roman font does not have Greek lowercase, although it does have the uppercase characters.

Another way is to redefine them like \mathchardef\alpha="0n0B where n is the (hexadecimal) number of a family compatible with math italic, containing for instance a bold math italic font.

#### 22.5 Assorted remarks

#### 22.5.1 New fonts in formulas

There are two ways to access a font inside mathematics. After  $font = \dots$  it is not possible to get the 'a' of the new font by  $\dots font a \dots$  because TeX does not look at the current font in math mode. What does work is

```
$ ... \hbox{\newfont a} ...$
```

but this precludes the use of the new font in script and scriptscript styles.

The proper solution takes a bit more work:

```
\font\newtextfont=...
\font\newscriptfont=... \font\newscriptfont=...
\newfam\newfontfam
\textfont\newfontfam=\newtextfont
\scriptfont\newfontfam=\newscriptfont
\scriptscriptfont\newfontfam=\newscriptfont
\def\newfont{\newtextfont \fam=\newfontfam}
```

after which the font can be used as

```
$... {\newfont a_{b_c}} ...$
```

in all three styles.

## 22.5.2 Evaluating the families

TeX will only look at what is actually in the \textfont et cetera of the various families at the end of the whole formula. Switching fonts in the families is thus not possible inside a single formula. The number of 16 families may therefore turn out to be restrictive for some applications.

# 第 23 章 Mathematics Typesetting

TEX has two math modes, display and non-display, and four styles, display, text, script, and scriptscript style, and every object in math mode belongs to one of eight classes. This chapter treats these concepts.

\everymath Token list inserted at the start of a non-display formula.

\everydisplay Token list inserted at the start of a display formula.

\displaystyle Select the display style of mathematics typesetting.

\textstyle Select the text style of mathematics typesetting.

\scriptstyle Select the script style of mathematics typesetting.

\scriptscriptstyle Select the scriptscript style of mathematics typesetting.

\mathchoice Give four variants of a formula for the four styles of mathematics typesetting.

\mathord Let the following character or subformula function as an ordinary object.

\mathop Let the following character or subformula function as a large operator.

\mathbin Let the following character or subformula function as a binary operation.

\mathrel Let the following character or subformula function as a relation.

\mathopen Let the following character or subformula function as a opening symbol.

\mathclose Let the following character or subformula function as a closing symbol.

\mathpunct Let the following character or subformula function as a punctuation symbol.

\mathinner Let the following character or subformula function as an inner

formula.

\mathaccent Place an accent in math mode.

\vcenter Construct a vertical box, vertically centred on the math axis.

\limits Place limits over and under a large operator.

\nolimits Place limits of a large operator as subscript and superscript expressions.

\displaylimits Restore default placement for limits.

\scriptspace Extra space after subscripts and superscripts. Plain TEX default: 0.5pt

\nonscript Cancel the next glue item if it occurs in scriptstyle or scriptscriptstyle.

\mkern Insert a kern measured in mu units.

\mskip Insert glue measured in mu units.

\muskip Prefix for skips measured in mu units.

\muskipdef Define a control sequence to be a synonym for a \muskip register.

\newmuskip Allocate a new muskip register.

\thinmuskip Small amount of mu glue.

\medmuskip Medium amount of mu glue.

\thickmuskip Large amount of mu glue.

\mathsurround Kern amount placed before and after in-line formulas.

\over Fraction.

\atop Place objects over one another.

\above Fraction with specified bar width.

\overwithdelims Fraction with delimiters.

\atopwithdelims Place objects over one another with delimiters.

\abovewithdelims Generalized fraction with delimiters.

\underline Underline the following \(math \) symbol\() or group.

\overline Overline the following \(math\) symbol\() or group.

\relpenalty Penalty for breaking after a binary relation not enclosed in a subformula. Plain TeX default: 500

\binoppenalty Penalty for breaking after a binary operator not enclosed in a subformula. Plain TFX default: 700

\allowbreak Macro for creating a breakpoint.

23.1 Math modes 225

#### 23.1 Math modes

TeX changes to *math mode* when it encounters a *math shift character*, category 3, in the input. After such an opening math shift it investigates (without expansion) the next token to see whether this is another math shift. In the latter case TeX starts processing in *display math mode* until a closing double math shift is encountered:

.. \$\$ displayed formula \$\$ ...

Otherwise it starts processing an in-line formula in *non-display math mode*:

.. \$ in-line formula \$ ..

The single math shift character is a (horizontal command).

Exception: displays are not possible in restricted horizontal mode, so inside an hbox the sequence \$\$ is an empty math formula and not the start of a displayed formula.

Associated with the two math modes are two \(\)token parameter\(\) registers (see also Chapter 14): at the start of an in-line formula the \(\)everymath tokens are inserted; at the start of a displayed formula the \(\)everydisplay tokens are inserted. Display math is treated further in the next chapter.

Math modes can be tested for: \ifmmode is true in display and non-display math mode, and \iffinner is true in non-display mode, but not in display mode.

## 23.2 Styles in math mode

Math formulas are set in any of eight *math styles*:

**D** display style,

T text style,

S script style,

SS scriptscript style,

and the four *cramped styles* variants D', T', S', SS' of these. The cramped styles differ mainly in the fact that superscripts are not raised as far as in the original styles.

## 23.2.1 Superscripts and subscripts

TEX can typeset a symbol or group as a superscript (or subscript) to the preceding symbol or group, if that preceding item does not already have a superscript (subscript). Superscripts (subscripts) are specified by the syntax

```
⟨superscript⟩⟨math field⟩
```

or

```
⟨subscript⟩⟨math field⟩
```

where a  $\langle superscript \rangle$  ( $\langle subscript \rangle$ ) is either a character of category 7 (8), or a control sequence \let to such a character. The plain format has the control sequences

```
\let\sp=^ \let\sb=_
```

as implicit superscript and subscript characters.

Specifying a superscript (subscript) expression as the first item in an empty math list is equivalent to specifying it as the superscript (subscript) of an empty expression. For instance,

```
^{\cdot} is equivalent to ^{\cdot}
```

For TEX's internal calculations, superscript and subscript expressions are made wider by \scriptspace; the value of this in plain TEX is 0.5pt.

## 23.2.2 Choice of styles

Ordering the four styles D, T, S, and SS, and considering the other four as mere variants, the style rules for math mode are as follows:

- In any style superscripts and subscripts are taken from the next smaller style. Exception: in display style they are taken in script style.
- Subscripts are always in the cramped variant of the style; superscripts are only cramped if the original style was cramped.
- In an {..\over..} formula in any style the numerator and denominator are taken from the next smaller style.
- The denominator is always in cramped style; the numerator is only in cramped style if the original style was cramped.
- Formulas under a \sqrt or \overline are in cramped style.

Styles can be forced by the explicit commands \displaystyle, \textstyle, \scriptstyle, and \scriptscriptstyle.

In display style and text style the \textfont of the current family is used, in scriptstyle the \scriptfont is used, and in scriptscriptstyle the \scriptscriptfont is used.

The primitive command

 $\mathbb{T}_{S}\{S\}$ 

lets the user specify four variants of a formula for the four styles. TeX constructs all four and inserts the appropriate one.

## 23.3 Classes of mathematical objects

Objects in math mode belong to one of eight  $math\ classes$ . Depending on the class the object may be surrounded by some amount of white space, or treated specially in some way. Commands exist to force symbols, or sequences of symbols, to act as belonging to a certain class. In the hexadecimal representation "xyzz the class is the  $\langle 3\text{-bit number} \rangle$  x.

This is the list of classes and commands that force those classes. The examples are from the plain format (see the tables starting at page 346).

- 1. *ordinary*: lowercase Greek characters and those symbols that are 'just symbols'; the command \mathord forces this class.
- 2. *large operator*: integral and sum signs, and 'big' objects such as \bigcap or \bigotimes; the command \mathop forces this class. Characters that are large operators are centred vertically, and they may behave differently in display style from in the other styles; see below.
- 3. *binary operation*: plus and minus, and things such as \cap or \otimes; the command \mathbin forces this class.
- 4. *relation* (also called *binary relation*): equals, less than, and greater than signs, subset and superset, perpendicular, parallel; the command \mathrel forces this class.
- 5. *opening symbol*: opening brace, bracket, parenthesis, angle, floor, ceiling; the command \mathopen forces this class.
- 6. *closing symbol*: closing brace, bracket, parenthesis, angle, floor, ceiling; the command \mathclose forces this class.
- 7. *punctuation*: most punctuation marks, but : is a relation, the \colon is a punctuation colon; the command \mathpunct forces this class.
- 8. variable family: symbols in this class change font with the \fam parameter;

in plain TEX uppercase Greek letters and ordinary letters and digits are in this class.

There is one further class: the *inner* subformulas. No characters can be assigned to this class, but characters and subformulas can be forced into it by \mathinner. The  $\langle generalized\ fraction \rangle s$  and  $\ensuremath{\texttt{left...}}$  right groups are inner formulas. Inner formulas are surrounded by some white space; see the table below.

Other subformulas than those that are inner are treated as ordinary symbols. In particular, subformulas enclosed in braces are ordinary: a+b looks like a+b. Note, however, that in a+b the whole subformula is treated as an ordinary symbol, not its components; therefore the result is a+b.

## 23.4 Large operators and their limits

The large operators in the Computer Modern fonts come in two sizes: one for text style and one for display style. Control sequences such as \sum are simply defined by \mathchardef to correspond to a position in a font:

```
\mathchardef\sum="1350
```

but if the current style is display style, TEX looks to see whether that character has a successor in the font.

Large operators in text style behave as if they are followed by \nolimits, which places the limits as sub/superscript expressions after the operator:

$$\sum_{k=1}^{\infty}$$

In display style they behave as if they are followed by \limits, which places the limits over and under the operator:

$$\sum_{k=1}^{\infty}$$

The successor mechanism (see page 214) lets TeX take a larger variant of the delimiter here.

The integral sign has been defined in plain  $T_E X$  as

\mathchardef\intop="1352 \def\int{\intop\nolimits}

which places the limits after the operator, even in display style:

$$\int_0^\infty e^{-x^2} dx = \sqrt{\pi}/2$$

With \limits\nolimits or \nolimits\limits the last specification has prece-

dence; the default placement can be restored by \displaylimits. For instance,

```
$ ... \sum\limits\displaylimits ... $
is equivalent to
   $ ... \sum ... $
and
   $$ ... \sum\nolimits\displaylimits ... $$
is equivalent to
   $$ ... \sum ... $$
```

## 23.5 Vertical centring: \vcenter

Each formula has an *axis*, which is for an in-line formula about half the x-height of the surrounding text; the exact value is the \fontdimen22 of the font in family 2, the symbol font, in the current style.

The bar line in fractions is placed on the axis; large operators, delimiters and \vcenter boxes are centred on it.

A \vcenter box is a vertical box that is arranged so that it is centred on the math axis. It is possible to give a spread or to specification with a \vcenter box.

The \vcenter box is allowed only in math mode, and it does not behave like other boxes; for instance, it can not be stored in a box register. It does not qualify as a  $\langle box \rangle$ . See page 149 for a macro that repairs this.

## 23.6 Mathematical spacing: mu glue

Spacing around mathematical objects is measured in *math units*: multiples of a mu. A mu is 1/18th part of \fontdimen6 of the font in family 2 in the current style, the *quad* value of the symbol font.

## 23.6.1 Classification of mu glue

The user can specify mu spacing by \mkern or \mskip, but most *mu glue* is inserted automatically by TEX, based on the classes to which objects belong (see above). First, here are some rules of thumb describing the global behaviour.

A \thickmuskip (default value in plain TpX: 5mu plus 5mu) is inserted around

(binary) relations, except where these are preceded or followed by other relations or punctuation, and except if they follow an open, or precede a close symbol.

- A \medmuskip (default value in plain TEX: 4mu plus 2mu minus 4mu) is put around binary operators.
- A \thinmuskip (default value in plain TeX: 3mu) follows after punctuation, and is put around inner objects, except where these are followed by a close or preceded by an open symbol, and except if the other object is a large operator or a binary relation.
- No mu glue is inserted after an open or before a close symbol except where
  the latter is preceded by punctuation; no mu glue is inserted also before
  punctuation, except where the preceding object is punctuation or an inner
  object.

The following table gives the complete definition of mu glue between math objects.

	0:	1:	2:	3:	4:	5:	6:	
	Ord	Op	Bin	Rel	Open	${\bf Close}$	Punct	Inner
0: Ord	0	1	(2)	(3)	0	0	0	(1)
1: Op	1	1	*	(3)	0	0	0	(1)
2: Bin	(2)	(2)	*	*	(2)	*	*	(2)
3: Rel	(3)	(3)	*	0	(2)	*	*	(2)
4: Open	0	0	*	0	0	0	0	0
5: Close	0	1	<b>(2)</b>	(3)	0	0	0	(1)
6: Punct	(1)	(1)	*	(1)	(1)	(1)	(1)	(1)
Inner	(1)	1	(2)	(3)	(1)	0	(1)	(1)

where the symbols have the following meanings:

- 0, no space; 1, thin space; 2, medium space; 3, thick space;
- ullet ( $\cdot$ ), insert only in text and display mode, not in script or scriptscript mode;
- cases \* cannot occur, because a Bin object is converted to Ord if it is the
  first in the list, preceded by Bin, Op, Open, Punct, Rel, or followed by Close,
  Punct, and Rel; also, a Rel is converted to Ord when it is followed by Close
  or Punct.

Stretchable mu glue is set according to the same rules that govern ordinary glue. However, only mu glue on the outer level can be stretched or shrunk; any mu glue enclosed in a group is set at natural width.

#### 23.6.2 Muskip registers

Like ordinary glue, mu glue can be stored in registers, the \muskip registers, of which there are 256 in TeX. The registers are denoted by

```
\muskip(8-bit number)
```

and they can be assigned to a control sequence by

```
\mbox{\mbox{\tt muskipdef}} \langle \mbox{\tt control sequence} \rangle \langle \mbox{\tt equals} \rangle \langle \mbox{\tt 8-bit number} \rangle
```

and there is a macro that allocates unused registers:

```
\newmuskip\(control\) sequence\()
```

Arithmetic for mu glue exists as for glue; see Chapter 8.

#### 23.6.3 Other spaces in math mode

In math mode space tokens are ignored; however, the math code of the space character is "8000 in plain T<sub>E</sub>X, so if its category is made 'letter' or 'other character', it will behave like an active character in math mode. See also page 213.

Admissible glue in math mode is of type  $\langle mathematical \ skip \rangle$ , which is either a  $\langle horizontal \ skip \rangle$  (see Chapter 6) or  $\langle mskip \rangle$ . Leaders in math mode can be specified with a  $\langle mathematical \ skip \rangle$ .

A glue item preceded by \nonscript is cancelled if it occurs in scriptstyle or scriptscriptstyle.

Control space functions in math mode as it does in horizontal mode.

In-line formulas are surrounded by kerns of size \mathsurround, the so-called 'math-on' and 'math-off' items. Line breaking can occur at the front of the math-off kern if it is followed by glue.

## 23.7 Generalized fractions

Fraction-like objects can be set with six primitive commands of type  $\langle generalized fraction \rangle$ . Each of these *generalized fractions* takes the preceding and the following subformulas and puts them over one another, if necessary with a fraction bar and with delimiters.

\over is the ordinary fraction; the bar thickness is \fontdimen8 of the extension font:

```
\pi gives \frac{\pi}{2}
```

\atop is equivalent to a fraction with zero bar thickness:

```
\pi gives \pi
```

\above(dimen) specifies the thickness of the bar line explicitly:

```
\pi spi above 1pt 2$ gives \frac{\pi}{2}
```

To each of these three there corresponds a \...withdelims variant that lets the user specify delimiters for the expression. For example, the most general command, in terms of which all five others could have been defined, is

```
\above with delims \langle delim_1 \rangle \langle delim_2 \rangle \langle dimen \rangle.
```

Delimiters in these generalized fractions do not grow with the enclosed expression: in display mode a delimiter is taken which is at least \fontdimen20 high, otherwise it has to be at least \fontdimen21 high. These dimensions are taken from the font in family 2, the symbol font, in the current style.

The control sequences \over, \atop, and \above are primitives, although they could have been defined as \...withdelims.., that is, with two null delimiters. Because of these implied surrounding null delimiters, there is a kern of size \nulldelimiterspace before and after these simple generalized fractions.

## 23.8 Underlining, overlining

The primitive commands \underline and \overline take a  $\langle$  math field $\rangle$  argument, that is, a  $\langle$  math symbol $\rangle$  or a group, and draw a line under or over it. The result is an 'Under' or 'Over' atom, which is appended to the current math list. The line thickness is font dimension 8 of the extension font, which also determines the clearance between the line and the  $\langle$  math field $\rangle$ .

Various other  $\omega_{EX}$ ; these are all macros that use the  $T_{EX}$   $\amplie_{EX}$  halign command.

## 23.9 Line breaking in math formulas

In-line formulas can be broken after relations and binary operators. The respective *penalties* are the \relpenalty and the \binoppenalty. However, TEX will only break after such symbols if they are not enclosed in braces. Other *breakpoints* can be created with \allowbreak, which is an abbreviation for \penalty0.

Unlike in horizontal or vertical mode where putting two penalties in a row is equivalent to just placing the smallest one, in math mode a penalty placed at

a break point —— that is, after a relation or binary operator —— will effectively replace the old penalty by the new one.

#### 23.10 Font dimensions of families 2 and 3

If a font is used in text mode, TEX will look at its first 7 \fontdimen parameters (see page 51), for instance to control spacing. In math, however, more font dimensions are needed. TEX will look at the first 22 parameters of the fonts in family 2, and the first 13 of the fonts in family 3, to control various aspects of math typesetting. The next two subsections have been quoted loosely from [?].

#### 23.10.1 Symbol font attributes

Attributes of the font in family 2, the *symbol font*, mainly specify the initial vertical positioning of parts of fractions, subscripts, superscripts, et cetera. The position determined by applying these attributes may be further modified because of other conditions, for example the presence of a fraction bar.

One text font dimension, number 6, the quad, determines the size of mu glue; see above.

Fraction numerator attributes: minimum shift up, from the main baseline, of the baseline of the numerator of a generalized fraction,

- 8. num1: for display style,
- 9. num2: for text style or smaller if a fraction bar is present,
- 10. num3: for text style or smaller if no fraction bar is present.

Fraction denominator attributes: minimum shift down, from the main baseline, of the baseline of the denominator of a generalized fraction,

- 11. denom1: for display style,
- 12. denom2: for text style or smaller.

Superscript attributes: minimum shift up, from the main baseline, of the baseline of a superscript,

- 13. sup1: for display style,
- 14. sup2: for text style or smaller, non-cramped,
- 15. sup3: for text style or smaller, cramped.

Subscript attributes: minimum shift down, from the main baseline, of the baseline of a subscript,

- 16. sub1: when no superscript is present,
- 17. sub2: when a superscript is present.

Script adjustment attributes: for use only with non-glyph, that is, composite, objects.

- 18. sup\_drop: maximum distance of superscript baseline below top of nucleus
- 19. sub\_drop: minimum distance of subscript baseline below bottom of nucleus.

Delimiter span attributes: height plus depth of delimiter enclosing a generalized fraction,

- 20. delim1: in display style,
- 21. delim2: in text style or smaller.

A parameter with many uses, the height of the math axis,

22. axis\_height: the height above the baseline of the fraction bar, and the centre of large delimiters and most operators and relations. This position is used in vertical centring operations.

#### 23.10.2 Extension font attributes

Attributes of the font in family 3, the *extension font*, mostly specify the way the limits of large operators are set.

The first parameter, number 8, default\_rule\_thickness, serves many purposes. It is the thickness of the rule used for overlines, underlines, radical extenders (square root), and fraction bars. Various clearances are also specified in terms of this dimension: between the fraction bar and the numerator and denominator, between an object and the rule drawn by an underline, overline, or radical, and between the bottom of superscripts and top of subscripts.

Minimum clearances around large operators are as follows:

- 9. big\_op\_spacing1: minimum clearance between baseline of upper limit and top of large operator; see below.
- 10. big\_op\_spacing2: minimum clearance between bottom of large operator and top of lower limit.
- 11. big\_op\_spacing3: minimum clearance between baseline of upper limit and top of large operator, taking into account depth of upper limit; see below.
- 12. big\_op\_spacing4: minimum clearance between bottom of large operator and top of lower limit, taking into account height of lower limit; see below.
- 13. big\_op\_spacing5: clearance above upper limit or below lower limit of a large

operator.

The resulting clearance above an operator is the maximum of parameter 7, and parameter 11 minus the depth of the upper limit. The resulting clearance below an operator is the maximum of parameter 10, and parameter 12 minus the height of the lower limit.

## 23.10.3 Example: subscript lowering

The location of a subscript depends on whether there is a superscript; for instance

$$X_1 + Y_1^2 = 1$$

If you would rather have that look like

$$X_1 + Y_1^2 = 1$$
,

it suffices to specify

\fontdimen16\textfont2=3pt \fontdimen17\textfont2=3pt

which makes the subscript drop equal in both cases. Since font dimension assignments are global, you have to specify this only once in your document.

# 第 24 章 Display Math

Displayed formulas are set on a line of their own, usually somewhere in a paragraph. This chapter explains how surrounding white space (both above/below and to the left/right) is calculated.

\abovedisplayskip \belowdisplayskip Glue above/below a display. Plain TrX default: 12pt plus 3pt minus 9pt

\abovedisplayshortskip \belowdisplayshortskip Glue above/below a display if the line preceding the display was short. Plain TEX defaults: Opt plus 3pt and 7pt plus 3pt minus 4pt respectively.

\predisplaypenalty \postdisplaypenalty Penalty placed in the vertical list above/below a display. Plain TeX defaults: 10 000 and 0 respectively.

\displayindent Distance by which the box, in which the display is centred, is indented owing to hanging indentation.

\displaywidth Width of the box in which the display is centred.

\predisplaysize Effective width of the line preceding the display.

\everydisplay Token list inserted at the start of a display.

\eqno Place a right equation number in a display formula.

\leqno Place a left equation number in a display formula.

## 24.1 Displays

TEX starts building a *display math* formula when it encounters two math shift characters (characters of category 3, \$ in plain TEX) in a row. Another such pair (possibly followed by one optional space) indicates the end of the display.

Math shift is a \(\lambda\) horizontal command\(\rangle\), but displays are only allowed in unrestricted horizontal mode (\$\$ is an empty math formula in restricted horizontal

mode). Displays themselves, however, are started in the surrounding (possibly internal) vertical mode in order to calculate quantities such as \prevgraf; the result of the display is appended to the vertical list.

The part of the paragraph above the display is broken into lines as an independent paragraph (but \prevgraf is carried over; see below), and the remainder of the paragraph is set, starting with an empty list and \spacefactor equal to 1000. The \everypar tokens are not inserted for the part of the paragraph after the display, nor is \parskip glue inserted.

Right at the beginning of the display the \everydisplay token list is inserted (but after the calculation of \displayindent, \displaywidth, and \predisplaysize). See page 241 for an example of the use of \everydisplay.

The page builder is exercised before the display (but after the \everydisplay tokens have been inserted), and after the display finishes.

The 'display style' of math typesetting was treated in Chapter 22.

## 24.2 Displays in paragraphs

Positioning of a display in a paragraph may be influenced by hanging indentation or a \parshape specification. For this, TEX uses the \prevgraf parameter (see Chapter 18), and acts as if the display is three lines deep.

If n is the value of \prevgraf when the display starts — so there are n lines of text above the display — \prevgraf is set to to n+3 when the paragraph resumes. The display occupies, as it were, lines n+1, n+2, and n+3. The shift and line width for the display are those that would hold for line n+2.

The shift for the display is recorded in \displayindent; the line width is recorded in

\displaywidth. These parameters (and the \predisplaysize explained below) are set immediately after the \$\$ has been scanned. Usually they are equal to zero and \hsize respectively. The user can change the values of these parameters; TeX will use the values that hold after the math list of the display has been processed.

A display is vertical material, and therefore not influenced by settings of \leftskip and \rightskip.

## 24.3 Vertical material around displays

A display is preceded in the vertical list by

- a penalty of size \predisplaypenalty (plain TFX default 10000), and
- glue of size \abovedisplayskip or \abovedisplayshortskip; this glue is omitted in cases where a \leqno equation number is set on a line of its own (see below).

#### A display is followed by

- a penalty of size \postdisplaypenalty (default 0), and possibly
- glue of size \belowdisplayskip or \belowdisplayshortskip; this glue is omitted in cases where an \eqno equation number is set on a line of its own (see below).

The 'short' variants of the glue are taken if there is no \leqno left equation number, and if the last line of the paragraph above the display is short enough for the display to be raised a bit without coming too close to that line. In order to decide this, the effective width of the preceding line is saved in \predisplaysize. This value is calculated immediately after the opening \$\$ of the display has been scanned, together with the \displaywidth and \displayindent explained above.

Remembering that the part of the paragraph above the display has already been broken into lines, the following method for finding the effective width of the last line ensues. TEX takes the last box of the list, which is a horizontal box containing the last line, and locates the right edge of the last box in it. The \predisplaysize is then the place of that rightmost edge, plus any amount by which the last line was shifted, plus two ems in the current font.

There are two exceptions to this. The \predisplaysize is taken to be \maxdimen if there was no previous line, that is, the display started the paragraph, or it followed another display; \predisplaysize is taken to be \maxdimen if the glue in the last line was not set at its natural width, which may happen if the \parfillskip contained only finite stretch. The reason for the last clause is that glue setting is slightly *machinedependent*, and such dependences should be kept out of TeX's global decision processes.

## 24.4 Glue setting of the display math list

The display has to fit in \displaywidth, but in addition to the formula there may be an equation number. The minimum separation between the formula and the equation number should be one em in the symbol font, that is, \fontdimen6 \textfont2.

If the formula plus any equation number and separation fit into \displaywidth, the glue in the formula is set at its natural width. If it does not fit, but the formula contains enough shrink, it is shrunk. Otherwise TeX puts any equation number on a line of its own, and the glue in the formula is set to fit it in \displaywidth. With the equation number on a separate line the formula may now very well fit in the display width; however, if it was a very long formula the box in which it is set may still be overfull. TeX nevers breaks a displayed formula.

## 24.5 Centring the display formula: displacement

Based on the width of the box containing the formula —— which may not really 'contain' it; it may be overfull —— TEX tries to centre the formula in the \displaywidth, that is, without taking the equation number into account. Initially, a displacement is calculated that is half the difference between \displaywidth and the width of the formula box.

However, if there is an equation number that will not be put on a separate line and the displacement is less than twice the width of the equation number, a new displacement is calculated. This new displacement is zero if the formula started with glue; otherwise it is such that the formula box is centred in the space left by the equation number.

If there was no equation number, or if the equation number will be put on a separate line, the formula box is now placed, shifted right by \displayindent plus the displacement calculated above.

## 24.6 Equation numbers

The user can specify a equation number for a display by ending it with  $\verb| eqno| (math\ mode\ material) $$$ 

for an equation number placed on the right, or

\leqno\math mode material\\$\$

for an equation number placed on the left.

#### 24.6.1 Ordinary equation numbers

Above it was described how TeX calculates a displacement from the display formula and the equation number, if this is to be put on the same line as the formula.

If the equation number was a \leqno number, TeX places a box containing

- the equation number,
- a kern with the size of the displacement calculated, and
- · the formula.

This box is shifted right by \displayindent.

If the equation number was an \eqno number, TEX places a box containing

- the formula,
- a kern with the size of the displacement calculated, and
- the equation number.

This box is shifted right by \displayindent plus the displacement calculated.

## 24.6.2 The equation number on a separate line

Since displayed formulas may become rather big, TeX can decide (as was described above) that any equation number should be placed on a line of its own. A left-placed equation number is then to be placed above the display, in a box that is shifted right by \displayindent; a right-placed equation number will be placed below the display, in a box that is shifted to the right by \displayindent plus \displaywidth minus the width of the equation number box.

In both cases a penalty of  $10\,000$  is placed between the equation number box and the formula.

TEX does not put extra glue above a left-placed equation number or below a right-placed equation number; TEX here relies on the baselineskip mechanism.

## 24.7 Non-centred displays

As a default, TEX will center displays. In order to get *non-centred displays* some macro trickery is needed.

One approach would be to write a macro *\DisplayEquation* that would basically look like

```
\def\DisplayEquation#1{%
   \par \vskip\abovedisplayskip
   \hbox{\kern\parindent$\displaystyle#1$}
   \vskip\belowdisplayskip \noindent}
```

but it would be nicer if one could just write

```
$$ ... \eqno ... $$
```

and having this come out as a leftaligning display.

Using the \everydisplay token list, the above idea can be realized. The basic idea is to write

```
\everydisplay{\IndentedDisplay}
\def\IndentedDisplay#1$${ ...
```

so that the macro \IndentedDisplay will receive the formula, including any equation number. The first step is now to extract an equation number if it is present. This makes creative use of delimited macro parameters.

```
\def\ExtractEqNo#1\eqno#2\eqno#3\relax
   {\def\Equation{#1}\def\EqNo{#2}}
\def\IndentedDisplay#1$${%
   \ExtractEqNo#1\eqno\eqno\relax
```

Next the equation should be set in the available space \displaywidth:

Note that the macro ends in the closing \$\$ to balance the opening dollars that caused insertion of the \everydisplay tokens. This also means that the box containing the displayed material will automatically be surrounded by \abovedisplayskip and \belowdisplayskip glue. There is no need to use \displayindent anywhere in this macro, because  $T_EX$  itself will shift the display appropriately.

# 第 25 章 Alignment

TFX provides a general alignment mechanism for making *tables*.

\halign Horizontal alignment.

\valign Vertical alignment.

\omit Omit the template for one alignment entry.

\span Join two adjacent alignment entries.

\multispan Macro to join a number of adjacent alignment entries.

\tabskip Amount of glue in between columns (rows) of an \halign (\valign).

\noalign Specify vertical (horizontal) material to be placed in between rows (columns) of an \halign (\valign).

\cr Terminate an alignment line.

\crcr Terminate an alignment line if it has not already been terminated by \cr.

\everycr Token list inserted after every \cr or non-redundant \crcr.

 $\label{thm:centering} \ Glue\ register\ in\ plain\ TE\!X\ for\ centring\ \eqalign\ and\ \eqalignno.$ 

Value: Opt plus 1000pt minus 1000pt

\hideskip Glue register in plain TpX to make alignment entries invisible.

Value: -1000pt plus 1fill

\hidewidth Macro to make preceding or following entry invisible.

#### 25.1 Introduction

TEX has a sophisticated alignment mechanism, based on templates, with one template entry per column or row. The templates may contain any common elements of the table entries, and in general they contain instructions for typesetting the entries. TEX first calculates widths (for \halign) or heights (for

\valign) of all entries; then it typesets the whole alignment using in each column (row) the maximum width (height) of entries in that column (row).

## 25.2 Horizontal and vertical alignment

The two alignment commands in TFX are

for horizontal alignment of columns, and

```
\operatorname{valign}(\operatorname{box} \operatorname{specification}) \{(\operatorname{alignment} \operatorname{material})\}
```

for vertical alignment of rows.  $\$  is a  $\langle vertical\ command \rangle$ , and  $\$  is a  $\langle horizontal\ command \rangle$ .

The braces induce a new level of grouping; they can be implicit.

The discussion below will mostly focus on horizontal alignments, but, replacing 'column' by 'row' and vice versa, it applies to vertical alignments too.

#### 25.2.1 Horizontal alignments: \halign

A horizontal alignment yields a list of horizontal boxes, the rows, which are placed on the surrounding vertical list. The page builder is exercised after the alignment rows have been added to the vertical list. The value of \prevdepth that holds before the alignment is used for the baselineskip of the first row, and after the alignment \prevdepth is set to a value based on the last row.

Each entry is processed in a group of its own, in restricted horizontal mode.

A special type of horizontal alignment exists: the  $display\ alignment$ , specified as

Such an alignment is shifted by \displayindent (see Chapter 24) and surrounded by

\abovedisplayskip and \belowdisplayskip glue.

## 25.2.2 Vertical alignments: \valign

A *vertical alignment* can be considered as a 'rotated' horizontal alignments: they are placed on the surrounding horizontal lists, and yield a row of columns. The \spacefactor value is treated the same way as the \prevdepth for horizontal alignments: the value current before the alignment is used for the first

column, and the value reached after the last column is used after the alignment. In between columns the \spacefactor value is 1000.

Each entry is in a group of its own, and it is processed in internal vertical mode.

#### 25.2.3 Material between the lines: \noalign

Material that has to be contained in the alignment, but should not be treated as an entry or series of entries, can be given by

```
\noalign{filler}{{\operatorname{vertical mode material}}}
```

for horizontal alignments, and

```
\noalign{filler}{\langle horizontal mode material \rangle}
```

for vertical alignments.

Examples are

```
\noalign{\hrule}
```

for drawing a horizontal rule between two lines of an \halign, and

```
\noalign{\penalty100}
```

for discouraging a page break (or line break) in between two rows (columns) of an halign (valign).

## 25.2.4 Size of the alignment

The  $\langle box\ specification \rangle$  can be used to give the alignment a predetermined size: for instance

```
\halign to \hsize{ ... }
```

Glue contained in the entries of the alignment has no role in this; any stretch or shrink required is taken from the \tabskip glue. This is explained below.

## 25.3 The preamble

Each line in an alignment is terminated by \cr; the first line is called the *template line*. It is of the form

```
u_1 # v_1 \& \dots \& u_n # v_n \backslash \mathsf{cr}
```

where each  $u_i$ ,  $v_i$  is a (possibly empty) arbitrary sequence of tokens, and the template entries are separated by the *alignment tab* character (& in plain  $T_FX$ ),

25.3 The preamble 245

that is, any character of category 4.

A  $u_i \# v_i$  sequence is the template that will be used for the i th column: whatever sequence  $\alpha_i$  the user specifies as the entry for that column will be inserted at the parameter character. The sequence  $u_i \alpha_i v_i$  is then processed to obtain the actual entry for the i th column on the current line. See below for more details.

The length n of the template line need not be equal to the actual number of columns in the alignment: the template is used only for as many items as are specified on a line. Consider as an example

```
\halign{a#&b#&c#\cr 1&2\cr 1\cr}
```

which has a three-item template, but the rows have only one or two items. The output of this is

```
a1b2
a1
```

#### 25.3.1 Infinite preambles

For the case where the number of columns is not known in advance, for instance if the alignment is to be used in a macro where the user will specify the columns, it is possible to specify that a trailing piece of the preamble can be repeated arbitrarily many times. By preceding it with &, an entry can be marked as the start of this repeatable part of the preamble. See the example of \matrix below.

When the whole preamble is to be repeated, there will be an alignment tab character at the start of the first entry:

```
\halign{& ... & ... \cr ... }
```

If a starting portion of the preamble is to be exempted from repetition, a double alignment tab will occur:

```
\halign{ ... & ... & ... && ... \cr ... }
```

The repeatable part need not be used an integral number of times. The alignment rows can end at any time; the rest of the preamble is then not used.

## 25.3.2 Brace counting in preambles

Alignments may appear inside alignments, so TEX uses the following rule to determine to which alignment an & or \cr control sequence belongs:

All tab characters and \cr tokens of an alignment should be on the same level of grouping.

From this it follows that tab characters and \cr tokens can appear inside an entry if they are nested in braces. This makes it possible to have nested alignments.

#### 25.3.3 Expansion in the preamble

All tokens in the preamble — apart from the tab characters — are stored for insertion in the entries of the alignment, but a token preceded by \span is expanded while the preamble is scanned. See below for the function of \span in the rest of the alignment.

### 25.3.4 \tabskip

Entries in an alignment are set to take the width of the largest element in their column. Glue for separating columns can be specified by assigning to \tabskip. TEX inserts this glue in between each pair of columns, and before the first and after the last column.

The value of \tabskip that holds outside the alignment is used before the first column, and after all subsequent columns, unless the preamble contains assignments to \tabskip. Any assignment to \tabskip is executed while TEX is scanning the preamble; the value that holds when a tab character is reached will be used at that place in each row, and after all subsequent columns, unless further assignments occur. The value of \tabskip that holds when \cr is reached is used after the last column.

Assignments to \tabskip in the preamble are local to the alignment, but not to the entry where they are given. These assignments are ordinary glue assignments: they remove any optional trailing space.

As an example, in the following table there is no tabskip glue before the first and after the last column; in between all columns there is stretchable tabskip.

```
\tabskip=Opt \halign to \hsize{
    \vrule#\tabskip=Opt plus 1fil\strut&
    \hfil#\hfil& \vrule#& \hfil#\hfil& \vrule#& \hfil#\hfil&
    \tabskip=Opt\vrule#\cr
    \noalign{\hrule}
     &\multispan5\hfil Just a table\hfil&\cr
    \noalign{\hrule}
     &one&&two&&three&\cr &a&&b&&c&\cr
    \noalign{\hrule}
}
```

The result of this is

Just a table							
one	two	three					
a	b	c					

All of the vertical rules of the table are in a separate column. This is the only way to get the space around the items to stretch.

## 25.4 The alignment

After the template line any number of lines terminated by \cr can follow. TEX reads all of these lines, processing the entries in order to find the maximal width (height) in each column (row). Because all entries are kept in memory, long tables can overflow TEX's main memory. For such tables it is better to write a special-purpose macro.

#### 25.4.1 Reading an entry

Entries in an alignment are composed of the constant u and v parts of the template, and the variable  $\alpha$  part. Basically TeX forms the sequence of tokens  $u\alpha v$  and processes this. However, there are two special cases where TeX has to expand before it forms this sequence.

Above, the \noalign command was described. Since this requires a different treatment from other alignment entries,  $T_EX$  expands, after it has read a \cr, the first token of the first  $\alpha$  string of the next line to see whether that is or expands to \noalign. Similarly, for all entries in a line the first token is expanded to see whether it is or expands to \omit. This control sequence will be described below.

Entries starting with an \if... conditional, or a macro expanding to one, may be misinterpreted owing to this premature expansion. For example,

```
\halign{$#$\cr \ifmmode a\else b\fi\cr}
```

will give

h

because the conditional is evaluated before math mode has been set up. The solution is, as in many other cases, to insert a \relax control sequence to stop the expansion. Here the \relax has to be inserted at the start of the alignment entry.

If neither \noalign nor \omit (see below) is found, TFX will process an input

stream composed of the u part, the  $\alpha$  tokens (which are delimited by either & or \span, see below), and the v part.

Entries are delimited by &, \span, or \cr, but only if such a token occurs on the same level of grouping. This makes it possible to have an alignment as an entry of another alignment.

#### 25.4.2 Alternate specifications: \omit

The template line will rarely be sufficient to describe all lines of the alignment. For lines where items should be set differently the command \omit exists: if the first token in an entry is (or expands to) \omit the trivial template # is used instead of what the template line specifies.

例子:The following alignment uses the same template for all columns, but in the second column an \omit command is given.

```
\tabskip=1em
\halign{&$<#>$\cr a&\omit (b)&c \cr}
The output of this is
```

## 25.4.3 Spanning across multiple columns: \span

Sometimes it is desirable to have material spanning several columns. The most obvious example is that of a heading above a table. For this TEX provides the \span command.

Entries are delimited either by &, by \cr, or by \span. In the last case TeX will omit the tabskip glue that would normally follow the entry thus delimited, and it will typeset the material just read plus the following entry in the joint space available.

```
As an example,
\tabskip=1em
\halign{&#\cr a&b&c&d\cr a&\hrulefill\span\hrulefill&d\cr}

gives

a b c d
a ____ d
```

Note that there is no tabskip glue in between the two spanned columns, but there is tabskip glue before the first column and after the last. Using the  $\mbox{\sc ommand}$  this same alignment could have been generated as

```
\halign{&#\cr a&b&c&d\cr a&\hrulefill\span\omit&d\cr}
```

The  $\span\$  macro  $\mbox{multispan}$ : for instance

```
\multispan4 gives \omit\span\omit\span\omit\span\omit
```

which spans across three tabs, and removes the templates of four entries. Repeating the above example once again:

```
\halign{&#\cr a&b&c&d\cr a&\multispan2\hrulefill&d\cr}
```

The argument of \multispan is a single token, not a number, so in order to span more than 9 columns the argument should be enclosed in braces, for instance \multispan{12}. Furthermore, a space after a single-digit argument will wind up in the output.

For a 'low budget' solution to spanning columns plain TEX has the macro \hidewidth, defined by

```
\newskip\hideskip \hideskip=-1000pt plus 1fill
\def\hidewidth{\hskip\hideskip}
```

Putting \hidewidth at the beginning or end of an alignment entry will make its width zero, with the material in the entry sticking out to the left or right respectively.

## 25.4.4 Rules in alignments

Horizontal rules inside a horizontal alignment will mostly be across the width of the alignment. The easiest way to attain this is to use

```
\noalign{\hrule}
```

lines inside the alignment. If the alignment is contained in a vertical box, lines above and below the alignment can be specified with

```
\vbox{\hrule \halign{...} \hrule}
```

The most general way to get horizontal lines in an alignment is to use

```
\mbox{\mbox{\tt multispan}} n\mbox{\mbox{\tt hrulefill}}
```

which can be used to underline arbitrary adjacent columns.

Vertical rules in alignments take some more care. Since a horizontal alignment breaks up into horizontal boxes that will be placed on a vertical list, TEX will insert baselineskip glue in between the rows of the alignment. If vertical

rules in adjacent rows are to abut, it is necessary to prevent baselineskip glue, for instance by the \offinterlineskip macro.

In order to ensure that rows will still be properly spaced it is then necessary to place a *strut* somewhere in the preamble. A strut is an invisible object with a certain height and depth. Putting that in the preamble guarantees that every line will have at least that height and depth. In the plain format \strut is defined statically as

```
\vrule height8.5pt depth3.5pt width0pt
```

so this must be changed when other fonts or sizes are used.

It is a good idea to use a whole column for a vertical rule, that is, to write \vrule#&

in the preamble and to leave the corresponding entry in the alignment empty. Omitting the vertical rule can then be done by specifying \omit, and the size of the rule can be specified explicitly by putting, for instance, height 15pt in the entry instead of leaving it empty. Of course, tabskip glue will now be specified to the left and right of the rule, so some extra tabskip assignments may be needed in the preamble.

#### 25.4.5 End of a line: \cr and \crcr

All lines in an alignment are terminated by the  $\c$  control sequence, including the last line. TeX is not able to infer from a closing brace in the  $\alpha$  part that the alignment has ended, because an unmatched closing brace is perfectly valid in an alignment entry; it may match an opening brace in the u part of the corresponding preamble entry.

TEX has a primitive command \crcr that is equivalent to \cr, but it has no effect if it immediately follows a \cr. Consider as an example the definition in plain TEX of \cases:

```
\def\cases#1{%
  \left\{\,\vcenter{\normalbaselines\m0th
                \ialign{ $##\hfil$& \quad##\hfil \crcr #1\crcr}}%
  \right.}
```

Because of the \crcr after the user argument #1, the following two applications of this macro

```
\cses{1\&2\cr 3\&4} and \cses{1\&2\cr 3\&4\cr}
```

both work. In the first case the \crcr in the macro definition ends the last line; in the second case the user's \cr ends the line, and the \crcr is redundant.

After \cr and after a non-redundant \crcr the \tank token parameter \everycr is inserted. This includes the \cr terminating the template line.

## 25.5 Example: math alignments

The plain format has several alignment macros that function in math mode. One example is \matrix, defined by

```
\def\matrix#1{\null\,\vcenter{\normalbaselines\m0th
  \ialign{\hfil$##$\hfil && \quad\hfil$##$\hfil\crcr
        \mathstrut\crcr
        \noalign{\kern-\baselineskip}
        #1\crcr
        \mathstrut\crcr
        \noalign{\kern-\baselineskip}}\,}
```

This uses a repeating (starting with &&) second preamble entry; each entry is centred by an \hfil before and after it, and there is a \quad of space in between columns. Tabskip glue was not used for this, because there should not be any glue preceding or following the matrix.

The combination of a \mathstrut and \kern-\baselineskip above and below the matrix increases the vertical size such that two matrices with the same number of rows will have the same height and depth, which would not otherwise be the case if one of them had subscripts in the last row, but the other not. The \mathstrut causes interline glue to be inserted and, because it has a size equal to \baselineskip, the negative kern will effectively leave only the interline glue, thereby buffering any differences in the first and last line. Only to a certain point, of course: objects bigger than the opening brace will still result in a different height or depth of the matrix.

Another, more complicated, example of an alignment for math mode is  $\ensuremath{\verb|}$  alignno.

```
\def\eqalignno#1{\begin{disp}l@y \tabskip\centering
\halign to\displaywidth{
  \hfil$\@lign\displaystyle{##}$% -- first column
    \tabskip\z@skip
  &$\@lign\displaystyle{{}##}$\hfil% -- second column
    \tabskip\centering
  &\llap{$\@lign##$}% -- third column
    \tabskip\z@skip\crcr % end of the preamble
  #1\crcr}}
```

Firstly, the tabskip is set to zero after the equation number, so this number is set flush with the right margin. Since it is placed by \llap, its effective width

is zero. Secondly, the tabskip between the first and second columns is also zero, and the tabskip before the first column and after the second is \centering, which is Opt plus 1000pt minus 1000pt, so the first column and second are jointly centred in the \hsize. Note that, because of the minus 1000pt, these two columns will happily go outside the left and right margins, overwriting any equation numbers.

# 第 26 章 Page Shape

This chapter treats some of the parameters that determine the size of the page and how it appears on paper.

\topskip Minimum distance between the top of the page box and the baseline of the first box on the page. Plain TFX default: 10pt

\hoffset \voffset Distance by which the page is shifted right/down with respect to the reference point.

\vsize Height of the page box. Plain TFX default: 8.9in

\maxdepth Maximum depth of the page box. Plain TxX default: 4pt

\splitmaxdepth Maximum depth of a box split off by a \vsplit operation.

Plain TFX default: \maxdimen

## 26.1 The reference point for global positioning

The page positioning on the paper is governed by a TeX convention, to which output device drivers must adhere, that the top left point of the page is one inch from the page edges. Unfortunately this may lead to lots of trouble, for instance if a printer (or the page description language it uses) takes, say, the *lower* left corner as the reference point, and is factory set to US paper sizes, but is used with European standard A4 paper.

The page is shifted on the paper if one assigns non-zero values to \hoffset or \voffset: positive values shift to the right and down respectively.

## 26.2 \topskip

The \topskip ensures to a certain point that the first baseline of a page will be at the same location from page to page, even if font sizes are switched

between pages or if the first line has no ascenders.

Before the first box on each page some glue is inserted. This glue has the same stretch and shrink as \topskip, but the natural size is the natural size of \topskip minus the height of the first box, or zero if this would be negative.

Plain TeX sets \topskip to 10pt. Thus the top lines of pages will have their baselines at the same place if the top portion of the characters is ten point or less. For the Computer Modern fonts this condition is satisfied if the font size is less than (about) 13 points; for larger fonts the baseline of the top line will drop.

The height of the page box for a page containing only text (and assuming a zero \parskip) will be the \topskip plus a number of times the \baselineskip. Thus one can define a macro to compute the \vsize from the number of lines on a page:

```
\def\HeightInLines#1{\count@=#1\relax
  \advance\count@ by -1\relax
  \vsize=\baselineskip
  \multiply\vsize by \count@
  \advance\vsize by \topskip}
```

Calculating the \vsize this way will prevent underfull boxes for text-only pages.

In cases where the page does not start with a line of text (for instance a rule), the topskip may give unwanted effects. To prevent these, start the page with

```
\hbox{}\kern-\topskip
```

followed by what you wanted on top.

Analogous to the \topskip, there is a \splittopskip for pages generated by a \vsplit operation; see the next chapter.

## 26.3 Page height and depth

TEX tries to build pages as a \vbox of height \vsize; see also \pagegoal in the next chapter.

If the last item on a page has an excessive depth, that page would be noticeably longer than other pages. To prevent this phenomenon  $T_EX$  uses \maxdepth as the maximum depth of the page box. If adding an item to the page would make the depth exceed this quantity, then the reference point of the page is moved down to make the depth exactly \maxdepth.

The 'raggedbottom' effect is obtained in plain TeX by giving the \topskip

some finite stretchability: 10pt  $\,$ plus 60pt. Thus the natural height of box 255 can vary when it reaches the output routine. Pages are then shipped out (more or less) as

```
\dimen0=\dp255 \unvbox255
\ifraggedbottom \kern-\dimen0 \vfil \fi
```

The \vfil causes the topskip to be set at natural width, so the effect is one of a fixed top line and a variable bottom line of the page.

Before \box255 is unboxed in the plain  $T_EX$  output routine, \boxmaxdepth is set to \maxdepth so that this box will made under the same assumptions that the page builder used when putting together \box255.

The depth of box split off by a \vsplit operation is controlled by the \splitmaxdepth parameter.

# 第27章 分页

本章讨论'页面构建器': **T<sub>E</sub>X** 确定在何处将主竖直列分为多个页面的模块。页面构建器在输出例程之前运行,它将所得结果放入 \box255 以送给输出例程。

\vsplit 分割出一个盒子的顶端部分。它可与分页作对比。

\splittopskip 在 \vsplit 分割出的盒子中,第一个项目到盒子顶部的最小距离。 Plain TpX 默认为 10pt。

\pagegoal 页面盒子的目标高度。它刚开始等于 \vsize,并且根据插入项的高度逐步减少。

\pagetotal 当前页面积累的自然高度。

\pagedepth 当前页面的深度。

\pagestretch 当前页面积累的零阶可伸长量。

\pagefilstretch 当前页面积累的一阶可伸长量。

\pagefillstretch 当前页面积累的二阶可伸长量。

\pagefilllstretch 当前页面积累的三阶可伸长量。

\pageshrink 当前页面积累的可收缩量。

\outputpenalty 在当前分页点的惩罚值,若不在惩罚处分页,它等于 10000。

\interlinepenalty 在段落内部两行间分页的惩罚值。Plain TpX 默认为 0。

\clubpenalty 在段落首行之后分页的额外惩罚值。Plain TFX 默认为 150。

\widowpenalty 在段落尾行之前分页的额外惩罚值。Plain TrX 默认为 150。

\displaywidowpenalty 在陈列公式上面的尾行之前分页的额外惩罚值。Plain TrX 默认为 50。

\brokenpenalty 在连字行之后分页的额外惩罚值。Plain TrX 默认为 100。

\penalty 在当前列表上添加一个惩罚项。

\lastpenalty 如果当前列表的上一项为惩罚项,它表示该惩罚项的值。

\unpenalty 如果当前列表的上一项为惩罚项,删除该项目。

## 27.1 当前页面与备选内容

**TeX** 的主竖直列被分为两部分: 当前页面和备选内容列。任何添加到主竖直列的素材被追加到备选内容中;将素材从备选内容移动到当前页面的操作称为执行页面构建器.

每次有内容移动到当前页面时,**TpX** 计算在该处分页的代价。如果 **TpX** 判断该处已经越过最佳分页点,当前页面在最佳分页点之前的所有内容就被放入\box255,而剩下的内容被放回备选内容顶部。如果页面在惩罚项处分页,该惩罚的值就被记录在 \outputpenalty 中,而且值为 10000 的惩罚项被放在备选内容的顶部;否则,\outputpenalty 就被设为 10000。

如果当前页面是空的,从备选内容移动过来的可弃项目将被丢弃。此机制会让分页点之后以及第一页顶部的粘连消失。在第一个非可弃项目移动到当前页面时,\topskip 粘连将会被插入;详见上一章。

要看到页面构建器的工作过程,可以将\tracingpages 设定为某个正值(见第 34 章)。

## 27.2 激活页面构建器

页面构建器将在下列位置起作用:

- 在段落前后:在\everypar 记号列被插入后,以及段落被加入到竖直列后。见本章结尾处的例子。
- 在陈列公式前后:在 \everydisplay 记号列被插入后,以及陈列公式被加入到 竖直列后。
- 在竖直模式的 \par 命令、盒子、插入项和显式惩罚项之后。
- 在输出例程结束后。

页面构建器在这些位置将备选内容移动到当前页面。注意页面构建器运行时 **TpX** 无需处于竖直模式中。在水平模式,激活页面构建器是为了将前面的竖直粘连(比如 \parskip 和 \abovedisplayskip)移动到当前页面。

\end 命令 ——它只能用于外部竖直模式中 ——在主竖直列为空且 \deadcycles = 0 时将终止 **TrX** 任务。否则,下列这串记号

 $\verb|\hbox{}| \verb|\vfill| penalty-2^{30}$ 

将被插入进来,这促使输出例程开始运行【译注:然后\end 命令将被重新读入】。

258 第 27 章 分页

## 27.3 页面长度的记录

如上一章所述,到达输出例程的页面盒子的高度和深度由 \vsize、\topskip和 \maxdepth确定。在第一个盒子出现当前页面时,TeX 放入 \topskip 粘连;而 \vsize和 \maxdepth 在第一个盒子或插入项出现在页面时读取。此后对这些参数的修改将不会被注意到,直到下一页或者,更严格地说,直到输出例程调用完毕之后。

在第一个盒子、标线或插入项出现在当前页面之后,\vsize 被记录在\pagegoal中,并且在\output 调用完毕之前不再被查看。改变\pagegoal 对当前页面不会有任何影响。当页面为空时,\pagegoal 等于\maxdimen,而\pagetotal 等于零。

积累的尺寸和可伸缩量记录在 \pagetotal \pagedepth \pagestretch \pagefilstretch \pagefillstretch \pagefillstretch 以及 \pageshrink 这些参数中。它们由页面构建器设定。在添加每个粘连到页面时,可伸长量和可收缩量参数都会被更新。如果最后一个项目是紧排或者粘连,\pagedepth 参数等于零。

这些参数都是〈special dimen〉;对它们中任何一个的赋值都是〈intimate assignment〉,而且自动就是全局的。

## 27.4 分页点

## 27.4.1 可能的分页点

分页点可以出现在与断行点相同类型的位置。竖直模式的断点如下:

- 在粘连处,只要它前面是非可弃项目;
- 在紧排处,只要它后面是一个粘连;
- 在惩罚处。

在添加段落行到竖直列时, $T_EX$  会插入行间粘连和各种行间惩罚,这使得页面上通常有足够的分页点。

## 27.4.2 分页点的惩罚

如果  $T_{EX}$  决定在惩罚项处分页,这个惩罚项,在多数情况下,是之前自动插入到 段落各行间的。

如果列表(未必得是竖直列)的最后一项是个惩罚项,它的值会在记录在 \lastpenalty 参数中。如果这个项目不是一个惩罚项,这个参数的值为零。列表的最后一个惩罚项可以用命令 \unpenalty 删除。见第 5.9.6 节的例子。

下面列出了各种竖直模式的惩罚:

\interlinepenalty 在段落内部两行间分页的惩罚值。在 plain TrX 中它默认为

27.4 分页点 259

零,因此两行间不会添加惩罚项。这样 **T<sub>E</sub>X** 可以在 \baselineskip 粘连处寻找有效分页点。

\clubpenalty 在段落首行之后分页的额外惩罚值。Plain TeX 默认为 150。这个数值将被加到 \interlinepenalty 上,依照所得结果插入一个惩罚项到包含段落第一行的 \hbox 之后,以替代 \interlinepenalty。后面几个惩罚的情形类似。

\widowpenalty 在段落尾行之前分页的额外惩罚值。Plain TrX 默认为 150。

\displaywidowpenalty 在陈列公式上面的尾行之前分页的额外惩罚值。在 plain TrX 中默认为 50。

\brokenpenalty 在连字行之后分页的额外惩罚值。在  $plain T_EX$  中默认为 100。 如果惩罚值等于零,惩罚项将不会被插入。

用户也可以插入惩罚项。比如 plain 格式有用于强制、阻止或鼓励分页的宏:

另外,\vadjust{\penalty ... }是另一种在竖直列中添加惩罚项的方法。它可以用于阻碍或鼓励在段落某行之后分页。

## 27.4.3 分页点的计算

每当有项目移动到当前页面, $T_{p}X$  计算在该位置分页时的惩罚值 p 和丑度 b。从惩罚值和丑度再计算出分页的代价 c。

代价最小的位置被记录下来,而当代价为 无穷时,即页面过满或惩罚值为  $p \leq -10000$ 时,当前页面就在(上回记录的)代价最小位置分 开。分出来的部分就被放入 \box255, 然后输出 例程记号列被插入。第 255 号盒子的高度总是 被设为 \vsize, 不管它包含多少素材。

丑度计算基于要将页面放入高度为 \vsize 深度不超过 \maxdepth 的盒子所需的伸长或收缩量。计算方法和断行时一样(见第8章)。丑度满足  $0 \le b \le 10\,000$ ,除了在页面过满时  $b = \infty$ 。

未满的页面 b = 10000

可行的断点 b < 10000

过满的页面  $b = \infty$ 

•

有些惩罚是由  $T_{E}X$  隐式插入的,比如 \interlinepenalty 就是在段落任何两行间自动插入的。其他惩罚可以由用户或用户宏隐式插入。惩罚值  $p \geq 10\,000$  将阻止分页;而惩罚值  $p \leq -10\,000$  (在外部竖直模式中) 将强制分页,并立即激活输出例程。

分页代价依照下面步骤计算:

260 第 27 章 分页

1. 若惩罚值小到导致强制分页并立即激活输出例程,而且页面不是过满的,即  $b < \infty$  且  $p \le -10000$ 

则代价等于惩罚值:c = p。

2. 若惩罚值不会导致强制或禁止分页,而且页面不是过满的,即

 $b<\infty \quad \, \, \, \, \, \, \, \, \, \, \, |p|<10\,000$ 

则代价等于 c = b + p。

3. 若页面非常糟糕,即

 $b = 10\,000$  且  $|p| < 10\,000$  则代价等于  $c = 10\,000$ .

4. 若页面过满,即

 $b = \infty$   $\exists$  p < 10000

则代价为无穷大:  $c=\infty$ . 此时 **TeX** 判定最佳分页点应该出现在前面,并且调用输出例程。超过  $10\,000$  的 \insertpenalties 值(见第 **29** 章) 同样给出无穷大的代价。

惩罚值  $p \le -10\,000$  将激活输出例程这个事实在 LYTeX 输出例程中多次用到: 差值码  $|p|-10\,000$  用于表示调用输出例程的原因【译注: 见 source2e 第 317 页】; 另外可以见下一章的第二个例子。

## 27.5 分割竖直列

用户可以通过 \vsplit 命令实现分页操作。

例子:

\setbox1 = \vsplit2 to \dimen3

将 2 号盒子顶部 \dimen3 大小的部分赋予 1 号盒子。这部分素材实际上 是从 2 号盒子移除出来的。可以将它与从当前页面分割出 \vsize 大小的 一块内容作对比。

分割命令

\vsplit(8-bit number)to(dimen)

提取出的结果是一个满足下列属性的盒子:

- 高度等于指定的 〈dimen〉; **TeX** 将遍历原始的盒子寄存器(它必须容纳一个竖直盒子)以找到最佳断点。最后可能得到一个未满盒子。
- 深度不超过 \splitmaxdepth; 与它类似的是页面盒子的 \maxdepth, 而不是对任何盒子都适用的 \boxmaxdepth。

27.6 分页的例子 261

• 第一个和最后一个标记放在 \splitfirstmark 和 \splitbotmark 寄存器中。 而经过 \vsplit 操作后盒子的剩余部分是这样的:

- 顶部的所有可弃项都被删除;
- 大小为 \splittopskip 的粘连被插入到顶部; 如果所分割的是第 255 号盒子, 它的顶部已经有了 \topskip 粘连;
- 其深度不得超过 \splitmaxdepth。

原始盒子的底部始终是 \vsplit 操作的合适断点。如果选择它为断点,剩余的盒子寄存器就是空的。提取出的盒子也可以是空的;它是空的当且仅当原始盒子是空的或者并非竖直盒子。

通常,\vsplit 被用于从 \box255 分割出一部分。通过设定 \splitmaxdepth 等于 \boxmaxdepth,得到的结果就和 TeX 的页面构建器的一样。在修剪 \box255 顶部之后,标记寄存器 \firstmark 和 \botmark 就包含 \box255 剩余部分的第一个和最后一个标记。见下一章关于标记的更多信息。

## 27.6 分页的例子

## 27.6.1 填满页面

假设某个竖直盒子太大以致在页面剩余部分放不下。要将页面填满并将该盒子放到下一页,使用

```
\vfil\vbox{ ... }
```

是错误的。这样 **TeX** 只会在 \vfil 粘连开始处分页,而分页后 \vfil 将会被丢弃:结果将得到一个未满页面,或者至少是一个有伸长太多的糟糕页面。另一方面,

```
\vfil\penalty0 % or any other value
\vbox{ ... }
```

就是正确的做法:TrX 将在惩罚处分页,而该页面将被填满。

## 27.6.2 确定断点

在接下来的例子中我们使用与分页机制相同的 \vsplit 操作。

假设已经给出下面的宏和参数设定:

```
\offinterlineskip \showboxdepth=1
\def\High{\hbox{\vrule height5pt}}
\def\HighAndDeep{\hbox{\vrule height2.5pt depth2.5pt}}
```

首先我们考虑伸长竖直列以到达断点的例子。

262 第 27 章 分页

```
\splitmaxdepth=4pt
                    \setbox1=\vbox{\High \vfil \HighAndDeep}
                    \setbox2=\vsplit1 to 9pt
给出
                    > \box2=
                    \forall x \in (9.0+2.5) \times 0.4, glue set 1.5fil
                    .\hbox(5.0+0.0)x0.4
                    .\glue 0.0 plus 1.0fil
                    .\glue(\lineskip) 0.0
                    .\hbox(2.5+2.5)x0.4 []
这两个盒子合起来的高度为7.5pt,因此粘连需要伸长1.5pt。
                    其次,我们减少结果列表所允许的深度值。
                    \splitmaxdepth=2pt
                    \setbox1=\vbox{\High \vfil \HighAndDeep}
                    \setbox2=\vsplit1 to 9pt
给出
                    > \box2=
                    \begin{tabular}{ll} \beg
                    .\hbox(5.0+0.0)x0.4 []
                    .\glue 0.0 plus 1.0fil
                    .\glue(\lineskip) 0.0
                    .\hbox(2.5+2.5)x0.4 []
此时基准点被下移 0.5pt,而伸长量也相应减少,但是结果列表的尺寸不会比所指定
的大。
                   作为这个事实的例子,再考虑下面的例子
                    \splitmaxdepth=3pt
                    \setbox1=\vbox{\High \kern1.5pt \HighAndDeep}
                    \setbox2=\vsplit1 to 9pt
这将会给出一个恰好 9pt 高 2.5pt 深的盒子:
                    > \box2=
                    \volume{1} \volume{1
                    .\hbox(5.0+0.0)x0.4 []
                    .\kern 1.5
                    .\glue(\lineskip) 0.0
                    .\hbox(2.5+2.5)x0.4 []
若改为 \splitmaxdepth=2pt,将不会让高度增加 0.5pt;反而由于断点提前而得到
  一个未满盒子:
                   > \box2=
                    \forall x = (9.0+0.0) \times 0.4
                    .\hbox(5.0+0.0)x0.4 []
```

27.6 分页的例子 263

有时候分割的时机也是重要的。**TeX** 首先寻找能得到所需高度的断点,然后看依照 \maxdepth 或 \splitmaxdepth 调节深度是否会超出规定高度。

```
考虑一个与此时机有关的例子:这段代码
```

```
\splitmaxdepth=4pt
\setbox1=\vbox{\High \vfil \HighAndDeep}
\setbox2=\vsplit1 to 7pt
```

所得结果并非一个 7pt 高 3pt 深的盒子,而是一个未满盒子:

```
> \box2=
\vbox(7.0+0.0)x0.4
.\hbox(5.0+0.0)x0.4 []
```

### 27.6.3 段落后的页面构建

在段落结束后,页面构建器将素材移动到当前页面,但它并不决定断点是否已经找到。

#### 例子:

```
\output{\interrupt \plainoutput}% show when you're active
\def\nl{\hfil\break}\vsize=22pt % make pages of two lines
a\nl b\nl c\par \showlists % make a 3-line paragraph
```

#### 将报告

```
### current page:
[...]
total height 34.0
  goal height 22.0
prevdepth 0.0, prevgraf 3 lines
```

纵使已经收集到过多的素材,\output 还是仅会在下个段落开始时才执行: 当\output 被插入到\everypar 后,键入 d 将给出

# 第 28 章 Output Routines

The final stages of page processing are performed by the output routine. The page builder cuts off a certain portion of the main vertical list and hands it to the output routine in \box255. This chapter treats the commands and parameters that pertain to the output routine, and it explains how output routines can receive information through marks.

\output Token list with instructions for shipping out pages.

\shipout Ship a box to the dvi file.

\mark Specify a mark text.

\topmark The last mark on the previous page.

\botmark The last mark on the current page.

\firstmark The first mark on the current page.

\splitbotmark The last mark on a split-off page.

\splitfirstmark The first mark on a split-off page.

\deadcycles Counter that keeps track of how many times the output routine has been called without a \shipout taking place.

\maxdeadcycles The maximum number of times that the output routine is allowed to be called without a \shipout occurring.

\outputpenalty Value of the penalty at the current page break, or 10 000 if the break was not at a penalty.

## 28.1 The \output token list

Common parlance has it that 'the output routine is called' when TEX has found a place to break the main vertical list. Actually, \output is not a macro but a token list that is inserted into TeX's command stream.

Insertion of the \output token list happens inside a group that is implicitly opened. Also, TeX enters internal vertical mode. Because of the group, non-local assignments (to the page number, for instance) have to be prefixed with \global. The vertical mode implies that during the workings of the output routine spaces are mostly harmless.

The \output token list belongs to the class of the  $\langle$ token parameter $\rangle$ s. These behave the same as \toksnnn token lists; see Chapter 14. Assigning an output routine can therefore take the following forms:

```
\verb|\output| \langle equals \rangle \langle general \ text \rangle \quad or \quad \verb|\output| \langle equals \rangle \langle filler \rangle \langle token \ variable \rangle
```

## 28.2 Output and \box255

TEX's page builder breaks the current page at the optimal point, and stores everything above that in \box255; then, the \output tokens are inserted into the input stream. Any remaining material on the main vertical list is pushed back to the recent contributions. If the page is broken at a penalty, that value is recorded in \outputpenalty, and a penalty of size 10000 is placed on top of the recent contributions; otherwise, \outputpenalty is set to 10000. When the output routine is finished, \box255 is supposed to be empty. If it is not, TEX gives an error message.

Usually, the output routine will take the pagebox, append a headline and/or footline, maybe merge in some insertions such as footnotes, and ship the page to the dvi file:

When box 255 reaches the output routine, its height has been set to \vsize. However, the material in it can have considerably smaller height. Thus, the above output routine may lead to underfull boxes. This can be remedied with a \vfil.

The output routine is under no obligation to do anything useful with \box255; it can empty it, or unbox it to let TeX have another go at finding a page break. The number of times that the output routing postpones the \shipout is recorded in \deadcycles: this parameter is set to 0 by \shipout, and increased by 1 just

before every \output.

When the number of dead cycles reaches \maxdeadcycles, TeX gives an error message, and performs the default output routine

```
\shipout\box255
```

instead of the routine it was about to start. The LATEX format has a much higher value for \maxdeadcycles than plain TeX, because the output routine in LATEX is often called for intermediate handling of floats and marginal notes.

The \shipout command can send any  $\langle box \rangle$  to the dvi file; this need not be box 255, or even a box containing the current page. It does not have to be called inside the output routine, either.

If the output routine produces any material, for instance by calling \unvbox255

this is put on top of the recent contributions.

After the output routine finishes, the page builder is activated. In particular, because the current page has been emptied, the \vsize is read again. Changes made to this parameter inside the output routine (using \global) will therefore take effect.

## 28.3 Marks

Information can be passed to the output routine through the mechanism of *marks*. The user can specify a token list with

```
\mathbf{x}_{\langle mark\ text \rangle}
```

which is put in a mark item on the current vertical list. The mark text is subject to expansion as in \edef.

If the mark is given in horizontal mode it migrates to the surrounding vertical lists like an insertion item (see page 78); however, if this is not the external vertical list, the output routine will not find the mark.

Marks are the main mechanism through which the output routine can obtain information about the contents of the currently broken-off page, in particular its top and bottom. TEX sets three variables:

\botmark the last mark occurring on the current page;

\firstmark the first mark occurring on the current page;

\topmark the last mark of the previous page, that is, the value of \botmark on the previous page.

28.4 Assorted remarks 267

If no marks have occurred yet, all three are empty; if no marks occurred on the current page, all three mark variables are equal to the \botmark of the previous page.

For boxes generated by a \vsplit command (see previous chapter), the \splitbotmark and \splitfirstmark contain the marks of the split-off part; \firstmark and \botmark reflect the state of what remains in the register.

例子:Marks can be used to get a section heading into the headline or footline of the page.

```
\def\section#1{ ... \mark{#1} ... }
\def\rightheadline{\hbox to \hsize
   {\headlinefont \botmark\hfil\pagenumber}}
\def\leftheadline{\hbox to \hsize
   {\headlinefont \pagenumber\hfil\firstmark}}
```

This places the title of the first section that starts on a left page in the left headline, and the title of the last section that starts on the right page in the right headline. Placing the headlines on the page is the job of the output routine; see below.

It is important that no page breaks can occur in between the mark and the box that places the title:

```
\def\section#1{ ...
  \penalty\beforesectionpenalty
  \mark{#1}
  \hbox{ ... #1 ...}
  \nobreak
  \vskip\aftersectionskip
  \noindent}
```

Let us consider another example with headlines: often a page looks better if the headline is omitted on pages where a chapter starts. This can be implemented as follows:

```
\def\endofchapter
\chapter#1{ ... \def\chtitle{#1}\mark{1}\mark{0} ... }
\def\theheadline{\expandafter\ifx\firstmark1
  \else \chapheadline \fi}
```

Only on the page where a chapter starts will the mark be 1, and on all other pages a headline is placed.

#### 28.4 Assorted remarks

#### 28.4.1 Hazards in non-trivial output routines

If the final call to the output routine does not perform a \shipout, TeX will call the output routine endlessly, since a run will only stop if both the vertical list is empty, and \deadcycles is zero. The output routine can set \deadcycles to zero to prevent this.

#### 28.4.2 Page numbering

The page number is not an intrinsic property of the output routine; in plain TEX it is the value of \count0. The output routine is responsible for increasing the page number when a shipout of a page occurs.

Apart from \count0, counter registers 1–9 are also used for page identification: at shipout TEX writes the values of these ten counters to the dvi file (see Chapter 33). Terminal and log file output display only the non-zero counters, and the zero counters for which a non-zero counter with a higher number exists, that is, if \count0 = 1 and \count3 = 5 are the only non-zero counters, the displayed list of counters is [1.0.0.5].

## 28.4.3 Headlines and footlines in plain TEX

Plain  $T_{\overline{E}}X$  has token lists \headline and \footline; these are used in the macros

\makeheadline and \makefootline. The page is shipped out as (more or less)

\vbox{\makeheadline\pagebody\makefootline}

Both headline and footline are inserted inside a \line. For non-standard headers and footers it is easier to redefine the macros \makeheadline and \makefootline than to tinker with the token lists.

### 28.4.4 Example: no widow lines

Suppose that one does not want to allow widow lines, but pages have in general no stretch or shrink, for instance because they only contain plain text. A solution would be to increase the page length by one line if a page turns out to be broken at a widow line.

TEX's output routine can perform this sort of trick: if the \widowpenalty is set to some recognizable value, the output routine can see by the \outputpenalty if a widow line occurred. In that case, the output routine can temporarily in-

28.4 Assorted remarks 269

crease the \vsize, and let the page builder have another go at finding a break point.

Here is the skeleton of such an output routine. No headers or footers are provided for.

```
\newif\ifLargePage \widowpenalty=147
\newdimen\oldvsize \oldvsize=\vsize
\output={
   \ifLargePage \shipout\box255
   \global\LargePagefalse
   \global\vsize=\oldvsize
   \else \ifnum \outputpenalty=\widowpenalty
      \global\LargePagetrue
   \global\advance\vsize\baselineskip
   \unvbox255 \penalty\outputpenalty
   \else \shipout\box255
   \fi \fi}
```

The test \ifLargePage is set to true by the output routine if the \outputpenalty equals the \widowpenalty. The page box is then \unvbox ed, so that the page builder will tackle the same material once more.

#### 28.4.5 Example: no indentation top of page

Some output routines can be classified as abuse of the output routine mechanism. The output routine in this section is a good example of this.

It is imaginable that one wishes paragraphs not to indent if they start at the top of a page. (There are plenty of objections to this layout, but occasionally it is used.) This problem can be solved using the output routine to investigate whether the page is still empty and, if so, to give a signal that a paragraph should not indent.

Note that we cannot use the fact here that the page builder comes into play after the insertion of \everypar: even if we could force the output routine to be activated here, there is no way for it to remove the indentation box.

The solution given here lets the \everypar terminate the paragraph immediately with

```
\par\penalty-\specialpenalty
```

which activates the output routine. Seeing whether the pagebox is empty (after removing the empty line and any \parskip glue), the output routine then can set a switch signalling whether the retry of the paragraph should indent.

There are some minor matters in the following routines, the sense of which

#### is left for the reader to ponder.

```
\mathchardef\specialpenalty=10001
\newif\ifPreventSwitch
\newbox\testbox
\topskip=10pt
\everypar{\begingroup \par
   \penalty-\specialpenalty
   \everypar{\endgroup}\parskip0pt
   \ifPreventSwitch \noindent \else \indent \fi
    \global\PreventSwitchfalse
   }
\output{
   \ifnum\outputpenalty=-\specialpenalty
        \setbox\testbox\vbox{\unvbox255
                  {\setbox0=\lastbox}\unskip}
        \ifdim\ht\testbox=Opt \global\PreventSwitchtrue
        \else \topskip=Opt \unvbox\testbox \fi
   \else \shipout\box255 \global\advance\pageno1 \fi}
```

## 28.4.6 More examples of output routines

A large number of examples of output routines can be found in [?] and [?].

## 第 29 章 Insertions

Insertions are TeX's way of handling floating information. TeX's page builder calculates what insertions and how many of them will fit on the page; these insertion items are then placed in insertion boxes which are to be handled by the output routine.

\insert Start an insertion item.

\newinsert Allocate a new insertion class.

\insertpenalties Total of penalties for split insertions. Inside the output routine, the number of held-over insertions.

\floatingpenalty Penalty added when an insertion is split.

\holdinginserts (TeX3 only) If this is positive, insertions are not placed in their boxes at output time.

\footins Number of the footnote insertion class in plain TFX.

\topins Number of the top insertion class.

\topinsert Plain TEX macro to start a top insert.

\pageinsert Plain TEX macro to start an insert that will take up a whole page.

\midinsert Plain TeX macro that places its argument if there is space, and converts it into a top insert otherwise.

\endinsert Plain TEX macro to wind up an insertion item that started with \topinsert, \midinsert, or \pageinsert.

#### 29.1 Insertion items

Floating information, items that are not bound to a fixed place in the vertical list, such as figures or footnotes, are handled by *insertions*. The treatment

272 第 29 章 Insertions

of insertions is a strange interplay between the user, TEX's internal workings, and the output routine. First the user specifies an insertion, which is a certain amount of vertical material; then TEX's page builder decides what insertions should go on the current page and puts these insertions in insertion boxes; finally, the output routine has to do something with these boxes.

An insertion item looks like

 $\insert\langle 8\text{-bit number}\rangle \{\langle \text{vertical mode material}\rangle \}$ 

where the 8-bit number should not be 255, because \box255 is used by TeX for passing the page to the output routine.

The braces around the vertical mode material in an insertion item can be implicit; they imply a new level of grouping. The vertical mode material is processed in internal vertical mode.

Values of \splittopskip, \splitmaxdepth, and \floatingpenalty are relevant for split insertions (see below); the values that are current just before the end of the group are used.

Insertion items can appear in vertical mode, horizontal mode, and math mode. For the latter two modes they have to migrate to the surrounding vertical list (see page 78). After an insertion item is put on the vertical list the page builder is exercised.

#### 29.2 Insertion class declaration

In the plain format the number for a new insertion class is allocated by \newinsert:

\newinsert\myinsert % new insertion class

which uses \chardef to assign a number to the control sequence.

Insertion classes are allocated numbering from 254 downward. As box 255 is used for output, this allocation scheme leaves \skip255, \dimen255, and \count255 free for scratch use.

## 29.3 Insertion parameters

For each insertion class n four registers are allocated:

• \box *n* When the output routine is active this box contains the insertion items of class *n* that should be placed on the current page.

- \dimen *n* This is the maximum space allotted for insertions of class *n* per page. If this amount would be exceeded T<sub>E</sub>X will split insertions.
- \skip *n* Glue of this size is added the first time an insertion item of class *n* is added to the current page. This is useful for such phenomena as a rule separating the footnotes from the text of the page.
- \count n Each insertion item is a vertical list, so it has a certain height. However, the effective height, the amount of influence it has on the text height of the page, may differ from this real height. The value of \count n is then 1000 times the factor by which the height should be multiplied to obtain the effective height.

Consider the following examples:

- Marginal notes do not affect the text height, so the factor should be 0.
- Footnotes set in double column mode affect the page by half of their height: the count value should by 500.
- Conversely, footnotes set at page width underneath a page in double column mode affect both columns, so provided that the double column mode is implemented by applying \vsplit to a double-height column the count value should be 2000.

## 29.4 Moving insertion items from the contributions list

The most complicated issue with insertions is the algorithm that adds insertion items to the main vertical list, and calculates breakpoints if necessary.

TeX never changes the \vsize, but it diminishes the \pagegoal by the (effective) heights of the insertion items that will appear before a page break. Thus the output routine will receive a \box255 that has height \pagegoal, not necessarily \vsize.

1. When the first insertion of a certain class n occurs on the current page TeX has to account for the quantity  $\sl p n$ . This step is executed only if no earlier insertion item of this class occurs on the vertical list —— this includes insertions that were split —— but  $\sl p n$  need not be empty at this time.

If  $\begin{subarray}{l} \begin{subarray}{l} \$ 

274 第 29 章 Insertions

2. If there is a split insertion of class n on the page —— this case and the previous step in the algorithm are mutually exclusive —— the \floatingpenalty is added to \insertpenalties. A split insertion is an insertion item for which a breakpoint has been calculated as it will not fit on the current page in its entirety. Thus the insertion currently under consideration will certainly not wind up on the current page.

3. After the preliminary action of the two previous points TEX will place the actual insertion item on the main vertical list, at the end of the current contributions. First it will check whether the item will fit without being split.

There are two conditions to be checked:

- adding the insertion item (plus all previous insertions of that class) to  $\box n$  should not let the height plus depth of that box exceed  $\dimen n$ , and
- either the effective height of the insertion is negative, or \pagetotal plus \pagedepth minus \pageshrink plus the effective size of the insertion should be less than \pagegoal.

If these conditions are satisfied, \pagegoal is diminished by the effective size of the insertion item, that is, by the height plus depth, multiplied by \count n/1000.

- 4. Insertions that fail on one of the two conditions in the previous step of the algorithm will be considered for splitting. TeX will calculate the size of the maximal portion to be split off the insertion item, such that
  - (a) adding this portion together with earlier insertions of this class to  $\begin{subarray}{l} \begin{subarray}{l} \begin{sub$
  - (b) the effective size of this portion, added to \pagetotal plus \pagedepth, will not exceed \pagegoal. Note that \pageshrink is not taken into account this time, as it was in the previous step.

Once this maximal size to be split off has been determined, TeX locates the least-cost breakpoint in the current insertion item that will result in a box with a height that is equal to this maximal size. The penalty associated with this breakpoint is added to \insertpenalties, and \pagegoal is diminished by the effective height plus depth of the box to be split off the insertion item.

## 29.5 Insertions in the output routine

When the output routine comes into action — more precisely: when TEX starts processing the tokens in the \output token list — all insertions that should be placed on the current page have been put in their boxes, and it is the responsibility of the output routine to put them somewhere in the box that is going to be shipped out.

例子:The plain TEX output routine handles top inserts and footnotes by packaging the following sequence:

```
\ifvoid\topins \else \unvbox\topins \fi
\pagebody
\ifvoid\footins \else \unvbox\footins \fi
```

Unboxing the insertion boxes makes the glue on various parts of the page stretch or shrink in a uniform manner.

With TEX3 the insertion mechanism has been extended slightly: the parameter \holdinginserts can be used to specify that insertions should not yet be placed in their boxes. This is very useful if the output routine wants to recalculate the \vsize, or if the output routine is called to do other intermediate calculations instead of ejecting a page.

During the output routine the parameter \insertpenalties holds the number of insertion items that are being held over for the next page. In the plain TeX output routine this is used after the last page:

```
\def\dosupereject{\ifnum\insertpenalties>0
    % something is being held over
    \line{}\kern-\topskip\nobreak\vfill\supereject\fi}
```

## 29.6 Plain TFX insertions

The plain TEX format has only two insertion classes: the footnotes and the top inserts. The macro \pageinsert generates top inserts that are stretched to be exactly \vsize high. The \midinsert macro tests whether the vertical material specified by the user fits on the page; if so, it is placed there; if not, it is converted to a top insert.

Footnotes are allowed to be split, but once one has been split no further footnotes should appear on the current page. This effect is attained by setting

```
\floatingpenalty=20000
```

276 第 29 章 Insertions

The \floatingpenalty is added to \insertpenalties if an insertion follows a split insertion of the same class. However, \floatingpenalty  $> 10\,000$  has infinite cost, so TeX will take an earlier breakpoint for splitting off the page from the vertical list.

Top inserts essentially contain only a vertical box which holds whatever the user specified. Thus such an insert cannot be split. However, the \endinsert macro puts a \penalty100 on top of the box, so the insertion can be split with an empty part before the split. The effect is that the whole insertion is carried over to the next page. As the \floatingpenalty for top inserts is zero, arbitrarily many of these inserts can be moved forward until there is a page with sufficient space.

Further examples of insertion macros can be found in [?].

# 第 30 章 File Input and Output

This chapter discusses the various ways in which TeX can read from and write to external *files*.

\input Read a specified file as TFX input.

\endinput Terminate inputting the current file after the current line.

\pausing Specify that TpX should pause after each line that is read from a file.

\inputlineno Number of the current input line.

\message Write a message to the terminal.

\write Write a \( \)general text\( \) to the terminal or to a file.

\read Read a line from a stream into a control sequence.

\newread \newwrite Macro for allocating a new input/output stream.

\openin \closein Open/close an input stream.

\openout \closeout Open/close an output stream.

\ifeof Test whether a file has been fully read, or does not exist.

\immediate Prefix to have output operations executed right away.

\escapechar Number of the character that is used when control sequences are being converted into character tokens. IniT<sub>E</sub>X default: 92.

\newlinechar Number of the character that triggers a new line in \write and \message statements.

## 30.1 Including files: \input and \endinput

Large documents can be segmented in TEX by putting parts in separate *input files*, and loading these with \input into the master file. The exact syntax for file names is implementation dependent; most of the time a .tex file extension is assumed if no explicit extension is given. File names can be delimited

with a space or with \relax. The \input command is expandable.

If TeX encounters in an input file the \endinput statement, it acts as if the file ends after the line on which the statement occurs. Any statements on the same line as \endinput are still executed. The \endinput statement is expandable.

## 30.2 File I/O

TeX supports input and output streams for reading and writing files one line at a time.

#### 30.2.1 Opening and closing streams

TeX supports up to 16 simultaneous input and 16 output *streams*. The plain TeX macros \newread and \newwrite give the number of an unused stream. This number is assigned by a \chardef command. Input streams are completely independent of output streams.

Input streams are opened by

 $\operatorname{\operatorname{\mathsf{Nopenin}}} \langle 4\text{-bit number} \rangle \langle \operatorname{\mathsf{equals}} \rangle \langle \operatorname{\mathsf{filename}} \rangle$ 

and closed by

\closein \( 4 \)-bit number \( \)

Output streams are opened by

 $\operatorname{\texttt{\file}}_{\operatorname{\texttt{\file}}} \operatorname{\texttt{\file}}_{\operatorname{\texttt{\file}}} \operatorname{\texttt{\file}}_{\operatorname{\texttt{\file}}}$ 

and closed by

 $\cline{4-bit number}$ 

If an output file does not yet exist, it is created by \openout; if it did exist, an \openout will cause it to be overwritten.

The output operations \openout, \closeout, and \write can all three be prefixed by \immediate; see below.

#### 30.2.2 Input with \read

In addition to the  $\inv input$  command, which reads a whole file,  $T_E X$  has the  $\inv input$  operation, which reads one line from a file (or from the user terminal). The syntax of the read command is

30.2 File I/O 279

The effect of this statement is that one input line is read from the designated stream, and the control sequence is defined as a macro without parameters, having that line as replacement text.

If the input line is not balanced with respect to braces, TEX will read more than one line, continuing for as long as is necessary to get a balanced token list. TEX implicitly appends an empty line to each input stream, so the last \read operation on a stream will always yield a single \par token.

Read operations from any stream outside the range 0–15 — or streams not associated with an open file, or on which the file end has been reached — read from the terminal. If the stream number is positive the user is prompted with the name of the control sequence being defined by the \read statement.

```
例子:
    \read16 to \data

displays a prompt
    \data=

and typing 'my name' in response makes the read statement equivalent to
    \def\data{my name }
```

The space at the end of the input derives from the line end; to prevent this one could write

```
{\endlinechar=-1 \global\read16 to \data}
```

#### 30.2.3 Output with \write

```
TEX's \write command
```

```
\write\number\\general text\
```

writes a balanced token list to a file which has been opened by \openout, to the log file, or to the terminal.

Write operations to a stream outside 0-15 — or to a stream that is not associated with an open file — go to the log file; if the stream number is positive they go to the terminal as well as to the log file.

```
The token list argument of \write, defined as
```

```
\langle general \ text \rangle \longrightarrow \langle filler \rangle \{\langle balanced \ text \rangle \langle right \ brace \rangle
```

can have an implicit opening brace. This argument is expanded as if it were the replacement text of an \edef, so, for instance, any macros and conditionals appearing are expanded. No commands are executed, however. This expansion occurs at the time of shipping out; see below. Until that time the argument token list is stored in a whatsit item on the current list. See further Chapter 12 for a discussion of expansion during writing.

A control sequence output by \write (or \message) is represented with a trailing space, and using character number \escapechar for the escape character. The IniTeX default for this is 92, the code for the backslash. The trailing space can be prevented by prefixing the control sequence with \string.

#### 30.3 Whatsits

There is an essential difference in execution between input and output: operations concerning output (\openout, \closeout, \write) are executed *asynchronously*. That is, instead of being done immediately they are saved until the box in which they appear is shipped out to the dvi file.

Writes and the other two output operations are placed in 'whatsit' items on whichever list is currently being built. The actual operation occurs when the part of the page that has the item is shipped out to the dvi file. This delayed output is made necessary by TEX's asynchronous output routine behaviour. See a worked-out example on page 145.

An \immediate\write —— or any other \immediate output operation —— is executed on the spot, and does not place a whatsit item on the current list.

The argument of a \special command (see page 297) is also placed in a whatsit.

Whatsit items in leader boxes are ignored.

## 30.4 Assorted remarks

## 30.4.1 Inspecting input

If the parameter \pausing is positive, TeX shows every line that is input on the terminal *screen*, and gives the user the opportunity to insert commands.

30.4 Assorted remarks 281

These can for instance be \show commands. Inserted commands are treated as if they were directly in the source file: it is for instance not necessary to prefix them with 'i', as would be necessary when TFX pauses for an error.

#### 30.4.2 Testing for existence of files

TEX is not the friendliest of systems when you ask it to input a non-existing file. Therefore the following sequence of commands can be used to prevent trouble:

```
\newread\instream \openin\instream= fname.tex
\ifeof\instream \message{File 'fname' does not exist!}
\else \closein\instream \input fname.tex
\fi
```

Here an input stream is opened with the given file name. The end-of-file test is also true if an input stream does not correspond to a physical file, so if this conditional is not true, the file exists and an \input command can safely be given.

#### 30.4.3 Timing problems

The synchronization between write operations on the one hand, and opening/closing operations of files on the other hand, can be a crucial point. Auxiliary files, such as are used by various formats to implement cross-references, are a good illustration of this.

Suppose that during a run of TEX the auxiliary file is written, and at the end of the run it has to be input again for a variety of purposes (such as seeing whether references have changed). An \input command is executed right away, so the file must have been closed with an \immediate\closeout. However, now it becomes possible that the file is closed before all writes to it have been performed. The following sequence remedies this:

```
\par\vfil\penalty -10000 \immediate\closeout\auxfile
```

The first three commands activate the output routine in order to close off the last page, so all writes will indeed have been performed before the file is closed.

#### 30.4.4 \message versus \immediate\write16

Messages to the user can be given using \message\( general text \), which writes to the terminal. Messages are appended to one another; the line is

wrapped when the line length (a T<sub>E</sub>X compile-time constant) has been reached. In T<sub>E</sub>X version2, a maximum of 1000 characters is written per message; this is not a compile-time constant, but is hard-wired into the T<sub>E</sub>X program.

Each message given with \immediate\write starts on a new line; the user can force a new line in the message by including the character with number \newlinechar. This parameter also works in \message. The plain TeX default for \newlinechar is -1; the LATeX default of 10 allows you to write \message{two^Jlines}.

#### 30.4.5 Write inside a vertical box

Since a write operation winds up on the vertical list in a whatsit, issuing one at the start of a \vtop will probably influence the height of that box (see Chapter 5). As an example,

```
have the \vtop{\write\terminal{Hello!}\hbox{more text}} dangling from
```

will have the more text dangling from the baseline (and when this book is TeXed the message 'Hello!' appears on the screen).

## 30.4.6 Expansion and spaces in \write and \message

Both \write and \message expand their argument as if it were the replacement text of an \edef. Therefore

will write out 'b'.

Unexpandable control sequences are displayed with a trailing space (and prefixed with the \escapechar):

```
\message{\hbox\vbox!}
```

will write out '\hbox \vbox !'. Undefined control sequences give an error here.

Expandable control sequences can be written out with some care:

```
\message{\noexpand\ifx}
\message{\string\ifx}
{\let\ifx\relax \message{\ifx}}
```

all write out '\ifx'.

Note, however, that spaces after expandable control sequences are removed in the input processor, which goes into state S after a control sequence. Therefore

```
\def\a{b}\def\c{d}
```

30.4 Assorted remarks 283

```
\message{\a \c}
```

writes out 'bd'. Inserting a space can be done as follows:

```
\def\space{ } % in plain TeX
\message{\a\space\c}
```

displays 'b d'. Note that

```
\mbox{message}(\a{ }\c)
```

does not work: it displays 'b{ }d' since braces are unexpandable character tokens.

## 第 31 章 Allocation

TEX has registers of a number of types. For some of these, explicit commands exist to define a synonym for a certain register; for all of them macros exist in the plain format to allocate an unused register. This chapter treats the synonym and allocation commands, and discusses some guidelines for macro writers regarding allocation.

\countdef Define a synonym for a \count register.

\dimendef Define a synonym for a \dimen register.

\muskipdef Define a synonym for a \muskip register.

\skipdef Define a synonym for a \skip register.

\toksdef Define a synonym for a \toks register.

\newbox Allocate an unused \box register.

\newcount Allocate an unused \count register.

\newdimen Allocate an unused \dimen register.

\newfam Allocate an unused math family.

\newinsert Allocate an unused insertion class.

\newlanguage (TpX3 only) Allocate a new language number.

\newmuskip Allocate an unused \muskip register.

\newskip Allocate an unused \skip register.

\newtoks Allocate an unused \toks register.

\newread Allocate an unused input stream.

\newwrite Allocate an unused output stream.

#### 31.1 Allocation commands

In plain TEX, \new... macros are defined for allocation of registers. The registers of TEX fall into two classes that are allocated in different ways. This is treated below.

The \newlanguage macro of plain TEX does not allocate any register. Instead it merely assigns a number, starting from 0. TEX (version 3) can have at most 256 different sets of hyphenation patterns.

The \new... macros of plain TEX are defined to be \outer (see Chapter 11 for a precise explanation), which precludes use of the allocation macros in other macros. Therefore the LATEX format redefines these macros without the \outer prefix.

#### 31.1.1 \count, \dimen, \skip, \muskip, \toks

For these registers there exists a  $\langle registerdef \rangle$  command, for instance  $\backslash countdef$ , to couple a specific register to a control sequence:

```
\langle registerdef \rangle \langle control sequence \rangle \langle equals \rangle \langle 8-bit number \rangle
```

After the definition

\countdef\MyCount=42

the allocated register can be used as

```
\MyCount=314
```

or

\vskip\MyCount\baselineskip

The  $\langle registerdef \rangle$  commands are used in plain TeX macros  $\langle registerdef \rangle$  cetera that allocate an unused register; after

```
\newcount\MyCount
```

\MyCount can be used exactly as in the above two examples.

#### 31.1.2 \box, \fam, \write, \read, \insert

For these registers there exists no  $\langle registerdef \rangle$  command in  $T_E X$ , so  $\langle registerdef \rangle$  is used to allocate box registers in the corresponding plain  $T_E X$  macros  $\langle registerdef \rangle$  for instance.

The fact that \chardef is used implies that the defined control sequence does not stand for the register itself, but only for its number. Thus after

286 第 31 章 Allocation

\newbox\MyBox

it is necessary to write

\box\MyBox

Leaving out the \box means that the character in the current font with number \MyBox is typeset. The \chardef command is treated further in Chapter 3.

#### 31.2 Ground rules for macro writers

The \new... macros of plain TEX have been designed to form a foundation for macro packages, such that several of such packages can operate without collisions in the same run of TEX. In appendix B of the TEX book Knuth formulates some ground rules that macro writers should adhere to.

- 1. The \new... macros do not allocate registers with numbers 0-9. These can therefore be used as 'scratch' registers. However, as any macro family can use them, no assumption can be made about the permanency of their contents. Results that are to be passed from one call to another should reside in specifically allocated registers.
  - Note that count registers 0–9 are used for page identification in the dvi file (see Chapter 33), so no global assignments to these should be made.
- 2. \count255, \dimen255, and \skip255 are also available. This is because inserts are allocated from 254 downward and, together with an insertion box, a count, dimen, and skip register, all with the same number, are allocated. Since \box255 is used by the output routine (see Chapter 28), the count, dimen, and skip with number 255 are freely available.
- 3. Assignments to scratch registers 0, 2, 4, 6, 8, and 255 should be local; assignments to registers 1, 3, 5, 7, 9 should be \global (with the exception of the \count registers). This guideline prevents 'save stack build-up' (see Chapter 35).
- 4. Any register can be used inside a group, as TEX's grouping mechanism will restore its value outside the group. There are two conditions on this use of a register: no global assignments should be made to it, and it must not be possible that other macros may be activated in that group that perform global assignments to that register.
- 5. Registers that are used over longer periods of time, or that have to survive in between calls of different macros, should be allocated by \new....

# 第 32 章 Running T<sub>E</sub>X

This chapter treats the run modes of TeX, and some other commands associated with the job being processed.

\everyjob Token list that is inserted at the start of each new job.

\jobname Name of the main TFX file being processed.

\end Command to finish off a run of TeX.

\bye Plain T<sub>F</sub>X macro to force the final output.

\pausing Specify that TFX should pause after each line that is read from a file.

\errorstopmode TeX will ask for user input on the occurrence of an error.

\scrollmode TpX fixes errors itself, but will ask the user for missing files.

\nonstopmode TeX fixes errors itself, and performs an emergency stop on serious errors such as missing input files.

\batchmode TEX fixes errors itself and performs an emergency stop on serious errors such as missing input files, but no terminal output is generated.

# 32.1 Jobs

 $T_E X$  associates with each run a name for the file being processed: the  $\j$ obname. If  $T_E X$  is run interactively —— meaning that it has been invoked without a file argument, and the user types commands —— the jobname is texput.

The \jobname can be used to generate the names of auxiliary files to be read or written during the run. For instance, for a file story.tex the \jobname is story, and writing

```
\openout\Auxiliary=\jobname.aux
\openout\TableOfContents=\jobname.toc
```

will create the files story.aux and story.toc.

## 32.1.1 Start of the job

TEX starts each job by inserting the \everyjob token list into the command stream. Setting this variable during a run of TEX has no use, but a format can use it to identify itself to the user. If a format fills the token list, the commands therein are automatically executed when TEX is run using that format.

# 32.1.2 End of the job

A TEX job is terminated by the \end command. This may involve first forcing the output routine to process any remaining material (see Chapter 27). If the end of job occurs inside a group TEX will give a diagnostic message. The \end command is not allowed in internal vertical mode, because this would be inside a vertical box.

Usually some sugar coating of the  $\ensuremath{\mbox{\mbox{\sc command}}}$  is necessary. For instance the plain TeX macro  $\ensuremath{\mbox{\sc bye}}$  is defined as

\def\bye{\par\vfill\supereject\end}

where the \supereject takes care of any leftover insertions.

# 32.1.3 The log file

For each run TEX creates a *log file*. Usually this will be a file with as name the value of \jobname, and the extension .log. Other extensions such as .lis are used by some implementations. This log file contains all information that is displayed on the screen during the run of TEX, but it will display some information more elaborately, and it can contain statistics that are usually not displayed on the screen. If the parameter \tracingonline has a positive value, all the log file information will be shown on the screen.

Overfull and underfull boxes are reported on the terminal screen, and they are dumped using the parameters \showboxdepth and \showboxbreadth in the log file (see Chapter 34). These parameters are also used for box dumps caused by the \showbox command, and for the dump of boxes written by \shipout if \tracingoutput is set to a positive value.

Statistics generated by commands such as \tracingparagraphs will be written to the log file; if \tracingonline is positive they will also be shown on the screen.

Output operations to a stream that is not open, or to a stream with a number that is not in the range 0–15, go to the log file. If the stream number is

32.2 Run modes 289

positive, they also go to the terminal.

## 32.2 Run modes

By default, TEX goes into \errorstopmode if an error occurs: it stops and asks for input from the user. Some implementations have a way of forcing TEX into errorstopmode when the user interrupts TEX, so that the internal state of TEX can be inspected (and altered). See page 308 for ways to switch the run mode when TEX has been interrupted.

Often, TEX can fix an error itself if the user asks TEX just to continue (usually by hitting the return key), but sometimes (for instance in alignments) it may take a while before TEX is on the right track again (and sometimes it never is). In such cases the user may want to turn on \scrollmode, which instructs TEX to fix as best it can any occurring error without confirmation from the user. This is usually done by typing 's' when TEX asks for input.

In \scrollmode, TEX also does not ask for input after \show... commands. However, some errors, such as a file that could not be found for \input, are not so easily remedied, so the user will still be asked for input.

With \nonstopmode TEX will scroll through errors and, in the case of the kind of error that cannot be recovered from, it will make an emergency stop, aborting the run. Also TEX will abort the run if a \read is attempted from the terminal. The \batchmode differs only from nonstopmode in that it gives messages only to the log file, not to the terminal.

# 第 33 章 TEX and the Outside World

This chapter treats those commands that bear relevance to dvi files and formats. It gives some global information about IniTeX, font and format files, Computer Modern typefaces, and web.

\dump Dump a format file; possible only in IniTFX, not allowed inside a group.

\special Write a \langle balanced text \rangle to the dvi file.

\mag 1000 times the magnification of the document.

\year The year of the current job.

\month The month of the current job.

\day The day of the current job.

\time Number of minutes after midnight that the current job started.

\fmtname Macro containing the name of the format dumped.

\fmtversion Macro containing the version of the format dumped.

# 33.1 T<sub>F</sub>X, IniT<sub>F</sub>X, VirT<sub>F</sub>X

In the terminology established in *TeX*: the *Program*, [?], TeX programs come in three flavours. IniTeX is a version of TeX that can generate formats; VirTeX is a production version without preloaded format, and TeX is a production version with preloaded (plain) format. Unfortunately, this terminology is not adhered to in general. A lot of systems do not use preloaded formats (the procedure for making them may be impossible on some operating systems), and call the 'virgin TeX' simply TeX. This manual also follows that convention.

#### 33.1.1 Formats: loading

A format file (usually with extension .fmt) is a compact dump of TeX's internal structures. Loading a format file takes a considerably shorter time than would be needed for loading the font information and the macros that constitute the format.

Both TEX and IniTEX can load a format; the user specifies this by putting the name on the command line

preceded by an ampersand (for UNIX, this should be \& on the command line). An input file name can follow the format name in both places.

IniTEX does not need a format, but if no format is specified for (Vir)TEX, it will try to load the plain format, and halt if that cannot be found.

## 33.1.2 Formats: dumping

IniTeX is the only version of TeX that can dump a format, since it is the only version of TeX that has the command \dump, which causes the internal structures to be dumped as a format. It is also the only version of TeX that has the command \patterns, which is needed to specify a list of hyphenation patterns.

Dumping is not allowed inside a group, that is

```
{ ... \dump }
```

is not allowed. This restriction prevents difficulties with TEX's save stack. After the \dump command TEX gives an elaborate listing of its internal state, and of the font names associated with fonts that have been loaded and ends the job.

An interesting possibility arises from the fact that IniTeX can both load and dump a format. Suppose you have written a set of macros that build on top of plain TeX, superplain.tex. You could then call

```
% initex &plain superplain
*\dump
```

and get a format file superplain.fmt that has all of plain, and all of your macros.

#### 33.1.3 Formats: preloading

On some systems it is possible to interrupt a running program, and save its 'core image' such that this can be started as an independent program. The executable made from the core image of a TeX program interrupted after it has loaded a format is called a TeX program with preloaded format. The idea behind preloaded formats is that interrupting TeX after it has loaded a format, and making this program available to the user, saves in each run the time for loading the format. In the good old days when computers were quite a bit slower this procedure made sense. Nowadays, it does not seem so necessary. Besides, dumping a core image may not always be possible.

# 33.1.4 The knowledge of IniTFX

If no format has been loaded, IniT<sub>E</sub>X knows very little. For instance, it has no open/close group characters. However, it can not be completely devoid of knowledge lest there be no way to define anything.

Here is the extent of its knowledge.

- \catcode`\\=0, \escapechar=`\\ (see page 23).
- \catcode`\^^M=5, \endlinechar=`\^^M (see page 24).
- \catcode`\ =10 (see page 24).
- \catcode`\%=14 (see page 24).
- \catcode`\^^?=15 (see page 24).
- \catcode x = 11 for x = `a...z, `A...z (see page 24).
- \catcode x = 12 for all other character codes (see page 24).
- \sfcode x = 999 for x = A...Z, \sfcode x = 1000 for all other characters (see page 208).
- \lccode`a..`z,`A..`Z=`a..`z,\uccode`a..`z,`A..`Z=`A..`Z,\lccode x=0,\uccode x=0 for all other characters (see page ??).
- \delcode`.=0, \delcode *x* =-1 for all other characters (see page 213).
- \mathcode x = "!7100 + x for all lowercase and uppercase letters, \mathcode x = "!7000 + x for all digits, \mathcode x = x for all other characters (see page 219).
- \tolerance=10000, \mag=1000, \maxdeadcycles=25.

# 33.1.5 Memory sizes of T<sub>E</sub>X and IniT<sub>E</sub>X

The main memory size of TEX and IniTEX is controlled by four constants in the source code: mem\_bot, mem\_top, mem\_min, and mem\_max. For IniTEX's memory mem\_bot = mem\_min and mem\_top = mem\_max; for TEX mem\_bot and mem\_top record the main memory size of the IniTEX used to dump the format. Thus versions of TEX and IniTEX have to be adapted to each other in this respect.

TEX's own main memory can be bigger than that of the corresponding IniTEX: in general mem\_min  $\leq$  mem\_bot and mem\_top  $\leq$  mem\_max.

For IniTeX a smaller main memory can suffice, as this program is typically not meant to do real typesetting. There may even be a real need for the main memory to be smaller, because IniTeX needs a lot of auxiliary storage for initialization and for building the hyphenation table.

## 33.2 More about formats

## 33.2.1 Compatibility

TEX has a curious error message: 'Fatal format error: I'm stymied', which is given if TEX tries to load a format that was made with an incompatible version of IniTEX. See the point above about memory sizes, and Chapter 35 for the hash size (parameters hash\_size and hash\_prime) and the hyphenation exception dictionary (parameter hyph\_size).

#### 33.2.2 Preloaded fonts

During a run of TEX the only information needed about fonts is the data that is found in the tfm files (see below). Since a run of TEX, especially if the input contains math material, can easily access 30–40 fonts, the disk access for all the tfm files can become significant. Therefore the plain format and LATEX load these metrics files in IniTEX. A TEX version using such a format does not need to load any tfm files.

On the other hand, if a format has the possibility of accessing a range of typefaces, it may be advantageous to have metrics files loaded on demand during the actual run of TeX.

## 33.2.3 The plain format

The first format written for T<sub>E</sub>X, and the basis for all later ones, is the plain format, described in the T<sub>E</sub>X book. It is a mixture of

- definitions and macros one simply cannot live without such as the initial \catcode assignments, all of the math delimiter definitions, and the \new... macros;
- constructs that are useful, but for which LATEX and other packages use a different implementation, such as the tabbing environment; and
- some macros that are insufficient for any but the simplest applications: \item and \beginsection are in this category.

It is the first category which Knuth meant to serve as a foundation for future macro packages, so that they can live peacefully together (see Chapter 31). This idea is reflected in the fact that the name 'plain' is not capitalized: it is the basic set of macros.

# 33.2.4 The LATEX format

The LATEX format, written by Leslie Lamport of Digital Equipment Corporation and described in [?], was released around 1985. The LATEX format, using its own version of plain.tex (called lplain.tex), is not compatible with plain TeX; a number of plain macros are not available. Still, it contains large parts of the plain format (even when they overlap with its own constructs).

LATEX is a powerful format with facilities such as marginal notes, floating objects, cross referencing, and automatic table of contents generation. Its main drawback is that the 'style files' which define the actual layout are quite hard to write (although LATEX is in the process of a major revision, in which this problem will be tackled; see [?] and [?]). As a result, people have had at their disposal mostly the styles written by Leslie Lamport, the layout of which is rather idiosyncratic. See [?] for a successful attempt to replace these styles.

#### 33.2.5 Mathematical formats

There are two formats with extensive facilities for mathematics typesetting: AmsTEX [?] (which originated at the American Mathematical Society) and LAMSTEX [?]. The first of these includes more facilities than plain TEX or LATEX for typesetting mathematics, but it lacks features such as automatic numbering and cross-referencing, available in LATEX, for instance. LAMSTEX, then, is the

33.3 The dvi file 295

synthesis of AmsTeX and LATeX. Also it includes still more features for mathematics, such as complicated tables and commutative diagrams.

#### 33.2.6 Other formats

Other formats than the above exist: for instance, Phyzzx [?], TeXsis [?], Macro TeX [?], eplain [?], and TeXT1 [?]. Typically, such formats provide the facilities of LaTeX, but try to be more easily adaptable by the user. Also, in general they have been written with the intention of being an add-on product to the plain format.

This book was, in its incarnation published by Addison-Wesley, also written in an 'other format': the *Lollipop* format. This format does not contain user macros, but the tools with which a style designer can program them; see [?]. The current version of this book is written in LATEX.

# 33.3 The dvi file

The dvi file (this term stands for 'device independent') contains the output of a TeX run: it contains compactly dumped representations of boxes that have been sent there by  $\shipout\langle box \rangle$ . The act of shipping out usually occurs inside the output routine, but this is not necessarily so.

#### 33.3.1 The dvi file format

A dvi file is a byte-oriented file, consisting of a preamble, a postamble, and a list of pages.

Access for subsequent software to a completed dvi file is strictly sequential in nature: the pages are stored as a backwards linked list. This means that only two ways of accessing are possible:

- given the start of a page, the next can be found by reading until an end-ofpage code is encountered, and
- starting at the end of the file pages can be read backwards at higher speed, as each beginning-of-page code contains the byte position of the previous one.

The preamble and postamble contain

• the magnification of the document (see below),

- the unit of measurement used for the document, and
- possibly a comment string.

The postamble contains in addition a list of the font definitions that appear on the pages of the file.

Neither the preamble nor the postamble of the file contains a table of byte positions of pages. The full definition of the dvi file format can be found in [?].

## 33.3.2 Page identification

Whenever a \shipout occurs, TEX also writes the values of counters 0–9 to the dvi file and the terminal. Ordinarily, only counter 0, the page number, is used, and the other counters are zero. Those zeros are not output to the terminal. The other counters can be used to indicate further structure in the document. Log output shows the non-zero counters and the zero counters in between.

## 33.3.3 Magnification

The *magnification* of a document can be indicated by the (integer parameter) \mag, which specifies 1000 times the magnification ratio.

The dvi file contains the value of \mag for the document in its preamble and postamble. If no true dimensions are used the dvi file will look the same as when no magnification would have been used, except for the \mag value in the preamble and the postamble.

Whenever a true dimension is used it is divided by the value of \mag, so that the final output will have the dimension as prescribed by the user. The \mag parameter cannot be changed after a true dimension has been used, or after the first page has been shipped to the dvi file.

Plain TEX has the \magnification macro for globally sizing the document, without changing the physical size of the page:

```
\def\magnification{\afterassignment\m@g\count@}
\def\m@g{\mag\count@
  \hsize6.5truein\vsize8.9truein\dimen\footins8truein}
```

The explanation for this is as follows: the command \m@g is saved with an \afterassignment command, and the magnification value (which is 1000 times the actual magnification factor) is assigned to \count@. After this assignment, the macro \m@g assigns the magnification value to \mag, and the horizontal and

33.4 Specials 297

vertical size are reset to their original values 6.5truein and 8.9truein. The \footins is also reset.

# 33.4 Specials

TEX is to a large degree machine independent, but it still needs a hook for machine-dependent extensions. This is done through specials. The \special command writes a  $\langle balanced text \rangle$  to the dvi file which TEX does not interpret like other token lists: it assumes that the printer driver knows what to do with it. The \special command is not supposed to change the x and y position on the page, so that the implementation of TEX remains independent of the actual  $device\ driver$  that handles the \special.

The most popular application of specials is probably the inclusion of graphic material, written in some page description language, such as *PostScript*. The size of the graphics can usually be determined from the file containing it (in the case of encapsulated PostScript through the 'bounding box' data), so TEX can leave space for such material.

# 33.5 Time

TEX has four parameters, \year, \month, \day, and \time, that tell the *time* and *date* when the current job started. After this, the parameters are not updated. The user can change them without this having any effect.

All four parameters are integers; the \time parameter gives the number of minutes since midnight that the current job started.

# 33.6 Fonts

Font information is split in the TEX system into the metric information (how high, wide, and deep is a character), and the actual description of the characters in a font. TEX, the formatter, needs only the metric information; printer drivers and screen previewers need the character descriptions. With this approach it is for instance possible for TEX to use with relative ease the resident fonts of a printer.

#### 33.6.1 Font metrics

The metric information of TEX's fonts is stored in tfm files, which stands for 'TEX font metrics' files. Metrics files contain the following information (see [?] for the full definition):

- the design size of a font;
- the values for the \fontdimen parameters (see Chapter 4);
- the height, depth, width, and italic correction of individual characters;
- kerning tables;
- ligature tables;
- information regarding successors and extensions of math characters (see Chapter 21).

Metrics files use a packed format, but they can be converted to and from a readable format by the auxiliary programs tftopl and pltotf (see [?]). Here pl stands for 'property list', a term deriving from the programming language Lisp. Files in pl format are just text, so they can easily be edited; after conversion they can then again be used as tfm files.

#### 33.6.2 Virtual fonts

With *virtual fonts* (see [?]) it is possible that what looks like one font to TEX resides in more than one physical font file. Also, virtual fonts can be used to change in effect the internal organization of font files.

For TeX itself, the presence of virtual fonts makes no difference: everything is still based on tfm files containing metric information. However, the screen or printer driver that displays the resulting dvi file on the screen or on a printer will search for files with extension .vf to determine how characters are to be interpreted. The vf file can, for instance, instruct the driver to interpret a character as a certain position in a certain font file, to interpret a character as more than one position (a way of forming accented characters), or to include \special information (for instance to set gray levels).

Readable variants of vf files have extension vpl, analogous to the pl files for the tfm files; see above. Conversion between vf and vpl files can be performed with the vftovp and vptovf programs.

However, because virtual fonts are a matter for *device drivers*, no more details will be given in this book.

33.6 Fonts 299

#### 33.6.3 Font files

Character descriptions are stored in three types of files.

**gf** Generic Font files. This is the file type that the Metafont program generates. There are not many previewers or printer drivers that use this type of file directly.

- pxl Pixel files. The pxl format is a pure bitmap format. Thus it is easy to generate pxl files from, for instance, scanner images.This format should be superseded by the pk format. Pixel files can become rather big, as their size grows quadratically in the size of the characters.
- **pk** Packed files. Pixel files can be packed by a form of run-length encoding: instead of storing the complete bitmap only the starting positions and lengths of 'runs' of black and white pixels are stored. This makes the size of pk files approximately linear in the size of the characters. However, a previewer or printer driver using a packed font file has to unpack it before it is able to use it.

The following conversion programs exist: gftopxl, gftopk, pktopxl, pxltopk.

# 33.6.4 Computer Modern

The only family of typefaces that comes with TEX in the standard distribution is the *Computer Modern* family of typefaces. This is an adaptation (using the terminology of [?]) by Donald Knuth of the Monotype Modern 8A typeface that was used for the first volume of his *Art of Computer Programming* series. The 'modern faces' all derive from the types that were cut between 1780 and 1800 by Firmin Didot in France, Giambattista Bodoni in Italy, and Justus Erich Walbaum in Germany. After the first two, these types are also called 'Didone' types. This name was coined in the Vox classification of types [?]. Ultimately, the inspiration for the Didone types is the 'Romain du Roi', the type that was designed by Nicolas Jaugeon around 1692 for the French Imprimerie Royale.

Didone types are characterized by a strong vertical orientation, and thin hairlines. The vertical accent is strengthened by the fact that the insides of curves are flattened. The result is a clear and brilliant page, provided that the printing is done carefully and on good quality paper. However, they are quite vulnerable; [?] compares them to the distinguished but fragile furniture from the same period, saying one is afraid to use either, 'for both seem in danger of breaking in pieces'. With the current proliferation of low resolution (around 300

dot per inch) printers, the Computer Modern is a somewhat unfortunate choice.

Recently, Donald Knuth has developed a new typeface (or rather, a subfamily of typefaces) by changing parameters in the Computer Modern family. The result is a so-called 'Egyptian' typeface: Computer Concrete [?]. The name derives from the fact that it was intended primarily for the book *Concrete Mathematics*. Egyptian typefaces (they fall under the 'Mécanes' in the Vox classification, meaning constructed, not derived from written letters) have a very uniform line width and square serifs. They do not have anything to do with Egypt; such types happened to be popular in the first half of the nineteenth century when Egyptology was developing and popular.

# 33.7 T<sub>F</sub>X and web

The TEX program is written in WEB, a programming language that can be considered as a subset of *Pascal*, augmented with a preprocessor.

TeX makes no use of some features of Pascal, in order to facilitate porting to Pascal systems other than the one it was originally designed for, and even to enable automatic translation to other programming languages such as C. For instance, it does not use the Pascal With construct. Also, procedures do not have output parameters; apart from writing to global variables, the only way values are returned is through Function values.

Actually, were is more than a superset of a subset of Pascal (and to be more precise, it can also be used with other programming languages); it is a 'system of structured documentation'. This means that the were programmer writes pieces of program code, interspersed with their documentation, in one file. This idea of 'literate programming' was introduced in [?]; for more information, see [?].

Two auxiliary programs, Tangle and Weave, can then be used to strip the documentation and convert web into regular Pascal, or to convert the web file into a TeX file that will typeset the program and documentation.

Portability of web programs is achieved by the 'change file' mechanism. A change file is a list of changes to be made to the web file; a bit like a stream editor script. These changes can comprise both adaptations of the web file to the particular Pascal compiler that will be used, and bug fixes to TeX. Thus the TeX.web file need never be edited.

# 33.8 The TEX Users Group

TeX users have joined into several users groups over the last decade. Many national or language users groups exist, and a lot of them publish newsletters. The oldest of all TeX users groups is simply called that: the TeX Users Group, or TUG, and its journal is called TUGboat. You can reach them at

TEX Users Group P.O. Box 2311 Portland, OR 97208-2311, USA

or electronically at office@tug.org on the Internet.

# 第 34 章 Tracing

TEX's workings are often quite different from what the programmer expected, so there are ways to discover how TEX arrived at the result it did. The \tracing... commands all write *statistics* information of a certain kind to the log file (and to the terminal if \tracingonline is positive), and a number of \show... commands can be used to ask the current status or value of various items of TEX.

In the following list, only \show and \showthe display their output on the terminal by default, other \show... and \tracing... commands write to the log file. They will write in addition to the terminal if \tracingonline is positive.

\meaning Give the meaning of a control sequence as a string of characters.

\show Display the meaning of a control sequence.

\showthe Display the result of prefixing a token with \the.

\showbox Display the contents of a box.

\showlists Display the contents of the partial lists currently built in all modes. This is treated on page 79.

\tracingcommands If this is 1 TeX displays primitive commands executed; if this is 2 or more the outcome of conditionals is also recorded.

\tracingmacros If this is 1, TEX shows expansion of macros that are performed and the actual values of the arguments; if this is 2 or more \text{\text{token parameter}} s such as \output and \everypar are also traced.

\tracingoutput If this is positive, the log file shows a dump of boxes that are shipped to the dvi file.

\showboxdepth The number of levels of box dump that are shown when boxes are displayed.

\showboxbreadth Number of successive elements on each level that are shown when boxes are displayed.

- \tracingonline If this parameter is positive, TeX will write trace information to the terminal in addition to the log file.
- \tracingparagraphs If this parameter is positive, TeX generates a trace of the line breaking algorithm.
- \tracingpages If this parameter is positive, TeX generates a trace of the page breaking algorithm.
- \tracinglostchars If this parameter is positive, TeX gives diagnostic messages whenever a character is accessed that is not present in a font. Plain default: 1.
- \tracingrestores If this parameter is positive, TEX will report all values that are restored when a group ends.
- \tracingstats If this parameter is 1, TeX reports at the end of the job the usage of various internal arrays; if it is 2, the memory demands are given whenever a page is shipped out.

# 34.1 Meaning and content: \show, \showthe, \meaning

The meaning of control sequences, and the contents of those that represent internal quantities, can be obtained by the primitive commands \show, \showthe, and \meaning.

The control sequences \show and \meaning are similar: the former will give output to the log file and the terminal, whereas the latter will produce the same tokens, but they are placed in TeX's input stream.

The meaning of a primitive command of TFX is that command itself:

```
\show\baselineskip
```

gives

\baselineskip=\baselineskip

The meaning of a defined quantity is its definition:

```
\show\pageno
```

gives

\pageno=\count0

The meaning of a macro is its parameter text and replacement text:

```
\def\foo#1?#2\par{\set{#1!}\set{#2?}}
\show\foo
```

gives

304 第 34 章 Tracing

```
\foo=macro:
#1?#2\par ->\set {#1!}\set {#2?}
```

For macros without parameters the part before the arrow (the parameter text) is empty.

The \showthe command will display on the log file and terminal the tokens that \the produces. After \show, \showthe, \showbox, and \showlists TeX asks the user for input; this can be prevented by specifying \scrollmode. Characters generated by \meaning and \the have category 12, except for spaces (see page 29); the value of \escapechar is used when control sequences are represented.

# 34.2 Show boxes: \showbox, \tracingoutput

If \tracingoutput is positive the log file will receive a dumped representation of all boxes that are written to the dvi file with \shipout. The same representation is used by the command \showbox\8-bit number\.

In the first case TEX will report 'Completed box being shipped out'; in the second case it will enter \errorstopmode, and tell the user 'OK. (see the transcript file)'. If \tracingonline is positive, the box is also displayed on the terminal; if \scrollmode has been specified, TEX does not stop for input.

The upper bound on the number of nested boxes that is dumped is \showboxdepth; each time a level is visited at most \showboxbreadth items are shown, the remainder of the list is summarized with etc. For each box its height, depth, and width are indicated in that order, and for characters it is stated from what font they were taken.

```
例子:After

\font\tenroman=cmr10 \tenroman \setbox0=\hbox{g} \showbox0

the log file will show
\hbox(4.30554+1.94444)x5.00002
.\tenroman g
```

indicating that the box was 4.30554pt high, 1.94444pt deep, and 5.00002pt wide, and that it contained a character 'g' from the font \tenroman. Note that the fifth decimal of all sizes may be rounded because TeX works with multiples of  $2^{-16}$ pt.

The next example has nested boxes,

```
\vbox{\hbox{g}\hbox{o}}
```

and it contains \baselineskip glue between the boxes. After a \showbox command the log file output is:

```
\vbox(16.30554+0.0)x5.00002
.\hbox(4.30554+1.94444)x5.00002
.\tenroman g
.\glue(\baselineskip) 5.75002
.\hbox(4.30554+0.0)x5.00002
.\tenroman o
```

Each time a new level is entered an extra dot is added to the front of the line. Note that TEX tells explicitly that the glue is \baselineskip glue; it inserts names like this for all automatically inserted glue. The value of the baselineskip glue here is such that the baselines of the boxes are at 12 point distance.

Now let us look at explicit (user) glue. TEX indicates the ratio by which it is stretched or shrunk.

This means that the horizontal box contained fil glue, and it was set such that its resulting width was 9pt.

 $\hbox(4.00000+0.14000)x15.0$ , glue set 9.00000fil

Underfull boxes are dumped like all other boxes, but the usual 'Underfull hbox detected at line...' is given. Overfull horizontal boxes contain a vertical rule of width \overfullrule:

306 第 34 章 Tracing

```
\hbox to 5pt {\kern10pt}
gives
    \hbox(0.0+0.0)x5.0
    .\kern 10.0
    .\rule(*+*)x5.0

Box leaders are not dumped completely:
    .\leaders 40.0
    .\hbox(4.77313+0.14581)x15.0, glue set 9.76852fil
    ...\tenrm a
    ...\glue 0.0 plus 1.0fil

is the dump for
```

Preceding or trailing glue around the leader boxes is also not indicated.

\leaders\hbox to 15pt{\tenrm a\hfil}\hskip 40pt

#### 34.3 Global statistics

The parameter \tracingstats can be used to force TEX to report at the end of the job the global use of resources. Some production versions of TEX may not have this option.

As an example, here are the statistics for this book:

```
Here is how much of TeX's memory you used:
```

String memory (bounded by 'pool size'):

```
877 strings out of 4649
9928 string characters out of 61781
```

Main memory, control sequences, font memory:

```
53071 words of memory out of 262141
2528 multiletter control sequences out of 9500
20137 words of font info for 70 fonts,
out of 72000 for 255
```

Hyphenation:

```
14 hyphenation exceptions out of 607
```

Stacks: input, nest, parameter, buffer, and save stack respectively,

```
17i,6n,19p,245b,422s stack positions out of 300i,40n,60p,3000b,4000s
```

# 第 35 章 Errors, Catastrophes, and Help

When TEX is running, various errors can occur. This chapter treats how errors in the input are displayed, and what sort of overflow of internal data structures of TEX can occur.

\errorcontextlines (TeX3 only) Number of additional context lines shown in error messages.

\errmessage Report an error, giving the parameter of this command as message.

\errhelp Tokens that will be displayed if the user asks further help after an \errmessage.

# 35.1 Error messages

When TEX is running in \errorstopmode (which it usually is; see Chapter 32 for the other running modes), errors occurring are reported on the user terminal, and TEX asks the user for further instructions. Errors can occur either because of some internal condition of TEX, or because a macro has issued an \errmessage command.

If an error occurs TeX shows the input line on which the error occurred. If the offending command was not on that line but, for instance, in a macro that was called —— possibly indirectly —— from that line, the line of that command is also shown. If the offending command was indirectly called, an additional \errorcontextlines number of lines is shown with the preceding macro calls.

A value of  $\ensuremath{\mbox{\mbox{\sc values}}}$  causes . . . to be printed as the sole indication that there is a context. Negative values inhibit even this.

For each macro in the sequence that leads to the offending command, TeX attempts to display some preceding and some following tokens. First one line is displayed ending with the —— indirectly —— offending command; then, one line lower some following tokens are given.

```
例子:
This paragraph ends \vship1cm with a skip.

gives
! Undefined control sequence.
1.1 This paragraph ends \vship

1cm with a skip.
```

If  $T_E X$  is not running in some non-stop mode, the user is given the chance to do some *error patching*, or to ask for further information. In general the following options are available:

- $\langle \mathbf{return} \rangle$  TeX will continue processing. If the error was something innocent that TeX could either ignore or patch itself, this is the easy way out.
- h Give further details about the error. If the error was caused by an \err-message command, the \errhelp tokens will be displayed here.
- i Insert. The user can insert some material. For example, if a control sequence is misspelled, the correct command can sometimes be inserted, as

```
i\vskip
```

for the above example. Also, this is an opportunity for inserting \show commands to inspect TeX's internal state. However, if TeX is in the middle of scanning something complicated, such commands will not be executed, or will even add to the confusion.

- s (\scrollmode) Scroll further errors, but display the messages. TeX will patch any further errors. This is a handy option, for instance if the error occurs in an alignment, because the number of subsequent errors tends to be rather large.
- r (\nonstopmode) Run without stopping. TeX will never stop for user interaction.
- q (\batchmode) Quiet running. TEX will never stop for user interaction, and does not give any more terminal output.
- x Exit. Abort this run of TEX.
- e Edit. This option is not available on all TEX system. If it is, the run of TEX is aborted, and an editor is started, opening with the input file, maybe even on the offending line.

35.2 Overflow errors 309

#### 35.2 Overflow errors

Harsh reality imposes some restrictions on how elaborate TeX's workings can get. Some restrictions are imposed by compile-time constants, and are therefore fairly loose, but some depend strongly on the actual computer implementation.

Here follows the list of all categories of overflow that prompt TEX to report 'Capacity exceeded'. Most bounds involved are (determined by) compile-time constants; their values given here in parentheses are those used in the source listing of TEX in [?]. Actual values may differ, and probably will. Remember that TEX was developed in the good old days when even big computers were fairly small.

# 35.2.1 Buffer size (500)

Current lines of all files that are open are kept in TEX's input buffer, as are control sequence names that are being built with \csname...\endcsname.

# 35.2.2 Exception dictionary (307)

The maximum number of hyphenation exceptions specified by \hyphenation must be a prime number. Two arrays with this many halfwords are allocated.

Changing this number makes formats incompatible; that is, TEX can only use a format that was made by an IniTEX with the same value for this constant.

# 35.2.3 Font memory (20,000)

Information about fonts is stored in an array of memory words. This is easily overflowed by preloading too many fonts in IniTeX.

# 35.2.4 Grouping levels

The number of open groups should be recordable in a quarter word. There is no compile-time constant corresponding to this.

## 35.2.5 Hash size (2100)

Maximum number of control sequences. It is suggested that this number should not exceed 10% of the main memory size. The values in TEX and IniTEX should agree; also the hash\_prime values should agree.

This value is rather low; for macro packages that are more elaborate than plain TFX a value of about 3000 is more realistic.

# 35.2.6 Number of strings (3000)

The maximum number of strings must be recordable in a half word.

# 35.2.7 Input stack size (200)

For each input source an item is allocated on the input stack. Typical input sources are input files (but their simultaneous number is more limited; see below), and token lists such as token variables, macro replacement texts, and alignment templates. A macro with 'runaway recursion' (for example, \def\mac{{\mac}}) will overflow this stack.

TeX performs some optimization here: before the last call in a token list all token lists ending with this call are cleared. This process is similar to 'resolving tail recursion' (see Chapter 11).

# 35.2.8 Main memory size (30,000)

Almost all 'dynamic' objects of TEX, such as macro definition texts and all material on the current page, are stored in the main memory array. Formats may already take 20 000 words of main memory for macro definitions, and complicated pages containing for instance the LATEX picture environment may easily overflow this array.

TeX's main memory is divided in words, and a half word is supposed to be able to address the whole of the memory. Thus on current 32-bit computers the most common choice is to let the main memory size be at most 64K bytes. A half word address can then be stored in 16 bits, half a machine word.

However, so-called 'Big TEX' implementations exist that have a main memory larger than 64K words. Most compilers will then allocate 32-bit words for addressing this memory, even if (say) 18 bits would suffice. Big TEXs therefore become immediately a lot bigger when they cross the 64K threshold. Thus they

35.2 Overflow errors 311

are usually not found on microcomputers, although virtual memory schemes for these are possible; see for instance [?].

TEX can have a bigger main memory than IniTEX; see Chapter 33 for further details.

## 35.2.9 Parameter stack size (60)

Macro parameters may contain macro calls with further parameters. The number of parameters that may occur nested is bounded by the parameter stack size.

# 35.2.10 Pattern memory (8000)

Hyphenation patterns are stored in a trie array. The default size of 8000 hyphenation patterns seems sufficient for English or Italian, for example, but it is not for Dutch or German.

## 35.2.11 Pattern memory ops per language

The number of hyphenation ops (see the literature about hyphenation: [?] and appendix H of [?]) should be recordable in a quarter word. There is no compile-time constant corresponding to this. TeX version 2 had the same upper bound, but gave no error message in case of overflow. Again, for languages such as Dutch and German this bound is too low. There are versions of TeX that have a higher bound here.

# 35.2.12 Pool size (32,000)

Strings are error messages and control sequence names. They are stored using one byte per character. TEX has initially about 23 000 characters worth of strings.

The pool will overflow if a user defines a large number of control sequences on top of a substantial macro package. However, even if the user does not define any new commands overflow may occur: crossreferencing schemes also work by defining control sequences. For large documents a pool size of  $40\,000$  or  $60\,000$  is probably sufficient.

#### 35.2.13 Save size (600)

Quantities that are assigned to inside a group must be restored after the end of that group. The save stack is where the values to be restored are kept; the size of the save stack limits the number of values that can be restored.

Alternating global and local assignments to a value will lead to 'save stack build-up': for each local assignment following a global assignment the previous value of the variable is saved. Thus an alternation of such assignments will lead to an unnecessary proliferation of items on the save stack.

#### 35.2.14 Semantic nest size (40)

Each time TeX switches to a mode nested inside another mode (for instance when processing an \hbox inside a \vbox) the current state is pushed on the semantic nest stack. The semantic nest size is the maximum number of levels that can be pushed.

#### 35.2.15 Text input levels (6)

The number of nested \input files has to be very limited, as the current lines are all kept in the input buffer.

# 第 36 章 The Grammar of TEX

Many chapters in this book contain pieces of the grammar that defines the formal syntax of TEX. In this chapter the structure of the rewriting rules of the grammar is explained, and some key notions are presented.

In the T<sub>E</sub>X book a grammar appears in Chapters 24–27. An even more rigorous grammar of T<sub>E</sub>X can be found in [?]. The grammar presented in this book is virtually identical to that of the T<sub>E</sub>X book.

## 36.1 Notations

Basic to the grammar are

grammatical terms These are enclosed in angle brackets:

⟨term⟩

**control sequences** These are given in typewriter type with a backslash for the escape character:

\command

Lastly there are

keywords Also given in typewriter type

keyword

This is a limited collection of words that have a special meaning for TeX in certain contexts; see below.

The three elements of the grammar are used in syntax rules:

```
\langle \operatorname{snark} \rangle \longrightarrow \operatorname{boojum} | \langle \operatorname{empty} \rangle
```

This rule says that the grammatical entity  $\langle snark \rangle$  is either the keyword boojum, or the grammatical entity  $\langle empty \rangle$ .

There are two other notational conventions. The first is that the double

quote is used to indicate hexadecimal (base 16) notation. For instance "ab56 stands for  $10 \times 16^3 + 11 \times 16^2 + 5 \times 16^1 + 6 \times 16^0$ . The second convention is that subscripts are used to denote category codes. Thus  $a_{12}$  denotes an 'a' of category 12.

# 36.2 Keywords

A keyword is sequence of characters (or character tokens) of any category code but 13 (active). Unlike the situation in control sequences, TEX does not distinguish between lowercase and uppercase characters in keywords. Uppercase characters in keywords are converted to lowercase by adding 32 to them; the \lccode and \uccode are not used here. Furthermore, any keyword can be preceded by optional spaces.

Thus both true cm and truecm are legal. By far the strangest example, however, is provided by the grammar rule

```
\langle \text{fil unit} \rangle \longrightarrow \text{fil} \mid \langle \text{fil unit} \rangle 1
```

which implies that fil L l is also a legal  $\langle$  fil dimen $\rangle$ . Strange errors can ensue from this; see page 140 for an example.

Here is the full list of all keywords: at, bp, by, cc, cm, dd, depth, em, ex, fil, height, in, l, minus, mm, mu, pc, plus, pt, scaled, sp, spread, to, true, width.

# 36.3 Specific grammatical terms

Some grammatical terms appear in a lot of rules. One such term is (optional spaces). The term *optional space* is probably clear enough, but here is the formal definition:

```
\langle \text{optional spaces} \rangle \longrightarrow \langle \text{empty} \rangle \mid \langle \text{space token} \rangle \langle \text{optional spaces} \rangle
```

which amounts to saying that (optional spaces) is zero or more space tokens.

Other terms may not be so immediately obvious. Below are some of them.

# $36.3.1 \langle equals \rangle$

In assignments the equals sign is optional; therefore there is a term  $\langle \text{equals} \rangle \longrightarrow \langle \text{optional spaces} \rangle \mid \langle \text{optional spaces} \rangle =_{12}$ 

in T<sub>E</sub>X's grammar.

## 36.3.2 \(\filler\), \(\langle general text \rangle \)

More obscure than the  $\langle optional\ spaces \rangle$  is the combination of spaces and  $\ relax\ tokens$  that is allowed in some places, for instance

```
\setbox0= \relax\box1
```

The quantity involved is

```
\langle \text{filler} \rangle \longrightarrow \langle \text{optional spaces} \rangle \mid \langle \text{filler} \rangle \rangle \rangle
```

One important occurrence of \( \) filler\( \) is in

```
\langle general \ text \rangle \longrightarrow \langle filler \rangle \{\langle balanced \ text \rangle \langle right \ brace \rangle
```

A  $\langle general\ text \rangle$  follows such control sequences as  $\backslash general\ text \rangle$  are explained in the next point.

# 36.3.3 {} and \(\text{left brace}\)\(\text{right brace}\)

The TeX grammar uses a perhaps somewhat unfortunate convention for braces. First of all

```
{ and }
```

stand for braces that are either explicit open/close group characters, or control sequences defined by \let, such as

```
\let\bgroup={ \let\egroup=}
```

The grammatical terms

```
⟨left brace⟩ and ⟨right brace⟩
```

stand for explicit open/close group characters, that is, characters of categories 1 and 2 respectively.

Various combinations of these two kinds of braces exist. Braces around boxes can be implicit:

```
\begin{cal}{l} \beg
```

Around a macro definition there must be explicit braces:

```
\langle definition \; text \rangle \longrightarrow \langle parameter \; text \rangle \langle left \; brace \rangle \langle balanced \; text \rangle \langle right \; brace \rangle
```

Finally, the (general text) that was mentioned above has to be explicitly closed, but it can be implicitly opened:

```
\langle general \ text \rangle \longrightarrow \langle filler \rangle \{\langle balanced \ text \rangle \langle right \ brace \rangle
```

The closing brace of a (general text) has to be explicit, since a general text is a

token list, which may contain  $\operatorname{legroup}$  tokens. TeX performs expansion to find the opening brace of a  $\operatorname{\langle general text \rangle}$ .

## 36.3.4 $\langle math field \rangle$

In math mode various operations such as subscripting or applying \underline take an argument that is a  $\langle$  math field $\rangle$ : either a single symbol, or a group. Here is the exact definition.

```
\begin{split} &\langle math \; field \rangle \longrightarrow \langle math \; symbol \rangle \; | \; \langle filler \rangle \{ \langle math \; mode \; material \rangle \} \\ &\langle math \; symbol \rangle \longrightarrow \langle character \rangle \; | \; \langle math \; character \rangle \end{split}
```

See page 42 for (character), and page 212 for (math character).

# 36.4 Differences between TEX versions 2 and 3

In 1989 Knuth released TEX version 3.0, which is the first real change in TEX since version 2.0, which was released in 1986 (version 0 of TEX was released in 1982; see [?] for more about the history of TEX). All intermediate versions were merely bug fixes.

The main difference between versions 2 and 3 lies in the fact that 8-bit input has become possible. Associated with this, various quantities that used to be 127 or 128 have been raised to 255 or 256 respectively. Here is a short list. The full description is in [?].

All 'codes' (\catcode, \sfcode, et cetera; see page 46) now apply to 256 character codes instead of 128.

A character with code \endlinechar is appended to the line unless this parameter is negative or more than 255 (this was 127) (see page 23).

No escape character is output by \write and other commands if \escapechar is negative or more than 255 (this was 127) (see page 29).

The ^^ replacement mechanism has been extended (see page 26).

Parameters \language, \inputlineno, \errorcontextlines, \lefthyphenmin, \righthyphenmin, \badness, \holdinginserts, \emergencystretch, and commands \noboundary, \setlanguage have been added.

The value of \outputpenalty is no longer zero if the page break was not at a penalty item; instead it is 10 000 (see page 257).

The plain format has also been updated, mostly with default settings for

parameters such as \lefthyphenmin, but also a few macros have been added.

# 第 37 章 Glossary of TEX Primitives

This chapter gives the list of all primitives of TEX. After each control sequence the grammatical category of the command or parameter is given, plus a short description. For some commands the syntax of their use is given.

For parameters the class to which they belong is given. Commands that have no grammatical category in the  $T_E X$  book are denoted either ' $\langle$ expandable command $\rangle$ ' or ' $\langle$ primitive command $\rangle$ ' in this list.

Grammatical terms such as  $\langle equals \rangle$  and  $\langle optional\ space \rangle$  are explained in Chapter 36.

\- \horizontal command\rangle Discretionary hyphen; this is equivalent to \discretionary""\{-}\{\}\. Can be used to indicate hyphenatable points in a word. Chapter 19.

\char32  $\langle$ horizontal command $\rangle$  Control space. Insert the same amount of space as a space token would if \spacefactor = 1000. Chapter 2,20.

\char47 \( \text{primitive command} \) Italic correction: insert a kern specified by the preceding character. Each character has an italic correction, possibly zero, specified in the tfm file. For slanted fonts this compensates for overhang. Chapter 4.

 $\label{lem:command} $$ \arrowvertext{ dimen} \arrowvertext{ (generalized fraction command) Fraction with specified bar width. Chapter 23.}$ 

\abovedisplayshortskip  $\langle$ glue parameter $\rangle$  Glue above a display if the line preceding the display was short. Chapter 24.

\abovedisplayskip \( \)glue parameter \( \) Glue above a display. Chapter 24.

 $\label{eq:command} $$\operatorname{delim}_1 \otimes \operatorname{delim}_2 \otimes \operatorname{dimen} \otimes \operatorname{delim}_2 \otimes \operatorname{dimen} \otimes \operatorname{delim}_2 \otimes \operatorname{dimen} \otimes \operatorname{delim}_2 \otimes \operatorname$ 

 $\accent{8-bit number}\accents on character}\accents on characters. Chapter 3.$ 

\adjdemerits  $\langle integer\ parameter \rangle$  Penalty for adjacent not visually compatible lines. Default 10 000 in plain TeX. Chapter 19.

 $\label{lem:command} $$\operatorname{advance}(\operatorname{numeric\ variable}) \ \langle \operatorname{optional\ by}(\operatorname{number}) \ \langle \operatorname{arithmetic\ assignment})$$ Arithmetic\ command\ to\ increase\ or\ decrease\ a\ \langle \operatorname{numeric\ variable}\rangle,\ that\ is,\ a\ \langle \operatorname{count\ variable}\rangle,\ \langle \operatorname{dimen\ variable}\rangle,\ \langle \operatorname{glue\ variable}\rangle,\ or\ \langle \operatorname{muglue\ variable}\rangle.$$ Chapter\ 7,8.$ 

 $\arrange \arrange \$ 

 $\verb|\atop| \langle dimen \rangle| \ \langle generalized \ fraction \ command \rangle| \ Place \ objects \ over \ one \ another.$  Chapter 23.

 $\hat{\beta}$  \atopwithdelims  $\hat{\beta}$  \delim<sub>1</sub> \angle \delim<sub>2</sub> \angle \text{generalized fraction command} \text{ Place} objects over one another with delimiters. Chapter 23.

\badness (internal integer) ( $T_EX3$  only) Badness of the most recently constructed box. Chapter 5.

\baselineskip \( \)glue parameter \\ \) The 'ideal' baseline distance between neighbouring boxes on a vertical list; 12pt in plain TpX. Chapter 15.

\batchmode \( \) interaction mode assignment \( \) TEX patches errors itself and performs an emergency stop on serious errors such as missing input files, but no terminal output is generated. Chapter 32.

\begingroup  $\langle primitive\ command \rangle$  Open a group that must be closed with \endgroup. Chapter 10.

 $\label{lowdisplayshortskip} $$ \langle glue\ parameter \rangle \ Glue\ below\ a\ display\ if\ the\ line\ preceding\ the\ display\ was\ short.\ Chapter\ 24.$ 

\belowdisplayskip \( \text{glue parameter} \) Glue below a display. Chapter 24.

\binoppenalty \langle integer parameter \rangle Penalty for breaking after a binary operator not enclosed in a subformula. Plain TeX default: 700. Chapter 23.

\botmark  $\langle expandable command \rangle$  The last mark on the current page. Chapter 28.

 $\verb|\box| \langle 8-bit number| \rangle | \langle box| \rangle | Use a box register, emptying it. Chapter 5.$ 

 $\label{lower} $$ \ \ $\operatorname{Maximum\ allowed\ depth\ of\ boxes.}$ Default \mbox{$\operatorname{Maximum\ allowed\ depth\ of\ boxes.}$ } $$$ 

\brokenpenalty \langle integer parameter \rangle Additional penalty for breaking a page

after a hyphenated line. Default 100 in plain TeX. Chapter 27.

 $\colon \colon \colon$ 

 $\label{lem:charce} $$ \character \ Explicit\ denotation\ of\ a\ character\ to\ be\ typeset.$$ Chapter\ 3.$ 

 $\$  leaders  $\$  As  $\$  leaders, but with box leaders any excess space is split into equal glue items before and after the leaders. Chapter 9.

 $\label{losein} $$ \close in \delta for number $$ $$ \delta for command $$ Close an input stream. $$ Chapter 30.$ 

 $\verb|\closeout| \langle 4-\texttt{bit number} \rangle \ \langle \texttt{primitive command} \rangle \ Close \ an \ output \ stream.$  Chapter 30.

\clubpenalty \(\)(integer parameter\)\) Additional penalty for breaking a page after the first line of a paragraph. Default 150 in plain TeX. Chapter 27.

\copy(8-bit number)  $\langle box \rangle$  Use a box register and retain the contents. Chapter 5.

 $\count(8-bit number)$  (internal integer); the control sequence itself is a (register prefix). Access count registers. Chapter 7.

 $\countdef(\control sequence)(\control sequence)(\control sequence)$  (shorthand definition); the control sequence itself is a (registerdef). Define a control sequence to be a synonym for a \count register. Chapter 7.

\crcr \( \text{primitive command} \) Terminate an alignment line if it has not already been terminated by \cr. Chapter 25.

\csname \( \) expandable command \( \) Start forming the name of a control sequence. Has to be balanced with \( \) endcsname. Chapter 11.

\day \langle integer parameter \rangle The day of the current job. Chapter 33.

\deadcycles \special integer \text{Counter that keeps track of how many times the output routine has been called without a \shipout taking place. If this number reaches \maxdeadcycles TeX gives an error message. Plain TeX default: 25. Chapter 28.

\def \def \Start a macro definition. Chapter 11.

\defaulthyphenchar  $\langle integer\ parameter \rangle$  Value of \hyphenchar when a font is loaded. Default value in plain TFX is `\-. Chapter 4,19.

 $\defaultskewchar \ (integer parameter) \ Value of \skewchar when a font is loaded. Default value in plain <math>T_FX$  is -1. Chapter 21.

 $\del{code} \del{eq:code} \de$ 

 $\label{lem:character} $$ \delimiter \end{cases}$ and character $$ Explicit denotation of a delimiter. Chapter 21.$ 

\delimiterfactor  $\langle integer\ parameter \rangle$  1000 times the part of a delimited formula that should be covered by a delimiter. Plain TeX default: 901. Chapter 21.

 $\label{limitershortfall} $$ \langle integer\ parameter \rangle \ Size\ of\ the\ part\ of\ a\ delimited formula\ that\ is\ allowed\ to\ go\ uncovered\ by\ a\ delimiter.\ Plain\ TeX\ default:\ 5pt.$  Chapter 21.

 $\dim(8-bit number)$  (internal dimen); the control sequence itself is a (register prefix). Access dimen registers. Chapter 8.

 $\dim \operatorname{def}(\operatorname{control} \operatorname{sequence}) \langle \operatorname{equals} \rangle \langle \operatorname{8-bit} \operatorname{number} \rangle \langle \operatorname{shorthand} \operatorname{definition} \rangle;$  the control sequence itself is a  $\langle \operatorname{registerdef} \rangle$ . Define a control sequence to be a synonym for a  $\dim \operatorname{register}$ . Chapter 8.

 $\discretionary{pre-break}{post-break}{no-break}$  (horizontal command) Specify the way a character sequence is split up at a line break. Chapter 19.

\displayindent \dimen parameter\rangle Distance by which the box, in which the display is centred, is indented owing to hanging indentation. This value is set automatically for each display. Chapter 24.

 $\label{lem:command} \mbox{Restore default placement for limits.} \\ Chapter 23.$ 

 $\label{lem:command} $$ \displaystyle $$ $$ \displaystyle of math typesetting. Chapter 23.$ 

 $\label{lem:displaywidowpenalty} $$ \langle integer\ parameter \rangle$ Additional\ penalty for\ breaking a page before the last line above a display formula. Default 50 in plain $T_E\!X$. Chapter 27.$ 

\displaywidth \dimen parameter\) Width of the box in which the display is centred. This value is set automatically for each display. Chapter 24.

\doublehyphendemerits  $\langle integer\ parameter \rangle$  Penalty for consecutive lines ending with a hyphen. Default 10 000 in plain TeX. Chapter 19.

 $\label{eq:control} $$ \dp(8-bit\ number) \ (internal\ dimen); the control\ sequence\ itself\ is\ a\ (box\ dimension). Depth\ of\ the\ box\ in\ a\ box\ register.\ Chapter\ 5.$ 

 $\langle vertical\ command \rangle$  Dump a format file; possible only in IniTeX, not allowed inside a group.

Chapter 33.

 $\ensuremath{\backslash}$  edef  $\ensuremath{\backslash}$  definition time. Chapter 11.

\else  $\langle expandable\ command \rangle$  Select  $\langle false\ text \rangle$  of a conditional or default case of \ifcase. Chapter 13.

\emergencystretch  $\langle$ dimen parameter $\rangle$  (TEX3 only) Assumed extra stretchability in lines of a paragraph in third pass of the line-breaking algorithm. Chapter 19.

\end \vertical command\rangle End this run. Chapter 32.

\endcsname \expandable command\rangle Delimit the name of a control sequence that was begun with \csname. Chapter 11.

\endgroup  $\langle primitive\ command \rangle$  End a group that was opened with \begingroup. Chapter 10.

 $\label{lem:command} \textbf{ Terminate inputting the current file after the current line. Chapter 30.}$ 

 $\label{linechar} $$\left\langle integer\ parameter\right\rangle$ The character code of the end-of-line character appended to input lines. IniTeX default: 13. Chapter 2.$ 

 $\label{eq:constraint} $$ \langle eqno \rangle \ Place \ a \ right \ equation \ number \ in \ a \ display \ formula. \ Chapter \ 24.$ 

\errhelp \tag{token parameter}\tag{Tokens that will be displayed if the user asks for help after an \errmessage. Chapter 35.

 $\ensuremath{\texttt{Verrmessage}}\ensuremath{\texttt{(general text)}}\ensuremath{\texttt{(primitive command)}}\ensuremath{\texttt{Report an error}}\ensuremath{\texttt{and give}}$  the user opportunity to act. Chapter 35.

\errorcontextlines \(\text{integer parameter}\) (TEX3 only) Number of additional context lines shown in error messages. Chapter 35.

\errorstopmode  $\langle interaction mode assignment \rangle$  Ask for user input on the occurrence of an error. Chapter 32.

 $\label{eq:control} $$\operatorname{control} \ \operatorname{control} \ \operatorname{contro$ 

\everycr \langle token parameter \rangle Token list inserted after every \cr or

non-redundant \crcr. Chapter 25.

 $\label{token parameter} \mbox{ Token list inserted at the start of a display. } Chapter \mbox{ 24}.$ 

 $\langle veryhbox \rangle$  (token parameter) Token list inserted at the start of a horizontal box. Chapter 5.

\everyjob  $\langle$ token parameter $\rangle$  Token list inserted at the start of each job. Chapter 32.

 $\label{token parameter} \mbox{ Token list inserted in front of paragraph text.} \\ Chapter \mbox{ 16}.$ 

\everyvbox  $\langle$  token parameter $\rangle$  Token list inserted at the start of a vertical box. Chapter 5.

\exhyphenpenalty \(\)(integer parameter\)\ Penalty for breaking a horizontal line at a discretionary in the special case where the prebreak text is empty.

Default 50 in plain TeX. Chapter 19.

 $\ensuremath{\mathtt{expandafter}}\ \langle expandable\ command \rangle$  Take the next two tokens and place the expansion of the second after the first. Chapter 12.

\fam \integer parameter \rangle The number of the current font family. Chapter 22.

\fi \( \)expandable command \( \) Closing delimiter for all conditionals. Chapter 13.

\floatingpenalty \( \) integer parameter \( \) Penalty amount added to \( \) insertpenalties when an insertion is split. Chapter 29.

 $\label{lem:control} $$ \operatorname{sequence} \langle \operatorname{equals} \rangle $$ (ile name) \ at clause) \ (simple assignment) Associate a control sequence with a tfm file. When used on its own, this control sequence is a $$ (font), denoting the current font. Chapter 4.$ 

 $\label{lem:cont} $$ \down{\down} \down{\do$ 

 $\time Tensor = Tens$ 

meaning of  $\langle token_2 \rangle$  to the  $\langle control sequence \rangle$ . Chapter 11.

\gdef \langle def \rangle Synonym for \global\def. Chapter 11.

\global  $\langle prefix \rangle$  Make the next definition, arithmetic statement, or assignment global. Chapter 10,11.

 $\globaldefs\ (integer\ parameter)\ Override\ \global\ specifications:\ a\ positive\ value\ of\ this\ parameter\ makes\ all\ assignments\ global,\ a\ negative\ value\ makes\ them\ local.\ Chapter\ 10.$ 

 $\$  \halign\box specification\{...}\\ optional assignments\\$\$ Chapter 25.

\hangafter  $\langle integer\ parameter \rangle$  If positive, this denotes the number of lines before indenting starts; if negative, its absolute value is the number of indented lines starting with the first line of the paragraph. The default value of 1 is restored after every paragraph. Chapter 18.

\hangindent \dimen parameter \rangle If positive, this indicates indentation from the left margin; if negative, this is the negative of the indentation from the right margin. The default value of Opt is restored after every paragraph. Chapter 18.

\hbadness \(\)(integer parameter\)\) Threshold below which TEX does not report an underfull or overfull horizontal box. Plain TEX default: 1000. Chapter 5.

 $\label{localization} $$ \box{box specification}_{\langle horizontal\ material \rangle} $$ \box{box} \ Construct\ a$ horizontal\ box. Chapter\ 5.$ 

\hfil  $\langle horizontal \ command \rangle$  Horizontal skip equivalent to \hskip 0cm plus 1fil. Chapter 8.

 $\label{lem:hfill} $$ \horizontal\ command$ Horizontal\ skip\ equivalent\ to $$ \hskip\ 0cm\ plus\ 1fill.\ Chapter\ 8.$ 

\hfilneg \horizontal command\rangle Horizontal skip equivalent to \hskip Ocm minus 1fil. Chapter 8.

\hfuzz \dimen parameter\rangle Excess size that TeX tolerates before it considers a horizontal box overfull. Plain TeX default: 0.1pt. Chapter 5.

\hoffset \dimen parameter \Distance by which the page is shifted to the right of the reference point which is at one inch from the left margin. Chapter 26.

\holdinginserts  $\langle integer\ parameter \rangle$  (only TeX3) If this is positive, insertions are not placed in their boxes when the \output tokens are inserted.

#### Chapter 29.

\hrule  $\langle vertical\ command \rangle$  Rule that spreads in horizontal direction. Chapter 9.

\hsize  $\langle$ dimen parameter $\rangle$  Line width used for text typesetting inside a vertical box. Chapter 5,18.

 $\label{localization} $$ \hskip\langle glue\rangle \ \langle horizontal\ command\rangle \ Insert\ in\ horizontal\ mode\ a\ glue\ item. $$ Chapter\ 8.$ 

\hss \(\text{horizontal command}\) Horizontal skip equivalent to \hskip Ocm plus 1fil minus 1fil. Chapter 8.

 $\hat{\beta}$  internal dimen; the control sequence itself is a  $\hat{\beta}$  dimension. Height of the box in a box register. Chapter 5.

\hyphenation\(\)general text\\rangle \(\)hyphenation assignment\(\) Define hyphenation exceptions for the current value of \language. Chapter 19.

\hyphenpenalty \( \)integer parameter \\ Penalty associated with break at a discretionary in the general case. Default 50 in plain TeX. Chapter 19.

 $\label{limin} $$ \left\langle \operatorname{dimen}_1 \right\rangle \left\langle \operatorname{relation} \right\rangle \left\langle \operatorname{dimen}_2 \right\rangle $$ $$ \left\langle \operatorname{expandable command} \right\rangle $$ Compare two dimensions. Chapter 13.$ 

 $\fine 4-bit number \end{area} \end{area} \end{area} Test whether a file has been fully read, or does not exist. Chapter 30.$ 

\iffalse \( \) expandable command \( \) This test is always false. Chapter 13.

 $\verb|\ifhbox| \langle 8-bit number|| \ \langle expandable \ command|| \ Test \ whether \ a \ box \ register \\ contains \ a \ horizontal \ box. \ Chapter \ 5.$ 

 $\$  restricted) horizontal mode. Chapter 13.

 $\$  Test whether the current mode is an internal mode. Chapter 13.

\ifmmode \langle expandable command \rangle Test whether the current mode is (possibly

display) math mode. Chapter 13.

 $\indeximal \$  (expandable command) Test whether a number is odd. Chapter 13.

\iftrue \( \) (expandable command \) This test is always true. Chapter 13.

 $\langle expandable\ command \rangle$  Test whether the current mode is (possibly internal) vertical mode. Chapter 13.

 $\texttt{\ifx}(\texttt{token}_1)(\texttt{token}_2)$  (expandable command) Test equality of macro expansion, or equality of character code and category code. Chapter 13.

 $\label{lem:command} \mbox{ ignorespaces } \langle primitive\ command \rangle\ Expands\ following\ tokens\ until something\ other\ than\ a\ \langle space\ token \rangle\ is\ found.\ Chapter\ 2.$ 

\immediate \( \)primitive command \( \) Prefix to have output operations executed right away. Chapter 30.

 $\label{lem:command} $$ Switch to horizontal mode and insert box with width $$ parindent. This command is automatically inserted before a $$ (horizontal command) in vertical mode. Chapter 16.$ 

 $\label{eq:command} $$ \arrowvert ($file name) $$ $$ \arrowvert ($expandable command) $$ Read a specified file as $T_E\!X$ input. Chapter $30.$ 

 $\label{linear} $$ \langle internal\ integer \rangle $$ (T_EX3\ only) \ Number\ of\ the\ current\ input\ line. $$ Chapter\ 30.$ 

\insertpenalties \special integer \rangle Total of penalties for split insertions. Inside the output routine the number of held-over insertions. Chapter 29.

 $\interline penalty (integer parameter)$  Penalty for breaking a page between lines of a paragraph. Default 0 in plain TeX. Chapter 27.

\jobname  $\langle expandable\ command \rangle$  Name of the main TeX file being processed. Chapter 32.

 $\kern\langle dimen \rangle \ \langle kern \rangle \ Add \ a \ kern \ item \ of the specified \ \langle dimen \rangle \ to \ the \ list; this can be used both in horizontal and vertical mode. Chapter 8.$ 

\language  $\langle integer\ parameter \rangle$  (TeX3 only) Choose a set of hyphenation patterns and exceptions. Chapter 19.

\lastbox  $\langle box \rangle$  Register containing the last element added to the current list, if this was a box. Chapter 5.

 $\arrange$  (internal dimen) If the last item on the list was a kern, the size of this. Chapter 8.

\lastpenalty  $\langle internal\ integer \rangle$  If the last item on the list was a penalty, the value of this. Chapter 27.

\lastskip  $\langle internal\ glue \rangle$  or  $\langle internal\ muglue \rangle$ . If the last item on the list was a skip, the size of this. Chapter 8.

 $\cline{10}$  (internal integer); the control sequence itself is a  $\cline{10}$  (codename). Access the character code that is the lowercase variant of a given code. Chapter 3.

 $\label{leaders} $$ \ensuremath{\mathsf{leaders}} \ensuremath{\mathsf{descrip}} \ensurema$ 

\left  $\langle primitive\ command \rangle$  Use the following character as an open delimiter. Chapter 21.

\lefthyphenmin \(\text{integer parameter}\) (TEX3 only) Minimum number of characters before a hyphenation. Chapter 19.

 $\label{eq:continuous} $$ \ensuremath{\mathsf{leftskip}}$ $$ $$ $ \ensuremath{\mathsf{glue}}$ parameter $$ $$ $$ Glue that is placed to the left of all lines. $$ $$ Chapter 18.$ 

 $\ensuremath{\mbox{leqno}}\mbox{\mbox{math mode material}}$  \$\$  $\ensuremath{\mbox{eqno}}\mbox{\mbox{Place a left equation number in a}}$  display formula. Chapter 24.

 $\label{eq:control} $\operatorname{det}(\operatorname{control} \operatorname{sequence})(\operatorname{equals})$ (token) $$ ($\operatorname{det} \operatorname{assignment})$ Define a control sequence to a token, assign its meaning if the token is a command or macro. Chapter 11.$ 

 $\label{limits} $$ \langle primitive\ command \rangle$ Place\ limits\ over\ and\ under\ a\ large\ operator.$$ This is\ the\ default\ position\ in\ display\ style.$$ Chapter\ 23.$ 

 $\label{linepenalty} $$ \langle integer\ parameter \rangle$ \ Penalty\ value\ associated\ with\ each\ line\ break. \ Default\ 10\ in\ plain\ TeX.\ Chapter\ 19.$ 

 $\langle$  glue parameter $\rangle$  Glue added if distance between bottom and top of neighbouring boxes is less than  $\langle$  lineskiplimit. Default 1pt in plain TeX. Chapter 15.

 $\label{lineskiplimit} $$ \langle dimen\ parameter \rangle \ Distance\ to\ be\ maintained\ between\ the\ bottom\ and\ top\ of\ neighbouring\ boxes\ on\ a\ vertical\ list.\ Default\ Opt\ in\ plain$ 

T<sub>F</sub>X. Chapter 15.

 $\langle prefix \rangle$  Indicate that the arguments of the macro to be defined are allowed to contain  $\langle par$  tokens. Chapter 11.

\looseness \(\)(integer parameter\)\) Number of lines by which this paragraph has to be made longer (or, if negative, shorter) than it would be ideally. Chapter 19.

 $\label{lowercase} $$ \langle general\ text \rangle\ \langle primitive\ command \rangle\ Convert\ the\ argument\ to\ its\ lowercase\ form.\ Chapter\ 3.$ 

\mag  $\langle integer\ parameter \rangle$  1000 times the magnification of the document. Default 1000 in IniTeX. Chapter 33.

\mark\general text\rangle \primitive command\rangle Specify a mark text. Chapter 28.

\mathaccent\langle 15-bit number \langle \mathfield \rangle \quad \text{primitive command} \rangle Place an accent in math mode. Chapter 21,23.

\mathbin\(math\) field\(\rangle\) (math\) atom\(\rangle\) Let the following \(math\) field\(\rangle\) function as a binary operation. Chapter 23.

 $\mbox{\mbox{\tt mathchar}}\langle \mbox{\tt 15-bit number}\rangle$   $\mbox{\mbox{\mbox{\it primitive command}}\rangle}$  Explicit denotation of a mathematical character. Chapter 21.

 $\label{lem:lemmatchardef} $$ \arrowvert a sequence $$ \langle equals \rangle \langle 15$-bit number \rangle $$ (shorthand definition) Define a control sequence to be a synonym for a math character code. Chapter 21.$ 

\mathchoice $\{D\}\{T\}\{S\}\{SS\}\$  \(\rangle\$ primitive command\)\) Give four variants of a formula for the four styles of math typesetting. Chapter 23.

 $\mbox{\sc math field}\ \ \mbox{\sc math atom}\ \ \mbox{\sc Let the following }\ \mbox{\sc math field}\ \ \mbox{\sc field}\ \ \mbox{\sc math field}\ \ \mbox{\sc field}\ \ \mbox{\sc math field}\ \ \mbox{\sc field}\ \mbox{\sc field}\ \ \mbox{\sc field}\ \ \mbox{\sc field}\ \ \mbox{\sc field}\ \mbox{\sc f$ 

 $\label{eq:control} $$\operatorname{a} \operatorname{code}(8-bit\ number) \ (internal\ integer)$; the control\ sequence\ itself\ is a \ (codename)$. Code\ of\ a\ character\ determining\ its\ treatment\ in\ math\ mode. Chapter\ 21.$ 

 $\mbox{\tt mathinner} \langle \mbox{\tt math} \ \ \mbox{\tt field} \rangle \ \langle \mbox{\tt math} \ \mbox{\tt atom} \rangle \ \mbox{\tt Let} \ \mbox{\tt the} \ \mbox{\tt following} \ \langle \mbox{\tt math} \ \mbox{\tt field} \rangle \ \mbox{\tt function}$  as an inner formula. Chapter 23.

 $\mbox{\sc math field}\ \ \mbox{\sc math atom}\ \ \mbox{\sc Let the following $\langle math field \rangle$ function as a large operator. Chapter 23.}$ 

 $\mbox{\mbox{$\$ 

\mathord\math field\rangle \dagger math atom\rangle Let the following \dagger math field\rangle function as

an ordinary object. Chapter 23.

 $\mbox{\mbox{\tt mathpunct}$\langle math field \rangle$ } \mbox{\mbox{\tt dmath atom}$\rangle$ Let the following $\langle math field \rangle$ function as a punctuation symbol. Chapter 23.}$ 

\mathrel\(math\) field\(\rangle\) (math\) atom\(\rangle\) Let the following \(math\) field\(\rangle\) function as a relation. Chapter 23.

 $\label{lem:mathsurround} $$ \langle dimen\ parameter \rangle \ Kern\ amount\ placed\ before\ and\ after in-line\ formulas.\ Chapter\ 23.$ 

\maxdeadcycles \(\) (integer parameter\) The maximum number of times that the output routine is allowed to be called without a \shipout occurring. IniTeX default: 25. Chapter 28.

\maxdepth  $\langle$ dimen parameter $\rangle$  Maximum depth of the page box. Default 4pt in plain TeX. Chapter 26.

\meaning  $\langle expandable command \rangle$  Give the meaning of a control sequence as a string of characters. Chapter 34.

\medmuskip \displaymedmuskip \

 $\mbox{\tt message}\langle\mbox{\tt general text}\rangle\ \langle\mbox{\tt primitive command}\rangle\ \mbox{\tt Write a message to the terminal. Chapter 30.}$ 

\mkern \langle primitive command \rangle Insert a kern measured in mu units. Chapter 23. \month \langle integer parameter \rangle The month of the current job. Chapter 33.

 $\label{local_moveleft_dimen} $$\operatorname{dox} \ \operatorname{dox} \ \operatorname{dox}$ 

 $\mbox{\command}\ \mbox{\command}\ \mbo$ 

 $\verb|\mox| \verb| (mathematical skip) Insert glue measured in mu units. Chapter 23.$ 

 $\label{eq:local_muskip} $$\operatorname{muskip}(8-bit\ number)$ $$\langle internal\ muglue\rangle$; the control sequence itself is a $$\langle register\ prefix\rangle$. Access skips measured in mu units. Chapter 23.$ 

\newlinechar  $\langle integer\ parameter \rangle$  Number of the character that triggers a new line in \write and \message statements. Plain TFX default -1; LATFX

default 10. Chapter 30.

 $\label{lem:command} $$\operatorname{command} \operatorname{Specify vertical (horizontal) material to be placed in between rows (columns) of an \align (\valign). Chapter 25.$ 

 $\label{localization} $$ \ \end{\command} \ Do \ not \ expand \ the \ next \ token. $$ Chapter \ 12.$ 

 $\label{limitive command} \mbox{ Switch to horizontal mode with an empty horizontal list. Chapter 16.}$ 

 $\mbox{\command}\xspace$  Place limits of a large operator as subscript and superscript expressions. This is the default position in text style. Chapter 23.

\nonscript \( \) primitive command \( \) Cancel the next glue item if it occurs in scriptstyle or scriptstyle. Chapter 23.

\nonstopmode \(\lambda\) interaction mode assignment\\\ TEX fixes errors as best it can, and performs an emergency stop when user interaction is needed. Chapter 32.

\nulldelimiterspace  $\langle$ dimen parameter $\rangle$  Width taken for empty delimiters. Default 1.2pt in plain TeX. Chapter 21.

\nullfont  $\langle fontdef\ token \rangle$  Name of an empty font that  $T_E X$  uses in emergencies. Chapter 4.

 $\verb|\number| \langle number| \rangle \ \langle expandable \ command| \rangle \ Convert \ a \ \langle number| \rangle \ to \ decimal \ representation. \ Chapter \ 7.$ 

 $\operatorname{\command}$  Omit the template for one alignment entry. Chapter 25.

 $\label{lem:command} $$\operatorname{openin}(4-bit\ number)\endreen 30. $$ \operatorname{filename} \endreen 30. $$$ 

 $\label{lem:command} $$\operatorname{openout}_{4-\text{bit number}} \ensuremeter 30. $$ \operatorname{openout}_{4-\text{bit number}} \ensuremeter 30. $$$ 

\or \( \text{primitive command} \) Separator for entries of an \ifcase. Chapter 13.

\outer  $\langle prefix \rangle$  Indicate that the macro being defined should occur on the outer level only. Chapter 11.

\output  $\langle$ token parameter $\rangle$  Token list with instructions for shipping out pages. Chapter 28.

\outputpenalty \( \text{integer parameter} \) Value of the penalty at the current page

break, or 10 000 if the break was not at a penalty. Chapter 27,28.

\over \( \text{generalized fraction command} \) Fraction. Chapter 23.

\overfullrule \dimen parameter\) Width of the rule that is printed to indicate overfull horizontal boxes. Plain TeX default: 5pt. Chapter 5.

 $\label{eq:coverline} $$\operatorname{define} \ \mathrm{def} \ \mathrm{dom} \ \mathrm{Overline} \ \mathrm{def} \ \mathrm{def} \ \mathrm{def} \ .$  Chapter 23.

 $\label{eq:command} $$\operatorname{\command}$ \ $\operatorname{\command}$ \ $\operatorname{\comm$ 

\pagedepth \langle special dimen \rangle Depth of the current page. Chapter 27.

\pagefill1stretch \special dimen \rangle Accumulated third-order stretch of the current page. Chapter 27.

\pagefillstretch \special dimen \rangle Accumulated second-order stretch of the current page. Chapter 27.

 $\pagefilstretch \slash special dimen \slash Accumulated first-order stretch of the current page. Chapter 27.$ 

\pagegoal \langle special dimen \rangle Goal height of the page box. This starts at \vsize, and is diminished by heights of insertion items. Chapter 27.

\pagestretch  $\langle special\ dimen \rangle$  Accumulated zeroth-order stretch of the current page. Chapter 27.

 $\label{lem:constraint} $$ \arrowvert a page total $$ $$ $$ (special dimen) Accumulated natural height of the current page. Chapter 27.$ 

 $\label{eq:command} $$ \operatorname{close} $ \text{ off a paragraph and go into vertical mode.} $$ Chapter $17$.$ 

\parfillskip  $\langle$ glue parameter $\rangle$  Glue that is placed between the last element of the paragraph and the line end. Plain TeX default: Opt plus 1fil. Chapter 17.

\parindent  $\langle$ dimen parameter $\rangle$  Size of the indentation box added in front of a paragraph. Chapter 16,18.

 $\parshape \langle equals \rangle n \ i_1 \ \ell_1 \dots i_n \ \ell_n$ 

specifies a number of lines n, and n pairs of an indentation and line length. Chapter 18.

\parskip \( glue \) parameter\\ Amount of glue added to vertical list when a

paragraph starts; default value 0pt plus 1pt in plain TpX. Chapter 16.

\patterns\(\)general text\(\) \(\)\(\)hyphenation assignment\(\)\ Define a list of hyphenation patterns for the current value of \language; allowed only in IniTeX. Chapter 19.

\pausing  $\langle$  integer parameter $\rangle$  Specify that TeX should pause after each line that is read from a file. Chapter 32.

\penalty  $\langle primitive command \rangle$  Specify desirability of not breaking at this point. Chapter 19,27.

 $\label{lem:postdisplaypenalty} $$ \langle integer\ parameter \rangle \ Penalty\ placed\ in\ the\ vertical\ list\ below\ a\ display.\ Chapter\ 24.$ 

\predisplaypenalty \(\)(integer parameter\) Penalty placed in the vertical list above a display. Plain TeX default: 10 000. Chapter 24.

 $\predisplaysize \ \langle dimen parameter \rangle \ Effective width of the line preceding the display. Chapter 24.$ 

\pretolerance \( \) integer parameter \( \) Tolerance value for a paragraph that uses no hyphenation. Default 100 in plain TeX. Chapter 19.

\prevdepth \special dimen \rangle Depth of the last box added to a vertical list as it is perceived by TrX. Chapter 15.

 $\prev{graf} \prev{graf} \pre$ 

\relax  $\langle \text{primitive command} \rangle$  Do nothing. Chapter 12.

\relpenalty \(\langle\) integer parameter\\\\ Penalty for breaking after a binary relation, not enclosed in a subformula. Plain TeX default: 500. Chapter 23.

\right  $\langle primitive\ command \rangle$  Use the following character as a closing delimiter. Chapter 21.

 $\mbox{\sc highthyphenmin}$  (integer parameter) (TEX3 only) Minimum number of characters after a hyphenation. Chapter 19.

\rightskip  $\langle$ glue parameter $\rangle$  Glue that is placed to the right of all lines. Chapter 18.

 $\verb|\command| command| Convert a positive | (any ber) | to lowercase roman representation. Chapter 7.$ 

 $\scriptfont\langle 4\text{-bit number}\rangle\ \langle family\ member\rangle;$  the control sequence itself is a  $\langle font\ range \rangle$ . Access the scriptfont of a family. Chapter 22.

 $\scriptscriptfont \langle 4-bit number \rangle$   $\langle family member \rangle$ ; the control sequence itself is a  $\langle font range \rangle$ . Access the scriptscriptfont of a family. Chapter 22.

 $\scriptscriptstyle \part command$  Select the scriptscript style of math typesetting. Chapter 23.

\scriptspace \dimen parameter\) Extra space after subscripts and superscripts. Default .5pt in plain TfX. Chapter 23.

\scriptstyle \( \)primitive command\\ \) Select the script style of math typesetting. Chapter 23.

\scrollmode  $\langle$  interaction mode assignment $\rangle$  TeX patches errors itself, but will ask the user for missing files. Chapter 32.

 $\scalebox \langle 8-bit number \rangle \langle equals \rangle \langle box \rangle \langle simple assignment \rangle$  Assign a box to a box register. Chapter 5.

 $\show\langle token \rangle$   $\show\langle token \rangle$  Display the meaning of a token on the screen. Chapter 34.

 $\verb|\showbox| \langle 8-bit number|| \ \langle primitive \ command|| \ Write \ the \ contents \ of \ a \ box \ to \\ the \ log \ file. \ Chapter \ 34.$ 

\showboxbreadth \( \) integer parameter \( \) Number of successive elements that are shown when \tracingoutput is positive, each time a level is visited. Plain TEX default: 5. Chapter 34.

\showboxdepth \(\lambda\) integer parameter\) The number of levels that are shown when \tracingoutput is positive. Plain TeX default: 3. Chapter 34.

\showlists \( \)primitive command \( \) Write to the log file the contents of the partial lists currently built in all modes. Chapter 6.

\showthe\langle internal quantity\rangle \text{(primitive command)} Display on the terminal the result of prefixing a token with \the. Chapter 34.

 $\scalebox{Skewchar}\langle font \rangle \ \langle internal\ integer \rangle \ Font\ position\ of\ an\ after-placed\ accent.$  Chapter 21.

 $\sline$ \skip $\langle 8$ -bit number $\rangle$   $\langle internal glue \rangle$ ; the control sequence itself is a  $\langle register prefix \rangle$ . Access skip registers Chapter 8.

 $\scalebox{$\scalebox{$\sim$} \scalebox{$\sim$} \scalebo$ 

\spacefactor  $\langle special integer \rangle$  1000 times the ratio by which the stretch component of the interword glue should be multiplied. Chapter 20.

\spaceskip  $\langle$ glue parameter $\rangle$  Interword glue if non-zero. Chapter 20.

\span \primitive command\rangle Join two adjacent alignment entries, or (in preamble) expand the next token. Chapter 25.

 $\$  Virite a token list to the dvi file. Chapter 33.

 $\label{thm:command} \textbf{ The last mark on a split-off page.}$  Chapter 28.

 $\$  The first mark on a split-off page. Chapter 28.

\splitmaxdepth \dimen parameter \Maximum depth of a box split off by a \vsplit operation. Default 4pt in plain TeX. Chapter 5,26.

 $\operatorname{\mathtt{f String}}(\operatorname{\mathtt{token}})\ \langle \operatorname{\mathtt{expandable}}\ \operatorname{\mathtt{Convert}}\ a\ \operatorname{\mathtt{token}}\ to\ a\ \operatorname{\mathtt{string}}\ of\ one\ or\ more\ \operatorname{\mathtt{characters}}.$  Chapter 3.

\tabskip \( \text{glue parameter} \) Amount of glue in between columns (rows) of an \halign (\valign). Chapter 25.

 $\textfont (4-bit number) (family member); the control sequence itself is a (font range). Access the textfont of a family. Chapter 22.$ 

 $\label{eq:command} \textbf{Select the text style of math type setting.}$  Chapter 23.

\the\(\)internal quantity\(\) \(\) \(\) (primitive command\(\) Expand the value of various quantities in ThX into a string of (character) tokens. Chapter 12.

\thickmuskip  $\langle muglue\ parameter \rangle$  Large amount of mu glue. Default value in plain TeX: 5mu plus 5mu. Chapter 23.

 $\label{lem:lem:muskip} $$\langle muglue\ parameter\rangle$ Small\ amount\ of\ mu\ glue.\ Default\ value\ in\ plain\ TeX:\ 3mu.\ Chapter\ 23.$ 

\time \( \)integer parameter \( \) Number of minutes after midnight that the current job started. Chapter 33.

 $\label{eq:control} $$\operatorname{cegister prefix} Access a token list register. Chapter 14. $$\ \operatorname{centrol sequence}(\ensuremath{\mbox{equals}}(\ensuremath{\mbox{8-bit number}})$$ (shorthand definition); the control sequence itself is a $$\ \operatorname{cegisterdef}(\ensuremath{\mbox{0.5}})$. Assign a control sequence to a $$\ \operatorname{chapter 14}$.$ 

\tolerance \(\lambda\) integer parameter\(\rangle\) Tolerance value for lines in a paragraph that does use hyphenation. Default 200 in plain TeX, 10000 in IniTeX. Chapter 19. \topmark \(\lambda\) expandable command\(\rangle\) The last mark of the previous page.

Chapter 28.

\topskip  $\langle$ glue parameter $\rangle$  Minimum distance between the top of the page box and the baseline of the first box on the page. Default 10pt in plain TeX. Chapter 26.

\tracingcommands  $\langle integer\ parameter \rangle$  When this is 1, TeX displays primitive commands executed; when this is 2 or more the outcome of conditionals is also recorded. Chapter 34.

\tracinglostchars \(\)(integer parameter\) If this parameter is positive, TeX gives diagnostic messages whenever a character is accessed that is not present in a font. Plain TeX default: 1. Chapter 34.

\tracingmacros \( \) integer parameter \( \) If this is 1, the log file shows expansion of macros that are performed and the actual values of the arguments; if this is 2 or more \( \) token parameter \( \) s such as \( \) output and \( \) everypar are also traced. Chapter 34.

\tracingonline  $\langle integer\ parameter \rangle$  If this parameter is positive, TeX will write trace information also to the terminal. Chapter 34.

\tracingoutput \langle integer parameter \rangle If this parameter is positive, the log file shows a dump of boxes that are shipped to the dvi file. Chapter 34.

\tracingpages  $\langle integer\ parameter \rangle$  If this parameter is positive, TeX generates a trace of the page-breaking algorithm. Chapter 34.

\tracingparagraphs  $\langle integer\ parameter \rangle$  If this parameter is positive, TeX generates a trace of the line-breaking algorithm. Chapter 34.

\tracingrestores \( \) integer parameter \( \) If this parameter is positive, TeX will report all values that are restored when a group level ends. Chapter 34.

\tracingstats \(\)(integer parameter\) If this parameter is positive, TeX reports at the end of the job the usage of various internal arrays. Chapter 34.

 $\colon \colon \colon$ 

\uchyph \(\text{integer parameter}\)\ Positive if hyphenating words starting with a capital letter is allowed. Plain TrX default 1. Chapter 19.

 $\mbox{\sc hunkern}\ \mbox{\sc primitive command}\ \mbox{\sc Remove the last item of the list if this was a kern. Chapter 8.}$ 

\unpenalty \( \text{primitive command} \) Remove the last item of the list if this was a penalty. Chapter 27.

 $\mbox{\sc hunskip}\ \mbox{\sc primitive command}\ \mbox{\sc Remove the last item of the list if this was a skip. Chapter 8.}$ 

 $\label{lem:containing} $\operatorname{unvbox}(8-bit\ number)$ $$ \langle vertical\ command\rangle$ Unpack\ a\ box\ register\ containing a\ vertical\ box,\ appending\ the\ contents\ to\ the\ list,\ and\ emptying\ the\ register.$$ Chapter\ 5.$ 

 $\unvcopy\langle 8-bit\ number\rangle\ \langle vertical\ command\rangle\ The\ same\ as\ \unvbox,\ but\ do\ not\ empty\ the\ register.\ Chapter\ 5.$ 

 $\label{lem:command} $$ \operatorname{\sc def} \ \operatorname{\sc command} \ \operatorname{\sc Convert} \ the \ argument \ to \ its \ uppercase form. \ Chapter 3.$ 

 $\label{lem:command} $$\operatorname{vadjust}_{filler}_{{\operatorname{command}}} $$\operatorname{primitive\ command}$ Specify in horizontal mode material for the enclosing vertical list. Chapter 6.$ 

  $\construct$  a vertical box vertically centred on the math axis. Chapter 23.

 $\$  Vertical skip equivalent to  $\$  Ocm plus 1fil. Chapter 8.

\vfill \vertical command \vertical skip equivalent to \vskip Ocm plus 1fill. Chapter 8.

 $\label{thm:command} $$ \end{\command} $$ Vertical skip equivalent to $$ \scalebox{0cm minus 1fil. Chapter 8.} $$$ 

\vfuzz \dimen parameter \Excess size that TeX tolerates before it considers a vertical box overfull. Plain TeX default: 0.1pt. Chapter 5.

\voffset \dimen parameter \Distance by which the page is shifted down from the reference point, which is one inch from the top of the page. Chapter 26.

 $\label{eq:command} \mbox{ Verule } \langle \mbox{horizontal command} \rangle \mbox{ Rule that spreads in vertical direction.}$  Chapter 9.

\vsize  $\langle$ dimen parameter $\rangle$  Height of the page box. Chapter 5,26.

 $\label{eq:command} $$ \scalebox{\command} \ Insert in vertical mode a glue item. $$ Chapter 8.$ 

 $\$  vsplit $\langle 8$ -bit number $\rangle$  to  $\langle$  dimen $\rangle$   $\langle$  primitive command $\rangle$  Split off the top part of a vertical box. Chapter 5,27.

\vss \(\vertical\) command\(\rightarrow\) Vertical skip equivalent to \\vskip\) Ocm plus 1fil minus 1fil. Chapter 8.

 $\displaystyle \langle box\ specification \rangle \{\langle vertical\ material \rangle\} \ \langle primitive\ command \rangle$ Construct a vertical box with reference point on the first item. Chapter 5.

 $\dots$  \wd\8-bit number\\ \( \text{internal dimen} \); the control sequence itself is a \( \text{box} \) dimension\\. Width of the box in a box register. Chapter 5.

\widowpenalty \(\text{integer parameter}\) Additional penalty for breaking a page before the last line of a paragraph. Default 150 in plain TeX. Chapter 27.

 $\mbox{\command}\ \mbox{\command}\ \mbo$ 

 $\d$  Synonym for  $\d$  Chapter 11.

 $\$  leaders  $\$  As \leaders, but with box leaders any excess space is spread equally between the boxes. Chapter 9.

\mathbb{xspaceskip} \( \text{glue parameter} \) Interword glue if non-zero and \mathbb{xspacefactor}  $\geq 2000$ . Chapter 20.

\year \langle integer parameter \rangle The year of the current job. Chapter 33.

# 第 38 章 编码表格

38.1 字符编码表 339

## 38.1 字符编码表

## 38.1.1 ASCII 字符编码

	ASCII C	HARACT	EF	R C(	DD	ES									dec C hex	HA	$\frac{\lambda R}{R}$			
b7 b6 b5	0 0	0 0 1	0	1	0	0	1	1	1	0	0	1	0	1	1	1	0	1	1	1
BITS b4 b3 b2 b1	CONT	ROL		SYI NU					ι	IPP	ER	CA	SE		L	OW	/EF	RCA	SE	
0 0 0 0	$^{\circ}_{\circ}$ NUL $_{\circ}$	DLE 20	32 20	SP	40	48 30	0	60	64 40	@	100	80 50	P	120	96 60	6	140	112 70	p	160
0 0 0 1	SOH	$^{17}_{_{11}}DC1_{_{21}}$	33 21	!	41	49 31	1	61	65 41	A	101	81 51	Q	121	97 61	a	141	113 71	q	161
0 0 1 0	<sup>2</sup> STX <sub>2</sub>		_	"	42		2	62	_	В	102		R	122	98 62	b	142	114 72	r	162
0 0 1 1		$^{19}_{13} DC3_{_{23}}$	35 23	#	43		3	63	67 43	C	103		S	123	99 63	c	143	115 73	s	163
0 1 0 0	4 EOT 4	$^{20}_{14} DC4_{_{24}}$		\$	44		4	64	68 44	D	104	84 54	Т	124	100 64	d	144	116 74	t	164
0 1 0 1	<sup>5</sup> <sub>5</sub> ENQ <sub>5</sub>	NAK 15 25	37 25	%	45		5	65	69 45	Е	105	85 55	U	125	101 65	e	145	117 75	u	165
0 1 1 0	6 ACK 6	SYN 16 23		&	46	36	6	66	70 46	F	106		V	126	102 66	f	146	76	v	166
0 1 1 1	BEL 7	ETB	39 27 40	,	47	37	7	67	71 47 72	G	107	87 57 88	W	127	103 67 104	g	147	119 77 120	w	167
1 0 0 0	8 8 BS 10	CAN	28 41	(	50	56 38 57	8	70		Η	110	58	X	130	68 105	h	150	78 121	X	170
1 0 0 1	9 HT 11	EM	l	)	51		9	71		Ι	111	59 90	Y	131	69	i	151	79 122	у	171
1 0 1 0	LF A 12	SUB	2A 43	*	52	3A 59	:	72	4A 75	J	112		Z	132	6A 107	j	152	7A 123	Z	172
1 0 1 1	VT B 13	ESC	l	+	53	3B	;	73	4B 76	K	113	5B	[	133	6B 108	k	153	7B	{	173
1 1 0 0	FF C 14	FS	2C	,	54	3C	<	74	4C	L	114	5C	\	134	6C	1	154	7C		174
1 1 0 1	CR 15	GS	2D 46	_	55	3D 62	=	75	4D 78	M	115		]	135	6D 110	m	155	7D	}	175
1 1 1 0	SO E 16	RS	2E	•	56	3E	>	76		N	116	5E	^	136	6E	n	156	7E	~	176
1 1 1 1	s SI	US	2F	/	57	3F	?	77	4F	O	117	5F	-	137	6F	0	157	_	)E]	L 177

第 38 章 编码表格

# 38.1.2 T<sub>E</sub>X 字符编码

	T <sub>E</sub> X CH	ARACTE	R (	COE	)ES	S									dec C hex	HA	AR oct			
b7 b6 b5	0 0	0 0 1	0	1	0	0	1	1	1	0	0	1	0	1	1	1	0	1	1	1
BITS b4 b3 b2 b1	CONT	ROL		SYI NU					l	IPP	ER	CA	SE	:	L	WC	/EF	RCA	SE	
0 0 0 0	° ^^@ °			SP	40		0	60	64 40	@	100	80 50	P	120	96 60	'	140	112 70	p	160
0 0 0 1	1	17 ^^Q 11 18	33 21 34	!	41	49 31 50	1	61	65 41 66	A	101	81 51 82	Q	121	97 61 98	a	141	113 71 114	q	161
0 0 1 0	<sup>2</sup> ^^B	^^R	22	"	42		2	62		В	102		R	122		b	142	72	r	162
0 0 1 1	^^C 3	^^S	23	#	43		3	63	43	С	103		S	123	63	c	143	73	s	163
0 1 0 0	^^D 4		24	\$	44	34 53	4	64	44 69	D	104	54 85	Т	124	64 101	d	144	74 117	t	164
0 1 0 1	5 5 <b>^^E</b> 6	15 25 22	25 38	%	45	35 54	5	65	45 70	Е	105	55 86	U	125	65 102	e	145	75 118	u	165
0 1 1 0	^^F		26 39	& ,	46	36 55	6	66	46 71	F	106	56 87	V	126	66 103	f	146	76 119	v	166
0 1 1 1	<sup>7</sup> ^^G <sub>7</sub>		27 40		47	37 56	7	67	47 72	G	107	57 88	W	127	67 104	g	147	77 120	W	167
1 0 0 0	9 ^^I	^^X 18 30 25 ^^Y	28 41		50	38 57	8	70	48 73	H 	110	58 89	X 	130	68 105	h	150	78 121	X	170
1 0 0 1	9 11 10 ^^J	19 31 26 ^^Z	29 42	) 	51	39 58	9	71	49 74	I — Ј	111	59 90	Y Z	131	69 106	1 	151	79 122	у 	171
1 0 1 1	A 12	1A 32 27 ^^[	2A 43	+	52	3A 59	•	72	4A 75		112	5A 91		132	6A 107	J k	152	7A 123	<b>z</b> {	172
1 1 0 0	B 13	1B 33 28	2B 44	,	53	60	, <	73	4B 76	L	113	5B 92	\	133	6B 108	1	153	7B 124	_ 	173
1 1 0 1	13 ^^M	<sup>29</sup> ^^]	45		54	61		74	4C 77	M	114	93		134	6C 109	m	154	7C 125	}	174
1 1 1 0	D 15	30 ^^^	46			3D 62	>	75	4D 78	N	115	94	^	135	110	n	155	7D 126	~	175
1 1 1 1	E 16	31 <b>^^</b>	2E 47	/	56	63	?	76	4E 79	О	116	5E 95	_	136	6E 111	0	156		^^?	176 ?
	F 17	l	2F		57	3F	•	77	4F		117	5F	_	137	6F		157	7F		177

## 38.2 计算机现代字体

#### 38.2.1 计算机现代罗马字体

#### COMPUTER MODERN ROMAN FONT LAYOUT

CO		0 1 1	_'`	IVIO		\ I \ \	···	IVI/ \		OIV		, , , ,	70	•							
0			16			32			48			64			80			96		112	
0	Γ	0	10	1	20	20	-	40	30	0	60	40	@	100	50	P	20	60	140	70	p 160
1			17			33			49			65			81			97		113	
	$\Delta$			J		l	!			1			Α			Q			$\mathbf{a}$		q
1		1	11		21	21		41	31		61	41		101	51	1	21	61	141	71	161
2	0		18	,		34	,,		50	0		66	ъ		82	ъ		98	1	114	
2	Θ	2	12		22	22		42	32	2	62	42	В	102	52	$R_{_{1}}$	22	62	b 142	72	r 162
3			19			35			51			67			83		-	99		115	
	Λ			,		l	#			3			$\mathbf{C}$			$\mathbf{S}$			c		$\mathbf{S}$
3		3	13		23	23	11	43	33		63	43		103	53	1	23	63	143	73	163
4	_		20	Ų		36	Ф		52			68	ъ		84	œ		100	,	116	
4	Ξ	4	14		24	24	\$	44	34	4	64	44	D	104	54	Τ,	24	64	d	74	t 164
5		-	21		24	37		44	53		04	69		104	85	- 1	24	101	144	117	104
	П			$\cup$		"	%		55	5		03	Е		03	U		101	e	111	u
5	11	5	15		25	25	/ 0	45	35	0	65	45		105	55		25	65	145	75	165
6			22			38			54			70			86			102		118	
	$\sum$	_		_	0.5		&			6			$\mathbf{F}$			V .	0.5		f		v
7		6	16 23		26	26 39		46	36 55		66	46 71		106	56 87	1	26	103	146	76 119	166
l '	Υ		23	0		39	,		33	7		/1	G		01	W		103	σ	119	w
7	_	7	17		27	27		47	37	'	67	47	u	107	57		27	67	g 147	77	167
8			24			40			56			72			88			104		120	
	Φ			د		l	(			8			Η			Χ			h		$\mathbf{X}$
8		10	18		30	28		50	38		70	48 73		110	58	1	30	68	150	78	170
9	Ψ		25	ß		41	)		57	9		13	T		89	Y		105	i	121	3.7
9	Ψ	11	19	13	31	29	)	51	39	9	71	49	1	111	59		31	69	151	79	y 171
10			26			42			58			74			90			106		122	-
	$\Omega$			æ		l	*			:			J			$\mathbf{Z}$			j		$\mathbf{Z}$
A		12	1A		32	2A		52	3A		72	4A		112	5A	1	32	6A	152	7A	172
11	ff		27	~		43			59			75	Κ		91	ſ		107	k	123	_
В	11	13	1B	œ	33	2B	+	53	3B	,	73	4B	17	113	5B	l 1	33	6B	K 153	7B	173
12			28			44			60			76			92			108		124	
	fi			Ø		l	,			i			$\mathbf{L}$			"			l		
С		14	1C		34	2C		54	3C		74	4C		114	5C	1	34	6C	154	7C	174
13	fl		29	ДГ.		45			61	_		77	ъл		93	1		109	****	125	"
D	П	15	1D	Æ	35	2D	-	55	3D	=	75	4D	М	115	5D	J 1	35	6D	m	7D	175
14		-	30			46			62			78		-	94			110		126	
	ffi			Œ		l				i			Ν			^			n		~
Е		16	1E		36	2E		56	3E		76	4E		116	5E	1	36	6E	156	7E	176
15	m		31	C		47	,		63	0		79	0		95			111		127	
F	ffl	17	1F	Ø	37	2F	/	57	3F	?	77	4F	O	117	5F	1	37	6F	O 157	7F	177
<u> </u>		11	L *'		51			51	J "			41		111	31		ψ1	01	131	_ /'	

## 38.2.2 计算机现代打字机字体

#### COMPUTER MODERN TYPEWRITER FONT LAYOUT

COM	FUIL		ODE	/ I V	1 1		VIXI	1 [	N F	ועוכ		AIC	<i>1</i> 0 I					
0		16		32			48			64			80		96		112	
								0			0		l	P		•	l	p
0	0	10	20	20		40	30		60	40		100	50	120	60	140	70	160
1		17		33			49			65			81	_	97		113	
		l			!		l	1			Α			Q		a		q
1	1	11	21	21		41	31		61	41		101	51	121	61	141	71	161
2		18		34	"		50	_		66	Б		82	ъ	98	,	114	
2	2	12	22	22		42	32	2	62	42	В	102	52	R 122	62	b	72	r 162
3		19		35		72	51		- 02	67		102	83	122	99	172	115	102
ľ		1 19		33	#		"	3		01	С		05	S	99	С	113	s
3	3	13	23	23	π	43	33	J	63	43	C	103	53	123	63	143	73	163
4		20		36			52			68			84		100		116	
					\$			4			D			T		d		t
4	4	14	24	24	•	44	34	_	64	44	_	104	54	124	64	144	74	164
5		21		37			53			69			85		101		117	
					%			5			Ε			U		е		u
5	5	15	25	25		45	35		65	45		105	55	125	65	145	75	165
6		22		38			54	_		70	_		86		102	_	118	
		1,0	26	26	&	46	١,,,	6	66	46	F	106		V 106		f	76	V 166
7	6	16	20	26		46	36		00	46 71		106	56	126	66	146	76	166
′		23		39	,		55	7		/1	~		87	1.7	103	_	119	
7	7	17	27	27		47	37	7	67	47	G	107	57	W 127	67	g <sub>147</sub>	77	<b>W</b>
8		24		40			56			72		101	88		104		120	101
l *					(		**	8			Н		"	X		h		x
8	10	18	30	28	•	50	38	O	70	48	-11	110	58	130	68	150	78	170
9		25		41			57			73			89		105		121	
					)			9			Ι			Y		i		У
9	11	19	31	29		51	39		71	49		111	59	131	69	151	79	171
10		26		42			58			74			90		106		122	
		l .			*			:			J			Z		j		Z
Α	12	1A	32	2A		52	3A		72	4A		112	5A	132	6A	152	7A	172
11		27		43			59			75	T.7		91	г	107	1_	123	r
В	13	1B	33	2B	+	53	3B	;	73	4B	K	113	5B	133	6B	k 153	7B	{ 173
12	1.5	28	33	44		- 55	60		13	76		113	92	133	108	133	124	113
12		20		1 77			"	<		10	L		92	\	100	1	124	1
С	14	1C	34	2C	,	54	3C	`	74	4C	Ъ	114	5C	134	6C	154	7C	1 174
13		29		45			61			77			93		109		125	
					_			=			М		l	1		m	l	}
D	15	1D	35	2D		55	3D		75	4D		115	5D	135	6D	155	7D	175
14		30		46			62			78			94		110		126	
								>			N		l	^		n	l	~
Е	16	1E	36	2E		56	3E		76	4E		116	5E	136	6E	156	7E	176
15		31		47			63			79	_		95		111		127	
I _					/			?			0					0	l	
F	17	1F	37	2F		57	3F		77	4F		117	5F	137	6F	157	7F	177

## 38.2.3 计算机现代意大利字体

#### COMPUTER MODERN ITALIC FONT LAYOUT

CO		JIL	_'`	VIO		VI V	117	LIC	10	INI	LA	100	JI										
0			16			32			48			64			80			96			112		
	Γ			$\imath$		l	-			0			(Q)			P			6			p	
0	-	0	10		20	20		40	30		60	40	_	100	50	-	120	60		140	70	P	160
1			17			33			49			65			81			97			113		
	Δ			J		l	!			1			A			Q			a			q	
1	_	1	11	J	21	21	•	41	31	1	61	41		101	51	æ	121	61	a	141	71	Ч	161
2			18			34			50			66			82			98			114		
	$\Theta$			`		l .	"		' '	2			В			R			b			r	
2	U	2	12		22	22		42	32	2	62	42		102	52	11	122	62	U	142	72	,	162
3			19			35			51		-	67			83			99			115		
	Λ			,		33	_//		"	3		٠.	C		00	S		33	0		110	0	
3	71	3	13		23	23	#	43	33	J	63	43	$\mathbf{c}$	103	53	D	123	63	c	143	73	s	163
4			20			36			52		- 00	68		100	84		120	100		110	116		100
"	Ξ		20	~		30	£		32	,		00	D		04	T		100	d		110	t	
4		4	14		24	24	L	44	34	4	64	44		104	54	1	124	64	a	144	74	$\iota$	164
5		-	21		2-7	37			53		04	69		104	85		124	101		177	117		104
1 5	П		21	U		31	07		55	E		09	$\mathbf{r}$		00	TΤ		101			11/		
5	П	5	15		25	25	%	45	35	5	65	45	E	105	55	U	125	65	e	145	75	u	165
		5			25			45			05			105			125			143			100
6			22	_		38	e,		54	0		70	$\mathbf{r}$		86	т.		102	c		118		
	$\Sigma$	6	16		26	26	$\mathcal{E}$	46	٦,	6	66	46	F	106		V	126	66	Ĵ	146	76	v	166
6		0			20			46	36		00			100	56		120			140	76		166
7	200		23	0		39	,		55	~		71	~		87	TT7		103			119		
	$\Upsilon$					l	/			$\gamma$			G			W			g			w	
7		7	17		27	27		47	37		67	47		107	57		127	67		147	77		167
8	-		24			40	,		56			72			88			104			120		
	$\Phi$			د		l	(			8			H			X			h			$\boldsymbol{x}$	
8		10	18		30	28	`	50	38		70	48		110	58		130	68		150	78		170
9			25	_		41	,		57			73			89			105			121		
	$\Psi$			ß		l	)			9			I			Y			i			y	
9		11	19		31	29		51	39		71	49		111	59		131	69		151	79		171
10			26			42			58			74			90			106			122		
	$\Omega$			æ		l	*			:			J			Z			j			z	
Α		12	1A		32	2A		52	3A		72	4A		112	5A		132	6A	J	152	7A		172
11			27			43			59			75			91			107			123		
1	ff			$\alpha$		l	+			;			K			[			k			_	
В	30	13	1B		33	2B		53	3B	,	73	4B		113	5B	L	133	6B		153	7B		173
12			28			44			60			76			92			108			124		
1	fi			Ø		l				i			L			"			1.			_	
С	J	14	1C	~	34	2C	7	54	3C	,	74	4C		114	5C		134	6C	٠	154	7C		174
13			29			45			61			77			93			109			125		$\neg$
1	fl			Æ		l	_			=			M			1			m			"	
D	J	15	1D	111	35	2D		55	3D		75	4D		115	5D	J	135	6D	,,,	155	7D		175
14			30			46			62			78			94			110			126		$\neg$
1	ffi			Œ		l				;			N			^			n			~	
Е	JJ v	16	1E	$\omega$	36	2E	•	56	3E	È	76	4E		116	5E		136	6E	10	156	7E		176
15			31			47			63			79			95			111			127		-
1	ffl			Ø			/			9		'	0			•			0			••	
F	$JJ^{t}$	17	1F	Ø	37	2F	/	57	3F	٠	77	4F	U	117	5F		137	6F	0	157	7F		177
		11	L *'		٥.	L'		٥.	L ~.		•••			**1	٥.		10.	٠.			"		211

## 38.2.4 计算机现代符号字体

#### COMPUTER MODERN SYMBOL FONT

CO	MP		_ 1 \ 1	VIO	DEI	VIV.	J 1 1	MR		FOI	v i										
0			16			32			48			64			80			96		112	
						ı	,		l	,			X			$\mathcal{P}$			$\vdash$		,
0	_	0	10	$\simeq$	20	20	$\leftarrow$	40	30	,	60	40	7/	100	50	P	120	60	140	70	V 160
		0			20			40			00			100			120		140	1	V 100
1			17			33			49			65			81	_		97		113	
				$\equiv$		ı	$\rightarrow$		l	$\infty$			$\mathcal{A}$			Q			$\dashv$		П
1		1	11		21	21		41	31		61	41		101	51	~	121	61	141	71	161
2			18			34			50			66			82			98		114	
_			1	_		J .			"	_		- 00	n		02	D		30	1	11.	$\nabla$
	X		l	$\subseteq$		ı	T		l	$\in$			$\mathcal{B}$			$\mathcal R$			L		$\nabla$
2		2	12		22	22		42	32		62	42		102	52		122	62	142	72	162
3			19			35			51			67			83			99		115	
	*			$\neg$		ı	- 1		l	$\ni$			$\mathcal{C}$			${\cal S}$					ſ
3	~	3	13	=	23	23	$\downarrow$	43	33	)	63	43	C	103	53	U	123	63	143	73	J 163
			-		23			7.5	_		03	_		103			125		143	+	103
4			20			36			52			68	_		84	_		100	_	116	
1	÷		1	$\leq$		l	$\leftrightarrow$		1	Δ			$\mathcal{D}$		l	$\mathcal{T}$					Ш
4		4	14	_	24	24		44	34		64	44		104	54	-	124	64	144	74	164
5			21			37			53			69			85			101		117	
ľ				_		ľ	7		١	_		١	C		١	11		101	٦	1	
	$\Diamond$	_	۱	$\geq$	0.5		/`			$\nabla$		4.5	${\cal E}$			$\mathcal{U}$	405			l	
5		5	15		25	25		45	35		65	45		105	55		125	65	145	75	165
6			22			38			54			70			86			102		118	
	$\pm$			$\preceq$		ı			l	/			$\mathcal{F}$			$\mathcal{V}$			{		
6		6	16	—,	26	26	×	46	36	/	66	46	J	106	56	V	126	66	146	76	= 166
																				1	
7			23			39			55			71	_		87			103	3	119	_
1	Ŧ		1	$\succeq$		l	$\simeq$		1	ŀ			$\mathcal{G}$		l	$\mathcal{W}$			}		$\supseteq$
7	'	7	17	_	27	27		47	37		67	47	_	107	57		127	67	147	77	— <sub>167</sub>
8			24			40			56			72			88			104		120	
	$\bigcirc$					l '	,		'	$\forall$			$\mathcal{H}$			$\mathcal{X}$			/		C
	$\oplus$	10	1.0	$\sim$	20	20	$\Leftarrow$	50		V	70	40	π	110		Л	120		150	70	§ 170
8		10	18		30	28		50	38		70	48		110	58		130	68	` 150	78	170
9			25			41			57			73			89			105		121	
1	$\ominus$		1	$\approx$		l	$\Rightarrow$		1	$\exists$			$\mathcal{I}$			$\mathcal{Y}$			>	1	†
9	$\circ$	11	19	, 0	31	29	_	51	39	_	71	49	_	111	59	J	131	69	151	79	171
10			26			42			58			74			90			106		122	
10	_		20	_		42			J 30			14	$\sigma$		90	~		100	1	1 122	1.
1	$\otimes$		1	$\subset$		l	$\uparrow$		1	$\neg$			$\mathcal{J}$		l	${\mathcal Z}$					‡
Α		12	1A		32	2A		52	3A		72	4A		112	5A		132	6A	152	7A	172
11			27			43			59			75			91			107		123	
1	0		1	$\neg$		l	$\Downarrow$		1	Ø			$\mathcal{K}$		l	U			II		$\P$
В	$\vee$	13	1B	$\supset$	33	2B	$\Psi$	53	3B	V)	73	4B	$\mathcal{L}$	113	5B	U	133	6B	153	7B	∏ 173
		13			JJ			55	-		13	_		113			133	_	100		113
12			28			44			60			76			92			108		124	_
1	$\odot$		1	~		l	$\Leftrightarrow$		1	$\Re$			$\mathcal{L}$		l	$\cap$			<b>‡</b>		*
С	_	14	1C		34	2C		54	3C		74	4C	_	114	5C		134	6C	¥ 154	7C	174
13			29			45			61			77			93			109		125	
1.3	$\bigcirc$		-"			I ~	K		"	$\sim$		l ''	1.4		95	1.0		109	$\Lambda$	1 123	^
1	$\bigcirc$			$\gg$		Ι.	1			$\Im$			$\mathcal{M}$		l _	$\forall$			<b>\$</b>		$\Diamond$
D		15	1D		35	2D		55	3D		75	4D		115	5D		135	6D	155	7D	175
14			30			46			62			78			94			110		126	
1	0		1	$\prec$		l	/		1	Т			$\mathcal{N}$		l	$\wedge$			\		$\Diamond$
Е	0	16	1E		36	2E	K	56	3E	- 1	76	4E	JV	116	5E	/ \	136	6E	156	7E	176
		10			50			50	_		10	_		110			100		130	_	110
15			31			47			63			79			95			111		127	
	•		1	$\succ$		l	$\propto$		1	$\perp$			$\mathcal{O}$		l	V			}		
										_	77	4F	_	117	5F		137	6F	157	1	
F	-	17	1F		37	2F		57	3F		11	4⊢		117	51		131	0F	157	7F	177

## 38.2.5 计算机现代数学扩展字体

#### COMPUTER MODERN MATH EXTENSION FONT

COIVI	FUIL	LK MOD		MAIL		ILIVSI	JIN FOINT			
0		16	32	/	48		64	80	96	112
0	( 0	10 ( 2	0 20	40	30	60	40 100	50 $\sum_{120}$	60 L 140	70 V 160
1		17	33	1	49		65	81	97	113
1 )	1	11 ) 2		41	31	61	41 / 101	<sub>51</sub> $\prod_{121}$	61 1 141	71 $\sqrt{}_{161}$
2		18	34	ſГ	50	_	66	82	98	114
2		12 ( 2		42	32	62	<b>I</b> 42 102	∫ J 122	62 142	72 $\sqrt{}$ 162
3		19	35	ו ד	51		67	83	99	115
3	3	13 ) 2	3 23	43	33	63	<b>I</b> 43 103	53 U 123	63 143	73 $\sqrt{}$ 163
4		20 F	36	ĺ	52		68	84	100	116
4	L 4	14 2	4 24	44	34	64	44 \ \ 104	54 \ \bigcap_{124}	64 144	74 \ \ 164
5		21	37	ı	53		69	85	101	117
							$\rangle$	<del> </del>	~	
5	5	15 2		45	35	65	45 / 105	55 125	65 145	75 165
6		22	38	Ī	54		70	86	102	118
						1		A		Г
7	6	16 2 23	6 26	46	36 55	66	46 106 71	56 126 87	66 146 103	76 166 119
,	,			7					~	
7	7	17 ] 2	7 27	47	37	<b>I</b> 67	47 📙 107	57 V 127	67 147	 77 167
8		24	40	(	56		72	88	104	120
8	{ 10	18 3	0 28	50	38	ſ <sub>70</sub>	∮ 110	58 $\sum_{130}$	68 [ 150	↑ 78 170
9	- 10	25	41	$\overline{}$	57		73	89	105	121
١ ،	1	]		l			ſ	п	]	,
9	11	19 3	1 29	51	39	<b>l</b> 71	49 9 111	<sub>59</sub> <b>11</b> <sub>131</sub>	69 151	↓ 79 171
10		26	42		58		74	90	106	122
	(	{		/		ι	. ①			_
Α	12	1A 3		52	3A	72	4A 112	5A J 132	6A L 152	7A 172
11		27	43	\	59		75	91	107 I	123
	<b>)</b>	}	.	>		J _	🔾	I U .		`
B '	13	1B 3	3 2B	53	3B 60	73	4B 113	5B 133	6B J 153	7B 173
1		/		/		J			Г	
С	14	1C 3	4 2C	54	3C	74	4C $\bigoplus_{114}$	5C   134	6C 154	7C 174
13		29	45	/	61		77	93	109	125
		\				Ţ	Ф	+	]	
D	15	1D / 3		55	3D	75	4D T 115	5D H 135	6D 155	7D 175
14		30	46		62		78	94	110	126
I .	/	/		/			4E 🛇	$\land$	{	介
E /	16	1E / 3	6 2E 47	/ 56	3E 63	76	4E 116	5E / \ <sub>136</sub>	6E \ 156	7E 176
15		31	47	\	03		(3)	95	)	127
F	\ ,,	,	,   ,-	\	_ ا	77	4F 🚫	FE V 12-	\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \	₩ 177
L F	17	1F \ 3	7 2F	\ 57	3F	77	4F 117	5F <b>V</b> 137	6F J 157	7F 177

# 38.3 Plain T<sub>E</sub>X 数学符号

#### 38.3.1 字符的数学码

下面列出的字符是用这个赋值定义的:

 $\verb|\mathcode| \langle 8\text{-bit number} \rangle \langle equals \rangle \langle 15\text{-bit number} \rangle$ 

Character	\mathcode	Class	Family	Hex position
•	"013A	ordinary	1	3A
/	"013D			3D
\	"026E		2	$6\mathrm{E}$
I	"026A			6A
+	"202B	binary operation	0	2B
_	"2200		2	00
*	"2203			03
:	"303A	relation	0	3A
=	"303D			3D
<	"313C		1	3C
>	"313E			3E
(	"4028	open symbol	0	28
Γ	"405B			5B
{	"4266		2	66
!	"5021	closing symbol	0	21
)	"5029			29
?	"503F			3F
]	"505D			5D
}	"5267		2	67
;	"603B	punctuation	0	3B
,	"613B		1	3B
	"8000			
1	"8000			
_	"8000			

### 38.3.2 字符的定界码

下面列出的字符是用这个赋值定义的:

 $\verb|\delcode| \langle 8\text{-bit number}\rangle \langle equals\rangle \langle 24\text{-bit number}\rangle$ 

它们可以与 \left 和 \right 一起使用。

ariant
Hex position
00
01
02
03
0A
0B
0E
0C
0F

## 38.3.3 定义普通符号

下面列出的字符是用这个赋值定义的:

 $\verb|\mathchardef| \langle control \ sequence \rangle \langle equals \rangle \langle 15\text{-bit number} \rangle$ 

Symbol	Control Sequence	\mathcode	Family	Hex position
$\partial$	\partial	"0140	1	40
þ	\flat	"015B		$5\mathrm{B}$
ф	\natural	"015C		$5\mathrm{C}$
#	\sharp	"015D		5D
$\ell$	\ell	"0160		60
$\imath$	\imath	"017B		7B
J	\jmath	"017C		$7\mathrm{C}$
Ø	\wp	"017D		7D
1	\prime	"0230	2	30
$\infty$	\infty	"0231		31
$\triangle$	\triangle	"0234		34
$\forall$	\forall	"0238		38
3	\exists	"0239		39
$\neg$	\neg	"023A		3A
Ø	\emptyset	"023B		3B
$\Re$	\Re	"023C		3C
3.	\Im	"023D		3D
Т	\top	"023E		3E

$\perp$	\bot	"023F	3F
×	\aleph	"0240	40
$\nabla$	\nabla	"0272	72
*	\clubsuit	"027C	$7\mathrm{C}$
$\Diamond$	\diamondsuit	"027D	7D
$\Diamond$	\heartsuit	"027E	$7\mathrm{E}$
•	\spadesuit	"027F	$7\mathrm{F}$

#### 38.3.4 定义巨算符

下面列出的字符是用这个赋值定义的:

 $\verb|\mathchardef| \langle control \ sequence \rangle \langle equals \rangle \langle 15\text{-bit number} \rangle$ 

Symbol	Control Sequence	\mathcode	Family	Hex position
$\int \int$	\smallint	"1273	2	73
$\sqcup \sqcup$	\bigsqcup	"1346	3	46
∮∮	\ointop	"1348		48
$\odot \odot$	\bigodot	"134A		4A
$\oplus \bigoplus$	\bigoplus	"134C		4C
$\otimes \bigotimes$	\bigotimes	"134E		4E
$\sum \sum$	\sum	"1350		50
$\prod_{a}$	\prod	"1351		51
$\int \int$	\intop	"1352		52
UŮ	\bigcup	"1353		53
$\cap \bigcap$	\bigcap	"1354		54
$\forall $	\biguplus	"1355		55
$\wedge \wedge$	\bigwedge	"1356		56
$\vee\bigvee$	\bigvee	"1357		57
$\coprod\coprod$	\coprod	"1360		60

## 38.3.5 定义二元运算符

下面列出的字符是用这个赋值定义的:

 $\mbox{\control sequence} \langle \mbox{\control sequence} \rangle \langle \mbox{\control sequence} \rangle$ 

Symbol	Control Sequence	\mathcode	Family	Hex position
$\triangleright$	\triangleright	"212E	1	$2\mathrm{E}$
⊲	\triangleleft	"212F		2F
*	\star	"213F		3F
	\cdot	"2201	2	01
×	\times	"2202		02
*	\ast	"2203		03
÷	\div	"2204		04
$\Diamond$	\diamond	"2205		05
$\pm$	\pm	"2206		06
干	\mp	"2207		07
$\oplus$	\oplus	"2208		08
$\ominus$	\ominus	"2209		09
$\otimes$	\otimes	"220A		0A
$\oslash$	\oslash	"220B		0B
$\odot$	\odot	"220C		0C
$\bigcirc$	\bigcirc	"220D		0D
0	\circ	"220E		$0\mathbf{E}$
•	\bullet	"220F		0F
$\triangle$	\bigtriangleup	"2234		34
$\nabla$	\bigtriangledown	"2235		35
U	\cup	"225B		5B
$\cap$	\cap	"225C		5C
$\forall$	\uplus	"225D		5D
$\wedge$	\wedge	"225E		$5\mathrm{E}$
V	\vee	"225F		$5\mathrm{F}$
\	\setminus	"226E		6E
?	\wr	"226F		$6\mathrm{F}$
П	\amalg	"2271		71
	\sqcup	"2274		74
П	\sqcap	"2275		75
†	\dagger	"2279		79
‡	\ddagger	"227A		7A

## 38.3.6 定义二元关系符

下面列出的字符是用这个赋值定义的:

 $\verb|\mathchardef| \langle control \ sequence \rangle \langle equals \rangle \langle 15\text{-bit number} \rangle$ 

350 第 38 章 编码表格

Symbol	Control Sequence	\mathcode	Family	Hex position
_	\leftharpoonup	"3128	1	28
$\overline{}$	\leftharpoondown	"3129		29
	\rightharpoonup	"312A		2A
$\rightarrow$	\rightharpoondown	"312B		2B
$\smile$	\smile	"315E		5E
$\overline{}$	\frown	"315F		$5\mathrm{F}$
$\approx$	\asymp	"3210	2	10
≡	\equiv	"3211		11
$\subseteq$	\subseteq	"3212		12
$\supseteq$	\supseteq	"3213		13
$\leq$	\leq	"3214		14
$\geq$	\geq	"3215		15
$\preceq$	\preceq	"3216		16
$\succeq$	\succeq	"3217		17
$\sim$	\sim	"3218		18
$\approx$	\approx	"3219		19
$\subset$	\subset	"321A		1A
$\supset$	\supset	"321B		1B
«	\11	"321C		1C
>>	\gg	"321D		1D
$\prec$	\prec	"321E		1E
$\succ$	\succ	"321F		1F
$\leftarrow$	\leftarrow	"3220		20
$\rightarrow$	\rightarrow	"3221		21
$\leftrightarrow$	\leftrightarrow	"3224		24
7	\nearrow	"3225		25
$\searrow$	\searrow	"3226		26
$\simeq$	\simeq	"3227		27
<=	\Leftarrow	"3228		28
$\Rightarrow$	\Rightarrow	"3229		29
$\Leftrightarrow$	\Leftrightarrow	"322C		2C
_	\nwarrow	"322D		2D
✓	\swarrow	"322E		2E
$\propto$	\propto	"322F		$2\mathrm{F}$
$\in$	\in	"3232		32
∋	\ni	"3233		33

/	\not	"3236	36
ŀ	\mapstochar	"3237	37
$\perp$	\perp	"323F	3F
$\vdash$	\vdash	"3260	60
$\dashv$	\dashv	"3261	61
	\mid	"326A	6A
	\parallel	"326B	6B
	\sqsubseteq	"3276	76
⊒	\sqsupseteq	"3277	77

352 第 38 章 编码表格

## 38.3.7 定义定界符

下面列出的字符是用这个赋值定义的:

 $\verb|\def| \langle control\ sequence| \\ | \langle control\$ 

Delimiters			
Symbol	Control Sequence	Hex code	Function
ſ	\lmoustache	"4000340	open symbol
ĺ	\rmoustache	"5000341	closing symbol
	\lgroup	"400033A	open symbol
	\rgroup	"500033B	closing symbol
ĺ	\arrowvert	"33C	ordinary
	\Arrowvert	"33D	ordinary
ı	\bracevert	"33E	ordinary
	\Vert	"26B30D	ordinary
	\vert	"26A30C	ordinary
<b>†</b>	\uparrow	"3222378	relation
$\downarrow$	\downarrow	"3223379	relation
<b>\$</b>	\updownarrow	"326C33F	relation
$\uparrow$	\Uparrow	"322A37E	relation
$\Downarrow$	\Downarrow	"322B37F	relation
<b>\$</b>	\Updownarrow	"326D377	relation
\	\backslash	"26E30F	ordinary
>	\rangle	"526930B	closing symbol
<	\langle	"426830A	open symbol
}	\rbrace	"5267309	closing symbol
{	\lbrace	"4266308	open symbol
]	\rceil	"5265307	closing symbol
ſ	\lceil	"4264306	open symbol
	\rfloor	"5263305	closing symbol
Ĺ	\lfloor	"4262304	open symbol

# 版本历史

#### Vection 1.4

Reinstated a couple of figures (baseline distance, plus one one paragraph shape that didn't make it into the original book.)

#### Version 1.3

Finally managed to reinstate the tables chapter.

Starting to add more concepts to the index.

#### Version 1.2

Added chapter references to glossary.

Fixed a bunch of typographic accidents.

#### Version 1.1

Small remark about \afterassignment after macro definitions.

Trouble with indexing macros fixed, I hope.

Separate letter and a4 versions.

Better intro for the chapter 20 on spacing.