

# SRM INSTITUTE OF SCIENCE AND TECHNOLOGY SCHOOL OF COMPUTING

**18CSC205J-Operating Systems** 

Unit- I

Prepared by

**Dr. M. Eliazer**CTECH, SCHOOL OF COMPUTING, SRMIST



### **UNIT 1 - CONTENT**

#### **Session-1**

- Operating System Objectives and functions
- Gaining the role of Operating systems

#### **Session-2**

- The evolution of operating system
- Major Achievements
- Understanding the evolution of Operating systems from early batch processing systems to modern complex systems

#### **Session-3**

- OS Design considerations for Multiprocessor and Multicore
- Understanding the key design issues of Multiprocessor Operating systems and Multicore Operating systems

#### **Session-6**

- Process Concept Processes, PCB
- Understanding the Process concept and Maintenance of PCB by OS

- Threads Overview and its Benefits
- Understanding the importance of threads

## CARS- EN-LIPE

#### **UNIT 1 - CONTENT**

#### Session-6

- Process Concept Processes, PCB
- Understanding the Process concept and Maintenance of PCB by OS

#### **Session-7**

- Threads Overview and its Benefits
- Understanding the importance of threads

#### Session-8

- Process Scheduling Scheduling Queues, Schedulers, Context switch
- Understanding basics of Process Scheduling

#### Session-11

- Operations on Process Process creation, Process termination
- Understanding the system calls fork(), wait(), exit()

#### Session-12

- Inter Process communication : Shared Memory, Message Passing ,Pipe()
- Understanding the need for IPC

- Process synchronization: Background, Critical section Problem
- Understanding the race conditions and the need for the Process synchronization

- Operating System Objectives and functions
- Gaining the role of Operating systems



#### **OS OBJECTIVES**

### What is an Operating System

Operating systems are those programs that interface the machine with the applications programs. The main function of these systems is to dynamically allocate the shared system resources to the executing programs.

- A program that controls the execution of application programs
- An interface between applications and hardware

### Main objectives of an OS

- Convenience
- Efficiency
- Ability to evolve



### **Operating System Functions**

- Program development
- Program execution
- Access I/O devices
- Controlled access to files
- System access
- Error detection and response
- Accounting



### **Role of Operating System**

### 1. The OS as a User/Computer Interface

- Computer Hardware-Software Structure
  - Layered organization
- OS services to users

#### 2. The Operating System as a Resource Manager

A computer is a set of resources for moving, storing, & processing data

- The OS is responsible for managing these resources
- The OS exercises its control through software



### **Role of Operating System**


### 3. Operating System as Software

- Functions in the same way as ordinary computer software
- Program, or suite of programs, executed by the processor
- Frequently relinquishes control and must depend on the processor to allow it to regain control



### **Role of Operating System**

### 4. Operating System as Resource Manager





- The evolution of operating system
- Major Achievements
- Understanding the evolution of Operating systems from early batch processing systems to modern complex systems




### **Evolution of Operating Systems**

A major OS will evolve over time for a number of reasons:

- Hardware upgrades
- New types of hardware
- New services
- Fixes



### **Evolution of Operating Systems**





### **Serial Processing**

#### **Earliest Computers:**

- No operating system
   Programmers interacted directly with the computer hardware
- Computers ran from a console with display lights, toggle switches, some form of input device, and a printer
- Users have access to the computer in "series"

#### Problems:

- Scheduling:
  - Most installations used a hardcopy sign-up sheet to reserve computer time.
  - Time allocations could run short or long, resulting in wasted computer time
  - Setup time
    - A considerable amount of time was spent just on setting up the program to run



### Simple Batch Systems

- Early computers were very expensive
  - Important to maximize processor utilization
- Monitor
  - User no longer has direct access to processor
  - Job is submitted to computer operator who batches them together and places them on an input device
  - Program branches back to the monitor when finished



#### **Monitor Point of View**

- Monitor controls the sequence of events
- Resident Monitor is software always in memory
- Monitor reads in job and gives control
- Job returns control to monitor




Figure 2.3 Memory Layout for a Resident Monitor



#### **Processor Point of View**

- Processor executes instruction from the memory containing the monitor
- Executes the instructions in the user program until it encounters an ending or error condition
- "control is passed to a job" means processor is fetching and executing instructions in a user program
- "control is returned to the monitor" means that the processor is fetching and executing instructions from the monitor program



### **Modes of Operation**

#### User Mode

- User program executes in user mode
- Certain areas of memory are protected from user access
- Certain instructions may not be executed

#### Kernel Mode

- Monitor executes in kernel mode
- Privileged instructions may be executed
- Protected areas of memory may be accessed



### Simple Batch System Overhead

- Processor time alternates between execution of user programs and execution of the monitor
- Sacrifices:
  - some main memory is now given over to the monitor
  - some processor time is consumed by the monitor
- Despite overhead, the simple batch system improves utilization of the computer. (How?)



### Multi programmed Batch Systems

Read one record from file	15 μs
Execute 100 instructions	$1 \mu s$
Write one record to file	<u>15 μs</u>
TOTAL	31 µs

Percent CPU Utilization = 
$$\frac{1}{31}$$
 = 0.032 = 3.2%


#### Processor is often idle

- Even with automatic job sequencing
- I/O devices are slow compared to processor

Figure 2.4 System Utilization Example




### Uniprogramming



The processor spends a certain amount of time executing, until it reaches an I/O instruction; it must then wait until that I/O instruction concludes before proceeding



### **Multiprogramming**




There must be enough memory to hold the OS (resident monitor) and one user program

When one job needs to wait for I/O, the processor can switch to the other job, which is likely not waiting for I/O



### **Multiprogramming**



#### Multiprogramming

- also known as multitasking
- memory is expanded to hold three, four, or more programs and switch among all of them



### **Multiprogramming Example**

Table 2.1 Sample Program Execution Attributes

	JOB1	JOB2	JOB3
Type of job	Heavy compute	Heavy I/O	Heavy I/O
Duration	5 min	15 min	10 min
Memory required	50 M	100 M	75 M
Need disk?	No	No	Yes
Need terminal?	No	Yes	No
Need printer?	No	No	Yes



### **Effects on Resource Utilization**

	Uniprogramming	Multiprogramming
Processor use	20%	40%
Memory use	33%	67%
Disk use	33%	67%
Printer use	33%	67%
Elapsed time	30 min	15 min
Throughput	6 jobs/hr	12 jobs/hr
Mean response time	18 min	10 min

Table 2.2 Effects of Multiprogramming on Resource Utilization



### **Time-Sharing Systems**

- Can be used to handle multiple interactive jobs
- Processor time is shared among multiple users
- Multiple users simultaneously access the system through terminals, with the OS interleaving the execution of each user program in a short burst or quantum of computation



### Batch Multiprogramming vs. Time Sharing

	Batch Multiprogramming	Time Sharing
Principal objective	Maximize processor use	Minimize response time
Source of directives to operating system	Job control language commands provided with the job	Commands entered at the terminal

Table 2.3 Batch Multiprogramming versus Time Sharing



### **Compatible Time-Sharing Systems**

#### **CTSS**

- One of the first time-sharing operating systems
- Developed at MIT by a group known as Project MAC
- Ran on a computer with 32,000 36-bit words of main memory, with the resident monitor consuming 5000 of that
- To simplify both the monitor and memory management a program was always loaded to start at the location of the 5000<sup>th</sup> word


#### **Time Slicing**

- System clock generates interrupts at a rate of approximately one every 0.2 seconds
- At each interrupt OS regained control and could assign processor to another user
- At regular time intervals the current user would be preempted and another user loaded in
- Old user programs and data were written out to disk
- Old user program code and data were restored in main memory when that program was next given a turn



### **Major Achievements**

Operating Systems are among the most complex pieces of software ever developed



Major advances in development include:

- Processes
- Memory management
- Information protection and security
- Scheduling and resource management
- System structure



#### **Process**

### Fundamental to the structure of operating systems

### A *process* can be defined as:

a program in execution

an instance of a running program

the entity that can be assigned to, and executed on, a processor

a unit of activity characterized by a single sequential thread of execution, a current state, and an associated set of system resources



### **Development of the Process**

Three major lines of computer system development created problems in timing and synchronization that contributed to the development:

#### multiprogramming batch operation

 processor is switched among the various programs residing in main memory

#### time sharing

• be responsive to the individual user but be able to support many users simultaneously

#### real-time transaction systems

• a number of users are entering queries or updates against a database



### **Components of a Process**

- A process contains three components:
  - An executable program
  - The associated data needed by the program (variables, work space, buffers, etc.)
  - The execution context (or "process state") of the program

- The execution context is essential:
  - It is the internal data by which the OS is able to supervise and control the process
  - Includes the contents of the various process registers
  - Includes information such as the priority of the process and whether the process is waiting for the completion of a particular I/O event



### **Process Management**

- The entire state of the process at any instant is contained in its context
- New features can be designed and incorporated into the OS by expanding the context to include any new information needed to support the feature





Figure 2.8 Typical Process Implementation



### **Memory Management**

The OS has five principal storage management responsibilities:





### Memory Management (contd..)

#### VIRTUAL MEMORY

- A facility that allows programs to address memory from a logical point of view, without regard to the amount of main memory physically available
- Conceived to meet the requirement of having multiple user jobs reside in main memory concurrently

#### PAGING

- Allows processes to be comprised of a number of fixed-size blocks, called pages
- Program references a word by means of a virtual address
  - consists of a page number and an offset within the page
  - each page may be located anywhere in main memory
- Provides for a dynamic mapping between the virtual address used in the program and a real (or physical) address in main memory



### **Information Protection and Security**

- The nature of the threat that concerns an organization will vary greatly depending on the circumstances
- The problem involves controlling access to computer systems and the information stored in them





### **Scheduling and Resource Management**

- Key responsibility of an OS is managing resources
- Resource allocation policies must consider:





# **Key Elements of an Operating System**




Figure 2.11 Key Elements of an Operating System for Multiprogramming



#### **Session-3**

- OS Design considerations for Multiprocessor and Multicore
- Understanding the key design issues of Multiprocessor Operating systems and Multicore Operating systems



# **OS** Design

#### **Distributed Operating System**

- Provides the illusion of
  - a single main memory space
  - single secondary memory space
  - unified access facilities
- State of the art for distributed operating systems lags that of uniprocessor and SMP operating systems

#### **Object-Oriented Design**

- Used for adding modular extensions to a small kernel
- Enables programmers to customize an operating system without disrupting system integrity
- Eases the development of distributed tools and full-blown distributed operating systems



# Symmetric Multiprocessor OS Considerations

• A multiprocessor OS must provide all the functionality of a multiprogramming system plus additional features to accommodate multiple processors

#### Key design issues:

# Simultaneous concurrent processes or threads

kernel routines
need to be
reentrant to
allow several
processors to
execute the
same kernel
code
simultaneously

#### **Scheduling**

any processor may perform scheduling, which complicates the task of enforcing a scheduling policy

#### **Synchronization**

with multiple
active processes
having potential
access to shared
address spaces or
shared I/O
resources, care
must be taken to
provide effective
synchronization

# **Memory** management

the reuse of physical pages is the biggest problem of concern

# Reliability and fault tolerance

the OS should provide graceful degradation in the face of processor failure



## **Multicore OS Considerations**

- The design challenge for a many-core multicore system is to efficiently harness the multicore processing power and intelligently manage the substantial on-chip resources efficiently
- Potential for parallelism exists at three levels:

hardware parallelism within each core processor, known as instruction level parallelism

potential for multiprogramming and multithreaded execution within each processor

potential for a single application to execute in concurrent processes or threads across multiple cores



#### **Session-6**

- Process Concept Processes, PCB
- Understanding the Process concept and Maintenance of PCB by OS



# **Process Concept**

- ☐ An operating system executes a variety of programs:
  - ∘Batch system **jobs**
  - •Time-shared systems user programs or tasks
- ☐ Textbook uses the terms *job* and *process* almost interchangeably
- □ Process a program in execution; process execution must progress in sequential fashion
- ☐ Multiple parts
  - •The program code, also called text section
  - °Current activity including program counter, processor registers
  - •Stack containing temporary data
    - •Function parameters, return addresses, local variables
  - Data section containing global variables
  - Heap containing memory dynamically allocated during run time




# **Process Concept**

- Program is *passive* entity stored on disk (executable file), process is *active* 
  - Program becomes process when executable file loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc
- One program can be several processes
  - Consider multiple users executing the same program




# **Process in Memory**





# **Diagram of Process State**





# **Process Control Block (PCB)**

Information associated with each process (also called task control block) ☐ Process state – running, waiting, etc Program counter – location of instruction to next execute ☐ CPU registers – contents of all process-centric registers ☐ CPU scheduling information- priorities, scheduling queue pointers ☐ Memory-management information memory allocated to the process  $\square$  Accounting information – CPU used, clock time elapsed since start, time limits


 $\Box$  I/O status information – I/O devices

allocated to process, list of open files

process state process number program counter registers memory limits list of open files



#### **CPU Switch From Process to Process**






# **Process Representation in Linux**

Represented by the C structure task struct

```
pid t_pid; /* process identifier */
long state; /* state of the process */
unsigned int time_slice /* scheduling information */
struct task_struct *parent; /* this process's parent */
struct list_head children; /* this process's children */
struct files_struct *files; /* list of open files */
struct mm_struct *mm; /* address space of this process */
```





#### **Session-7**

- Threads Overview and its Benefits
- Understanding the importance of threads



#### **Threads**

- Processes have two characteristics:
  - Resource ownership process includes a virtual address space to hold the process image
  - Scheduling/execution follows an execution path that may be interleaved with other processes
- These two characteristics are treated independently by the operating system
- The unit of dispatching is referred to as a *thread* or lightweight process
- The unit of resource ownership is referred to as a process or *task*



# **Multithreading – Types of Threading**

The ability of an OS to support multiple, concurrent paths of execution within a single process.




Figure 4.1 Threads and Processes [ANDE97]




# **Single Thread Approaches**

- MS-DOS supports a single user process and a single thread.
- Some UNIX, support multiple user processes but only support one thread per process



# Threads vs. processes






Figure 4.2 Single Threaded and Multithreaded Process Models



# **Importance of Threads**

- Takes less time to create a new thread than a process
- Less time to terminate a thread than a process
- Switching between two threads takes less time that switching processes
- Threads can communicate with each other without invoking the kernel



#### One or More Threads in Process

- Each thread has
  - An execution state (running, ready, etc.)
  - Saved thread context when not running
  - An execution stack
  - Some per-thread static storage for local variables
  - Access to the memory and resources of its process (all threads of a process share this)



#### **Session-8**

- Process Scheduling Scheduling Queues, Schedulers, Context switch
- Understanding basics of Process Scheduling




# **Process Scheduling**

- ☐ Maximize CPU use, quickly switch processes onto CPU for time sharing
- ☐ Process scheduler selects among available processes for next execution on CPU
- ☐ Maintains scheduling queues of processes
  - •Job queue set of all processes in the system
  - •Ready queue set of all processes residing in main memory, ready and waiting to execute
  - Device queues set of processes waiting for an I/O device
  - •Processes migrate among the various queues




#### Ready Queue And Various I/O Device Queues





## Representation of Process Scheduling

• Queueing diagram represents queues, resources, flows





#### **Schedulers**

**Short-term scheduler** (or **CPU scheduler**) – selects which process should be executed next and allocates CPU

Sometimes the only scheduler in a system

Short-term scheduler is invoked frequently (milliseconds) ⇒ (must be fast)

**Long-term scheduler** (or **job scheduler**) – selects which processes should be brought into the ready queue

Long-term scheduler is invoked infrequently (seconds, minutes) ⇒ (may be slow)

The long-term scheduler controls the **degree of multiprogramming** Processes can be described as either:

I/O-bound process – spends more time doing I/O than computations, many short CPU bursts


**CPU-bound process** – spends more time doing computations; few very long CPU bursts

Long-term scheduler strives for good *process mix* 



# **Addition of Medium Term Scheduling**

- Medium-term scheduler can be added if degree of multiple programming needs to decrease
  - Remove process from memory, store on disk, bring back in from disk to continue execution: swapping





#### **Context Switch**

☐ When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch ☐ Context of a process represented in the PCB ☐ Context-switch time is overhead; the system does no useful work while switching  $\circ$ The more complex the OS and the PCB  $\square$  the longer the context switch ☐ Time dependent on hardware support ∘Some hardware provides multiple sets of registers per CPU □ multiple contexts loaded at once



#### **Session-11**

- Operations on Process Process creation, Process termination
- Understanding the system calls fork(), wait(), exit()



# **Operations on Processes**

- Process creation,
- Process termination,
- Process execution




#### **Process Creation**

- ☐ Parent process create children processes, which, in turn create other processes, forming a tree of processes
- ☐ Generally, process identified and managed via a **process identifier** (**pid**)
- ☐ Resource sharing options
  - Parent and children share all resources
  - •Children share subset of parent's resources
  - Parent and child share no resources
- ☐ Execution options
  - •Parent and children execute concurrently
  - Parent waits until children terminate



# **A Tree of Processes in Linux**





# **Process Creation (Cont.)**

#### Address space


Child duplicate of parent

Child has a program loaded into it

#### UNIX examples

fork() system call creates new process

exec() system call used after a fork() to replace the process' memory space with a new program





# C Program Forking Separate Process

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid_t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
   else if (pid == 0) { /* child process */
      execlp("/bin/ls", "ls", NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait (NULL);
      printf("Child Complete");
   return 0;
```



### Creating a Separate Process via Windows API

```
#include <stdio.h>
#include <windows.h>
int main(VOID)
STARTUPINFO si;
PROCESS_INFORMATION pi;
   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));
   /* create child process */
   if (!CreateProcess(NULL, /* use command line */
     "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
     NULL, /* don't inherit thread handle */
     FALSE. /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
     &si.
     &pi))
      fprintf(stderr, "Create Process Failed");
      return -1;
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");
   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
```



#### **Process Termination**

- Process executes last statement and then asks the operating system to delete it using the exit() system call.
  - •Returns status data from child to parent (via wait())
  - •Process' resources are deallocated by operating system
- ☐ Parent may terminate the execution of children processes using the abort() system call. Some reasons for doing so:
  - •Child has exceeded allocated resources
  - •Task assigned to child is no longer required
  - •The parent is exiting and the operating systems does not allow a child to continue if its parent terminates



#### **Process Termination**

Some operating systems do not allow child to exists if its parent has terminated. If a process terminates, then all its children must also be terminated. •cascading termination. All children, grandchildren, etc. are terminated •The termination is initiated by the operating system. ☐ The parent process may wait for termination of a child process by using the wait () system call. The call returns status information and the pid of the terminated process pid = wait(&status); ☐ If no parent waiting (did not invoke wait()) process is a zombie ☐ If parent terminated without invoking wait, process is an orphan



## **Multiprocess Architecture – Chrome Browser**

- ☐ Many web browsers ran as single process (some still do)
  - oIf one web site causes trouble, entire browser can hang or crash
- ☐ Google Chrome Browser is multiprocess with 3 different types of processes:
  - •Browser process manages user interface, disk and network I/O
  - •Renderer process renders web pages, deals with HTML, Javascript. A new renderer created for each website opened
    - •Runs in sandbox restricting disk and network I/O, minimizing effect of security exploits
  - •Plug-in process for each type of plug-in





## **Session-12**

- Inter Process communication : Shared Memory, Message Passing ,Pipe()
- Understanding the need for IPC



•Message passing


# **Interprocess Communication**

☐ Processes within a system may be *independent* or *cooperating* ☐ Cooperating process can affect or be affected by other processes, including sharing data ☐ Reasons for cooperating processes: Information sharing Computation speedup Modularity Convenience ☐ Cooperating processes need interprocess communication (IPC) ☐ Two models of IPC •Shared memory



## **Communications Models**

(a) Message passing. (b) shared memory.





# **Cooperating Processes**

- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by the execution of another process
- ☐ Advantages of process cooperation
  - oInformation sharing
  - °Computation speed-up
  - Modularity
  - °Convenience



## **Producer-Consumer Problem**

Paradigm for cooperating processes, *producer* process produces information that is consumed by a *consumer* process unbounded-buffer places no practical limit on the size of the buffer

**bounded-buffer** assumes that there is a fixed buffer size



## **Bounded-Buffer – Shared-Memory Solution**

Shared data

```
#define BUFFER_SIZE 10
typedef struct {
    . . .
} item;

item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```

Solution is correct, but can only use BUFFER\_SIZE-1 elements



## **Bounded-Buffer – Producer**

```
item next_produced;
while (true) {
    /* produce an item in next produced */
    while (((in + 1) % BUFFER_SIZE) == out)
        ; /* do nothing */
    buffer[in] = next_produced;
    in = (in + 1) % BUFFER_SIZE;
}
```



## **Bounded Buffer – Consumer**

```
item next_consumed;
while (true) {
    while (in == out)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;

    /* consume the item in next consumed */
}
```



# **Interprocess Communication – Shared Memory**

	An area of memory shared among the processes that wish to
	communicate
	The communication is under the control of the users processes not
	the operating system.
	Major issues is to provide mechanism that will allow the user
	processes to synchronize their actions when they access shared
	memory.
П	Synchronization is discussed in great details in Chapter 5



## **Interprocess Communication – Message Passing**

- Mechanism for processes to communicate and to synchronize their actions
   Message system processes communicate with each other
- without resorting to shared variables
- ☐ IPC facility provides two operations:
  - osend(message)
  - oreceive(message)
- ☐ The *message* size is either fixed or variable



## **Message Passing (Cont.)**

- $\square$  If processes P and Q wish to communicate, they need to:
  - •Establish a *communication link* between them
  - •Exchange messages via send/receive
- ☐ Implementation issues:
  - •How are links established?
  - •Can a link be associated with more than two processes?
  - •How many links can there be between every pair of communicating processes?
  - •What is the capacity of a link?
  - •Is the size of a message that the link can accommodate fixed or variable?
  - •Is a link unidirectional or bi-directional?



## **Message Passing (Cont.)**

#### Implementation of communication link

Physical:

Shared memory

Hardware bus

Network

Logical:

Direct or indirect

Synchronous or asynchronous

Automatic or explicit buffering



# **Examples of IPC Systems - POSIX**

- POSIX Shared Memory
  - •Process first creates shared memory segment
    shm\_fd = shm\_open(name, O CREAT | O RDWR, 0666);
  - Also used to open an existing segment to share it
  - •Set the size of the object

```
ftruncate(shm fd, 4096);
```

• Now the process could write to the shared memory

```
sprintf(shared memory, "Writing to shared
memory");
```



## **IPC POSIX Producer**

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";
/* shared memory file descriptor */
int shm fd:
/* pointer to shared memory obect */
void *ptr;
   /* create the shared memory object */
   shm_fd = shm_open(name, O_CREAT | O_RDWR, 0666);
   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);
   /* write to the shared memory object */
   sprintf(ptr, "%s", message_0);
   ptr += strlen(message_0);
   sprintf(ptr, "%s", message_1);
   ptr += strlen(message_1);
   return 0:
```



## **IPC POSIX Consumer**

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm fd:
/* pointer to shared memory obect */
void *ptr;
   /* open the shared memory object */
   shm_fd = shm_open(name, O_RDONLY, 0666);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);
   /* read from the shared memory object */
   printf("%s",(char *)ptr);
   /* remove the shared memory object */
   shm_unlink(name);
   return 0;
}
```

# Examples of IPC Systems - Mach

- ☐ Mach communication is message based
  - •Even system calls are messages
  - •Each task gets two mailboxes at creation- Kernel and Notify
  - Only three system calls needed for message transfer

```
msg_send(), msg_receive(), msg_rpc()
```


•Mailboxes needed for commuication, created via

```
port_allocate()
```

- •Send and receive are flexible, for example four options if mailbox full:
  - Wait indefinitely
  - Wait at most n milliseconds
  - •Return immediately
  - •Temporarily cache a message



## **Local Procedure Calls in Windows**






# **Pipes**

Acts as a conduit allowing two processes to communicate
Issues:
°Is communication unidirectional or bidirectional?
oIn the case of two-way communication, is it half or full-duplex?
•Must there exist a relationship (i.e., <i>parent-child</i> ) between the communicating processes?
°Can the pipes be used over a network?
Ordinary pipes – cannot be accessed from outside the
process that created it. Typically, a parent process creates
a pipe and uses it to communicate with a child process that
it created.
Named pipes – can be accessed without a parent-child
relationship.



# **Ordinary Pipes**

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the **read-end** of the pipe)
- Ordinary pipes are therefore unidirectional
- Require parent-child relationship between communicating processes



• See Unix and Windows code samples in textbook



# **Named Pipes**

Named Pipes are more powerful than ordinary pipes
Communication is bidirectional
No parent-child relationship is necessary between the
communicating processes
Several processes can use the named pipe for
communication
Provided on both UNIX and Windows systems



### **Session-13**

- Process synchronization: Background, Critical section Problem
- Understanding the race conditions and the need for the Process synchronization



# **Process Synchronization**

• **Process Synchronization** means sharing system resources by **processes** in a such a way that, Concurrent access to shared data is handled thereby minimizing the chance of inconsistent data. Maintaining data consistency demands mechanisms to ensure **synchronized** execution of cooperating **processes**.

#### In other ways,

- Processes can execute concurrently
  - May be interrupted at any time, partially completing execution
- Concurrent access to shared data may result in data inconsistency
- Maintaining data consistency requires mechanisms to ensure the orderly execution of cooperating processes
- Illustration of the problem:

Suppose that we wanted to provide a solution to the consumer-producer problem that fills **all** the buffers. We can do so by having an integer **counter** that keeps track of the number of full buffers. Initially, **counter** is set to 0. It is incremented by the producer after it produces a new buffer and is decremented by the consumer after it consumes a buffer.



## **Producer**

```
while (true) {
    /* produce an item in
next produced */

    while (counter ==
BUFFER_SIZE);
    /* do nothing */
    buffer[in] =
next_produced;
    in = (in + 1) %
BUFFER_SIZE;
    counter++;
}
```

## Consumer

```
while (true) {
    while (counter == 0)
        ; /* do nothing */
    next_consumed =
buffer[out];
    out = (out + 1) %
BUFFER_SIZE;
        counter--;
    /* consume the item in
next consumed */
}
```



## **Race Condition**

- Occurs when multiple processes or threads read and write shared data items
- The final result depends on the order of execution
  - the "loser" of the race is the process that updates last and will determine the final value of the variable



# **Race Condition**

- Assume P1 and P2 are executing this code and share the variable a
- Processes can be preempted at any time.
- Assume P1 is preempted after the input statement, and P2 then executes entirely
- The character echoed by P1 will be the one read by P2 !!
  - This is an example of a *race condition*
- Individual processes (threads) execute sequentially in isolation, but concurrency causes them to interact.
- We need to prevent concurrent execution by processes when they are changing the same data. We need to enforce *mutual exclusion*.

```
static char a;
```

```
void echo()
{
   cin >> a;
   cout << a;</pre>
```



# **Critical Section Problem**

- When a process executes code that manipulates shared data (or resources), we say that the process is in its critical section (CS) for that shared data
- We must enforce mutual exclusion on the execution of critical sections.
- Only one process at a time can be in its CS (for that shared data or resource).

Each process must ask permission to enter critical section in **entry section**, may follow critical section with **exit section**, then **remainder section** 



# **Critical Section**

```
General structure of process P_i
do {

    entry section

    critical section

    exit section

    remainder section
} while (true);
```



## **Solution to Critical-Section Problem**

- 1. Mutual Exclusion If process  $P_i$  is executing in its critical section, then no other processes can be executing in their critical sections
- 2. **Progress** If no process is executing in its critical section and there exist some processes that wish to enter their critical section, then the selection of the processes that will enter the critical section next cannot be postponed indefinitely
- 3. **Bounded Waiting** A bound must exist on the number of times that other processes are allowed to enter their critical sections after a process has made a request to enter its critical section and before that request is granted
  - Assume that each process executes at a nonzero speed
  - lacktriangle No assumption concerning **relative speed** of the n processes



# **Critical-Section Handling in OS**

Two approaches depending on if kernel is preemptive or non- preemptive

Preemptive – allows preemption of process when running in kernel mode

Non-preemptive – runs until exits kernel mode, blocks, or voluntarily yields CPU

Essentially free of race conditions in kernel mode



# Reference

S

- 1. Abraham Silberschatz, Peter Baer Galvin, Greg Gagne, Operating systems, 9th ed., John Wiley & Sons, 2013
- 2. William Stallings, Operating Systems-Internals and Design Principles, 7th ed., Prentice Hall, 2012



# Thank You!!!