- APPENDIX D - ERROR CODES

GEMDOS/BIOS Errors

Upon return from most **GEMDOS** and **BIOS** functions, register D0 contains a longword error code describing the failure or success of an operation. The **BIOS** uses error codes -1 to -31 while **GEMDOS** uses error codes -32 and lower. A return value of 0 always indicates success. The error codes and their meanings are as follows:

Name	BIOS#	Meaning
E_OK	0	No error
ERROR	-1	Generic error
EDRVNR	-2	Drive not ready
EUNCMD	-3	Unknown command
E_CRC	-4	CRC error
EBADRQ	-5	Bad request
E_SEEK	-6	Seek error
EMEDIA	-7	Unknown media
ESECNF	-8	Sector not found
EPAPER	-9	Out of paper
EWRITF	-10	Write fault
EREADF	-11	Read fault
EWRPRO	-12	Device is write protected
E_CHNG	-14	Media change detected
EUNDEV	-15	Unknown device
EBADSF	-16	Bad sectors on format
EOTHER	-17	Insert other disk (request)

	GEMDOS	
Name	#	Meaning
EINVFN	-32	Invalid function
EFILNF	-33	File not found
EPTHNF	-34	Path not found
ENHNDL	-35	No more handles
EACCDN	-36	Access denied
EIHNDL	-37	Invalid handle
ENSMEM	-39	Insufficient memory
EIMBA	-40	Invalid memory block address
EDRIVE	-46	Invalid drive specification
ENSAME	-48	Cross device rename
ENMFIL	-49	No more files
ELOCKED	-58	Record is already locked
ENSLOCK	-59	Invalid lock removal request
ERANGE or	-64	Range error
ENAMETOOLONG		
EINTRN	-65	Internal error
EPLFMT	-66	Invalid program load format
EGSBF	-67	Memory block growth failure
ELOOP	-80	Too many symbolic links
EMOUNT	-200	Mount point crossed (indicator)