운영체제

Reader & Writer Problem

학번 : 20143104

이름 : 조승현

```
void reset(char *fileVar) {
// fileVar라는 이름의 파일이 없을 때만
// fileVar라는 이름의 텍스트 화일을 새로 만들고 O값을 기록한다.
  FILE *f = fopen(fileVar, "r");
  if(f==NULL)
     f = fopen(fileVar , "w");
     fprintf(f, "%d\n", 0);
  }
 fclose(f);
void Store(char *fileVar,int i) {
// fileVar 화일 끝에 i 값을 append한다.
 FILE *f = fopen(fileVar, "a+");
    while(!feof(f));
 fprintf(f, "%d\n", 0);
 fclose(f);
int Load(char *fileVar) {
// fileVar 화일의 마지막 값을 읽어 온다.
  int data;
  FILE *f = fopen(fileVar, "r");
  while(!feof(f))
   fscanf(f, "%d", &data);
 fclose(f);
  return data;
void add(char *fileVar,int i) {
// fileVar 화일의 마지막 값을 읽어서 i를 더한 후에 이를 끝에 append 한다.
 int data;
  pid_t pid = getpid();
  FILE *f = fopen(fileVar, "a+");
  while(!feof(f))
   fscanf(f, "%d", &data);
  fprintf(f, "%d\n", (i+data));
 fclose(f);
void sub(char *fileVar,int i) {
// fileVar 화일의 마지막 값을 읽어서 i를 뺀 후에 이를 끝에 append 한다.
  pid_t pid = getpid();
  int data;
 FILE *f = fopen(fileVar, "a+");
  while(!feof(f))
   fscanf(f, "%d", &data);
  fprintf(f, "%d\n", (data-i));
 fclose(f);
```

```
// Class CondVar
typedef struct _cond {
  int semid;
  char *queueLength;
} CondVar;
void initCondVar(CondVar *c, key_t semkey, char *queueLength) {
  c->queueLength = queueLength;
  reset(c->queueLength); // queueLength=0
  if ((c->semid = initsem(semkey,0)) < 0)
  // 세마포를 연결한다.(없으면 초기값을 0로 주면서 새로 만들어서 연결한다.)
     exit(1);
}
void Wait(CondVar *c, Lock *lock) {
//P연산을 통해 CondVar의 wait 큐에 추가한다.
 add(c->queueLength, 1);
 Release(lock);
 p(c->semid);
 Acquire(lock);
}
void Signal(CondVar *c) {
//V연산을 통해 CondVar의 큐에 하나만을 깨운다.
 if(Load(c->queueLength) >0){
   v(c->semid);
   sub(c->queueLength, 1);
 }
}
void Broadcast(CondVar *c) {
//V연산을 통해 CondVar의 큐에 모든 것을 깨운다.
 while(Load(c->queueLength) > 0){
   v(c->semid);
   sub(c->queueLength,1);
 }
}
```

<reader.c>

```
void main(int argc, char *argv[]){
  struct timeval bgn.end; //시간을 기록하기 위한 변수
  gettimeofday(&bgn, NULL); //프로그램 시작 시간 기록
  int diff;
  key_t semkey = 0x200; //semaphore ID(lock)
  key_t semkey2 = 0x100; //semaphore ID(oktoread)
  key_t semkey3 = 0x300; //semaphore ID(oktowrite)
  pid_t pid;
  Lock lock;
  CondVar okToRead;
  CondVar okToWrite;
  pid = getpid();
  initLock(&lock, semkey);
  initCondVar(&okToRead, semkey2, "oktoread"); // CondVar 초기화
  initCondVar(&okToWrite, semkey3, "oktowrite");
  reset("AR");
  reset("AW");
  reset("WR");
  reset("WW");
  sleep(atoi(argv[1])); // 지역시간
  Acquire(&lock);
  while((Load("AW") + Load("WW")) > 0){ //실행중이거나 기다리는 writer 가 있으면
    gettimeofday(&end, NULL);
    diff = end.tv_sec - bgn.tv_sec;
    printf("process %d in reader waiting %ds\n", pid, diff); // waiting 시간 측정
    add("WR", 1); // reader waiting
    Wait(&okToRead, &lock); // reader waiting
    gettimeofday(&end, NULL);
    diff = end.tv_sec - bgn.tv_sec;
    printf("process %d in reader wake up %ds\n", pid, diff); // wake up 시간측정
    sub("WR",1); // reader wake up
  gettimeofday(&end, NULL);
  diff = end.tv_sec - bgn.tv_sec;
  printf("process %d in reader %ds\n", pid, diff); // 실행되는 reader 시간 측정
  add("AR",1);
              // reader active
  Release(&lock);
  sleep(atoi(argv[2])); // 실행
  Acquire(&lock);
  gettimeofday(&end, NULL);
  diff = end.tv_sec - bgn.tv_sec;
  printf("process %d in reader exiting %ds\n", pid, diff); //Active 한 reader 가끝는 시간측정
  sub("AR", 1); // reader closed
  if(Load("AR")==0 && Load("WW") > 0){ // 마지막 reader 의 경우 waiting writer가 있으면 writer wake up
    Signal(&okToWrite);
  Release(&lock);
  exit(0);
}
```

<writer.c>

```
void main(int argc, char *argv[]){
  struct timeval bgn,end; //시간을 기록하기 위한 변수
  gettimeofday(&bgn, NULL); //프로그램 시작 시간 기록
  int diff;
  key_t semkey = 0x200; //semaphore ID(lock)
  key_t semkey2 = 0x100; //semaphore ID(oktoread)
  key_t semkey3 = 0x300; //semaphore ID(oktowrite)
  int semid;
  pid t pid;
 Lock lock;
  CondVar okToRead;
  CondVar okToWrite;
  pid = getpid();
  initLock(&lock, semkey);
 initCondVar(&okToRead, semkey2, "oktoread"); //CondVar 초기화
  initCondVar(&okToWrite, semkey3, "oktowrite");
  reset("AR");
  reset("AW");
  reset("WR");
  reset("WW");
  sleep(atoi(argv[1])); // 지연시간
  Acquire(&lock);
  while((Load("AW")) + Load("AR")) > 0){ //기다리는 writer 거나 실행중인 reader가 있으면
   gettimeofday(&end, NULL);
   diff = end.tv_sec - bgn.tv_sec;
   printf("process %d in writer waiting %ds\n", pid, diff); //waiting 시간 측정
   add("WW", 1); //reader waiting
   Wait(&okToWrite, &lock); //reader waiting
   gettimeofday(&end, NULL);
   diff = end.tv_sec - bgn.tv_sec;
   printf("process %d in writer wake up %ds\n", pid, diff); //wake up 시간 측정
   sub("WW",1); //writer wake up
  gettimeofday(&end, NULL);
  diff = end.tv_sec - bgn.tv_sec;
  printf("process %d in writer %ds\n", pid, diff); //실행되는 writer 시간 측정
  add("AW", 1); //writer active
  Release(&lock);
  sleep(atoi(argv[2])); //실행
  Acquire(&lock);
  gettimeofday(&end, NULL);
  diff = end.tv_sec - bgn.tv_sec;
  printf("process %d in writer exiting %ds\n", pid, diff)://Active한 writer 끝나는 시간측정
  sub("AW", 1); //writer closed
  if(Load("WW") > 0){ //기다리는 writer가 있으면 wake up
   Signal(&okToWrite);
 else if(Load("WR") > 0){ //기다리는 writer가 없고 기다리는 reader가 있으면 reader 전부 깨우기
   Broadcast(&okToRead);
  Release(&lock);
  exit(0);
```

	1초	2초	3초	4초	5초	6초	7초	10초	13초	16초	18초
시작	R1	R2	W1	R3	R4	W2					
AR	R1(1)	R2(2)				R1(1)	R2(0)		R3(1)	R4(1)	R3(0)
AII	K1(1)	NZ(Z)				K1(1)			R4(2)		
WR				R3(1)	R4(2)						
AW						XA71/1	TA71(1)	W1(1) W1(0)	W2(0)		
							W1(1)	W2(1)	VV Z(O)		
WW			W1(1)			W2(2)	W1(1)	W2(0)			

<실제로 실행되는 과정을 나타낸 표>

<분석>

1초 - AR=0 WR=0 AW=0 WW=0 (Reader1 실행 전) AR=1 WR=0 AW=0 WW=0 (Reader1 실행 후)

```
while((Load("AW") + Load("WW")) > 0){
  add("WR", 1);
  Wait(&okToRead, &lock);
  sub("WR",1);
}

gettimeofday(&end, NULL);
diff = end.tv_sec - bgn.tv_sec;
printf("process %d in reader %ds\n", pid, diff);
add("AR",1);
```

2초 - AR=1 WR=0 AW=0 WW=0 (Reader2 실행 전) AR=2 WR=0 AW=0 WW=0 (Reader2 실행 후)

```
while((Load("AW") + Load("WW")) > 0){
  add("WR", 1);
  Wait(&okToRead, &lock);
  sub("WR",1);
}

gettimeofday(&end, NULL);
diff = end.tv_sec - bgn.tv_sec;
printf("process %d in reader %ds\n", pid, diff);
add("AR",1);
```

3초 - AR=2 WR=0 AW=0 WW=0 (Writer1 실행 전) AR=2 WR=1 AW=0 WW=1 (Writer1 실행 후)

```
while((Load("AW") + Load("AR")) > 0){
  add("WW", 1);
  Wait(&okToWrite, &lock);
  sub("WW",1);
}

gettimeofday(&end, NULL);
diff = end.tv_sec - bgn.tv_sec;
printf("process %d in writer %ds\n", pid, diff);
add("AW", 1);
```

Queue			
Reader	Writer		
	W1		

4초 - AR=2 WR=0 AW=0 WW=1 (Reader3 실행 전) AR=2 WR=1 AW=0 WW=1 (Reader3 실행 후)

```
while((Load("AW") + Load("WW")) > 0){
  add("WR", 1);
  Wait(&okToRead, &lock);
  sub("WR",1);
}

gettimeofday(&end, NULL);
diff = end.tv_sec - bgn.tv_sec;
printf("process %d in reader %ds\n", pid, diff);
add("AR",1);
```

Queue			
Reader	Writer		
R3	W1		

5초 - AR=2 WR=1 AW=0 WW=1 (Reader4 실행 전) AR=2 WR=2 AW=0 WW=1 (Reader4 실행 후)



Queue			
Rea	der	Writer	
R	3	W1	
R	4		

6초 - AR=2 WR=2 AW=0 WW=1 (Reader1 종료 전, Writer2 실행 전)
AR=1 WR=2 AW=0 WW=1 (Reader1 종료 후)
AR=1 WR=2 AW=0 WW=2 (Writer2 실행 후)

```
sub("AR", 1);
if(Load("AR")==0 && Load("WW") > 0){
   Signal(&okToWrite);
}
```

```
while((Load("AW") + Load("AR")) > 0){
   add("WW", 1);
   Wait(&okToWrite, &lock);
   sub("WW",1);
}

gettimeofday(&end, NULL);
diff = end.tv_sec - bgn.tv_sec;
printf("process %d in writer %ds\n", pid, diff);
add("AW", 1);
```

Queue			
Reader	Writer		
R3	W1		
R4	W2		

7초 - AR=1 WR=2 AW=0 WW=2 (Reader2 종료 전) AR=0 WR=2 AW=1 WW=1 (Reader2 종료 후) Writer1 wake up

```
sub("AR", 1);
if(Load("AR")==0 && Load("WW") > 0){
    Signal(&okToWrite);
}
```

Queue			
Reader	Writer		
R3	W2		
R4			

10초 - AR=0 WR=2 AW=1 WW=1 (Writer1 종료 전) AR=0 WR=2 AW=1 WW=0 (Writer1 종료 후) Writer2 wake up

```
sub("AW", 1);
if(Load("WW") > 0){
    Signal(&okToWrite);
}
else if(Load("WR") > 0){
    Broadcast(&okToRead);
}
```

Queue			
Reader	Writer		
R3			
R4			

13초 - AR=0 WR=2 AW=1 WW=0 (Writer2 종료 전) AR=2 WR=0 AW=0 WW=0 (Writer2 종료 후) Reader broadcast

```
sub("AW", 1);
if(Load("WW") > 0){
   Signal(&okToWrite);
}
else if(Load("WR") > 0){
   Broadcast(&okToRead);
}
```

Queue				
Reader	Writer			

16초 - AR=1 WR=0 AW=0 WW=0 (Reader4 종료)

```
sub("AR", 1);
if(Load("AR")==0 && Load("WW") > 0){
   Signal(&okToWrite);
}
```

18초 - AR=0 WR=0 AW=0 WW=0 (Reader3 종료)

```
sub("AR", 1);
if(Load("AR")==0 && Load("WW") > 0){
    Signal(&okToWrite);
}
```

<결과 1>

```
csh4096@csh4096-ThinkPad-T440:-/OS/hw2$ process 21826 in reader 1s process 21827 in reader 2s process 21828 in writer waiting 3s process 21829 in reader waiting 4s process 21830 in reader waiting 5s process 21826 in reader exiting 6s process 21826 in writer waiting 6s process 21827 in reader exiting 7s process 21828 in writer wake up 7s process 21828 in writer 7s process 21828 in writer 7s process 21828 in writer exiting 10s process 21831 in writer wake up 10s process 21831 in writer wake up 10s process 21831 in writer i0s process 21831 in writer i0s process 21831 in writer exiting 13s process 21829 in reader wake up 13s process 21829 in reader wake up 13s process 21830 in reader exiting 16s process 21830 in reader exiting 16s process 21829 in reader exiting 18s
```

<결과 2>

