7. CMAQ Programs and Libraries

Overview

The core CMAQ programs that are needed to perform a basic air quality model simulation are MCIP, ICON, BCON, JPROC, and CCTM. The relationships among these programs are depicted within the green box in Figure 7-1 CMAQ Core Programs. The blue boxes represent programs that are not part of the CMAQ distribution package but supply data necessary for an air quality simulation (emissions and meteorology data). The yellow boxes represent the standard CMAQ preprocessors: MCIP, ICON, BCON, and JPROC. The red box represents the CMAQ chemistry-transport model (CCTM), the Eulerian air quality modeling component of CMAQ. Data flows between the CMAQ programs are represented in by arrows. The red arrows illustrate the flow of data from the CMAQ preprocessors and the emissions model to CCTM. The green arrows show the data feedbacks from CCTM to create initial and boundary conditions for nested simulations. The black arrow illustrates the connection between the meteorological model and MCIP. Finally, the blue arrow shows that the output from MCIP can be used to drive an emissions model.

A meteorological model, such as WRF-ARW, generates gridded meteorology for input to both CMAQ and the emissions model. These data are processed for input to CMAQ using MCIP.

An emissions model converts emissions inventories to gridded, hourly emissions formatted for CMAQ. The SMOKE emissions model is currently available for preparing emissions data for CMAQ.

CMAQ includes several "in-line" options to support coupling between meteorology and chemistry processes, and to facilitate operational air quality forecast modeling (see Chapter 4). The user can incorporate photolysis rate calculations and emissions processing during a CCTM simulation. There are several advantages of incorporating these processes directly in a CCTM simulation:

- 1. Photolysis rate calculations use the aerosol concentrations and meteorology from the CCTM simulation, simulating the feedbacks of the input emissions and resulting air quality on photochemistry
- 2. Emissions are meteorologically modulated at the synchronization (chemistry) time step rather than being linearly time-interpolated within each simulation hour
- 3. Disk space may be saved, because a 3-D emissions file is no longer needed for elevated point sources

4. CMAQ can more easily be coupled with a meteorological model, enabling direct emissions modulation by the underlying, freshly computed meteorological variables




Figure 7-1.CMAQ core programs

MCIP is the first program in the CMAQ distribution package that a user should run when setting up a new simulation. MCIP is used to preprocess the data from a meteorological model for CMAQ and SMOKE.

ICON creates a binary netCDF initial conditions file for input to CCTM. Users have the option to create initial conditions data either from a text file of vertical concentration profiles or from an existing CCTM output file. ICON outputs initial conditions data that are configured for a specific modeling grid and chemical parameterization.

BCON creates a binary netCDF lateral boundary conditions file for input to CCTM. Users have the option to create boundary conditions from either a text

file of vertical concentration profiles or from an existing CCTM or larger-scale (e.g., global-scale) output file. BCON outputs boundary conditions data that are configured for a specific modeling grid and chemical parameterization. If derived from an existing CCTM or larger-scale output file, BCON produces dynamic boundary conditions that vary in time and space. When derived from vertical concentration profiles, BCON produces static boundary conditions for input to CCTM.

JPROC converts physical information about photoreactive molecules into clear-sky photolysis rate look-up tables for input to CCTM. The in-line photolysis approach allows photolysis rates to be adjusted by simulated gas and aerosol concentrations rather than by climatological values in the off-line approach. JPROC is not required when the in-line photolysis approach is selected.

CCTM is run last in the sequence of programs. All of the other CMAQ programs, and the emissions and meteorological models, are used to prepare the inputs to CCTM. By using data that are synchronized for a particular modeling time period, model grid, vertical layer configuration, and chemical parameterization, CCTM can produce estimates of pollutant concentrations, wet and dry deposition rates, and visibility metrics.

In addition to the core programs shown in Figure 7-1 CMAQ Core Programs, the CMAQ distribution package also includes utilities (\$CMAQ_HOME/UTIL) and post-processors (\$CMAQ_HOME/POST) for utilizing additional technical and diagnostic features in CMAQ. The CMAQ utility programs CHEMMECH CSV2NML, CREATE_EBI, and INLINE_PHOT_PREPROC are used to modify or prepare new chemical mechanisms for CMAQ. The CMAQ preprocessor CALMAP creates maps of the crop calendar for use in estimating windblown dust emissions. The CMAQ post-processors are described in the CMAQv5.1 documentation and are used to prepare CMAQ output data for analysis.

This chapter provides detailed descriptions of the CMAQ programs and utilities. Information about the third-party libraries used by CMAQ—such as I/O API, netCDF, and MPI are available in Chapter 6. When viewing the tables that list each program's input and output files, recall that the various I/O API file formats shown are also described in Chapter 6.

BCON

Description

The program BCON prepares lateral chemical boundary conditions (BCs) for CCTM from either ASCII vertical profiles or from an existing CCTM output concentration (CONC) file. The BCs created by BCON can be static in both time and space (i.e., time-invariant with uniform concentrations in all boundary grid cells), dynamic in both time and space, or a combination of the two. The

ASCII vertical profiles are primarily used to create static BCs. Dynamic BCs can be extracted from CONC files on either the same horizontal grid spacing (i.e., as a windowed modeling domain) or for a finer-resolution model grid (i.e., for a nested simulation), or they can be interpolated from a larger-scale CTM simulation (which is analogous to defining lateral BCs for WRF-ARW).

There are two distinct modes of operation for BCON, and the mode used depends on the nature of the input data. When creating BCON executables, the user must specify whether the input data will be ASCII vertical profiles or a CONC file by selecting either "profile" or "m3conc", respectively, for the setting of the *ModType* variable. This variable determines the input module to use when creating a BCON executable.

CCTM can also be forced with chemical boundary conditions downscaled from global chemistry models (GCMs), such as GEOS-Chem and MOZART. BCON does not support the processing of data from GCMs. BCs derived from GCMs must be calculated with custom codes or scripts that are not available in the CMAQ distribution package. The CAMx developers (Ramboll Environ) have codes available for extracting regional model BCs from both GEOS-Chem and MOZART. Visit the Support Software section of www.CAMx.com to download these utilities.

Files, configuration, and environment variables

Figure 7-2 shows the input and output files and configuration options for BCON. A distinction is made between the options that are invoked at compilation versus those invoked at execution of the program. When compiling BCON, the user specifies a chemical mechanism to configure the gas-phase chemistry and aerosol mechanism used to create the chemical BCs. Setting the *ModMech* and *Mechanism* variables in the BCON compile script configures the program to use a specific set of mechanism INCLUDE files to build an executable. Setting the *ModType* variable in the BCON compile script configures the program to input either a text file of static concentrations or a binary netCDF file of time-dependent concentrations for estimating BCs for CCTM. Separate BCON executables must be prepared for different mechanism and input file configurations.




Figure 7-2. BCON input and output files

When BCON is run, it converts a data file of chemical ambient concentrations to BCs on a predefined model grid. Through the specification of the *ModInpt* variable in the BCON run script, BCON will input either an ASCII vertical profile file (BC_PROFILE) or an existing CCTM concentration file (CTM_CONC_1); the choice depends on how the user compiled the model. The BC input file provided by the user must have chemical speciation that is consistent with the mechanism configuration of the BCON executable. For example, if BCON was compiled to create BCs using the CB05 mechanism, the input BC profile data must be in terms of the CB05 mechanism. CMAQ is distributed with ASCII vertical profiles representing clean continental BCs for North America for the following chemical mechanisms: cb05e51_ae6_aq, saprc07tb_ae6_aq and racm2_aq6_aq. It is the user's responsibility to generate BC inputs for other mechanism configurations.

The horizontal grid and vertical layer structures for BCON are defined at execution through the input of a grid description (GRIDDESC) file and a meteorology cross-point 3-D (MET_CRO_3D) file, respectively. BCON interpolates between the input vertical layer structure and output layer structure if they are different.

BCON input files

Table 7-1. BCON input files

${\bf Name Formal Description}$

BC_PROFSICIEI Vertical ${\it chem-}$ icalprofiles ${\rm from}$ which toderiveboundary conditions; this file iscreated by the user; ${\it used}$ only when the BCenvironment variable is set

to "profile"

NameFormaDescription

$\mathtt{CTM_COORDDED3} \mathrm{MAQ}$

con-

cen-

tra-

tion

file

from

which

to

de-

rive

bound-

ary

con-

di-

tions;

this

file

is

out-

put

 ${\rm from}$

CCTM;

used

only

when

the

BC

envi-

ron-

ment

vari-

able

is

set to

"m3conc"

NameFormaDescription

```
MET_CRORIBBEIOSESme
               and
               lo-
               ca-
               tion
               of
               the
               coarse-
               \operatorname{grid}
               MET_CRO_3D
               file
               that
               is
               re-
               quired
               for
               cre-
               at-
               ing
               the
               ver-
               ti-
               \operatorname{cal}
               grid
               struc-
               {\rm ture}
               if
               this
               struc-
               ture
               changes
               be-
               tween
               nested
               sim-
               ula-
               tions;
               this
               file
               is
               out-
               put
               by
```

MCIP

NameFormaDescription

MET_CRORDEDEDESAme and location of the fine- grid MET_CRO_3D file that is required if the verti- cal grid struc- ${\rm ture}$ changes between nested simulations; this ${\rm file}$ isoutput

by MCIP

NameFormaDescription

GRIDDEASSCII Horizontal

grid

de-

scrip-

tion

file

 $\quad \text{for} \quad$

defin-

ing

the

model

grid;

this

file

is

out-

put

by

MCIP

or

can

be

cre-

 ${\rm ated}$

by

the user

NameFormaDescription

LAYER_CARRIDDEED33-D

cross-

point

me-

teo-

rol-

ogy

METCRO3D

file

 $\quad \text{for} \quad$

defin-

ing

the

ver-

ti-

 cal

layer

struc-

 ${\rm ture}$

of

the

model

grid;

this

file

is

out-

put by

MCIP

File NameFormaDescription

```
{\tt gc\_matASGLInfNl}{\rm amelist}
               file
               for
               defin-
               ing
               the
               gas-
               phase
               species
               that
               are
               in-
               put
               to
               the
               model
               through
               the
               boundary\\
\verb"ae_matASGCLIniN] \\ amelist
               file
               for
               {\rm defin}\text{-}
               ing
               the
               aerosol
               species
               that
               are
               in-
               put
               to
               the
               model
               through
               the
               boundary\\
```

```
NameFormaDescription
{\tt nr\_matASICXLIniNl} {\tt lamelist}
              file
              for
              defin-
              ing
              the
              non-
              reactive
              species
              that
              are
              in-
              put
              to
              the
              model
              through
              the
              boundary
{\tt tr\_matASGLIniNl} amelist
              file
              for
              defin-
              ing
              the
              tracer
              species
              that
              are
              in-
              put
              to
              the
              model
              through
              the
              boundary
```

BCON output files
Table 7-2. BCON output files

NameFormaDescription ${\tt BNDY_CENNOARYS}{\rm ame}$ and location of the gridded boundarv conditions data out-

put on the model grid defined by

GRID_NAME

File

The default location of the BCON output files is the \$CMAQ_DATA/bcon directory, controlled by the OUTDIR variable in the run script. The default naming convention for all BCON output files uses the APPL and GRID_NAME environment variables in the file name. For boundary conditions created from existing CCTM CONC files, the Julian date is also used in the file name through the DATE environment variable. All of the file-naming variables for BCON outputs are set in the run script.

Compilation Configuration Variables

The configuration options listed here are set during compilation of the BCON executable. When these options are invoked they create a binary executable that is fixed to the specified configuration. To change these options you must recompile BCON and create a new executable.

• CopySrc Uncomment to copy the source code into a working build (BLD) directory.

If commented, only the compiled object and executable files will be placed in the BLD directory.

• MakeFileOnly

Uncomment to build a Makefile to compile the executable. Comment out to both create a Makefile and compile.

• ModType: [default: module profile] Defines the format of the boundary conditions input files to be used by

BCON.

- m3conc: input a CCTM CONC file; used for nested simulations or windows of a parent domain
- profile: input an ASCII vertical profiles file
- tracer: use the tracer namelist file to create BCs of tagged tracer species

• Mechanism: [default: cb05e51 ae6 aq]

Specifies the gas-phase, aerosol, and aqueous-phase chemical mechanisms for which to create boundary conditions. The choices for the *Mechanism* variable are the mechanism directory names under the \$CMAQ_HOME/CCTM/src/MECHS directory. Also see the Mechanism Definitions Table). Examples include:

- cb6r3_ae6_aq: CB6, revision 3 gas-phase mechanism, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05e51_ae6_aq: CB05 gas-phase mechanism with CMAQv5.1 updates, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tucl_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tump_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, mercury, and air toxics, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM, aqueous/cloud chemistry; this is the CMAQv5 multipollutant mechanism
- saprc07tb_ae6_aq: SAPRC-07 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
- racm2_ae6_aq: RACM2 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism

• Tracer [default trac0]

Specifies tracer species. Invoking inert tracer species in CMAQ requires defining the tracers using namelist files and compiling the CMAQ programs with these files. The setting for this module corresponds to the directory name in the \$CMAQ_HOME/CCTM/src/MECHS directory that contains the namelist files for the tracer configuration. The default setting is to not use any tracers.

- trac[n]

Execution Configuration Variables

The environment variables listed here are invoked during execution of the program and are set in the BCON run script.

- APPL [default: None]
 - BCON executable identifier. Must match APPL Variable setting in the BCON build script.
- CFG [default: None]
 - Configuration identifier for the BCON simulation.
- MECH [default: None]
 - CMAQ chemical mechanism. Must match Mechanism variable setting in the BCON build script.
- EXEC: [default: BCON_\${APPL}_\${EXECID}]

 Executable to use for the simulation. The variable CFG is set in the BCON run script. The variable EXECID is set in the configuration
- GRIDDESC: [default: \$CMAQ_HOME/scripts/GRIDDESC1] Grid description file for setting the horizontal grid definition.
- GRID_NAME: [default:CMAQ-BENCHMARK]

 Name of the grid definition contained in the GRIDDESC file that specifies the horizontal grid for the current application of the model.
- IOAPI_ISPH: [default: 20] I/O API setting for spheroid type. See I/O API documentation for setsphere for more information.
- IOAPI_OFFSET_64: [default: NO]
 - I/O API setting for large time-step records. If your output time step is going to produce data that are greater than 2GB per time step, then this needs to be set to YES.
- LAYER FILE: [default: none]
 - Name and location of a MET_CRO_3D file for specifying the vertical layer structure for the current application of the model.
- gc_matrix.nml: [default: none]
 Gas-phase species namelist file. This file is used to configure the gas-phase species that will be output by BCON.
- ae_matrix.nml: [default: none]
 Aerosol-phase species namelist file. This file is used to configure the aerosol-phase species that will be output by BCON
- nr_matrix.nml: [default: none]
 Nonreactive species namelist file. This file is used to configure the nonreactive species that will be output by BCON
- tr_matrix.nml: [default: none]
 Tracer species namelist file. This file is used to configure the tracer species that will be output by BCON
- OUTDIR: [default: \$CMAQ_HOME/data/bcon] Output data directory.
- BC: Sets the input file type. The setting of this variable determines how

the run script sets the input and output environment variables.

- profile: sets the output file name to include the tag "profile" in the name; uses the variable BC_PROFILE to point to an ASCII vertical profile file for input to BCON.
- m3conc: used for nested simulations; sets the output file name to include a start date in the name; uses the variable CTM_CONC_1 to point to a CCTM CONC file for input to BCON.
- DATE: Sets the Julian date to use in naming the BCON output file for nested runs.
- SDATE: [default: \${DATE}] Julian start date for extracting boundary conditions from a CCTM CONC file for a nested simulation. If SDATE is not set, it will be set automatically from the CTM CONC 1 file.
- STIME: [default: 000000] Start time for extracting boundary conditions from a CCTM CONC file for a nested simulation. If STIME is not set, it will be set automatically from the CTM CONC 1 file.
- RUNLEN: [default: 240000] Number of hours of boundary conditions to extract from a CCTM CONC file for a nested simulation. If RUNLEN is not set, it will be set automatically from the CTM_CONC_1 file.

Compiling and Running

Compile BCON

Chapter 5 provides an overview of how to install and compile the CMAQ preprocessor programs for a test simulation. Follow those steps (summarized below) to compile new versions of BCON.

- Compile Bldmake, the CMAQ source code and compilation management program. This needs to be done only once—the first time CMAQ is installed.
- Configure the BCON use the config.cmaq script, which points to the available I/O API and netCDF libraries.
- Configure the BCON build script for your application by setting the compilation configuration variables described above.
- Invoke the build script to create an executable.

cd \$CMAQ_HOME/PREP/bcon/scripts/
./bldit.bcon |& tee build.bcon.log

Run BCON

Set the run script settings according to the execution configuration variables described above. Run BCON to produce boundary conditions for the CCTM:

cd \$CMAQ_HOME/PREP/BCON
./run.bcon |& tee bcon.log

Calmap

Description

The preprocessor program Calmap produces gridded planting start dates, planting end dates, and harvesting end dates for different crop types for estimating the impacts of agricultural activities on windblown dust emissions. The CMAQ windblown dust emissions module can optionally use the output from Calmap to simulate the effects of crop cycles on dust emissions.

Files, configuration, and environment variables

Figure 7-3 shows that Calmap reads five input files to produce eight outputs, only three of which are used by the CCTM. Calmap uses the GRIDCRO2D file, produced by MCIP, to define the modeling grid. The BELD01 file points to a BELD3 "a" file of gridded land cover/land use data containing coverage for several different crop categories. The BELD3 "a" file is an input to the BEIS emissions model and can be generated by the Spatial Allocator. The rest of the inputs to Calmap are crop calendar data for the United States that are packaged with CMAQv5. Calmap converts to the data to I/O API GRDDED3 files on the modeling grid defined in the GRIDCRO2D file. The CROPMAP01 file contains planting start dates for specific crops. The CROPMAP04 file contains planting end dates for specific crops. The CROPMAP08 file contains harvesting end dates for specific crops. Each of these files are input to the CCTM when the erodible agricultural land (CTM_ERODE_AGLAND) feature is turned on.




Figure 7-3. Calmap input and output files

Calmap input files

Table 7-3. Calmap input files

NameFormaDescription

GRID_CORROD_NAMBe

and

lo-

ca-

tion

of

the

time-

independent

2-D

cross-

point

me-

teo-

rol-

ogy

file;

out-

put

by

МСІР

NameFormaDescription

BELD@RDD**BD**BD

land

use

"A"

data

file

for

cal-

culat-

ing

wind-

blown

 dust

emis-

sions;

pro-

duced

with

BELD

land

use tiles

and

the

Spa-

tial

Allocator

${\rm CPCA} \underline{\tt MSD} {\rm II} \, {\rm Calendar}$

of

agri-

cul-

tural

ac-

tivi-

ties

by

state

NameFormaDescription ${\bf NCRORSCII\, Number}$ and names of crop species in- ${\rm cluded}$ inthe cropcalendar USSTAAISCII Two digit USstate codes

included in the crop calendar

File

Calmap output files

Table 7-4. Calmap output files

NameFormaDescription

CROP**MAPONA**

and

lo-

ca-

tion

of

the

grid-

 $\overline{\operatorname{ded}}$

plant-

ing

 start

dates

file.

CROP**MAPOX**

and

lo-

ca-

tion

of

the

 $\begin{array}{c} \text{grid-} \\ \text{ded} \end{array}$

???

 start

dates

file;

 $_{
m not}$

used by

the

CCTM.

NameFormaDescription

CROP**MAPONA**

and

lo-

ca-

tion

of

the

grid-

 ded

???

dates

file; not

used

by

the

CCTM

CROP**MAPDED**

and

lo-

ca-

tion

of

the grid-

ded

plant-

ing

end

dates

file.

NameFormaDescription

CROP**MAPON**A

and

lo-

ca-

tion

of

the

grid-

 ded

???

start

dates

file;

 not

 ${\it used}$

by

the

 CCTM

CROP**MAPOND**ae

and

lo-

ca-

tion

of the

grid-

 ded

???

startdates

file;

 not

used

by

the

 CCTM

File NameFormaDescription

CROP**MADDA**

and lo-ca-tion of the grid-ded harvesting end dates file.

Execution Configuration Variables

The environment variables listed here are invoked during execution of the program and are set in the Calmap run script.

- BASE: [default: \$CMAQ_HOME/PREP/agdust/scripts] Base Calmap installation location.
- GRID_CRO_2D: [default: none] Directory path and name of the GRID_CRO_2D file for defining the
- BELD01: [default: none] Directory path and name of the BELD3 A file for defining the gridded 1
- · CROPMAP01-08: [default: none] Directory path and names of Calmap output files. The CROPMAP01

Compiling and Running

Compile Calmap

Calmap is compiled with a Makefile. The configuration options in the Makefile include only the compiler and compiler flags to use for building the executable. The Makefile is located in the directory with the Calmap source code \$CMAQ_HOME/PREP/agdust/src. To compile Calmap, source the config.cmaq file and invoke the Makefile at the command line.

```
cd $CMAQ_HOME/PREP/agdust/src
source $CMAQ_HOME/config.cmaq
./make |& tee make.calmap.log
```

To port Calmap to different compilers, change the compiler names, locations, and flags in the config.cmaq script.

Run Calmap

Set the run script settings according to the execution configuration variables described above. Run Calmap to produce crop calendar input for the CCTM inline windblown dust model:

```
cd $CMAQ_HOME/PREP/agdust
./run.calmap |& tee run.calmap.log
```

CCTM

Description

CCTM is the Eulerian chemistry and transport component of CMAQ. It uses input data produced by the other CMAQ programs and from meteorological and emissions models. CCTM produces multiple output files for each simulation. The basic CCTM outputs include instantaneous and average hourly concentration files, wet and dry deposition files, and visibility estimates. Other CCTM outputs can include diagnostic aerosol and cloud files and processes analysis files.

CCTM contains several science configurations for simulating transport, chemistry, and deposition. All of the science configuration options in CCTM, such as the chemical mechanism to be used, are set when compiling the executable. The model grid and vertical layer structure for CCTM are set at execution. The important distinction between selecting the science configuration and the model grid, layer configuration is that CCTM does not need to be recompiled when changing model grids, layers but does need to be recompiled when new science options are invoked.

Optional output files are created when their associated processes are invoked in CCTM. For example, when CCTM is compiled with process analysis turned on, additional output files are created.

CCTM includes options for the in-line processing of emissions and photolysis rates. In-line refers to the handling of processes that had previously been accomplished outside of CCTM, such as emissions processing with SMOKE, with algorithms internal to CCTM. The benefits of in-line emissions processing include the integration of higher time-resolution meteorology in the computation of biogenic emissions and plume rise from point sources and the avoidance of the large data storage burden required for emissions data. The benefit of in-line photolysis rate calculations is the inclusion of predicted gas and aerosol concentrations in the rate calculations.

Both in-line emissions and photolysis are invoked through compile-time configuration options for CCTM. When CCTM is instrumented for in-line emissions

calculations, a series of additional input files and environment variables are required at execution. The details of these additional inputs are provided below. In-line photolysis does not require any additional inputs as CCTM includes all of the photolysis rate data internal to the in-line instrumented version of the model.

Files, configuration, and environment variables

Figure 7-4 shows the input and output files and configuration options for CCTM. A distinction is made between the options that are invoked at compilation time versus those invoked at execution of the program. When compiling CCTM, the user specifies a chemical mechanism to configure the gas-phase chemistry and aerosol mechanism used for the air quality calculations. Setting the Mechanism variable in CCTM compile script configures the program to use a specific set of mechanism INCLUDE files to build an executable. All of the science processes simulated by CCTM must also be selected during the compilation step for CCTM. Separate CCTM executables must be prepared for different mechanism and science configurations. During the execution step, or when CCTM is run, the user sets the horizontal and vertical grid definitions and the input files used for the simulation. Different spatial domains, vertical grid structures and input files can be used with a single CCTM executable, as long as the input files are consistent with the scientific configuration built into the executable. For example, with the gas-phase photochemical mechanism configuration built into a CCTM executable, different modeling domains can be simulated with the executable as long as the emissions and IC/BC files are consistent with the photochemical mechanism configuration built into the executable.





Figure 7-4. CCTM input and output files

CCTM input files

Table 7-5. Required CCTM input files



NameFormaDescription

OCEAN_CIRDDEDSame

and

lo-

ca-

tion

of

the

time-

independent

2-D

file

for

defin-

ing the

frac-

tion

of

each

model

grid

cell

cov-

ered by

open

ocean

NameFormaDescription

```
EMIS_1GRDDEDSame
               and
               lo-
               ca-
               tion
               of
               the
               {\it time-}
               dependent
               2-D
               or
               3-D
               emis-
               sion
               file
               spe-
               ci-
               ated
               for
               a
               par-
               tic-
               ular
               gas-
               phase
               chem-
               ical
               mech-
               a-
               nism
               and
               PM
               model;
               out-
               put
               {\rm from}
               an
               \quad \text{emis-} \quad
               sion
               model,
               \operatorname{such}
               as
               {\rm SMOKE}
               or
               CONCEPT
```

NameFormaDescription

```
INIT_[CPANNETDAERO_ENONR/TRAC]_1
              and
              lo-
              ca-
              tion
              of
              the
              {\it time-}
              dependent,
              single-
              time\text{-}
              step,
              3-D
              ini-
              tial
              con-
              di-
              tions
              file
              spe-
              ci-
              ated
              for
              a
              par-
              tic-
              ular
              gas-
              phase
              chem-
              ical
              mech-
              a-
              nism
              and
              PM
              model;
              out-
              put
              {\rm from}
```

ICON

NameFormaDescription

```
BNDY_[ENEXT/ANERO/NONR/TRAC]_1
              and
              lo-
              ca-
               tion
               of
               the
               {\it time-}
              dependent,
              ei-
               ther
              single-
              time-
              step
              or
              multi-
              time-
              step,
              3-D
              bound-
              ary
              con-
              di-
               tions
               file
              spe-
              ci-
              ated
               for
              \mathbf{a}
              par-
              tic-
               ular
              gas-
              phase
              chem-
              ical
              \operatorname{mech-}
              a-
              nism
              and
              PM
              model;
              out-
              put
        32
              {\rm from}
```

BCON

NameFormaDescription

GRID **CORRODINADI**e

and

lo-

ca-

tion

of

the

time-

independent

2-D

cross-

point

me-

teo-

rol-

ogy

file;

out-

put

by

MCIP

$\operatorname{GRID}\underline{\operatorname{\textbf{GPODID}}}\underline{\operatorname{\textbf{RADB}}}\mathrm{e}$

and

lo-

ca-

tion

of

the time-

independent

2-D

dot-

point

me-

teo-

rol-

ogy

file;

out-

put

by

MCIP

NameFormaDescription

MET_**GRO**D**NA**3e and location of the ${\it time-}$ dependent 2-D crosspoint meteorologyfile; output by MCIP $\mathrm{MET}_\mathbf{ORDDND3}\mathrm{e}$ and location of the timedependent 3-D dotpoint meteorologyfile; output

by MCIP

NameFormaDescription

```
MET_GRODND3e
            and
            lo-
            ca-
            tion
            of
            the
            {\it time-}
            dependent
            3-D
            cross-
            point
            me-
            teo-
            rol-
            ogy
            file;
            out-
            put
            by
            MCIP
MET_BNDNANDae
            and
            lo-
            ca-
            tion
            of
            the
            time-
            dependent
            3-D
            bound-
            ary
            me-
            teo-
            rol-
            ogy
            file;
            out-
            put
```

by MCIP

NameFormaDescription

CSQY_ABATTA bsorption

cross

sec-

tion

and

quan-

 tum

yield

data

for

cal-

cu-

lat-

ing

in-

line

pho-

tol-

001

ysis

rates

OMI ASCII Ozone

Map-

ping

In-

stru-

 ment

ver-

ti-

 cal

ozone

col-

umn

data

by

lati-

 ${\rm tude}$

 $\quad \text{for} \quad$

dif-

fer-

 ent

years

File NameFormaDescription

OPTICSSCDAWAvelength,

Opti- cal and Surface ${\bf Albedo}$ Parame- ters for CMAQ In-Line Photolysis calculation $gc_ma \textbf{ASCIInN} amelist$ file for defining the gasphase species that are input to the modelthrough

the boundary

\mathbf{File}

${\bf Name Formal Description}$

```
ae_maArSCHhNamelist
             file
             for
             defin-
             ing
             the
             aerosol
             species
             that
             are
             in-
             put
             to
             the
             model
             through
             the
             boundary
nr\_ma \textbf{ASCIIIN} ame list
             file
             for
             defin-
             ing
             the
             non-
             reactive
             species
             that
             are
             in-
             put
             to
             the
             model
             through
             the
             boundary
```

File NameFormaDescription
tr_matArSCHIMNamelist
file
for
defin-
ing
the
tracer
species
that
are
in-
put
to
the
model
through
the
boundary

Table 7-6. Optional CCTM input files

File Name	Format	Description
XJ_DATA	ASCII	Name and
		location of
		the daily
		clear-sky
		photolysis
		rates file
		speciated
		for a
		particular
		gas-phase
		chemical
		mechanism;
		output
		from
		JPROC -
		only needed
		for offline
		photolysis
		configuration

File Name Format Description

STK_GRPS_GRADDEDStack

parameter file for calculating $\quad \text{inline} \quad$ plume rise for point source emissions - $\,$ nn refers to the sector ID number, where there could be multiple point source stack groups used in a single $\,$ simulation; produced by the SMOKE program Elevpoint

File Name	Format	Description
STK_EMIS	GARDDEI	DBmissions
		for elevated
		point
		sources -
		nn refers to
		the sector
		ID number
		where there
		could be
		multiple
		point
		source
		sectors
		used in a
		single
		simulation;
		produced by the
		SMOKE
		program
		Smkmerge
GSPRO	ASCII	Speciation
001100	110011	profile file.
		Contains
		the factors
		that are
		used to
		separate
		aggregated
		inventory
		pollutant
		emissions
		totals into
		emissions
		of model
		species
		required by CCTM

File Name	Format	Description
B3GRD	GRDDE	DN ormalized
		biogenic
		emissions
		for input to
		BEIS3;
		produced
		by the
		SMOKE
		program
		Normbeis3.

File Name Format Description

BIOSEASONGRDDEDIndicates

the biogenic emissions factors to use for each day in a given year. This file can be created using the **SMOKE** utility program Metscan. The BIOSEA-SON file is timedependent and usually contains data for an entire year (365 or 366days). It uses one variable, SEASON, which is either 0(grid cell should use winter factors for current day) or 1 (grid cell should use

> summer factors for current day.

File Name	Format	Description
SOILINP	GRDDE	D B iogenic
		NO soil
		input
		restart file;
		output by
		the
		previous
		day CCTM
		simulation.
DUST_LU	_GRDDE	DBELD land
		use "A"
		data file for
		calculating
		windblown
		dust
		emissions;
		produced
		with BELD
		land use
		tiles and
		the Spatial
		Allocator
DUST_LU_	_ g rdde	DBELD land
		use "TOT"
		data file for
		calculating
		windblown
		dust
		emissions;
		produced
		with BELD
		land use
		tiles and
		the Spatial
		Allocator

File Name	Format	Description
MODIS_FI	PARDDE	DMODIS
		derived
		time-
		varying
		vegetation
		land cover
		data. Can
		be
		generated
		with the
		Spatial
		Allocator
		Raster
		Tools.
CROPMAP	'0GRDDE	
		planting
		start dates
		for
		estimating
		dust .
		emissions
		from
		erodible
		cropland;
		produced
		by the
		CMAQ pre-
		processor Crangal
CROPMAP		Cropcal D3ridded
CHOI MAI	Official	planting
		end dates
		for
		estimating
		dust
		emissions
		from
		erodible
		cropland;
		produced
		by the
		ČMAQ pre-
		processor
		Cropcal
		•

File Name	Format	Description
CROPMAP	0&RDDE	D3ridded
		harvesting
		end dates
		for
		estimating
		dust
		emissions
		from
		erodible
		cropland;
		produced
		by the
		CMAQ pre-
		processor
		Cropcal
LTNGNO	GRDDE	D B ightning
		NO
		emissions
		file with
		rate of
		production
		(moles/sec)
		for each
		model layer
		at each
		time step
NLDN_ST	R IMEIS DE	-
_		observed
		lightning
		strikes
		(km-2)
		gridded to
		the CCTM
		domain.

File Name Format Description LTNGPARM SREDIDEDB imeindependent, gridded lightning parameters file that includes monthly flash count totals, scaling factors for calculating flashes using the convectiveprecipitation rate, ratio of intercloud to cloud-toground flashes, and moles of NO per flash BELD4_LU GRDDED $\!B$ ELD4 land use file with fractional crop distributions gridded to the modeling

domain

File Name	Format	Description
E2C_SOIL	GRDDE	DBPIC soil
		properties
		file for each
		crop type
		gridded to
		the
		modeling
		domain.
		This time-
		independent
		file
		contains
		the soil pH
		for each
		agricultural
		crop being
		modeled for
		the 1 -cm
		surface
		layer and
		10-cm tilled
		layer
		v

File Name	Format	Description
E2C_FERT	GRDDE	DBPIC crop
		type file
		gridded to
		the
		modeling
		domain.
		This file
		contains
		the initial
		soil
		ammonium
		concentra-
		tions for
		the first
		day of the
		simulation
		estimated
		by EPIC
		and the
		fertilizer
		application
		depth and
		rate

CCTM output files

Table 7-7 lists the logical file names, formats, and descriptions of the output files that are produced by the base configuration of CCTM. Activating different science modules, in-line deposition, and in-line emissions processing produces additional output files from CCTM. Table 7-8 lists the logical file names, formats, and descriptions of the output files that are produced by optional configurations of CCTM.

Table 7-7. CCTM base output files

File Name	Format	Description
CTM_CON	NGRIDDE	Distourly 3-D
		instanta-
		neous gas-
		and aerosol-
		phase
		pollutant
		estimates

File Name	Format	Description
S_CGRID	GRDDE	DSimulation-
		ending 3-D
		full CGRID
		(gas- and
		aerosol-
		phase
		pollutants)
		concentra-
		tions for
		use as a
		restart file
A_CONC_	1GRDDE	DHourly 2-D
		or 3-D
		integral
		average gas-
		and aerosol-
		phase
		pollutant
		estimates
CTM_DRY		Distourly 3-D
		gas- and
		aerosol-
		phase dry
		deposition
		estimates
CTM_WE	T <u>G</u> RENDE	DHourly 3-D
		gas- and
		aerosol-
		phase wet
		deposition
		estimates
$CTM_VIS_$	_GRDDE	D B nstantaneou
		top of the
		hour,
		hourly 3-D
		visibility
		metrics

Table 7-8. CCTM optional output files

File Name Format	Description
CTM_SSEMIS_GRDDED3	sea salt emissions; set the variable CTM_SSEMDIAG to "Y" in the CCTM to run script to write this
CTM_WET_DEPGRDDED3	file Name and location of hourly 2-D cloud diagnostics file; set the variable CLD_DIAG to "Y" in the CCTM run script to write this file
CTM_DEPV_DIGEDDED3	

File Name	Format	Description
CTM_IPR[1 6BD DED3	
		or 3-D
		integrated
		process rate
		(IPR) files;
		multiple
		files written
		when
		CCTM is
		configured
		to run with
		IPR
CTM_IRR[1GBDDED3	Hourly 2-D
		or 3-D
		integrated
		reaction
		rate (IRR)
		files;
		multiple
		files written
		when
		CCTM is
		configured
		to run with
		IRR

-	
CTM_RJ[1-28DDED3	Hourly photolysis diagnostic output file; multiple files written when there are a large number of photolytic reactions in a chemical mechanism; set the variable CTM_PHOTDIAG to "Y" in the CCTM run script to write this file Hourly biogenic emissions file; output when in-line biogenic emissions processing is activated by setting CTM_BIOGEMIS to "Y" and the variable B3GTS_DIAG is set to "Y" in the CCTM run

File Name	Format	Description
SOILOUT	GRDDED3	Hourly soil
		NO
		emissions
		file; output
		when
		in-line
		biogenic
		emissions
		processing
		is activated
		by setting
		CTM_BIOGEMIS
		to "Y"
CTM_DUST_E	MGBDDED3	Hourly 2-D
		dust
		emissions
		file; output
		when the
		CCTM
		dust
		module is
		activated
	by setting	
	CTM_WB_DUST	
	to "Y" and	
	the variable	
	CTM_DUSTEM_D	
	is set to "Y"	
	in the	
		CCTM run
		script

		
File Name	Format	Description
LTNGOUT1	GRDDED3	Hourly
		average 3-D
		lighting NO
		emissions
		file; output
		when the
		CCTM
		lightning
		module is
		activated
		by setting
		CTM_LTNG_NO
		to "Y" and
		the variable
		LTNGDIAG
		is set to "Y" in the
		CCTM run
		script
LTNGOUT2	GRDDED3	Hourly
LINGUUIZ	GIUDDEDO	column
		total NO
		lighting
		emissions
		file; output
		when the
		CCTM
		lightning
		module is
		activated
		by setting
		CTM_LTNG_NO
		to "Y" and
		the variable
		LTNGDIAG
		is set to "Y"
		in the
		CCTM run
		script

File Name Format Description CTM_PT3D_DIGREDDED3 Hourly 3-D pointsource emissions file; output when in-line emissions processing is activated by setting CTM_PT3DEMIS to "Y" and the variable PT3DDIAG is set to "Y" in the CCTM run script PLAY_SRCID_CHADDEED3 Hourly 3-D layer ${\it fractions}$ file; output when in-line emissions processing is activated by setting CTM_PT3DEMIS to "Y" and the variable PT3DFRAC is set to "Y" in the CCTM run script CTM_DRY_DEPGRIDSED3

 ${\tt CTM_DRY_DEPG{\tt ETSDED3}}$

File Name	Format	Description
MEDIA_CONC	GRDDED3	Hourly
		mercury
		deposition
		output file;
		output
		when bidi-
		rectional
		mercury
		flux is
		activated
		by setting
		the variable
		CTM_HGBIDI
		to "Y" in
		the CCTM
		run script
CTM_VDIFF_	DGFAICEDED3	Hourly
		vertical
		diffusion
		diagnostic
		data;
		activate by
		setting the
		variable
		VDFF_DIAG_FILE
		to "Y" in
		the CCTM
		run script
CTM_VSED_D	IARDDED3	Hourly
		gravita-
		tional
		settling
		diagnostic
		data;
		activate by
		setting the
		variable
		VDFF_DIAG_FILE
		to "Y" in
		the CCTM
		run script

File Name	Format	Description
CTM_AOD_1	GRDDED3	Hourly
		aerosol
		optical
		depth
		estimates;
		activate by
		setting the
		variable
		$\mathtt{CTM_AOD}\ \mathrm{to}$
		"Y" in the
		CCTM run
		script
CTM_AVIS_1	GRDDED3	Hourly-
		averaged
		3-D
		visibility
		metrics; set
		the variable
		CTM_AVISDI
		to "Y" in
		the CCTM
		run script
		to write
		this file

File Name Format	Description
CTM_PMDIAG_GRDDED3	Hourly
	instanta-
	neous 3-D
	aerosol
	diagnostics
	for
	conditions
	at the top
	of the hour;
	dp and
	sigmas for
	Aitken and
	accumula-
	tion mode
	aerosol
	species; set
	the variable
	CTM_PMDIAG
	to "Y" in
	the CCTM
	run script
	to write
	this file
CTM_APMDIAGGRDDED3	Hourly
	average
	3-D aerosol
	diagnostics;
	dp and
	sigmas for
	Aitken and
	accumula-
	tion mode
	aerosol
	species; set
	the variable
	CTM_APMDIA
	to "Y" in
	the CCTM
	run script
	to write
	this file

The default location of the CCTM output files is the $\texttt{CMAQ_HOME/data/cctm}$

directory, controlled by the OUTDIR variable in the run script. The default naming convention for all CCTM output files uses the EXEC and APPL environment variables in the file name. All of the variables for naming the CCTM outputs are set in the run script.

Compilation Configuration Variables

The configuration options listed here are set during compilation of the CCTM executable. When these options are invoked they create a binary executable that is fixed to the specified configuration. To change these options you must recompile CCTM and create a new executable.

Several of the CCTM science modules have more than one option. Brief descriptions of these options are provided here. For details on the science of the different options refer to the CMAQ Release Notes.

The following five options are invoked by uncommenting the line in the CCTM build script. Comment the line in the script using a "#" to turn the option off.

• CopySrc

Uncomment to copy the source code into a working build (BLD) directory. If commented, only the compiled object and executable files will be placed in the BLD directory.

• set ParOpt

Build an executable for running on multiple processors. Invoking this command requires the availability of the MPI library/INCLUDE files.

• MakeFileOnly

Uncomment to build a Makefile to compile the executable. Comment out to both create a Makefile and compile.

• set build_parallel_io

Uncomment to build CMAQ with true parallel I/O feature (requires ioapi3.2 and pnetcdf)

• set build_twoway

Uncomment to build WRF-CMAQ twoway - this cannot be set for standalone CMAQ

• set potvort03

Uncomment to build CMAQ with potential vorticity free-troposphere O3 scaling

The following configuration settings may have multiple options. Select one option in the CCTM build script.

• ModDriver: [default: driver/wrf]

The CCTM generalized -coordinate driver module.

- driver/wrf

use WRF-based scheme for mass-conserving advection; select this option when using WRF meteorology

- driver/yamo

use Yamartino scheme for mass-conserving advection

• ModGrid: [default: Cartesian]

The CCTM model grid configuration module. Currently only Cartesian coordinates are supported by CMAQ. Do not change this module setting.

- grid/cartesian

• ModInit: [default: init/yamo]

The CCTM time-step initialization module that uses a Yamartino scheme for mass-conserving advection. Do not change this module setting.

- init/yamo

• ModCpl: [default: couple/gencoor wrf]

Mass coupling concentration conversion module options. Unit conversion and concentration coupling module.

- couple/gencoor_wrf

Coupling scheme compatible with the WRF-based advection scheme; select this option when ModDriver is set to ctm_wrf

- couple/gencoor

Coupling scheme compatible with the Yamartino advection scheme; select this option when ModDriver is set to ctm_yamo.

• ModHadv: [default: hadv/yamo]

Horizontal advection module. Currently only the Yamartino global mass-conserving hoizontal advection scheme is supported.

- hadv/yamo

• ModVadv: [default: vadv/wrf]

Vertical advection module.

- vadv/wrf

use the WRF omega calculation with the Piecewise Parabolic Method (PPM) to calculate vertical advection; this module should be used only with WRF meteorology

- vadv/yamo

use the global mass-conserving scheme to calculate vertical advection

• ModHdiff: [default: hdiff/multiscale]

The only option in CMAQv5 for the horizontal diffusion module is *hd-iff/multiscale*, which uses a diffusion coefficient based on local wind deformation. Do not change this module setting.

- hdiff/multiscale

• ModVdiff: [default: vdiff/acm2]

Vertical diffusion and surface exchange module. Do not change this module setting.

- vdiff/acm2

calculate vertical diffusion using the Asymmetric Convective Model version $2~(\mathrm{ACM2})$

• ModDepv: [default: depv/m3dry]

Deposition velocity calculation module. Do not change this module setting.

depv/m3dry

CMAQ dry deposition velocity routine

• ModEmis: [default: emis/emis]

CMAQ in-line anthropogenic and natural emissions module. In line emissions are activated in the CCTM run script. Do not change this module setting.

- emis/emis
- ModBiog: [default: biog/beis3]

Calculate biogenic emissions in-line with the BEIS3 model. Inline biogenic emissions are activated in the CCTM run script. Do not change this module setting.

- biog/beis3
- ModPlmrs: [default: plrise/smoke]

Calculate in-line plume rise for large point sources using the Briggs algorithm as it is implemented in SMOKE. Inline emissions plume rise in controlled in the CCTM run script. Do not change this module setting.

- plrise/smoke
- ModCgrds: [default: spcs/cgrid_spcs_nml]

CMAQ model species configuration module.

- spcs/cgrid_spcs_nml
 namelist files used to configure CMAQ model species
- namelist files used to configure CMAQ model speci
 spcs/cgrid specs icl
- use Fortran INCLUDE files used to configure CMAQ model species
- ModPhot: [default: phot/inline]

Photolysis calculation module.

- phot/inline
 - calculate photolysis rates in-line using simulated aerosols and ozone concentrations
- phot/table

calculate clear-sky photolysis rates off-line using the CMAQ program JPROC; provide daily photolysis rate look-up tables to CCTM

Mechanism: [default: cb05e51_ae6_aq]

Chemistry mechanism for gas, aerosol, and aqueous chemistry. See the CMAQ Mechanism Definitions Table for a listing of the mechanism choices that are available in CMAQv5.2.

• Tracer [default trac0]

Specifies tracer species. Invoking inert tracer species in CMAQ requires defining the tracers using namelist files and compiling the CMAQ programs with these files. The setting for this module corresponds to the directory name in the '\$CMAQ_HOME/CCTM/src/MECHS directory that contains the namelist files for the tracer configuration. The default setting is to not use any tracers.

- trac[n]
- ModGas: [default: gas/ebi] Gas-phase chemistry solver module.
 - smvgear
 use the SMVGEAR chemistry solver
 - ros3
 - use the Rosenbrock chemistry solver

 ebi
 use the Euler Backward Iterative solver
- ModAero: [default: aero6]

CMAQ aerosol module.

- aero6

sixth-generation modal CMAQ aerosol model with extensions for sea salt emissions and thermodynamics; includes a new formulation for secondary organic aerosol yields

• ModCloud: [default: cloud/acm ae6]

CMAQ cloud module for modeling the impacts of clouds on deposition, mixing, photolysis, and aqueous chemistry.

- cloud/acm_ae6

ACM cloud processor that uses the ACM methodology to compute convective mixing with heterogeneous chemistry for AERO6

- cloud/acm_ae6_mp

ACM cloud processor that uses the ACM methodology to compute convective mixing with heterogeneous chemistry for AERO6 and air toxics; this is the multipollutant mechanism in CMAQv5

- cloud/acm_ae6_kmt

ACM cloud processor that uses the ACM methodology to compute convective mixing with heterogeneous chemistry for AERO6 and aqueous chemistry with kinetic mass transfer and Rosenbrock solver

- cloud/acm_ae6i_kmti

ACM cloud processor that uses the ACM methodology to compute convective mixing with heterogeneous chemistry for AERO6 and aqueous chemistry with kinetic mass transfer and Rosenbrock solver with an extension to simulate the aqueous phase formation of SOA in cloud droplets, see: CMAQv5.1 Aqueous Chemistry

• ModUtil: [default: util]

CMAQ utility modules. Do not change this module setting.

- util/util
- ModPvO3: [default: pv_o3]

Potential vorticity parameterization for free-troposphere exhange of ozone. This option is configured using the potvorO3 variable in the CCTM build script. Do not change this module setting.

- pv_o3

• ModPa: [default: procan/pa]

Process analsis is controlled in the CCTM run script. Do not change this module setting.

- procan/pa

Execution Configuration Variables

The environment variables listed below are invoked during execution of the CCTM and are set in the CCTM run script.

- PROC [default: mpi]
 - Sets if the CCTM will run in multi-processor or serial mode.
 - mpi

Use MPI multi-processor configuration. Additional configuration settings are required when selecting mpi. The CCTM must have been built to support MPI. The run script requires settings for the number of processors and other MPI configuration variables required by the Linux system.

- serial
 - Run the CCTM in serial, single-processor mode.
- APPL [default: None]
 - CCTM executable identifier. Must match APPL Variable setting in the CCTM build script.
- CFG [default: None]
 - Configuration identifier for the CCTM simulation.
- MECH [default: None]
 - CMAQ chemical mechanism. Must match Mechanism variable setting in the CCTM build script.
- EXEC [default: CCTM_\$APPL_\$EXECID] The name of the CCTM executable.

MPI Configuration

- NPCOL_NPROW [default: 1 1]
 - The numbers of columns and rows for decomposing the modeling domain in an MPI configuration. The product of this pair of numbers must equal the total number of processors allocated to the CCTM simulation. For serial or single-processor MPI runs set to 1 1. For multi-processor simulations, the number of columns (i.e, the first number in the pair) should be greater than or equal to the number of rows. For example, for an 8 processor MPI simulation, set to 4 2
- NPROCS [default: 1]
 - Number of processors to allocate for the CCTM simulation; equal to the product of NPCOL x NPROW. For serial or single-processor MPI runs set to 1, otherwise set to the product of the two numbers used in NPCOL_NPROW.

Timestep Configuration

• STDATE

Simulation start date in Julian format (YYYYDDD)

STTIME

Simulation start time (HHMMSS)

• NSTEPS [default: 240000]

Number of simulation time steps (HHMMSS)

• TSTEP [default: 010000]

Simulation output time step interval (HHMMSS)

YEAR

Simulation year specified using 4 digits (YYYY)

MONTH

Simulation Month specified using 2 digits (MM)

DAY

Simulation Day specified using 2 digits (DD)

YMD

Year+Month+Day; automatically calculated by the script

CCTM Configuration Options

- LOGFILE [default: \$BASE/\$APPL.log]
 Uncomment to capture CCTM standard output to a log file; the LOGFILE variable sets the name and location of the log.
- GRID_NAME [default: CMAQ-BENCHMARK]

Name of the grid definition contained in the GRIDDESC file that specifies the horizontal grid for the current application of the model.

- GRIDDESC [default: \$CMAQ_HOME/scripts/GRIDDESC1] Grid description file for setting the horizontal grid definition.
- CTM_APPL [default: \$APPL] CCTM log file naming extension.
- CONC_SPCS [if commented out, all species] Model species to be written to the CCTM CONC file.
- CONC_BLEV_ELEV [if commented out, all layers]
 Vertical model layer range for the CONC-file concentrations; this variable sets the lower and upper layers over which to output the CONC file.
- AVG_CONC_SPCS [if commented out, output all species]
 Model species for calculating integral average concentrations for each output time step. Options can be any of the standard output species that are written to the CCTM CONC file. The species in this list will be written to the ACONC output file.
- ACONC_BLEV_ELEV [default: if commented out, all layers] Vertical model layer range for integral average concentrations; this variable sets the lower and upper layers over which to calculate integral average concentrations. For example, setting this variable to "1 5" will produce integral average concentrations for model layers 1 through 5.
- AVG_FILE_ENDTIME [default: N] Change the time stamp of the ACONC file output time step from the

default of the beginning of the hour to the end of the hour.

- Y: Set the time stamp to the end of each hour.
- N: Set the time stamp to the beginning of the hour.
- EXECUTION ID

The name of the CCTM executable; automatically set by the script.

Synchronization Time Step and Tolerance Options

• CTM_MAXSYNC [default: 720]

Maximum synchronization time step in seconds

• CTM_MINSYNC [default: 60]

Minimum synchronization time step in seconds

• SIGMA_SYNC_TOP [default: .70]

Top sigma level thru which sync step determined

• CTM_ADV_CFL [default: .75]

Maximum Courant-Friedrichs-Lewy (cfl) condition

• RB_ATOL [default: 1.0E-07]

Global Rosenbrock (ROS3) chemistry solver absolute tolerance

Science Options

• CTM WB DUST [default: Y]

Setting to calculate in-line windblown dust emissions in CCTM. Setting this variable to Y requires the availability of gridded land use input files that include the following BELD USGS land use classifications: shrubland, shrubgrass, and sprsbarren. See Chapter 8 for a description of the DUST_LU_1 and DUST_LU_2 input files. Comment out variable or set to Y to turn on; set to N to turn off.

• CTM_ERODE_AGLAND [default: N]

Setting to use optional erodible agricultural land classifications for computing windblown dust emissions from agricultural land. Setting this variable to Y requires the availability of gridded crop timing data that describe planting start dates, planting end dates, and harvesting end dates for 18 crop types. See Chapter 8 for a description of the CROPMAP01, CROPMAP04, and CROPMAP08 input files. If CTM_WB_DUST is set to N, this setting will be ignored. Set to Y to turn on; comment out variable or set to N to turn off.

• CTM_WBDUST_BELD [default: BELD3]

Landuse database for identifying dust source regions; ignore if CTM WB DUST = N $\,$

- BELD3
 - Use BELD3 landuse data
- BELD4

Use BELD4 landuse data

• CTM LTNG NO [default: Y]

Setting to activate lightning NO emissions. Setting this variable to Y

requires additional variables to define the configuration of the lightning NO emissions calculation. See the settings for LTNGNO, LTNGPARAMS, NLDN_STRIKES, and LTNGDIAG below. Set to Y to turn on; comment out variable or set to N to turn off.

• CTM_WVEL [default: N] Setting to output the CCTM-calculated vertical velocities to the CONC

file. Set to Y to turn on; comment out variable or set to N to turn off.

• KZMIN [default: Y]

If KZMIN is set to Y, CCTM will read the urban land use fraction variable (PURB) from the GRID_CRO_2D meteorology file and use this information to determine the minimum eddy diffusivity in each grid cell. In CMAQv5, grid cells that are predominantly urban use a KZMIN value of 1.0 m2/s and non-urban cells use a value of 0.01 m2/s. If this variable is set to N, the PURB variable will not be used and a uniform KZMIN value of 1.0 m2/s will be used throughout the modeling domain.

CTM_ILDEPV [default: Y]

Calculate in-line deposition velocities. Comment out variable or set to Y to turn on; set to N to turn off.

• CTM_MOSAIC [default N]

Calculate land use specific deposition velocities and fluxes.

• CTM_FST [default: N]

Use MOSAIC method to get land-use specific stomatal flux.

• CTM_ABFLUX [default: N]

Activate fertilizer ammonia bidirectional flux for in-line emissions and deposition velocities. If CTM_ILDEPV is set to N this variable is ignored. Setting this variable to Y requires four additional input files that include gridded fractional crop distributions (B4LU_file), soil properties (E2C_Soilfile), fertilizer conditions (E2C_Fertfile), and an agricultural soil initial conditions file (INIT_MEDC_1). Activation of this setting will produce additional variables in the output dry deposition file. See Chapter 8 for a description of the required input files. Set to Y to turn on; comment out or set to N to turn off.

• CTM HGBIDI [default: N]

Activate mercury bidirectional flux for in-line emissions and deposition velocities. If CTM_ILDEPV is set to N this variable is ignored. Activation of this setting will produce additional variables in the output dry deposition file. Set to Y to turn on; comment out or set to N to turn off.

• CTM_SFC_HONO [default: Y]

Calculate surface HONO interactions. If CTM_ILDEPV is set to N this variable is ignored. Comment out or set to Y to turn on; set to N to turn off.

• CTM_GRAV_SETL [default Y]

Activate gravitational sedimentation for aerosols. Comment out or set to Y to turn on; set to N to turn off.

• CTM BIOGEMIS [default: Y]

Calculate biogenic emissions. Comment out or set to Y to turn on;

set to N to turn off. If this option is activated, several additional variables must be set (see the In-line biogenic emissions configuration settings)

• CTM_PT3DEMIS [default: N]

Calculate plume rise for elevated point sources. Set to Y to turn on; comment out or set N to turn off. If this option is activated several additional variables must be set (see the Inline emissions configuration settings) following variables must be set.

Process analysis options

• CTM_PROCAN [default: N]

Activate process analysis in the CCTM. Set this to Y and use \$CMAQ_DATA/pacp/pacp.inp to configure the integrated process rate and integrated reaction rate settings for the CCTM. Additional process analysis output files will be created when this setting is activated.

• PA_BCOL_ECOL [default: None]

Modeling grid domain column range for the process analysis calculations. Set to the two digits representing the beginning and ending column number bounding the process analysis domain.

• PA_BROW_EROW [default: None]

Modeling grid domain row range for the process analysis calculations. Set to the two digits representing the beginning and ending row number bounding the process analysis domain.

• PA_BLEV_ELEV [default: None]

Modeling grid domain layer range for the process analysis calculations. Set to the two digits representing the bottom and top layer numbers bounding the process analysis domain.

I/O Controls

- IOAPI LOG WRITE [default: Y]
 - Set to T to turn on excess WRITE3 logging by the I/O API.
- FL_ERR_STOP [default: N]

Set to T to configure the program to exit if inconsistent headers are found in the input files.

• PROMPTFLAG [default: N]

Turn on I/O-API PROMPTFILE interactive mode. Set to T to require interactive prompts for different I/O API operations.

• IOAPI_OFFSET_64 [default: N]

I/O API setting for large time step records. If your output time step is going to produce data that are >2GB per time step, then this needs to be set to YES.

Aerosol Diagnostics Controls

- CTM_AVISDIAG [default: N]
 Output visibility diagnostics file. Set to Y to turn on; comment out or set to N to turn off.
- CTM_PMDIAG [default: N]
 Output aerosol diagnostics and properties file. Set to Y to turn on; comment out or set to N to turn off.
- CTM_APMDIAG [default: N]
 Output hourly average aerosol diagnostics and properties file. Set to Y to turn on; comment out or set to N to turn off.
- APMDIAG_BLEV_ELEV [default: None] Modeling grid domain layer range for the hourly average aerosol diagnostics and properties file. Set to the two digits representing the bottom and top layer numbers to bound the output domain.

Diagnostic Output Flags

- CTM_CKSUM [default: Y]
 Write science processes summaries to the standard output. Impacts run speed and log file output size. Comment out or set to Y to turn on; set to N to turn off.
- CLD_DIAG [default: N]
 Output an hourly wet deposition diagnostic file (CTM_WET_DEP_2) that includes convective wet deposition estimates. Set to Y to turn on; comment out or set to N to turn off.
- CTM_PHOTDIAG [default: N]
 Output in-line photolysis rates and associated data to diagnostic netCDF output files. The file CTM_RJ_1 contains gridded photolysis rates for O3 (JO3O1D) and NO2 (JNO2) that include both clear-sky and cloud effects, total downward irradiance at the surface (ETOT_SFC_W), aerosol optical depth (TAU_AERO_W), total optical depth (TAU_TOT_W), optical depth of ozone above the model domain (TAUO3_TOP_W), Rayleigh optical depth above the model domain (TAU_RAY_W), and surface albedo (ALBEDO_W). The file CTM_RJ_2 contains gridded photolysis rates for all other photolysis reactions in the selected chemical mechanism. Set to Y to turn on; comment out or set to N to turn off.
- CTM_SSEMDIAG [default: N]
 Output the calculated sea salt emissions to a diagnostic netCDF output file (CTM_SSEMIS_1). Set to Y to turn on; comment out or set to N to turn off.
- CTM_DUSTEM_DIAG [default: N]
 Output the in-line dust emissions to a diagnostic netCDF output file (CTM_DUST_EMIS_1). The diagnostic file includes not only the total dust emissions, but also dust emissions by land use category and dust model parameters, such as gridded erodible land use fractions. Set to Y

to turn on; comment out or set to N to turn off.

• CTM_DEPV_FILE [default: N]

Output an hourly diagnostic file (CTM_DEPV_DIAG) for the in-line deposition velocity calculations. If CTM_ILDEPV is set to N this variable is ignored. Set to Y to turn on; comment out or set to N to turn off.

• VDIFF_DIAG_FILE [default: N]

Output a diffusion and aero gravitational sedimentation diagnostic file. Set to Y to turn on; comment out or set to N to turn off.

• CTM_AOD [default N]

Output an aerosol optical depth (AOD) calculation diagnostics file. Set to Y to turn on; comment out or set to N to turn off.

• DISP [default: keep]

Controls the maintenance of existing log files.

- delete delete output log if it already exists
- keep abort simulation if output log exists

Inline emissions configuration

• NPTGRPS [default: 1]

The number of input point-source elevated emission sector file groups. A maximum of 9 sectors is allowed.

• STK GRPS

Directory path and file name of the stack groups file for sector ##, where ##=01,02,...,NPTGRPS. Each ## refers to one of the plume rise point-source sectors.

• STK_EMIS_##

Directory path and file name of the point emissions file for sector ##, where ##=01,02,...,NPTGRPS. Each ## refers to the one of the plume rise point-source sectors.

• LAYP STDATE [HHMMSS]

Start date for calculating elevated-point-source emissions.

• LAYP_STTIME [HHMMSS]

Start time for calculating elevated-point-source emissions.

• LAYP NSTEPS [HHHHHHH]

Number of time steps for calculating elevated-point-source emissions.

• CTM_EMLAYS [default: max no of model layers]

Number of emissions layers for calculating elevated-point-source emissions. If not set (commented out), the maximum number of model layers will be used.

• PT3DDIAG [default: N]

Output the in-line 3-D point-source emissions to a diagnostic netCDF output file (CTM_PT3D_DIAG). Set to Y to turn on; comment out or set to N to turn off.

• PT3DFRAC [default: N]

Output the in-line 3-D point-source layer fractions to a diagnostic netCDF output file (PLAY_SRCID_NAME). Set to Y to turn on; comment out or set to N to turn off.

• REP_LAYER_MIN [default: -1]

Minimum layer number for reporting plume rise values to the plume rise diagnostics file. Set to -1 or comment out to report all layers.

Lightning NOx configuration

CMAQ Lightning NOx Module Documentation

• LTNGNO [default:InLine]

Setting to define whether the lightning emissions calculation will be in-line or off-line. This variable can be set to a gridded netCDF file of lightning NO emissions to use emissions calculated with a preprocessor outside of CCTM. Setting this variable to "inline" activates the in-line emissions calculation in CCTM and requires the LTNGPARMS variable (see below) to define the configuration of the in-line emissions.

• USE_NLDN [default: Y]

Use hourly NLDN strikes file to compute inline lighing NO emissions. Activating this setting requires the NLDN_STRIKES input file. Comment out or set to Y to turn on; set to N to turn off.

• LTNGPARAMS [default: Y]

Use the lightning parameters configuration file to compute inline lightning NO emissions. When the variable LTNGNO is set to "inline", this setting is used to define how the in-line emissions will be calculated. Commenting out this variable or setting it to Y will compute lightning NO from input hourly flash count observations. Setting this variable to N will compute lightning NO strictly from convective precipitation rates in the input meteorology data. When this variable is set to Y, an additional input lightning parameter file (LTNGPARMS_FILE) will need to be available that includes intercloud to cloud-to-ground flash ratios, scaling factors for calculating flashes using the convective precipitation rate, and the moles of NO per flash.

• NLDN STRIKES [default: None]

Hourly NLDN lightning strike netCDF FILE. Required when LTNGNO is set to Inline and USE_NLDN is set to Y; otherwise ignore this setting.

• LOG_START [default: 0.9]

Convective precipitation (RC) value to transition the lightning NO emissions calculation from linear to log linear.

• LTNGDIAG [default: N]

Output a lightning NO emissions diagnostics file. Set to Y to turn on; comment out or set to N to turn off.

- LTNGPARMS_FILE [default: None]
 Lightning parameters output netCDF file; ignore if LTNGPARAMS = N
- LTNGOUT [default: None]
 Lightning diagnostics output netCDF file; ignore if LTNGDIAG = N

In-line biogenic emissions configuration

• GSPRO [default: None]

Directory path and file name for input ASCII speciation profiles.

• B3GRD [default: None]

Grid-normalized biogenic emissions input netCDF file.

• BIOG_SPRO [default: None]

Profile ID for speciating biogenic VOCs. This profile ID must be present in the GSPRO file.

• BIOSW_YN [default: Y]

Use the frost dates switch file to determine whether to use winter or summer biogenic emissions. Comment out or set to Y to turn on; set to N to turn off.

• BIOSEASON [default: None]

File name for the frost dates switch input netCDF file.

• SUMMER_YN [default: Y]

Toggle for summer season normalized biogenic emissions. This variable is ignored if BIOSW_YN is set to Y. Comment out or set to Y to select summer season biogenic emissions factors; set to N to turn off.

• PX VERSION [default: Y]

Setting to indicate whether the Pleim-Xiu land-surface model was used for the input meteorology. If this setting is set to Y the input meteorology data must include soil moisture (SOILM), soil temperature (SOILT), and soil type (ISLTYP) variables for use in the calculation of soil NO emissions.

INITIAL_RUN [default: N]

Set to Y if this is the first time that biogenic NO soil emissions will be calculated. If there is a previously created file, set to N.

• SOILINP [default: None]

Directory path and file name of biogenic NO soil emissions file. If INI-TIAL_RUN is set to N or F, the soil NO emissions file from the previous day's simulation will be a required input file.

• B3GTS_DIAG [default: N]

Write the inline biogenic emissions (mass units) to a diagnostic netCDF output file (B3GTS_S). Set to Y to turn on; comment out or set to N to turn off.

• B3GTS_S

Diagnostic output netCDF file of biogenic emissions. This variable is ignored if B3GTS DIAG is set to N.

Windblown dust emissions configuration

CMAQ Windblown Dust Module Documentation

• DUST_LU_1

Input BELD "A" landuse netCDF file gridded to the modeling domain. Used if CTM WBDUST BELD is set to BELD3.

• DUST_LU_2

Input BELD "TOT" landuse netCDF file gridded to the modeling domain. Used if CTM_WBDUST_BELD is set to BELD3.

• MODIS_FPAR

Input MODIS FPAR time-varying vegetation netCDF file gridded to the modeling domain.

• BELD4 LU

Input BELD4 landuse netCDF file gridded to the modeling domain. Used if CTM WBDUST BELD is set to BELD4.

• CROPMAPO1

Input beginning planting dates netCDF file gridded to the modeling domain.

CROPMAP04

Input end planting dates netCDF file gridded to the modeling domain.

• CROPMAPO8

Input end harvesting dates netCDF file gridded to the modeling domain.

Compiling and Running

Compile CCTM

Chapter 5 provides an overview of how to install and compile the CMAQ preprocessor programs for a test simulation. Follow those steps (summarized below) to compile new versions of CCTM.

- 1. Compile Bldmake, the CMAQ source code and compilation management program. This needs to be done only once—the first time CMAQ is installed.
- Configure the CCTM build script to use the config.cmaq script, which points to the available I/O API and netCDF libraries.
- Configure the CCTM build script for your application by setting the compilation configuration variables described above.
- Invoke the build script to create an executable:

```
cd $CMAQ_HOME/CCTM/scripts
./bldit.cctm |& tee build.cctm.log
```

Run CCTM

Set the run script settings according to the execution configuration variables described above. Run CCTM using the following command:

cd \$CMAQ_HOME/CCTM/scripts
./run.cctm |& tee run.cctm.log

CHEMMECH and CSV2NML

Description

The program CHEMMECH generates mechanism source code files for all chemical mechanism-dependent CMAQ programs. Using an ASCII mechanism definition file as input, the Fortran program CHEMMECH creates all of the Fortran files that define the gas-phase chemical mechanisms for the CMAQ programs. The C-Shell script CSV2NML converts a comma-delimited text file that defines the processes (e.g., input as emissions, input through boundary conditions, transport, deposition) impacting the concentrations of each model species to a NAMELIST file for input to the CMAQ programs. In combination the Fortran source and NAMELIST files define chemical mechanisms in the CMAQ programs.

Implementing new mechanisms created by CHEMMECH and CSV2NML in the CMAQ programs is a two-step process. CHEMMECH generates the mechanism RXNS source files that must be used in the compilation of CMAQ source code into an executable. CSV2NML generates species NAMELIST files that are input to the CMAQ programs during execution. Care must be taken to ensure that the RXNS and NAMELIST files are consistent with each other in order to correctly update or implement new mechanisms in CMAQ.

CHEMMECH reads in a mechanism definition (mech.def) text file that lists the stoichiometry and kinetics of a photochemical reaction mechanism. The program converts the mech.def file to two RXNS files, RXNS_DATA_MODULE.F90 and RXNS_FUNC_MODULE.F90 that get compiled with the CMAQ source code into a new executable. The source files created by CHEMMECH must be manually moved to the correct directory location in the CMAQ source code directories to be available during compilation of the CMAQ programs. The mechanism files for CMAQ are found in \$CMAQ_HOME/CCTM/src/MECHS/\$Mechanism, where \$Mechanism is the unique ID of a chemical mechanism (e.g., cb05e51_aq6_aq).

CSV2NML reads in a series of CSV files that define the processes that impact the concentrations of all of the CMAQ species. The CSV files are converted to NAMELIST files that are invoked at execution of the various CMAQ programs. Environment variables in the run scripts for ICON, BCON, and CCTM must be set to point to the NAMELIST files for a particular mechanism.

See Chapter 9 for details on how to update existing mechanisms or create new mechanisms in CMAQ.

Files, configuration, and environment variables

Figure 7-5 shows the input and output files and configuration options for CHEM-MECH and CSV2NML. The full set of mechanism files required by the CMAQ programs is generated in two steps. In the first step, the program CHEMMECH is run with the mechanism definition file, mech.def, provided as input. The resulting RXNS files are then input to the CMAQ build scripts to compile CMAQ with a new chemical mechanism configuration. CSV2NML is used to convert the species definition files from CSV format to NAMELIST files. The NAMELIST files are used as inputs to the CMAQ programs ICON, BCON, or CCTM to define the processes that will impact each model species. Three NAMELIST files define the processes for gas-phase species (GC.nml), aerosol species (AE.nml), and nonreactive species (NR.nml).




Figure 7-5. CHEMMECH and CSV2NML input and output files (Update this Image)

To implement a new mechanism in CMAQ, start with a mechanism definition (mech.def) file and CSV species files from an existing mechanism in the model. Edit the mech.def file to include the new reactions, species, and reaction rates and provide this new mech.def file as input to CHEMMECH. Edit the CSV species files to include the new species and provide these files as input to CSV2NML. Detailed examples of updating an existing mechanism and adding a new mechanism to CMAQ are provided in Chapter 9. Neither CHEMMECH nor CSV2NML requires horizontal grid, vertical layer, or temporal settings.

CHEMMECH input files

Table 7-9. CHEMMECH input files

NameFormaDescription

File

NameFormaDescription

$\operatorname{MCFLASCIICMAQ}$

(mech.def) mech-

.

nism

1115111

 def -

inition

file;

pho-

to-

chem-

ical

mech-

a-

nism

list-

ing

 $\quad \text{with} \quad$

both

mech-

a-

nis-

 tic

and

ki-

netic

in-

for-

ma-

tion

about

all

re-

ac-

 ${\rm tions}$

that

com-

pose

a

chem-

ical

77 mechanism

 ${\bf File} \\ {\bf Name Formal Description}$

CHEMMECH output files Table 7-10. CHEMMECH output files

File Name Format	Description
RXCM.EXT ASCII RXDT.EXT ASCII	Mechanism common INCLUDE file; lists all of the chemical mechanism variables and parameters Mechanism data INCLUDE file; chemical mechanism definition formatted as DATA blocks to be read in
SPCS.EXT ASCII	as CMAQ source code Species INCLUDE file; not used

The location of the CHEMMECH output files is set in the run script by the variable Opath. To compile a version of the CMAQ programs that use the INCLUDE files created by CHEMMECH, these output INCLUDE files need to be moved to a new directory under the \$CMAQ_HOME/models/mechs/release directory. Point the CMAQ build scripts to this new directory through the "Mechanism" variable.

CSV2NML input files

Detailed descriptions of the formats of the files shown in Table 7-11 are provided in Chapter 8.

File

Table 7-11. CSV2NML input files

${\bf Name Formal Description}$ GC.csvASCII Gasphase species process paramters. This file defines the source and sink processes that impact the concentrations of every gasphase species inthe chem-

ical

mechanism.

File

NameFormaDescription

 $AE.csvASCII\,Aerosol-$

phase

species

pro-

cess

pa-

ram-

e-

 $\qquad \text{ters.}$

This

file

de-

fines

the

 $\quad \text{source} \quad$

and

 sink

pro-

cesses

that

im-

pact

the con-

cen-

tra-

tions

of

every

aerosol-

phase

species

in

the

chem-

ical

mechanism.

```
NameFormaDescription
NR.csv\!ASCII\,N on reactive
             species
             pro-
             cess
             pa-
             ram-
             e-
             ters.
             This
             file
             de-
             fines
             the
             source
             and
             sink
             pro-
             cesses
             that
             im-
             pact
             the
             con-
             cen-
             tra-
             tions
             of
             ev-
             ery
             non-
             re-
             ac-
             tive
             species
             in
             the
             chem-
             ical
```

CSV2NML output files

mechanism.

Table 7-12. CSV2NML output files

${\bf Name Formal Description}$

GC.nmASCII Gas-

phase

species

pro-

cess

pa-

ram-

e-

ters.

This

file

de-

 ${\rm fines}$

the

source and

sink

pro-

cesses

that

im-

pact

the

con-

cen-

tra-

tions

of

ev-

ery gas-

phase

species

in

the

chem-

ical

 ${\rm mechanism}$

File

NameFormaDescription

 $AE.nm {\tt A}SCII\,Aerosol-$

phase

species

pro-

cess

pa-

ram-

e-

 $\qquad \text{ters.}$

This

file

defines

the

source

and

 sink pro-

cesses

that

im-

pact the

con-

cen-

tra-

tions

of

ev- ery

aerosol-

phase

species

in

the

chem-

ical

 ${\rm mechanism}$

```
{\bf Name Formal Description}
NR.nm \color{red} ASCII\, Nonreactive
               species
               pro-
               cess
               pa-
               ram-
               e-
               ters.
               This
               file
               de-
               fines
               the
               source
               and
               sink
               pro-
               cesses
               that
               im-
               pact
               the
               con-
               cen-
               {\rm tra}\text{-}
               tions
               of
               ev-
               ery
               non-
               re-
               ac-
               tive
               species
               in
               the
               {\it chem-}
               ical
               mechanism
```

Execution Configuration Variables

The environment variables listed here are invoked at run time and are set in the CHEMMECH run script. The default run script is called MP.saprc99.csh.

- Xpath [default: \$BASE]
 Executable directory path

 EXEC [default: CHEMMECH]
- EXEC [default: CHEMMECH]

Executable name

- Mechanism [default: None] Name of the output mechanism.
- Opath [default: ../exts]
 Output file directory path
- Mpath [default: ../exts]
 Mechanism definition file directory path
- MECHDEF [default: None]

 Mechanism definition file name
- MAPPING_ROUTINE [default: None]
- SPCSDATX [default: \$Opath/SPECIES.ext] Name of output species INCLUDE file
- RXNS_DATA_MODULE [default: \$Opath/RXNS_DATA_MODULE.F90] Name of output mechanism data Fortran file
- RXNS_FUNC_MODULE [default: \$Opath/RXNS_FUNC_MODULE.F90] Name of output mechanism common Fortran file
- EQNS_KPP_FILE [default: None]
- SPCS_KPP_FILE [default: None]

Compiling and Running

Compile Chemmech

To compile CHEMMECH, run the build script:

```
cd $CMAQ_HOME/UTIL/chemmech/scripts
./bldit.chemmech |& tee build.chemmech.log
```

To port CHEMMECH to different compilers, change the compiler names, locations, and flags in the config.cmaq script.

Run Chemmech

Set the run script settings according to the execution configuration variables described above. Run CHEMMECH using the following command:

```
cd $CMAQ_HOME/UTIL/chemmech/scripts
./run.chemmech |& tee run.chemmech.log
```

CSV2NML usage

The CSV2NML script is configured to read in a CSV file from the command line and output a NAMELIST file that can be used with CMAQ. An example of how to use CSV2NML to create a gas-phase species NAMELIST file is include below:

```
cd $CMAQ_HOME/UTIL/nml/scripts
./csv2nml GC.CSV
There is also a script to convert an existing namelist file to a CSV
cd $CMAQ_HOME/UTIL/nml/scripts
./nml2csv GC.nml
```

CREATE_EBI

Description

The program CREATE_EBI generates Fortran source code for the mechanism-dependent Euler Backward Iterative (EBI) solver. This utility program allows users to create new EBI solver code when mechanisms are modified or added to CMAQ. The source code generated by CREATE_EBI should be used to build versions of the CCTM that use the new or modified chemistry mechanisms.

See Chapter 9) for details on how to update existing mechanisms or create new mechanisms in CMAQ.

Files, configuration, and environment variables

To implement a new mechanism in CMAQ, start with a mechanism definition (mech.def) file and CSV species files from an existing mechanism in the model. Edit the mech.def file to include the new reactions, species, and reaction rates and provide this new mech.def file as input to the program CHEMMECH. CHEMMECH will output a RXNS_DATA_MODULE.F90 file, which is used as input to CREATE_EBI.

CREATE_EBI input files
Table 7-13. CREATE_EBI input files

 \mathbf{File} NameFormaDescription ${\rm RXNS}\underline{\textbf{ADCILLCMSRQ}}.{\rm F90}$ mechanismreaction listing inFor- tran 90 format; output ${\rm from}$ the pro- gram CHEMMECH

$\label{eq:created} \textbf{CREATE_EBI output files}$

Table 7-14. CREATE_EBI output files

File Name	Format	Description
*.F	ASCII	Fortran 90
	F90	source code
		for the
		CCTM EBI
		chemistry
		solver

File Name	Format	Description
RXNS_DA	T A SØIOD	UNLECTE 200ism
	F90	data
		Fortran
		source file;
		chemical
		mechanism
		definition
		formatted
		as DATA
		blocks to
		be read in
		as CMAQ
		source code

The location of the CREATE_EBI output files is set in the run script by the variable OUTDIR. To compile a version of the CMAQ programs that use the F90 files created by CREATE_EBI, these output F90 files need to be moved to a new directory under the \$CMAQ_HOME/CCTM/src/gas directory. Point the CMAQ build scripts to this new directory through the "Mechanism" variable.

Compilation Configuration Variables

- GC_NAME [default: None]
 - Name identifier for gas phase mechanisms
 - CB6R3
 - Carbon Bond version 6 revision 3
 - CB05E51
 - Carbon Bond 05 with modifications for CMAQ version 5.1
 - CB05MP51
 - Carbon Bond 05 multipollutant mechanism for CMAQ version 5.1
 - CB05TUCL
 - Carbon Bond 05 with modified toluene and chlorine chemistry
 - CB05TUMP
 - Carbon Bond 05 with modified toluene and multipollutant chemistry
 - SAPRCO7TB
 - SAPRC07 with modified toluene chemistry
 - SAPRCOTTC
 - SAPRC07 with modified toluene chemistry
 - SAPRCOTTIC
 - SAPRC07 with modified toluene chemistry
 - RACM2
 - RACM2 chemistry

• AE_NAME [default: None]

Name identifier for particle phase mechanisms

- AE ϵ
 - CMAQ aerosols version 6
- AE6I

CMAQ aerosols version 6i

• AQ_NAME [default: AQ]

Name identifier for the CMAQ aqueous phase mechanism

Execution Configuration Variables

The environment variables listed here are invoked at run time and are set in the CREATE_EBI run script.

• EXEC [default: CHEMMECH]

Executable name

• GC_NAME [default: None]

Name identifier for gas phase mechanisms

- CB6R3
 - Carbon Bond version 6 revision 3
- CB05E51
- Carbon Bond 05 with modifications for CMAQ version 5.1
- CB05MP51

Carbon Bond 05 multipollutant mechanism for CMAQ version 5.1

- CB05TUCL
 - Carbon Bond 05 with modified toluene and chlorine chemistry
- CB05TUMP

Carbon Bond 05 with modified toluene and multipollutant chemistry

- SAPRCO7TB
 - SAPRC07 with modified toluene chemistry
- SAPRCO7TC
 - SAPRC07 with modified toluene chemistry
- SAPRCOTTIC
 - SAPRC07 with modified toluene chemistry
- RACM2

RACM2 chemistry

• AE_NAME [default: None]

Name identifier for particle phase mechanisms

- AE6
- CMAQ aerosols version 6
- AE6I

CMAQ aerosols version 6i

• AQ_NAME [default: AQ]

Name identifier for the CMAQ aqueous phase mechanism

• OUTDIR [default: ../output]

Output file directory path

- COPYRT_FLAG
- CVS HDR FLAG
- PAR_NEG_FLAG [default: F]

Include PAR negative stoichiometry.

- T for Carbon Bond mechanisms
- F for SAPRC and RACM mechanisms
- DEGRADE_SUBS
- NO2EX_CYCLE
- MECH NO

Mechanism name for nitric oxide

• MECH NO2

Mechanism name for nitrogen dioxide

• MECH NO2EX

SAPRC, RACM Mechanism name for excited nitrogen dioxide; not in Carbon Bond

• MECH_03

Mechanism name for ozone

• MECH_O3P

Mechanism name for ground state oxygen atom

- O for Carbon Bond mechanisms
- O3P for SAPRC and RACM mechanisms
- MECHO_O1D

Mechanism name for excited state oxygen atom

• MECH_OH

Mechanism name for hydroxyl radical

• MECH_HO2

Mechanism name for hydroperoxy radical

• MECH_HONO

Mechanism name for nitrous acid

• MECH_HNO4

Mechanism name for peroxynitric acid

- PNA for Carbon Bond mechanisms
- HNO4 for SAPRC and RACM mechanisms
- MECH_PAN

Mechanism name for peroxy acetyl nitrate

• MECH_C203

Mechanism name for peroxy acetyl radical

- C203 for Carbon Bond mechanisms
- MECO3 for SAPRC and RACM mechanisms
- MECHO_NO3

Mechanism name for nitrate radical

MECH_N205

Mechanism name for dinitrogen pentoxide

Compiling and Running

Compile CREATE EBI

To compile CREATE EBI, invoke the build file at the command line:

```
cd $CMAQ_HOME/UTIL/create_ebi/scripts
./bldit.create_ebi |& tee build.create_ebi.log
```

To port CREATE_EBI to different compilers, change the COMPILER variable in the bldit script.

Run CREATE_EBI

Set the run script settings according to the execution configuration variables described above. Run CREATE EBI using the following command.

```
cd $CMAQ_HOME/UTIL/create_ebi/scripts
./run.create_ebi |& tee run.create_ebi.log
```

ICON

Description

The program ICON prepares chemical initial conditions (ICs) for CCTM from either ASCII vertical profiles or from an existing CCTM output concentration (CONC) file. ICON creates an output file with a single time step that represents the chemical conditions in each grid cell at the beginning of a CCTM simulation. The ICs can be either spatially uniform or variable across the model grid, depending on the source of the initial chemical concentration data. If deriving ICs from the ASCII vertical profiles, ICON can create only spatially uniform ICs within each model layer; it can create different ICs across model layers. From CONC files, ICON can extract spatially varying ICs, either on the same grid cell resolution, as a windowed modeling domain, or for a finer-resolution model grid (as for a nested simulation).

There are two distinct modes of operation for ICON, depending on the nature of the input data. When creating ICON executables, the user must specify whether the input data will be ASCII vertical profiles or a CONC file by selecting either "profile" or "m3conc", respectively, for the setting of the *ModType* variable. This variable determines the input module to use when creating an ICON executable.

CCTM can also be forced with initial conditions downscaled from global chemistry models (GCMs), such as GEOS-Chem and MOZART. ICON does not support the processing of data from GCMs. ICs derived from GCMs must be

calculated with custom codes or scripts that are not available in the CMAQ distribution package. The CAMx developers (Ramboll Environ) have codes available for extracting regional model ICs from both GEOS-Chem and MOZART. Visit the Support Software section of www.CAMx.com to download these utilities

Files, configuration, and environment variables

Figure 7-6 shows the input and output files and configuration options for ICON. A distinction is made between the options that are invoked at compilation versus those invoked at execution of the program. When compiling ICON, the user specifies a chemical mechanism to configure the gas-phase chemistry and aerosol mechanism used to create the chemical ICs. Setting the *ModMech* and *Mechanism* variables in the ICON compile script configures the program to use a specific set of mechanism namelist files to build an executable. Setting the *ModType* variable in the ICON compile script configures the program to input either a text file of static concentrations or a binary netCDF file of time-dependent concentrations for estimating ICs for CCTM. Separate ICON executables must be prepared for different mechanism and input file configurations.




Figure 7-6. ICON input and output files

When ICON is run, it converts a data file of chemical ambient concentrations to ICs on a predefined model grid. Through the specification of the *ModType* variable in the ICON run script, ICON will input either an ASCII vertical profile file (IC_PROFILE) or an existing CCTM concentration file (CTM_CONC_1); the choice depends on how the user compiled the model. The IC input file provided by the user must have chemical speciation that is consistent with the mechanism configuration of the ICON executable. For example, if ICON was compiled to create ICs using the CB05 mechanism, the input IC profile data must be

in terms of the CB05 mechanism. CMAQ is distributed with ASCII vertical profiles representing clean continental ICs for North America for the following chemical mechanisms: cb05_ae6_aq, saprc07tb_ae6_aq, racm2_aq6_aq, and saprc99_ae6_aq. It is the user's responsibility to generate IC inputs for other mechanism configurations.

The horizontal grid and vertical layer structures for ICON are defined at execution through the input of a grid description (GRIDDESC) file and a meteorology cross-point 3-D (MET_CRO_3D) file, respectively. ICON interpolates between the input vertical layer structure and output layer structure if they are different.

ICON input files

Table 7-15. ICON input files

File

${\bf Name Formal Description}$

IC_PR**ACMCILIE**Vertical

 ${\it chem-}$

ical

pro-

files

from

which

to

de-

rive

. .

 $_{\rm tial}^{\rm ini-}$

con-

di-

tions;

this

file

is

cre-

ated

by

the

user;

used only

when

. 1

the

IC

en-

vi-

ronment

vari-

able

is

 set

to "profile"

NameFormaDescription

CTM_**GRIDIONEID**3e

and

lo-

ca-

tion

of

the

 CMAQ

con-

cen-

tra-

tion

file

from which

to

de-

rive

ini-

tial

con-

di-

tions;

this

file

is

out-

put

 ${\rm from}$

CCTM;

used

only

when

the

BC

en-

vi-

ronment

vari-

vari-

 $\quad \text{able}\quad$

 $_{\rm set}^{\rm is}$

to

"m3conc"

File

NameFormaDescription

MET_**GRO**D**ND**3CRS

and

lo-

ca-

tion

of

the

coarse-

grid

MET_CRO_3D

file

that

is

re-

quired

for

cre-

at-

ing

the

ver-

ti-

 cal

grid

structure

if

this

struc-

ture changes

be-

tween

nested

sim-

ula-

tions;

 $\quad \text{this} \quad$

file

is

out-

put

by

MCIP

File

NameFormaDescription

MET_**GRO**D**ND**3**¢**FIN

and

lo-

ca-

tion

of

the fine

 grid

MET_CRO_3D

file

that

is

re-

quired

if

the

ver-

ti-

 cal

grid

struc-

 ${\rm ture}$

changes

be-

tween

nested

sim-

ulations;

this

file

is

out-

put

by MCIP

NameFormaDescription

GRIDD**AISSCU**I Horizontal

 grid

de-

scrip-

tion

file

 $\quad \text{for} \quad$

defin-

ing

the

model

grid;

this

file

is

out-

put

by

MCIP

or

can

be

cre-

 ${\rm ated}$

by

the user

NameFormaDescription

LAYERGREDDED3

cross-

point

me-

teo-

rol-

ogy

file

for

defin-

ing

the

ver-

ti-

 cal

 ${\rm layer}$

 struc -

ture

of

the

model

grid;

this

file

is

output

by

MCIP

File NameFormaDescription

```
gc\_maAsCIIhNamelist
              file
              for
              defin-
              ing
              the
              gas-
              phase
              species
              that
              are
              in-
              put
              to
              the
              model
              through
              the
              boundary
ae\_ma \textbf{ASCIIhN} amelist
              file
              for
              {\rm defin}\text{-}
              ing
              the
              aerosol
              species
              that
              are
              in-
              put
              to
              the
              model
              through
              the
```

boundary

```
NameFormaDescription
nr\_maArSCIIhNamelist
              file
              for
              defin-
              ing
              the
              non-
              re-
              ac-
              tive
              species
              that
              are
              in-
              put
              to
              the
              model
              through
              the
              boundary
tr_matA:SCHInNamelist
              file
              for
              {\rm defin}\text{-}
              \operatorname{ing}
              the
              tracer
              species
              that
              are
              in-
              put
              to
              the
              model
              through
              the
```

File

ICON output files

boundary

Table 7-16. ICON output files

File		
${\bf Name Formal Description}$		
INIT_ GRDNEDS ame		
	and	
	lo-	
	ca-	
	tion	
	of	
	the	
	grid-	
	ded	
	ini-	
	tial	
	con-	
	di-	
	tions	
	data	
	out-	
	put	
	on	
	the	
	model	
	grid	
	de-	
	fined	
	by	
	GRID_NAME	

The default location of the ICON output files is the \$CMAQ_DATA/icon directory, controlled by the OUTDIR variable in the run script. The default naming convention for all ICON output files uses the APPL and GRID_NAME environment variables in the file name. For initial conditions created from existing CCTM CONC files, the Julian date is also used in the file name through the DATE environment variable. All of the file-naming variables for ICON outputs are set in the run script.

Compilation Configuration Variables

The configuration options listed here are set during compilation of the ICON executable. When these options are invoked they create a binary executable that is fixed to the specified configuration. To change these options you must recompile ICON and create a new executable.

• CopySrc

Uncomment to copy the source code into a working build (BLD) directory. If commented, only the compiled object and executable files will be placed in the BLD directory.

• MakeFileOnly

Uncomment to build a Makefile to compile the executable. Comment out to both create a Makefile and compile.

• ModType: [default: module profile]

Defines the format of the initial conditions input files to be used by ICON.

- m3conc: input a CCTM CONC file; used for nested simulations or windows of a parent domain
- profile: input an ASCII vertical profiles file
- tracer: use the tracer namelist file to create ICs of tagged tracer species

• Mechanism: [default: cb05e51_ae6_aq]

Specifies the gas-phase, aerosol, and aqueous-phase chemical mechanisms for which to create initial conditions. The choices for the *Mechanism* variable are the mechanism directory names under the \$CMAQ_HOME/CCTM/src/MECHS directory. Also see the Mechanism Definitions Table). Examples include:

- cb6r3_ae6_aq: CB6, revision 3 gas-phase mechanism, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05e51_ae6_aq: CB05 gas-phase mechanism with CMAQv5.1 updates, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tucl_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tump_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, mercury, and air toxics, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM, aqueous/cloud chemistry; this is the CMAQv5 multipollutant mechanism
- saprc07tb_ae6_aq: SAPRC-07 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
- racm2_ae6_aq: RACM2 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism

• Tracer [default trac0]

Specifies tracer species. Invoking inert tracer species in CMAQ requires defining the tracers using namelist files and compiling the CMAQ programs with these files. The setting for this module corresponds to the directory name in the \$CMAQ_HOME/CCTM/src/MECHS directory that contains the namelist files for the tracer configuration. The default setting is to not use any tracers.

- trac[n]

Execution Configuration Variables

The environment variables listed here are invoked during execution of the program and are set in the BCON run script.

- APPL [default: None]
 - ICON executable identifier. Must match APPL Variable setting in the ICON build script.
- CFG [default: None]
 Configuration identifier for the ICON simulation.
- MECH [default: None] CMAQ chemical mechanism. Must match Mechanism variable setting in
- the ICON build script.

 EXEC: [default: ICON_\${APPL}_\${EXECID}]

 Executable to use for the simulation. The variable CFG is set in the ICON run script. The variable EXECID is set in the config.cmaq configuration
- GRIDDESC: [default: \$CMAQ_HOME/scripts/GRIDDESC1] Grid description file for setting the horizontal grid definition.
- GRID_NAME: [default:CMAQ-BENCHMARK]

 Name of the grid definition contained in the GRIDDESC file that specifies the horizontal grid for the current application of the model.
- IOAPI_ISPH: [default: 20] I/O API setting for spheroid type. See I/O API documentation for setsphere for more information.
- IOAPI_OFFSET_64: [default: NO] I/O API setting for large time-step records. If your output time step is going to produce data that are >2GB per time step, then this needs to be set to YES.
- LAYER_FILE: [default: none]

 Name and location of a MET_CRO_3D file for specifying the vertical layer structure for the current application of the model.
- gc_matrix.nml: [default: none]
 Gas-phase species namelist file. This file is used to configure the gas-phase species that will be output by BCON.
- ae_matrix.nml: [default: none]
 Aerosol-phase species namelist file. This file is used to configure the aerosol-phase species that will be output by BCON
- nr_matrix.nml: [default: none] Nonreactive species namelist file. This file is used to configure the nonreactive species that will be output by BCON
- tr_matrix.nml: [default: none]

 Tracer species namelist file. This file is used to configure the tracer species that will be output by BCON

- OUTDIR: [default: \$CMAQ_HOME/data/bcon] Output data directory.
- IC:

Sets the input file type. The setting of this variable determines how the run script sets the input and output environment variables.

- profile: sets the output file name to include the tag "profile" in the name; uses the variable IC_PROFILE to point to an ASCII vertical profile file for input to ICON.
- m3conc: used for nested simulations; sets the output file name to include a start date in the name; uses the variable CTM_CONC_1 to point to a CCTM CONC file for input to ICON.
- DATE:

Sets the Julian date to use in naming the ICON output file for nested runs.

• SDATE: [default: \${DATE}]

Julian start date for extracting boundary conditions from a CCTM CONC file for a nested simulation. If SDATE is not set, it will be set automatically from the CTM CONC 1 file.

• STIME: [default: 000000]
Start time for extracting boundary conditions from a CCTM CONC file for a nested simulation. If STIME is not set, it will be set automatically from the CTM CONC 1 file.

Compiling and Running

Compile ICON

Chapter 5 provides an overview of how to install and compile the CMAQ preprocessor programs for a test simulation. Follow those steps (summarized below) to compile new versions of ICON.

- 1. Compile Bldmake, the CMAQ source code and compilation management program. This needs to be done only once—the first time CMAQ is installed.
- Configure the ICON use the config.cmaq script, which points to the available I/O API and netCDF libraries.
- Configure the ICON build script for your application by setting the compilation configuration variables described above.
- Invoke the build script to create an executable:

cd \$CMAQ_HOME/PREP/icon/scripts
./bldit.icon |& tee build.icon.log

Run ICON

Set the run script settings according to the execution configuration variables described above. Run ICON to produce initial conditions for the CCTM:

cd \$CMAQ_HOME/PREP/icon/scripts
./run.icon |& tee icon.log

INLINE_PHOT_PREPROC

Description

The program INLINE_PHOT_PREPROC generates absorption cross-section/quantum yield (CSQY) data files for the CCTM inline photolysis module. This utility program allows users to create new CSQY tables when reaction rate data are modified or added to CMAQ. The data tables generated by INLINE_PHOT_PREPROC should be used to create the photochemistry data tables needed for inline photolysis configurations of the CCTM.

See Chapter 9 for details on how to update existing mechanisms or create new mechanisms in CMAQ.

Files, configuration, and environment variables

To implement new CSQY data in CMAQ, start with individual CSQY data files for each photolysis reaction in an applicable photochemical mechanism. Add to or modify these data to create the CCTM inline CSQY data table.

INLINE_PHOT_PREPROC input files
Table 7-17. INLINE_PHOT_PREPROC input files

NameFormaDescription

RXNS_AB&TILACMAAQDULE.F90

mech-

a-

nism

re-

ac-

tion

list-

ing

in

For-

tran

90

for-

mat;

out-

put

 ${\rm from}$

the

pro-

gram

CHEMMECH

File NameFormaDescription CSQY ABOUTADin ROAWy of photolysis reactionspecific absorption cross section and quan- tum yield dataas a function of wavelengthWVBI**NSEILW**avelength ${\rm bins}$ for which to include CSQYdataFLUX ASCIESolar flux (pho- $\rm tons/s/bin)$ by $0.05 \mathrm{nm}$

wavelength bin

NameFormaDescription

```
WATERSCII Water
              re-
              frac-
              tive
              in-
              dices
              by
              wavelength \\
INSOLAUSCIE Optical
              prop-
              er-
              ties
              of
              soil
              aerosol
              material
{\rm DUST\,ASCII\,Optical}
              prop-
              er-
              ties
              of
              soil
              aerosol
              material
SOLUAISCII Optical
              prop-
              er-
              ties
              of
              wa-
              \operatorname{ter}
              sol-
              u-
              ble
              aerosol
```

material

 \mathbf{File} ${\bf Name Formal Description}$ ${\bf SOOTASCII\,Optical}$ proper- ${\rm ties}$ of ${\rm soot}$ (BC) aerosol materialSEASAISCII Optical properties of seasalt aerosol material

INLINE_PHOT_PREPROC output files Table 7-18. INLINE_PHOT_PREPROC output files

File Name	Format	Description
CSQY_DAT A SCII		Tabulated
		CSQY data
		as a
		function of
		tempera-
		ture and
		wavelength
		$_{ m bin}$
PHOT_OP	TASSII	Wavelength,
		Optical and
		Surface
		Albedo
		Parameters
		for CMAQ
		In-Line
		Photolysis
		calculation.

The location of the INLINE_PHOT_PREPROC output files is set in the run script by the variable OUTDIR. To compile a version of the CMAQ programs that use the files created by INLINE_PHO_PREPROC, copy the output files to a new directory under the \$CMAQ_HOME/CCTM/src/MECHS/\$Mechanism directory. Point the CMAQ build scripts to this new directory with the "Mechanism" variable.

Compilation Configuration Variables

- Mechanism: [default: cb05e51_ae6_aq]
 Specifies the gas-phase, aerosol, and aqueous-phase chemical mechanisms for which to create initial conditions. The choices for the Mechanism variable are the mechanism directory names under the \$CMAQ_HOME/CCTM/src/MECHS directory. Also see the Mechanism Definitions Table). Examples include:
 - cb6r3_ae6_aq: CB6, revision 3 gas-phase mechanism, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
 - cb05e51_ae6_aq: CB05 gas-phase mechanism with CMAQv5.1 updates, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
 - cb05tucl_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
 - cb05tump_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, mercury, and air toxics, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM, aqueous/cloud chemistry; this is the CMAQv5 multipollutant mechanism
 - saprc07tb_ae6_aq: SAPRC-07 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
 - racm2_ae6_aq: RACM2 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
- COMPILER

Compiler to use for building the program

- PGF90
- INTEL
- GFORT

Execution Configuration Variables

The environment variables listed here are invoked at run time and are set in the CREATE_EBI run script.

• Mechanism: [default: cb05e51_ae6_aq]

Specifies the gas-phase, aerosol, and aqueous-phase chemical mechanisms for which to create initial conditions. The choices for the *Mechanism* variable are the mechanism directory names under the \$CMAQ_HOME/CCTM/src/MECHS directory. Also see the Mechanism Definitions Table). Examples include:

- cb6r3_ae6_aq: CB6, revision 3 gas-phase mechanism, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05e51_ae6_aq: CB05 gas-phase mechanism with CMAQv5.1 updates, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tucl_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, sixth-generation
 CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tump_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, mercury, and air toxics, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM, aqueous/cloud chemistry; this is the CMAQv5 multipollutant mechanism
- saprc07tb_ae6_aq: SAPRC-07 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
- racm2_ae6_aq: RACM2 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
- USE_RXNS_MODULES [default: T] Compatibility flag for CMAQ. Set to "T" for CMAQ version 5.1 and higher; set to "F" for older versions of CMAQ.
- WVL_AE_REFRAC [default: T] Include spectral values of refractive indices for aerosol species. Only needed for CMAQv5.1 and higher; set to "F" for older versions of CMAQ.
- SPLIT_OUTPUT [default: T] Split optical and CSQY output data to separate files. Only needed for CMAQv5.1 and higher; set to "F" for older versions of CMAQ.

Compiling and Running

Compile CREATE_EBI

To compile CREATE EBI, invoke the build file at the command line:

cd \$CMAQ_HOME/UTIL/create_ebi/scripts
./bldit.create_ebi |& tee build.create_ebi.log`

To port CREATE_EBI to different compilers, change the COMPILER variable in the bldit script.

Run CREATE_EBI

Set the run script settings according to the execution configuration variables described above. Run CREATE_EBI using the following command:

```
cd $CMAQ_HOME/UTIL/create_ebi/scripts
./run.create_ebi |& tee run.create_ebi.log
```

JPROC

Description

The program JPROC calculates daily clear-sky photolysis rates from look-up tables of molecular absorption cross-section and quantum yield (CSQY) data, and climatologically derived ozone-column and optical depth data. The outputs from JPROC are ASCII look-up tables of daily clear-sky photolysis rates for photochemical reactions in a selected gas-phase photochemical mechanism at different altitudes, latitudes, and hours from noon. The photochemical mechanism from which these rates are derived is selected during compilation of JPROC. The altitudes (meters), latitudes (degrees), and hour angles (from noon) for which the rates are derived are hardwired in the JPROC source code.

CCTM includes an in-line photolysis option that calculates photolysis rates using predicted ozone and aerosols. JPROC is not needed if the in-line photolysis option is selected in CCTM (*ModPhot* set to inline). JPROC is required to produce daily photolysis rate look-up tables if CCTM is compiled with *ModPhot* set to table.

Files, configuration, and environment variables

Figure 7-7 shows the input and output files for JPROC. Some options are invoked at compilation, while others are invoked with execution of the program. When compiling JPROC, the user specifies a chemical mechanism to indicate the gas-phase chemistry for which to calculate photolysis rates. Setting the *Mechanism* variable in the JPROC compile script configures the program to use a specific set of mechanism INCLUDE files to build an executable. JPROC executables are hard-wired to a specific mechanism configuration.




Figure 7-7. JPROC input and output files

While JPROC does not require any technical configuration at execution, such as domain specifications, there are several required and optional input files that the user must provide to the program. For the selected photochemical mechanism, the user must provide a set of molecular absorption CSQY data files that are consistent with the photolysis reactions in the mechanism. CMAQ is distributed with a full set of CSQY files for the Carbon Bond, SAPRC, and RACM photochemical mechanism versions supported by the model. If new mechanisms are added to CMAQ, the user must produce the appropriate CSQY data files for the added mechanism. The user also has the option of using the default atmospheric profiles contained in the PROFILES input file or using Total Ozone Mapping Spectrometer (TOMS) data to replace the climatologically derived ozone column data in the PROFILES file.

JPROC input files

Table 7-19. JPROC input files

File Nam	neFormaDescription
ET	ASCII Extraterrestrial
	ra-
	dia-
	tion
	as a
	func-
	tion
	of
	wavelength

NameFormaDescription

PROFIA SISII Seasonal

ver-

ti-

 cal

pro-

 ${\rm files}$

of

ozone

con-

cen-

trations,

aerosol

at-

ten-

ua-

tion,

tem-

per-

a-

ture,

air

density

and

Dob-

son

values

NameFormaDescription

${\bf TOMSASCII\,Total}$

ozone

col-

umn

mea-

sure-

ments

 ${\rm from}$

the

То-

 tal

Ozone

Map-

ping

Spec-

trom-

eter

in-

stru-

ment

aboard

the

sun-

synchronous

po-

lar

or-

bit-

ing

Nimbus

satellite

NameFormaDescription

O2ABSASCII Absorption CSQYdatafor molecular охуgen as a function of wavelengthO3ABSASCII Absorption CSQYdatafor ozone $as\ a$ function of

wavelength

File		
${\bf Name Formal Description}$		
CSQY ASCII Directory		
(di-	path	
rec-	con-	
tory	tain-	
path)		
	ab-	
	sorp-	
	tion	
	CSQY	
	data	
	for	
	gas-	
	phase	
	pho-	
	tol-	
	ysis	
	re-	
	ac-	
	tions	
	as a	
	func-	
	tion	
	of	
	wavelength	

JPROC output files

Table 7-20. JPROC output files

File Name	Format	Description
JTABLE_\$Date	ASCII	Daily clear-sky photolysis rates file

The default location of the JPROC output files is the \$CMAQ_HOME/data/jproc directory, controlled by the OUTDIR variable in the run script. The default naming convention for all JPROC output files uses the Date environment variable in the file name, which is aliased to the STDATE environment variable in the run script.

Compilation Configuration Variables

The configuration options listed here are set during compilation of the JPROC

executable. When these options are invoked they create a binary executable that is fixed to the specified configuration. To change these options it is necessary to recompile JPROC and create a new executable.

• CopySrc

Uncomment to copy the source code into a working build (BLD) directory. If commented, only the compiled object and executable files will be placed in the BLD directory.

• MakefileOnly

Uncomment to build a Makefile to compile the executable. Comment out to create a Makefile and compile.

• Mechanism: [default: cb05e51_ae6_aq]

Specifies the gas-phase, aerosol, and aqueous-phase chemical mechanisms for which to create initial conditions. The choices for the *Mechanism* variable are the mechanism directory names under the \$CMAQ_HOME/CCTM/src/MECHS directory. Also see the Mechanism Definitions Table). Examples include:

- cb6r3_ae6_aq: CB6, revision 3 gas-phase mechanism, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05e51_ae6_aq: CB05 gas-phase mechanism with CMAQv5.1 updates, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tucl_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, sixth-generation CMAQ aerosol mechanism with sea salt and speciated PM Other, aqueous/cloud chemistry
- cb05tump_ae6_aq: CB05 gas-phase mechanism with active chlorine chemistry, updated toluene mechanism, mercury, and air toxics, sixthgeneration CMAQ aerosol mechanism with sea salt and speciated PM, aqueous/cloud chemistry; this is the CMAQv5 multipollutant mechanism
- saprc07tb_ae6_aq: SAPRC-07 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism
- racm2_ae6_aq: RACM2 gas-phase mechanism with toluene updates and sixth-generation CMAQ aerosol mechanism

• Tracer [default trac0]

Specifies tracer species. Invoking inert tracer species in CMAQ requires defining the tracers using namelist files and compiling the CMAQ programs with these files. The setting for this module corresponds to the directory name in the \$CMAQ_HOME/CCTM/src/MECHS directory that contains the namelist files for the tracer configuration. The default setting is to not use any tracers.

- trac[n]

Execution Configuration variables

The environment variables listed here are invoked during execution of the program and are set in the JPROC run script.

- APPL [default: None]
 JPROC executable identifier. Must match APPL Variable setting in the JRPOC build script.
- CFG [default: None]
 Configuration identifier for the JPROC simulation.
- MECH [default: None] CMAQ chemical mechanism. Must match Mechanism variable setting in the JPROC build script.
- EXEC: [default: JPROC_\${APPL}_\${EXECID}]

 Executable to use for the simulation. The variable CFG is set in the JPROC run script. The variable EXECID is set in the config.cmaq configuration file.
- STDATE
 Start Julian date (YYYYDDD) for computing clear sky photolysis rates.
- ENDATE
 End Julian date (YYYYDDD) for computing clear sky photolysis rates.

Compiling and Running

JPROC compilation

Chapter 5 provides an overview of how to install and compile the CMAQ programs for the tutorial simulation. Follow the steps outlined in Chapter 5 (summarized below) to compile new versions of JPROC:

- 1. Compile Bldmake, the CMAQ source code and compilation management program. This needs to be done only once—the first time CMAQ is installed.
- Cnfigure the JPROC build script to use the config.cmaq script, which points to the available I/O API and netCDF libraries.
- Configure the JPROC build script for your application by setting the compilation configuration variables described above.
- Invoke the build script to create an executable:

```
cd $CMAQ_HOME/PREP/jproc/scripts
./bldit.jproc |& tee build.jproc.log
```

Run JPROC

Set the run script settings according to the execution configuration variables described above. Run JPROC to produce offline clear-sky photolysis rates for the CCTM:

```
cd $CMAQ_HOME/PREP/jproc/scripts
./run.jproc |& tee run.jproc.log
```

MCIP

Description

The Meteorology-Chemistry Interface Processor (MCIP) processes meteorological model output from either MM5 or WRF-ARW model into I/O API-formatted files that are compatible with CMAQ and SMOKE. MCIP automatically determines whether an input file is generated by MM5 or WRF-ARW by trying to open the file as a netCDF file. If the file can be read as netCDF, MCIP assumes the input is a WRF-ARW dataset; otherwise, MM5 is assumed.

Many of the fields that are simulated by the meteorological model are not modified by MCIP for the emissions model and CCTM, and they are written to I/O API files. Fields that are required for the transformation to CMAQ's generalized coordinate system are calculated within MCIP. The dry deposition velocities are no longer calculated by the current version of MCIP. CMAQv5 can now calculate all deposition velocities, MCIPv3.4 will be the last version of MCIP to calculate those velocities internally.

MCIP can extract both temporal and spatial subsets of the input meteorology files. The run script allows the user to specify the beginning and end dates/times of the MCIP simulation; these dates/times can fall anywhere within the range of the input meteorological time period, but must be consistent with the time granularity of the meteorological files. MCIP cannot perform temporal interpolations to artificially increase the temporal resolution of the meteorology fields. Two types of horizontal domain windowing are allowed with MCIP. The boundary trim option ("BTRIM") uniformly trims grid cells off each of the four lateral boundaries of the input meteorology grid. The nonuniform trim option specifies an offset from the lower left corner of the input meteorology domain and the number of cells in the X and Y directions from the revised origin to extract from the input domain. More information about how to invoke these options is provided in the next section: MCIP execution options. MCIP also provides the capability to reconfigure the vertical layer structure in the input meteorology through interpolation from the input structure to an output structure defined through sigma coordinates in the run script. Commonly referred to as "layer collapsing," this option should be exercised with caution as it can significantly impact the conservation of energy assumption inherent in the meteorology through its effects on the predicted wind fields.

Files, configuration, and environment variables

Figure 7-8 shows the input and output files and configuration options for MCIP. All MCIP configurations are accomplished at execution (rather than at compile

time) and via Fortran namelist variables, a distinction from the rest of the CMAQ programs. The user does not need to directly edit the MCIP namelist file. All configuration settings are contained in the MCIP run script, which automatically creates a new namelist file each time the script is executed.




Figure 7-8. MCIP input and output files

MCIP Input Files

Table 7-21. MCIP input files

\mathbf{File}

NameFormaDescription

File

NameFormaDescription

```
InMetPilinary List
(MM5)of
or MM5
netCD6r
(WRF-WRW-)ARW
out-
put
files
for
in-
put
to
MCIP
```

NameFormaDescription

```
{\rm In Ter F \emph{b} \emph{lie} nary \, MM5}
               {\rm Ter}\text{-}
               rain
                file
               with
                frac-
                tional
               {\rm land}
                use
               cat-
               e-
               gories;
               used
               for
               cal-
               cu-
               lat-
               ing
               land-
               use-
               dependent
               ver-
                ti-
               cal
               dif-
                fu-
               siv-
               ity.
               Not
               nec-
               es-
               sary
               with
               WRF-ARW;
                this
               in-
                for-
               ma-
                tion
               is
               in-
               cluded
               in
               the
               WRF-
        124
               ARW
               met
```

file.

File NameFormaDescription InSatFiles GOES satellite

cloud data

MCIP Output Files

Table 7-22. MCIP output files

 \mathbf{File}

${\bf Name Formal Description}$ $\operatorname{GRID} \text{DAISSCOI}\operatorname{Grid}$ description file $\quad \text{with} \quad$ coordinate and grid definition information ${\rm GRID}\underline{{\rm BBNDMA}}\underline{{\rm I\!R\!2M}}{\rm D3}{\rm e}\text{-}$ independent 2-D boundary meteorology file

\mathbf{File} ${\bf Name Formal Description}$ $\operatorname{GRID}\underline{\text{CCRR00}}\underline{\text{res}}$ independent2-D crosspoint meteorology file GRID CORRODESIDAEindependent 3-D crosspoint meteorology file $\operatorname{GRID}\underline{\operatorname{GPODID}}\underline{\operatorname{EHD}}_{e^{-}}$ independent 2-D dotpoint meteorology ${\rm file}$ MET_BINDYARM3edependent 3-D boundary meteorol-

ogy file

\mathbf{File} NameFormaDescription MET_**GRD**D**ED**3e- ${\it dependent}$ 2-D crosspoint meteorology file MET_**GRO**D**ED**: dependent 3-D crosspoint meteorology file MET_**©RD**D**BD**&dependent 3-D dotpoint me-

teorology file

File		
NameFormaDescription		
mmhea AlS CII Content		
	of	
	MM5	
	header	
	in-	
	clud-	
	ing	
	con-	
	fig-	
	ura-	
	tion	
	in-	
	for-	
	ma-	
	tion;	
	not	
	gen-	
	er-	
	ated	
	for	
	WRF-ARW	
	input	

The default location of the MCIP output files is the \$CMAQ_HOME/data/mcip/\$GridName directory. Since the default file names do not have any information about the model grid that they are simulating, the name of the grid is set in the output directory path. The default naming convention for all MCIP output files uses only the APPL environment variable in the file name. All of the file-naming variables for the MCIP outputs are set in the run script.

Compilation Configuration

All model configuration options for MCIP are set during execution. System compiler options must be set in the provided Linux Makefile to build the program for different operating system/compiler combinations. Example compiler paths, flags, and library locations are provided in the default Makefile.

Execution Configuration Variables

The environment variables listed here are invoked during execution of the program and are set in the MCIP run script.

• APPL [default: None]

Application name; scenario ID for file naming

• CoordName [default: None]

Coordinate system name of the MCIP output grid that is written to the GRIDDESC file

• GridName [default: None]

Model grid name of the MCIP output grid that is written to the GRID-DESC file

• DataPath [default: \$CMAQ_DATA]

Input/output data directory path

• InMetDir [default: None]

Path of the input data directory containing the MM5 or WRF-ARW output data files

• InTerDir [default: None]

Path of the input data directory containing the MM5 TERRAIN or WRF Geogrid file

• InSatDir [default: None]

Path of the input data directory containing GOES satellite files for using observed cloud cover data.

• OutDir [default: \$CMAQ_HOME/data/mcip]

Path of the MCIP output data directory

• ProgDir [default: \$CMAQ_HOME/PREP/mcip/src] Working directory containing the MCIP executable

• WorkDir [default: \$OutDir]

Temporary working directory for Fortran links and the namelist file

• InMetFiles [default: None]

List of input meteorology files, including the directory path for each file; without modifying MCIP, up to 300 meteorological model output files are allowed as input to a single MCIP execution

• InSatFiles [default: None]

List of input GOES satellite cloud data files.

• IfTer [default: F]

Binary flag indicating the availability of an input MM5 TERRAIN or WRF Geogrid file; options include T (true) or F (false)

• InTerFile [default: None]

Name and location of input MM5 TERRAIN or WRF Geogrid file

• LPV: [default: 0]

Compute and output potential vorticity. This must be activated to support the CCTM O3 potential vorticity scaling.

- 0: Do not compute and output potential vorticity
- 1: Compute and output potential vorticity
- LWOUT [default: 0]

Output vertical velocities.

- 0: Do not output vertical velocity
- 1: Output vertical velocity
- LUVCOUT [default: 0]

Output u- and v-component winds on C-grid.

- 0: Do not output u- and v-component winds on C-grid
- 1: Output u- and v-component winds on C-grid
- LSAT [default: 0]

Use GOES satellite cloud observations to replace model-derived input on clouds

- 0: No satellite data are available
- 1: Use GOES observed cloud information to replace model-derived input
- MCIP_START [format: YYYY-MM-DD-HH:MM:SS.SSSS]

Beginning date and time (UTC) of data to output from MCIP. The start date and time must be contained within the input data from MM5 or WRF-ARW.

- MCIP_END [format: YYYY-MM-DD-HH:MM:SS.SSSS] End date and time (UTC) of data to output from MCIP. The end date and time must be contained within the input data from MM5 or WRF-ARW.
- INTVL [default: 60]
 Output interval in minutes. This setting determines the amount of model time contained in each output time step. The output interval for MCIP can be less frequent than the incoming meteorological model output (e.g.,

process 30-minute data for CCTM from 15-minute WRF-ARW output).

- CTMLAYS [default: "-1.0"] Sigma values of the vertical layers in the 3-D MCIP output. Commadelimited values for each sigma value must be in descending order starting at 1 and ending with 0. There are a maximum of 100 layers allowed. To use the all of the layers from the input meteorology without collapsing (or explicitly specifying), set CTMLAYS = -1.0.
- MKGRID [default: T]

Determines whether to output static (GRID) meteorology files

• BTRIM [default: 5]

The number of boundary points to remove on each of the four horizontal sides of the MCIP domain. Setting BTRIM = 0 will specify the maximum extent of the input meteorology domain. To remove the MM5 or WRF-ARW lateral boundaries, set BTRIM = 5 (recommended).

This setting affects the output MCIP horizontal domain by reducing the input meteorology domain by 2BTRIM + 2NTHIK + 1, where NTHIK is the lateral boundary thickness (from the BDY files). The extra point reflects the conversion from the grid points (dot points) to grid cells (cross points).

For windowing a subset domain of the input meteorology, set BTRIM = -1; this setting causes BTRIM to be replaced by the information provided by X0, Y0, NCOLS, and NROWS (see below).

• X0 [used only if BTRIM = -1]

The x-coordinate of the lower-left corner of the full MCIP cross-point domain (including the MCIP lateral boundary) based on the input MM5 or WRF-ARW domain. X0 refers to the east-west direction.

- Y0 [used only if BTRIM = -1]

 The y-coordinate of the lower-left corner of the full MCIP cross-point domain (including the MCIP lateral boundary) based on the input MM5 or WRF-ARW domain. Y0 refers to the north-south direction.
- NCOLS [used only if BTRIM = -1]
 Number of columns in the output MCIP domain (excluding MCIP lateral boundaries)
- NROWS [used only if BTRIM = -1]
 Number of rows in the output MCIP domain (excluding MCIP lateral boundaries)
- LPRT_COL [default: 0]

 Column cell coordinate for diagnostic outputs on the MCIP modeling domain
- LPRT_ROW [default: 0]
 Row cell coordinate for diagnostic outputs on the MCIP modeling domain
- WRF_LC_REF_LAT [default: -999.0] WRF Lambert Conformal reference latitude. Use this setting to force the reference latitude in the output MCIP data. If not set, MCIP will use the average of the two true latitudes. This setting is useful for matching WRF grids to existing MM5 grids.

Compiling and Running

Compile MCIP

Chapter 5 provides an overview of how to install and compile the CMAQ programs for the tutorial simulation. Follow the steps outlined in Chapter 5 (summarized below) to compile new versions of MCIP.

MCIP is compiled with a Makefile. The configuration options in the Makefile include only the compiler and compiler flags to use for building the executable. The Makefile is located in the directory with the MCIP source code (\$CMAQ_HOME/PREP/mcip/src). To compile MCIP, source the config.cmaq file and invoke the Makefile at the command line:

```
cd $CMAQ_HOME/PREP/mcip/src/
source $CMAQ_HOME/config.cmaq
./make |& tee make.mcip.log
```

To port MCIP to different compilers, change the compiler names, locations, and flags in the config.cmaq script.

Run MCIP

Set the run script settings according to the execution configuration variables described above. Run MCIP to produce meteorology input data for the CCTM:

```
cd $CMAQ_HOME/PREP/mcip
```

References for Chapter 7: CMAQ Programs and Libraries

Arya, P., 1984: Parametric relations for the atmospheric boundary layer. Bound.-Layer Meteor., 30, 57–73.

Byun, D. W., and J. K. S. Ching, 1999: Science Algorithms of the EPA Models-3 Community Multiscale Air Quality (CMAQ) Modeling System. U. S. Environmental Protection Agency Rep. EPA-600/R-99/030, 727 pp. [Available from Office of Research and Development, EPA, Washington, DC 20460.]

Hanna, S. R., G. A. Briggs, and R. P. Hosker, 1982: Handbook on atmospheric diffusion, U.S. DOE, DOE/TIC-11223, DE82002045, National Technical Info. Center, Springfield, VA.

Hicks, B.B., 1985: Behavior of turbulence statistics in the convective boundary layer. J. Clim. Appl. Meteor., 24, 607–614.

Irwin, J. S., 1979: Scheme for estimating dispersion parameters as a function of release height, EPA-600/4-79-062, Research Triangle Park, NC.

Niewstadt, F. T. M., 1984: Some aspects of the turbulent stable boundary layer. Bound.-Layer Meteor., 30, 31–55.

Pleim, J. E., A. Xiu, P. L. Finkelstein, and T. L. Otte, 2001: A coupled land-surface and dry deposition model and comparison to field measurements of surface heat, moisture, and ozone fluxes. Water Air Soil Pollut. Focus, 1, 243–252.

Venkatram, A., 1988: Dispersion in the stable boundary layer. Chapter 5, in Lectures on Air Pollution Modeling, A. Venkatram and J. Wyngaard, Eds., American Meteorology Society, Boston, MA.

Weil. J. C., 1988: Dispersion in the convective boundary layer. Chapter 4, in Lectures on Air Pollution Modeling, A. Venkatram and J. Wyngaard, Eds., American Meteorology Society, Boston, MA.

Wesely, M. L., 1989: Parameterization of surface resistances to gaseous dry deposition in regional-scale numerical models. *Atmos. Environ.*, **23**, 1293–1304.

<< Previous Chapter - Home - Next Chapter >> CMAQ Operational Guidance Document (c) 2016