## CMAQ Installation Quick Start Guide

## System Checks

The following support software are required for compiling and running CMAQ.

- 1. Fortran and C compilers, e.g., Intel, Portland Group, Gnu
- 2. Git
- 3. I/O API
- 4. netCDF
- 5. Message Passing Interface (MPI), e.g., OpenMPI or MVAPICH2.

#### Install CMAQ and Required Libraries

In the directory where you would like to install CMAQ, issue the following command to clone the CMAS CENTER GitHub repository for CMAQv5.2 Beta:

git clone -b 5.2Gamma https://github.com/CMASCenter/EPA-CMAQ.git CMAQ\_v5.2Gamma

For instructions on installing CMAQ from tarballs, see Chapter 5.

### Configure the CMAQ build environment

Edit the file CMAQv5.2/config.cmaq to configure the CMAQ installation for the local computing architecture and compilers.

- 1. Set the script variable CMAQ\_HOME to point the installation directory location of CMAQ on your Linux system.
- 2. Set the script variable compiler for one of the supported compilers.
- 3. Install the CMAQ libraries

The CMAQ build scripts require the following libraries and INCLUDE files to be available in the CMAQ\_LIB directory (Note the CMAQ\_LIB gets set automatically by the config.cmaq script, where CMAQ\_LIB = \$CMAQ\_HOME/lib):

- netCDF library and INCLUDE files are located in the \$CMAQ\_LIB/netcdf directory
- I/O API library and module files are located in the \$CMAQ\_LIB/ioapi directory
- MPI library and INCLUDE files are located in the  $\CMAQ_LIB/mpi$  directory

The config.cmaq script will automatically link the required libraries into the CMAQ\_LIB directory. Set the locations of the netCDF, I/O API, and MPI installations on your Linux system with the following config.cmaq environment variables:

- setenv IOAPI: the location of the I/O API installation on your system.
- setenv NETCDF: the location of the netCDF installation on your system.
- setenv MPI: the location of the MPI (OpenMPI or MVAPICH) on your system.

For example, if your netCDF libraries and includes files are installed in /usr/local/netcdf, set NETCDF to /usr/local/netcdf. Similarly, if your I/O API library is installed in /home/cmaq/ioapi/Linux2\_x86\_64ifort, set IOAPI to /home/cmaq/ioapi/Linux2\_x86\_64ifort.

- 4. Check the names of the I/O API and netCDF libraries using the ioapi\_lib and netcdf\_lib script variables.
- 5. Check the name of the MPI library using the mpi script variable. For MVAPICH use -lmpich; for openMPI use -lmpi.

6. Invoke the settings in the configuration script: source \$CMAQ\_HOME/config.cmaq

# Compiling CMAQ

Compile the model builder, bldmake:

```
cd $CMAQ_HOME/UTIL/bldmake/src
make
Create the model executables for ICON, BCON, and CCTM:
cd $CMAQ_HOME/PREP/icon/scripts
./bldit.icon |& tee bldit.icon.log
cd $CMAQ_HOME/PREP/bcon/scripts
./bldit.bcon
cd $CMAQ_HOME/CCTM/scripts
./bldit.cctm
```

## Install the CMAQ input reference/benchmark data

Dwnloaded the CMAQ reference data from the CMAS Center Software Clearinghouse and copy to \$CMAQ\_HOME. Navigate to the \$CMAQ\_HOME directory, unzip and untar the CMAQv5.2.DATA.tar.gz file:

```
cd $CMAQ_HOME
tar xvzf CMAQv5.2.DATA.tar.gz
```

### Running the CMAQ Installation Test Simulation

To run the test simulation for the various CMAQ programs, change directories to the location of each program and execute the run script.

Run ICON to produce initial conditions:

```
cd $CMAQ_HOME/PREP/icon/scripts
./run.icon |& tee icon.log
Run BCON to produce boundary conditions:
cd $CMAQ_HOME/PREP/bcon/scripts
./run.bcon |& tee bcon.log
```

Check the ICON and BCON log file to ensure that the programs completed successfully. Note that CMAQ test simulation doesn't actually require that ICON and BCON be run; the test input data include CCTM-ready initial and boundary conditions files.

## Configure the CCTM script for MPI

```
For an MPI configuration with 6 processors,
cd $CMAQ_HOME/CCTM/scripts
Edit the CCTM run script (run.cctm) for the MPI configuration that you will use:
setenv NPROCS 6
setenv NPCOL_NPROW "3 2"
```

Most clustered multiprocessor systems require a command to start the MPI run-time environment. The default CCTM run script uses the *mpirun* command. Consult your system administrator to find out how to invoke MPI when running multiprocessor applications.

For single-processor computing, set NPROCS to 1 and NPCOL\_NPROW to "1 1"

For single-processor computing,

```
setenv NPROCS 1
setenv NPCOL_NPROW to "1 1"
```

After configuring the MPI settings for your Linux system, using the following command to run the CCTM. Per the note above, different Linux systems have different requirements for submitting MPI jobs. The command below is an example of how to submit the CCTM run script and may differ depending on the MPI requirements of your Linux system.

./run.cctm |& tee cctm.log

 $\begin{array}{l} \mbox{Home - Next Chapter} >> \\ \mbox{CMAQ Operational Guidance Document (c) 2016} \end{array}$