## Hack a Day

Fresh hacks every day

- Home
- Submit a tip
- <u>forums</u>
- Shop
- Search this website ...

Search

# How to write udev rules

September 18, 2009 By Mike Szczys 32 Comments



Since the adoption of Kernel 2.6, Linux has used the <u>udev system</u> to handle devices such as USB connected peripherals. If you want to change the behavior when you plug something into a USB port, this section is for you. As an example, we will use a USB thumb drive but these methods should translate to any device handled by udev. As a goal for this exercise we decided to create a symlink and execute a script when a specific thumb drive was loaded. The operating system we used for this exercise is Ubuntu 9.04 Jaunty Jackalope.

## **Background Investigation**

Before writing rules, we have to gather all the information needed to identify our device. We found the <u>block device node</u> that the drive was assigned to by plugging it in and checking /var/log/messages. We then pass that location (/dev/sdd1) to two commands that we run at the same time. Some distributions use the "udevinfo" command but with Ubuntu 9.04 the command has changed to "udevadm info":

```
1 udevadm info -a -p $(udevadm info -q path -n /dev/sdd1)
```

The output of this is pretty meaty. We need to find the top of the chain that provides the block node which is used for mounting removable storage (in our case, /dev/sdd1). Using this KERNEL as identification will ensure that our symlink points to a mountable block device and not some part of the USB controller. We are also looking for device specific identifiers that differentiate this particular thumbdrive from all others:

```
looking at device '/devices/pci0000:00/0000:00:02.1/usb1/1-2/1-
   2:1.0/host29/target29:0:0/29:0:0:0/block/sdd/sdd1':
02
    KERNEL=="sdd1"
03
    SUBSYSTEM=="block"
    DRIVER==""
04
05
    ATTR{partition}=="1"
    ATTR{start}=="63"
    ATTR{size}=="31310622"
07
    ATTR{stat}==" 208
                                       16282
                                                  776
                                                                                2
08
                              15448
                              788"
   12
                     508
09
   looking at parent device '/devices/pci0000:00/0000:00:02.1/usb1/1-2':
10
11
   KERNELS=="1-2"
   SUBSYSTEMS=="usb"
12
13
   DRIVERS=="usb"
   ATTRS{configuration}==""
14
    ATTRS{bNumInterfaces}==" 1"
15
    ATTRS{bConfigurationValue}=="1"
16
17
    ATTRS{bmAttributes}=="80"
    ATTRS{bMaxPower}=="200mA"
18
19
    ATTRS{urbnum}=="1858"
    ATTRS{idVendor}=="13fe"
20
    ATTRS{idProduct}=="1f00"
21
    ATTRS{bcdDevice}=="0110"
22
23
    ATTRS{bDeviceClass}=="00"
    ATTRS{bDeviceSubClass}=="00"
24
25
    ATTRS{bDeviceProtocol}=="00"
26
    ATTRS{bNumConfigurations}=="1"
27
    ATTRS{bMaxPacketSize0}=="64"
28
    ATTRS{speed}=="480"
29
    ATTRS{busnum}=="1"
    ATTRS{devnum}=="69"
    ATTRS{version}==" 2.00"
31
    ATTRS{maxchild}=="0"
32
33
    ATTRS{quirks}=="0x0"
    ATTRS{authorized}=="1"
35
    ATTRS{manufacturer}=="0CZ"
    ATTRS{product}=="DIESEL"
36
    ATTRS{serial}=="50E6920B000AE8"
```

In writing a udev rule, any of these characteristics can be used as conditions for the rule's execution. That being said, only properties from **one** parent of the device and from the device itself can be match. Trying to match values from more than one parent in the chain will be invalid and will not work.

#### The Rule

Rule files are stored in the /etc/udev/rules.d/ directory. We got some advice from the README in that directory on how to name rule files:

Files should be named xx-descriptive-name.rules, the xx should be

chosen first according to the following sequence points:

< 60 most user rules; if you want to prevent an assignment being overriden by default rules, use the := operator.

these cannot access persistent information such as that from vol\_id

- < 70 rules that run helpers such as vol\_id to populate the udev db
- < 90 rules that run other programs (often using information in the udev db)
- >=90 rules that should run last

We plan to run a script with this rule so we gave it a name that started with a higher number than our other rules but lower than 90. We used the filename:

```
81-thumbdrive.rules
```

The first part of a udev rule is the matching keys. We will use the KERNEL entry from the very top of the chain as well as the idVendor, idProduct, and serial attributes from the device specific information. This will positively identify this particular thumb drive and ignore all others. The kernel argument uses a question mark as a wild card so that if our drive were mounted on a different node (ie: sda1, sdb1, sdc1, etc.) it could still be identified.

```
1 KERNEL=="sd?1", ATTRS{idVendor}=="13fe", ATTRS{idProduct}=="1f00",
    ATTRS{serial}=="50E6920B000AE8"
```

Now that we have the keys necessary to identify the particular hardware we're looking for we can add assignment arguments. In our case we added two. The first creates a symlink to this device inside of the /dev/ directory. The second executes a script in our home directory:

```
1 SYMLINK+="hackaday", RUN+="/home/mike/notify-plugin.sh 'HackaDay Thumbdrive:' 'Connected as: $KERNEL'"
```

Here is the final rule assembled into one line:

```
1 KERNEL=="sd?1", ATTRS{idVendor}=="13fe", ATTRS{idProduct}=="1f00",
   ATTRS{serial}=="50E6920B000AE8", SYMLINK+="hackaday", RUN+="/home/mike/notify-plugin.sh
   'HackaDay Thumbdrive:' 'Connected as: $KERNEL'"
```

We added this as the only line in our rule file and then restarted udev using these commands:

```
sudo nano /etc/udev/rules.d/81-thumbdrive.rules
sudo /etc/init.d/udev restart
```

## The Script (and the bug workaround)

We wanted to use the pop-up notification we covered a while back but couldn't get it to work. After a bit

of frustration we found out that <u>the notify-send package has trouble</u> putting notifications on a user's screen when called from a script run by root. There is a <u>workaround for this bug</u>. We altered the script just a bit for our purposes and pasted it to a new file named: /usr/local/bin/alt-notify-send

```
01 | #!/bin/sh
02 | user=`whoami`
03 pids=`pgrep -u $user gnome-panel`
04
   title=$1
05
   text=$2
06
   timeout=$3
07
   icon=$4
08
   if [ -z "$title" ]; then
09
   echo You need to give me a title >&2
11
   exit 1
12
   fi
   if [ -z "$text" ]; then
13
14
    text=$title
15
   fi
   if [ -z "$timeout" ]; then
16
17
   timeout=60000
18
19
20
   for pid in $pids; do
21
    # find DBUS session bus for this session
22
    DBUS_SESSION_BUS_ADDRESS=`grep -z DBUS_SESSION_BUS_ADDRESS \
23
    /proc/$pid/environ | sed -e 's/DBUS_SESSION_BUS_ADDRESS=//'
24
    # use it
25
26
    #icon hack:
    if [ -z $icon ]; then
27
    DBUS_SESSION_BUS_ADDRESS=$DBUS_SESSION_BUS_ADDRESS \
28
    notify-send -u low -t $timeout "$title" "$text"
29
30
31
    DBUS_SESSION_BUS_ADDRESS=$DBUS_SESSION_BUS_ADDRESS \
    notify-send -u low -t $timeout -i "$icon" "$title" "$text"
32
    fi
33
34
   done
```

We then created the script that the udev rule calls. This is placed in our home directory at /home/mike/notify-plugin.sh

```
1 #!/bin/bash
2 | su mike alt-notify-send "$1" "$2" 6000 "/home/mike/hackaday_icon.png"
```

The script can do just about anything we want it to. In this case it calls the notification workaround script passing two strings from the udev rule, a delay time, and an icon to display with the pop-up.

#### **Order of events:**

Now that everything's in place, let's take a look at what happens when our drive is plugged in.

- 1. -USB drive is plugged into the computer
- 2. -Udev checks the /etc/udev/rules.d/ directory and starts using the rule files in order
- 3. -Udev gets to our file: 81-thumbdrive.rules and matches the "sd?1" kernel, idVendor, idProduct, and

serial number of the thumbdrive.

- 4. -If udev confirms a match on our four conditions, a symlink is created at /dev/hackaday and the /home/mike/notify-plugin.sh script is executed, passing it a message that includes the kernel information.
- 5. -Our script executes creating a pop-up notification using the alt-notify-send workaround.
- 6. -HAL takes over, automatically mounting our drive (this is part of Ubuntu's removable storage handling and unrelated to our udev rule).

Here we see the symlink pointing to our block device and the pop-up notification:

```
[~] $ ls /dev/h* -la
4 2009-09-14 11:58 /dev/hackaday -> sdd1
251, 0 2009-09-13 18:05 /dev/hidraw0
10, 228 2009-09-13 18:05 /dev/hpet
```



#### Other uses:

Udev rules give you control over the hardware attached to your machine. If you are working on a USB connected project, these rules will allow you to set permissions for access, execute scripts when added or removed, and provide a persistent symlink for accessing this hardware without relying on the same node name each time the device is connected. We use a udev rule to allow <u>avrdude</u> to access our <u>AVR Dragon</u> programmer without root permission. In this case our rule sets read/write permissions for owner and group, then assigns the device to the "plugdev" group. As long as the user trying to run avrdude is a member of the plugdev group the program will be able to access the dragon. Here's the rule:

```
SUBSYSTEM=="usb", ATTR{idVendor}=="03eb", ATTR{idProduct}=="2107", MODE="0660",
GROUP="plugdev"
```

We hope this helps clarify how the udev system works. Give it a try with your next project.

#### **Resources:**

- Writing udev rules by Daniel Drake: <a href="http://reactivated.net/writing">http://reactivated.net/writing</a> udev rules.html
- notify-send bug: <a href="https://bugs.launchpad.net/ubuntu/+source/libnotify/+bug/160598">https://bugs.launchpad.net/ubuntu/+source/libnotify/+bug/160598</a>
- notify-send workaround: <a href="http://ubuntuforums.org/showthread.php?p=6889270#post6889270">http://ubuntuforums.org/showthread.php?p=6889270#post6889270</a>

Smart wheely Santa-Pede Challenge: Take Two

Bejeweled Blitz bot makes your high score look just sad

How-to: Prepare vour Eagle designs for manufacture

Engine Hacks: Liquid fuel amateur rocket roundup

Filed Under: <u>linux hacks</u> Tagged With: <u>AVR</u>, <u>block</u>, <u>dragon</u>, <u>hal</u>, <u>linux</u>, <u>notify-send</u>, <u>plugdev</u>, <u>programmer</u>, <u>root</u>, <u>rules</u>, <u>thumb drive</u>, <u>ubuntu</u>, <u>udev</u>, <u>udev rules</u>, <u>usb</u>

#### **Comments**

1. *medix* says:

September 18, 2009 at 11:00 am

Excellent work Mike! This will come in handy very soon..

Reply Report comment

2. *nave.notnilc* says:

September 18, 2009 at 11:18 am

now /this/ is a neat post. what sort of practical stuff would one do with this? backup script triggered by plugging in the backup medium?

**Reply Report comment** 

3. Mike Szczys says:

September 18, 2009 at 11:45 am

@nave.notnilc: Indeed, a lot of folks use programs like rsync to do this. Setup a script to run rsync with the settings you want and then execute the script with a udev rule.

Reply Report comment

4. anon says:

September 18, 2009 at 11:49 am

@nave: that's what I was thinking, plug and play backup.

Reply Report comment

5. *Marl* says:

September 18, 2009 at 1:33 pm

Meanwhile on every other operating system you just pick the option you want from the window that pops up when you plug the device in.

WTG Linux.

#### Reply Report comment

6. *Adam Ziegler* says:

September 18, 2009 at 2:29 pm

@Marl... fact is many linux distos work that way also... but if you want more control now you have it.

## Reply Report comment

7. *Scott* says:

September 18, 2009 at 2:34 pm

Anyone know if there's a way to leverage this with serial-to-USB converters (such as the PL-2303)? I have a couple old serial devices that I want to identify and handle differently, but I have 2 identical PL-2303's so they "look" like the same device? Is there some way I could communicate with it and see what it returns to differentiate that the serial device is that is behind the USB-to-serial converter??

## Reply Report comment

8. Ragnar says:

September 18, 2009 at 3:13 pm

@Marl: and if you have an idea yourself what should happen to your not so common USB-Device (e.g. Multimeter, Datalogger, Microcontroller, Homeautomation), then you have a neat way to do this under Linux, or you wait till someone writes something for you under windows, which may never happen. You decide.

## Reply Report comment

9. *OgreProgrammer* says:

September 18, 2009 at 4:02 pm

Uh, Marl?

Every other operating system lets you select one action for ALL like devices as far as I recall. For example, two identical canon DSLR cameras would detect the same.

That was exactly how my two rocketfish web cams work anyway.

In this system you could set it that way, or they could act uniquely based on serial number.

WTG paying attention.

## Reply Report comment

10. *Joshua* says:

September 18, 2009 at 4:16 pm

Nice idea! You can use a specific USB-Stick as a Crypto-Key or save storing device with a kind of automount triggered by this stuff. Like a encoded ignition key.

Right USB-stick and right key = more safety!

Or if you connect a WiFi-USB to start it as a "Kismet drone".

## Reply Report comment

## 11. *Jimmy* says:

September 18, 2009 at 4:30 pm

@Scott,

You can. Try using the USB serial number.

#### Reply Report comment

## 12. bobdole says:

September 18, 2009 at 4:34 pm

Nice writeup!

I was looking into this a couple months ago, I have a sata dock that I can just drop harddrives into, and I was hoping to make it so instead of mounting the drive it would dd /dev/zero to it, making into a hard drive nuking cradle, but I couldn't get it to work..

## Reply Report comment

#### 13. *pRoFiT* says:

September 18, 2009 at 5:07 pm

bobdole, haha you running for press on the next election?

Anyways, why would you want to nuke a drive automaticly! that could be dangerous if you didn't want to kill a drive. Are you trying to have something incase the FBI break your door down looking for ilegal MP3's!

If so i always wanted a super magnet in the doorway so all drives coming out of the room would fry :)

#### Reply Report comment

#### 14. *medix* says:

September 18, 2009 at 5:32 pm

@Jimmy: This can be spoofed with a microcontroller such as the 18F4550 using Microchip's mass storage firmware. Get the serial number from the thumb drive and you're in. This seems like a far more versatile system, since you can specify a set of credentials rather than just one for recognition.

I believe there was a USB Serial Key entry system posted on hackaday awhile back.

#### Reply Report comment

#### 15. bobdole says:

September 18, 2009 at 6:42 pm

@pRoFiT:

I work at a computer store and we occasionally use harddrives for cloning or testing, so when we're done we like to at least zero the drive once before reselling it. It'd be nice to just drop it into a cradle and walk away rather than grabbing an unused computer, putting in a DBAN boot disk, booting it up and clicking through menu options.

Nothing top secret or anything, a single pass of zeroes should at least make the data unrecoverable by amateur efforts.

## Reply Report comment

#### 16. miked says:

September 18, 2009 at 8:41 pm

I LOLed at the idea of a magnetic door way that destroys electrical devices....I pictured the FBI raiding me and trying to get all my electronics through the window.

#### Reply Report comment

#### 17. Chad Oliver says:

September 18, 2009 at 8:57 pm

Hmm ... no-one seems to be saying what I'm thinking:

Thank you hack-a-day, that was the type of article I like to read ... meaty, useful, original. This is what everyone wants. Keep it up!

You know how one-upon-a-time you did articles on cpld's and etc? .... give us some more in that vein.

Way to go, H-A-D, you're getting it right!

#### Reply Report comment

#### 18. *Noobius* says:

September 19, 2009 at 1:50 am

Finally a decent post. Very usefull and well written. Good job and please post more like this one.

#### Reply Report comment

#### 19. *Greycode* says:

September 19, 2009 at 3:10 pm

Mike I had a hard time reading all of your write up because of the tears I had in my eyes because it makes me proud I kept this link on my homepage. THIS is what I am looking for, you mad skill b\*st\*rd you! Grats man, grats! Now I need to go get some tissues to wipe my face and blow my nose.

#### Reply Report comment

## 20. Camille Goudeseune says:

September 19, 2009 at 3:57 pm

Yay! Now my prs-505 ebook reader gets fresh copies of the .txt's and .pdf's that organize my life, without doing the manual plug in, mount, run ruby script, unmount, unplug dance.

#### Reply Report comment

21. *tedxrochester* says:

September 21, 2009 at 11:50 am

Excellent! I had seen information of this type years ago, but couldn't find it when I went looking. I had wanted to setup my laptop to automatically launch gpsd & gpsdrive whenever I plugged in my GPS receiver into the USB port.

Of course, I've long since given up on that now that I have an iPhone, but I have no doubt this kind of info will come in handy again! Thanks very much for the research and detail you put into it.

#### Reply Report comment

22. *Frederik* says:

October 9, 2009 at 3:26 pm

Very powerful. How would one go about executing a script this way after the drive is mounted (done automatically)? With the above rules, it's not yet possible to automatically copy something from the disk for instance, as it's only being mounted in step 6 according to the order of events.

## **Reply Report comment**

23. Camille Goudeseune says:

October 9, 2009 at 4:07 pm

The script that's called at the end can mount the disk and then copy files in either direction. For example, my (ruby) script, invoked as ...RUN+="/usr/local/bin/doit.rb", does among other things:

DirInstall = "/media/disk/database/media/books"
FAlreadyMounted = File.exists? DirInstall
if !FAlreadyMounted
`mount /media/disk 2>/dev/null`
sleep 2
end
... copy files to/from DirInstall

#### Reply Report comment

24. *speedlight* says:

February 21, 2010 at 5:44 am

Hi,

I have 2 serial-usb identical device. How can I differentiate them. I can't find any unique attributes. Attached is the diff result of both udevinfo:

```
# diff ttyUSB7 ttyUSB8
8,9c8,9
< looking at device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.4/1-6.4.4:1.0/ttyUSB7/tty/ttyUSB7':
looking at device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.3/1-
```

```
6.4.3:1.0/ttyUSB8/tty/ttyUSB8':
    > KERNEL=="ttyUSB8"
    12c12
    ATTR{dev}=="188:8"
    14c14
    looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.3/1-
    6.4.3:1.0/ttyUSB8/tty':
    19,20c19,20
    < looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.4/1-
    6.4.4:1.0/ttyUSB7':
    looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.3/1-
    6.4.3:1.0/ttyUSB8':
    > KERNELS=="ttyUSB8"
    25,26c25,26
    < looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.4/1-6.4.4:1.0':
    looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.3/1-6.4.3:1.0':
    > KERNELS=="1-6.4.3:1.0"
    37,38c37,38
    < looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.4':
    looking at parent device '/devices/pci0000:00/0000:00:1d.7/usb1/1-6/1-6.4/1-6.4.3':
    > KERNELS=="1-6.4.3"
    41c41
    ATTRS{dev}=="189:15"
    47c47
    ATTRS{urbnum}=="36"
    58c58
    ATTRS{devnum}=="16"
    76c76
    ATTRS{urbnum}=="77"
    Thanks,
    speedlight
   Reply Report comment
25. Eric says:
    November 8, 2010 at 6:45 am
    Thanks for the post!
```

Reply Report comment

26. *graf* says:

June 3, 2011 at 6:46 am

Thanks for the great article, though I've not yet succeeded in getting my automatic updates done – my udev rules are matched 13 times, and i dont know how to get it matched

only a single time.

Anyways I've found an cleaner workaround for the notify-send problem, just do it like this

DISPLAY=:0 /bin/su username -c 'notify-send Oink!'

works for me (although I'm using e-notify-send, but it has the same issues).

## Reply Report comment

## 27. LinuxNoob says:

June 25, 2011 at 3:58 am

I was trying your method.

This is the udev rules file

ATTRS{bDeviceClass}=="00",ATTRS{bInterfaceClass}=="08",SYMLINK+="USB MASS STORAGE",RUN+="/home/hello/notification.sh"

#!/bin/sh

notify-send "Drive Detected" -t 10000

When I insert my flash drive, the script doesnt run.

#### Reply Report comment

## 28. Mark Watson says:

November 27, 2011 at 11:49 am

I was tearing my hair out with udev. This article was very helpful. I could not get udev to write any debug into to syslog and found another way to get the debug messages was (as root):

- i) /etc/init.d/udev stop
- ii) udevd –debug

(this runs in the foreground and logs lots of useful stuff on connect/disconnect on rules run/rule files edited etc)

Once debugged stop this and switch it back on:

iii) /etc/init.d/udev start

## Reply Report comment

## 29. *Nik* says:

December 6, 2011 at 8:46 am

This is just what I needed. I have a few USB gizmos that I want to attach, that Windows recognizes as thumb drives or serial devices, but my debian box is clueless about. Most of the udev articles I;ve read seem to written with the assumption that you already know how to write udev rules. This article answered my two main questions: how to find the info to identify the device, and how udev fits into the scheme of things.

#### **Reply Report comment**

30. *Justin M. Bennett* says:

#### May 9, 2012 at 2:29 am

Very useful post, including the referenced notify-send workaround.

I had to make a slight change to the /usr/local/bin/alt-notify-send script, in using XFCE4 instead of Gnome3:

```
pids=`pgrep -u $user gnome-panel`
```

**Becomes** 

```
pids=`pgrep -u $user xfce4-panel`
```

Now to code some rsync for synchonizing my Android's pictures to my computer, and pushing a music folder to the Android when plugged in.

## Reply Report comment

31. *dejot* says:

October 3, 2012 at 2:44 am

thanks a lot for the tutorial. one mistake i found cost me some nerves: string substitutions in udev must not be capitalized – use \$kernel or %k instead of \$KERNEL, as described.

#### Reply Report comment

32. Rahul Panwar says:

December 6, 2012 at 11:22 pm

I am writing a udev rule but it is not working,

KERNEL=="pcmSwitch", ENV{MAJOR}=="253", SUBSYSTEM=="char",

NAME="linuxexplore/rahul/%k"

I am writing this rule for my custom driver of a PCM switch. But i need to create the node manually, udev rule not working for me. Is there any UDEV specific method to write a driver.


**Thanks** 

Reply Report comment

## Leave a Reply

Enter your comment here...

#### **Never Miss a Hack**



## **Categories**



## In case you missed it



# **Nerf Sentry Gun for the Apocalypse**

## 27 Comments



# Train set built in a suitcase does more than you'd think

#### 15 Comments



# An even more useless machine

## 47 Comments



# FireHero: Raspberry Pi Controlled Pyrotechnics

#### 23 Comments



# **Watermelon air boat**

#### 34 Comments

More Posts from this Category

#### **Recent Comments**

- Louis Charles Bruckner on Ask Hackaday: What to do with a home intercom system?
- Anonymous on Write code, fix the space station, win \$10,000
- nullsmack on Write code, fix the space station, win \$10,000
- flink on Ask Hackaday: What to do with a home intercom system?
- AndroidCat on Building an automatic bicycle transmission in a week
- steven-x on Ask Hackaday: What to do with a home intercom system?
- steven-x on Ask Hackaday: What to do with a home intercom system?
- qwerty on Write code, fix the space station, win \$10,000
- polossatik on <u>Custom gauges with a stepper motor breakout board</u>
- Jon on Write code, fix the space station, win \$10,000

#### Find Hacks by Date

September 2009

SMTWTFS

<u>1 2 3 4 5</u>

<u>6 7 8 9 10 11 12</u>

<u>13 14 15 16 17 18 19</u>

<u>20 21 22 23 24 25 26</u>

27 28 29 30

« Aug Oct »

# Return to top of page

Copyright © 2013 · Genesis Framework · WordPress · Log in

8