Joyent
smart computing

Performance Analysis: The USE Method

Brendan Gregg

Lead Performance Engineer, Joyent

brendan.gregg@joyent.com

FISL13
July, 2012

whoami

Joyent

- **I work at the top of the performance support chain**
- **I also write open source performance tools out of necessity to solve issues**
  - http://github.com/brendangregg
  - http://www.brendangregg.com/#software
- **And books (DTrace, Solaris Performance and Tools)**
- **Was Brendan @ Sun Microsystems, Oracle, now Joyent**

Joyent

Joyent

- **Cloud computing provider**
- **Cloud computing software**
- **SmartOS**
  - host OS, and guest via OS virtualization
- **Linux, Windows**
  - guest via KVM

Agenda

Joyent

- **Example Problem**
- **Performance Methodology**
  - Problem Statement
  - The USE Method
  - Workload Characterization
  - Drill-Down Analysis
- **Specific Tools**

Example Problem

Joyent

- **Recent cloud-based performance issue**
- **Customer problem statement:**
  - "Database response time sometimes take multiple seconds. Is the network dropping packets?"
  - Tested network using traceroute, which showed some packet drops

Example: Support Path

Joyent

- **Performance Analysis**



Example: Support Path

Joyent

- **Performance Analysis**



my turn

“network looks ok, CPU also ok”

“ran traceroute, can’t reproduce”

Example: Network Drops

Joyent

- **Old fashioned: network packet capture (sniffing)**
  - Performance overhead during capture (CPU, storage) and post-processing (wireshark)
  - Time consuming to analyze: not real-time

Example: Network Drops

Joyent

- **New: dynamic tracing**
  - Efficient: only drop/retransmit paths traced
  - Context: kernel state readable
  - Real-time: analysis and summaries

```
# ./tcplistendrop.d
TIME                     SRC-IP            PORT     DST-IP              PORT
2012 Jan 19 01:22:49  10.17.210.103     25691 -> 192.192.240.212       80
2012 Jan 19 01:22:49  10.17.210.108     18423 -> 192.192.240.212       80
2012 Jan 19 01:22:49  10.17.210.116     38883 -> 192.192.240.212       80
2012 Jan 19 01:22:49  10.17.210.117     10739 -> 192.192.240.212       80
2012 Jan 19 01:22:49  10.17.210.112     27988 -> 192.192.240.212       80
2012 Jan 19 01:22:49  10.17.210.106     28824 -> 192.192.240.212       80
2012 Jan 19 01:22:49  10.12.143.16      65070 -> 192.192.240.212       80
[...]
```

Example: Methodology

Joyent

- Instead of network drop analysis, I began with the USE method to check system health

Example: Methodology

Joyent

- **Instead of network drop analysis, I began with the USE method to check system health**
- **In < 5 minutes, I found:**
  - **CPU**: ok (light usage)
  - **network**: ok (light usage)
  - **memory**: available memory was exhausted, and the system was paging
  - **disk**: periodic bursts of 100% utilization
- **The method is simple, fast, directs further analysis**

Example: Other Methodologies

Joyent

- **Customer was surprised (are you sure?) I used latency analysis to confirm. Details (if interesting):**
  - **memory**: using both microstate accounting and dynamic tracing to confirm that anonymous pagins were hurting the database; worst case app thread spent 97% of time waiting on disk (data faults).
  - **disk**: using dynamic tracing to confirm latency at the application / file system interface; included up to 1000ms fsync() calls.
- **Different methodology, smaller audience (expertise), more time (1 hour).**

Example: Summary

Joyent

- **What happened:**
  - customer, 1st and 2nd level support spent much time chasing network packet drops.
- **What could have happened:**
  - customer or 1st level follows the USE method and quickly discover memory and disk issues
    - memory: fixable by customer reconfig
    - disk: could go back to 1st or 2nd level support for confirmation
  - Faster resolution, frees time

Performance Methodology

Joyent

- Not a tool
- Not a product
- Is a procedure (documentation)

Performance Methodology

Joyent

- Not a tool -> but tools can be written to help
- Not a product -> could be in monitoring solutions
- Is a procedure (documentation)

Why Now: past

Joyent

- **Performance analysis circa ‘90s, metric-orientated:**
  - Vendor creates metrics and performance tools
  - Users develop methods to interpret metrics
- **Common method: “Tools Method”**
  - List available performance tools
  - For each tool, list useful metrics
  - For each metric, determine interpretation
- Problematic: vendors often don’t provide the best metrics; can be blind to issue types

Why Now: changes

Joyent

- **Open Source**
- **Dynamic Tracing**
  - See anything, not just what the vendor gave you
  - Only practical on *open source* software
  - Hardest part is knowing what *questions* to ask

Why Now: present

Joyent

- **Performance analysis now (post dynamic tracing), question-orientated:**
  - Users pose questions
  - Check if vendor has provided metrics
    - Develop custom metrics using dynamic tracing
- **Methodologies pose the questions**
  - What would previously be an academic exercise is now practical

Methology Audience

Joyent

- Beginners: provides a starting point
- Experts: provides a checklist/reminder

Performance Methodolgies

Joyent

- **Suggested order of execution:**

1. Problem Statement
2. The USE Method
3. Workload Characterization
4. Drill-Down Analysis (Latency)

Problem Statement

Joyent

- **Typical support procedure (1st Methodology):**

1. What makes you think there is a problem?
2. Has this system ever performed well?
3. What changed? Software? Hardware? Load?
4. Can the performance degradation be expressed in terms of latency or run time?
5. Does the problem affect other people or applications?
6. What is the environment? What software and hardware is used? Versions? Configuration?

The USE Method

Joyent

- **Quick System Health Check (2nd Methodology):**
- **For every resource, check:**
  - Utilization
  - Saturation
  - Errors

The USE Method

Joyent

- **Quick System Health Check (2nd Methodology):**
- **For every resource, check:**
  - Utilization: time resource was busy, or degree used
  - Saturation: degree of queued extra work
  - Errors: any errors



The USE Method: Hardware Resources

Joyent

- CPUs
- Main Memory
- Network Interfaces
- Storage Devices
- Controllers
- Interconnects

The USE Method: Hardware Resources

Joyent

- **A great way to determine resources is to find (or draw) the server *functional diagram***
  - The hardware team at vendors should have these
- **Analyze every component in the data path**

The USE Method: Functional Diagrams, Generic Example

Joyent



The USE Method: Resource Types

Joyent

- **There are two different resource types, each define utilization differently:**
  - **I/O Resource**: eg, network interface
    - utilization: time resource was busy.
      current IOPS / max or current throughput / max
      can be used in some cases
  - **Capacity Resource**: eg, main memory
    - utilization: space consumed
- **Storage devices act as both resource types**

The USE Method: Software Resources

Joyent

- Mutex Locks
- Thread Pools
- Process/Thread Capacity
- File Descriptor Capacity

The USE Method: Flow Diagram

Joyent



The USE Method: Interpretation

Joyent

- **Utilization**
  - 100% usually a bottleneck
  - 70%+ often a bottleneck for I/O resources, especially when high priority work cannot easily interrupt lower priority work (eg, disks)
  - Beware of time intervals. 60% utilized over 5 minutes may mean 100% utilized for 3 minutes then idle
  - Best examined per-device (unbalanced workloads)

The USE Method: Interpretation

Joyent

- **Saturation**
  - Any non-zero value adds latency
- **Errors**
  - Should be obvious

The USE Method: Easy Combinations

Joyent

Resource	Type	Metric
CPU	utilization	
CPU	saturation	
Memory	utilization	
Memory	saturation	
Network Interface	utilization	
Storage Device I/O	utilization	
Storage Device I/O	saturation	
Storage Device I/O	errors	

The USE Method: Easy Combinations

Joyent

Resource	Type	Metric
CPU	utilization	CPU utilization
CPU	saturation	run-queue length
Memory	utilization	available memory
Memory	saturation	paging or swapping
Network Interface	utilization	RX/TX tput/bandwidth
Storage Device I/O	utilization	device busy percent
Storage Device I/O	saturation	wait queue length
Storage Device I/O	errors	device errors

The USE Method: Harder Combinations

Joyent

Resource	Type	Metric
CPU	errors	
Network	saturation	
Storage Controller	utilization	
CPU Interconnect	utilization	
Mem. Interconnect	saturation	
I/O Interconnect	saturation	

The USE Method: Harder Combinations

Joyent

Resource	Type	Metric
CPU	errors	eg, correctable CPU cache ECC events
Network	saturation	“nocanputs”, buffering
Storage Controller	utilization	active vs max controller IOPS and tput
CPU Interconnect	utilization	per port tput / max bandwidth
Mem. Interconnect	saturation	memory stall cycles
I/O Interconnect	saturation	bus throughput / max bandwidth

The USE Method: tools

Joyent

- **To be thorough, you will need to use:**
  - CPU performance counters
    - For bus and interconnect activity; eg, perf events, cpustat
  - Dynamic Tracing
    - For missing saturation and error metrics; eg, DTrace
- **Both can get tricky; tools can be developed to help**
  - Please, no more top variants! ... unless it is *interconnect*-top or *bus*-top
  - I've written dozens of open source tools for both CPC and DTrace; much more can be done

Workload Characterization

Joyent

- **May use as a 3rd Methodology**
- **Characterize workload by:**
  - **who** is causing the load? PID, UID, IP addr, ...
  - **why** is the load called? code path
  - **what** is the load? IOPS, tput, type
  - **how** is the load changing over time?
- **Best performance wins are from *eliminating unnecessary work***
- **Identifies class of issues that are load-based, not architecture-based**

Drill-Down Analysis

Joyent

- May use as a 4th Methodology
- Peel away software layers to drill down on the issue
- Eg, software stack I/O latency analysis:



Drill-Down Analysis: Open Source

Joyent

- With Dynamic Tracing, all function entry & return points can be traced, with nanosecond timestamps.
- One Strategy is to measure latency pairs, to search for the source; eg, A->B & C->D:

```
static int
arc_cksum_equal(arc_buf_t *buf)
{
        zio_cksum_t zc;
        int equal;

        mutex_enter(&buf->b_hdr->b_freeze_lock);
        fletcher_2_native(buf->b_data, buf->b_hdr->b_size, &zc);

        equal = ZIO_CHECKSUM_EQUAL(*buf->b_hdr->b_freeze_cksum, zc);
        mutex_exit(&buf->b_hdr->b_freeze_lock);

        return (equal);
}
```

A

B

C

D

Other Methodologies

Joyent

- **Method R**
  - A latency-based analysis approach for Oracle databases. See “Optimizing Oracle Performance" by Cary Millsap and Jeff Holt (2003)
- **Experimental approaches**
  - Can be very useful: eg, validating network throughput using iperf

Specific Tools for the USE Method

Joyent

illumos-based

Joyent

- **http://dtrace.org/blogs/brendan/2012/03/01/the-use-method-solaris-performance-checklist/**

Resource	Type	Metric
CPU	Utilization	per-cpu: `mpstat 1`, "idl"; system-wide: `vmstat 1`, "id"; per-process:`prstat -c 1` ("CPU" == recent), `prstat -mLc 1` ("USR" + "SYS"); per-kernel-thread: `lockstat -Ii` *`rate`*, DTrace profile stack()
CPU	Saturation	system-wide: `uptime`, load averages; `vmstat 1`, "r"; DTrace dispqlen.d (DTT) for a better "vmstat r"; per-process: `prstat -mLc 1`, "LAT"
CPU	Errors	`fmadm faulty`; `cpustat` (CPC) for whatever error counters are supported (eg, thermal throttling)
Memory	Saturation	system-wide: `vmstat 1`, "sr" (bad now), "w" (was very bad); `vmstat -p 1`, "api" (anon page ins == pain), "apo"; per-process: `prstat -mLc 1`, "DFL"; DTrace anonpgpid.d (DTT), vminfo:::anonpgin on execname

- **... etc for all combinations (would span a dozen slides)**

Linux-based

Joyent

- **http://dtrace.org/blogs/brendan/2012/03/07/the-use-method-linux-performance-checklist/**

Resource	Type	Metric
CPU	Utilization	per-cpu: `mpstat -P ALL 1`, "%idle"; `sar -P ALL`, "%idle"; system-wide: `vmstat 1`, "id"; `sar -u`, "%idle"; `dstat -c`, "idl"; per-process:`top`, "%CPU"; `htop`, "CPU%"; `ps -o pcpu`; `pidstat 1`, "%CPU"; per-kernel-thread: `top`/`htop` ("K" to toggle), where VIRT == 0 (heuristic). [1]
CPU	Saturation	system-wide: `vmstat 1`, "r" > CPU count [2]; `sar -q`, "runq-sz" > CPU count; `dstat -p`, "run" > CPU count; per-process: /proc/PID/schedstat 2nd field (sched_info.run_delay); `perf sched latency` (shows "Average" and "Maximum" delay per-schedule); dynamic tracing, eg, SystemTap schedtimes.stp "queued(us)" [3]
CPU	Errors	`perf` (LPE) if processor specific error events (CPC) are available; eg, AMD64's "04Ah Single-bit ECC Errors Recorded by Scrubber" [4]

- **... etc for all combinations (would span a dozen slides)**

Products

Joyent

- Earlier I said methodologies could be supported by monitoring solutions
- At Joyent we develop Cloud Analytics:



Future

Joyent

- **Methodologies for advanced performance issues**
  - I recently worked a complex KVM bandwidth issue where no current methodologies really worked
- **Innovative methods based on open source + dynamic tracing**
- **Less performance mystery. Less guesswork.**
- **Better use of resources (price/performance)**
- **Easier for beginners to get started**

Thank you

Joyent

- **Resources:**
  - http://dtrace.org/blogs/brendan
    - http://dtrace.org/blogs/brendan/2012/02/29/the-use-method/
    - http://dtrace.org/blogs/brendan/tag/usemethod/
    - http://dtrace.org/blogs/brendan/2011/12/18/visualizing-device-utilization/ - ideas if you are a monitoring solution developer
- brendan@joyent.com