Building and running applications with Xenomai 2.99.0
Duilding and gumping applications with Vanamai 0.00
Building and running applications with Xenomai 2.99.0

REVISION HISTORY					
NUMBER	DATE	DESCRIPTION	NAME		

Contents

1	Compiling a Xenomai application	1
2	Running a Xenomai application	1
3	Available real-time APIs	2

The latest version of this document is available at this address.

Make sure to read the installation document before going through this one.

For questions, corrections and improvements, write to the mailing list.

1 Compiling a Xenomai application

You should use the xeno-config script to get the proper compilation and linker flags related to Xenomai, in order to build your application for whichever *Cobalt* or *Mercury* core.

Here is a trivial Makefile fragment retrieving the compiler and flags for building the single-file application vxapp.c, over the VxWorks emulation API:

2 Running a Xenomai application

For Cobalt, you will need the real-time core built into the target Linux kernel as described in this document.

For *Mercury*, you need no Xenomai-specific kernel support so far, beyond what your host Linux kernel already provides. Your kernel should at least provide high resolution timer support (CONFIG_HIGH_RES_TIMERS), and likely complete preemption (*PREEMPT_RT*) if your application requires short and bounded latencies.

An application recognises a set of options that may be passed on the command line, namely:

--<api>--clockresolution=<ns> The clock resolution available with the real-time API, given as a count of nano-seconds, i.e. HZ=(10000000000 / ns).

<api> is the name of one of the existing Xenomai APIs your application can be linked against, e.g. psos, vxworks or alchemy. When your application combines multiple APIs, you may pass several clock-resolution switches to set them all.

The default value depends on the API being considered. For instance, the VxWorks TM and pSOS TM emulators default to 1 millisecond clock rates. The Alchemy API is tickless by default, i.e. -- alchemy-clock-resolution=1.



Caution

Specifying a resolution greater than 1 nanosecond requires the low resolution clock support to be available from the Xenomai libraries (see the --enable-lores-clock configuration switch).

--mem-pool-size=<kb>

The initial size in Kilobytes of the main memory pool. This option only makes sense when the TLSF allocator is being used (i.e. --enable-debug is not specified when compiling the Xenomai libraries). This is only a hint, since TLSF will increase the main pool size dynamically as needed, if needed.

However, this option may be used to pre-allocate the specified amount of memory to the application process, thus avoiding costly system calls to extend the data segment of such process while operating in time critical mode.

--no-mlock

Tells the Xenomai libraries not to lock the process memory while initializing. The application will have to handle this task when and how it sees fit, in order to avoid the extra latency induced by virtual memory paging. Otherwise, mlockall (M CL_CURRENT | MCL_FUTURE) is automatically invoked as part of the API initialization duties.

This flag only applies to the *Mercury* core. Memory must be locked when invoking dual kernel services, therefore this switch is a nop over *Cobalt*.

--registry-root=<path>

Tells Xenomai to root the object registry at the given path, instead of /mnt/xenomai by default (see the --enable-registry switch from the configuration options).

--no-registry

This switch disables registry support at runtime. No real-time objects will be exported to /mnt/xenomai/<session>.<pid>, despite the registry code was compiled in.

--session=<label>

Name of the session the new process will be part of (or create if not present). If --enable-pshared was given when configuring the Xenomai libraries, this label allows multiple processes giving the same label at startup to operate on the same set of objects.

For instance, a process can post a semaphore created by another process from the same session. This is done using a common heap area, shared by all processes within the same session.

This label is also used to form the registry mount point for each process, e.g. /mnt/xenomai/<session>.<pid>.<pid>.<pid>.</pid>.

By default, *anon* is used as the session label.

--reset

Forces removal of an older session. This only works if the process which initiated the former session has exited, otherwise an error is raised.

--cpu-affinity=<cpu[,cpu]...>

Sets the CPU affinity of threads created by the Xenomai libraries within the new process.

--enable-async-cancel

Enables asynchronous cancellation of Xenomai threads, making provision to protect the Xenomai APIs accordingly. When disabled, Xenomai assumes that threads may exit due to cancellation only when they reach cancellation points (like system calls). Defaults to enabled.

3 Available real-time APIs

Alchemy This is a re-implementation from scratch of Xenomai's 2.x *native* API, fully rebased on the new

RTOS abstraction interface.

pSOS pSOS TM is a registered trademark of Wind River Systems, Inc.

VxWorks VxWorks TM is a registered trademark of Wind River Systems, Inc.