Xenomai 3.0.1

Generated by Doxygen 1.8.10

Contents

1	API	service	e tags		1
2	Dep	recated	d List		3
3	Mod	ule Ind	lex		5
	3.1	Modul	es		5
4	Data	Struc	ture Inde	ex	7
	4.1	Data S	Structures	8	7
5	File	Index			11
	5.1	File Lis	st		11
6	Mod	ule Do	cumenta	ation	21
	6.1	Chann	els and r	ranges	21
		6.1.1	Detailed	Description	22
	6.2	Big du	al kernel	lock	24
		6.2.1	Detailed	Description	24
		6.2.2	Macro D	Definition Documentation	24
			6.2.2.1	cobalt_atomic_enter	24
			6.2.2.2	cobalt_atomic_leave	25
			6.2.2.3	RTDM_EXECUTE_ATOMICALLY	25
	6.3	Spinlo	ck with p	reemption deactivation	27
		6.3.1	Detailed	Description	27
		6.3.2	Macro D	Definition Documentation	27
			6.3.2.1	rtdm_lock_get_irqsave	28
			6.3.2.2	rtdm_lock_irqrestore	29
			6.3.2.3	rtdm_lock_irqsave	29
		6.3.3	Function	n Documentation	29
			6.3.3.1	rtdm_lock_get(rtdm_lock_t *lock)	29
			6.3.3.2	rtdm_lock_init(rtdm_lock_t *lock)	29
			6.3.3.3	rtdm_lock_put(rtdm_lock_t *lock)	30
			6.3.3.4	rtdm lock put irgrestore(rtdm lock t *lock, rtdm lockctx t context)	30

iv CONTENTS

6.4	User-s	space driv	ver core
	6.4.1	Detailed	Description
	6.4.2	Macro D	Definition Documentation
		6.4.2.1	UDD_IRQ_CUSTOM
		6.4.2.2	UDD_IRQ_NONE
		6.4.2.3	UDD_MEM_LOGICAL 33
		6.4.2.4	UDD_MEM_NONE
		6.4.2.5	UDD_MEM_PHYS
		6.4.2.6	UDD_MEM_VIRTUAL
		6.4.2.7	UDD_RTIOC_IRQDIS
		6.4.2.8	UDD_RTIOC_IRQEN
		6.4.2.9	UDD_RTIOC_IRQSIG
	6.4.3	Function	Documentation
		6.4.3.1	udd_disable_irq(struct udd_device *udd, rtdm_event_t *done) 34
		6.4.3.2	udd_enable_irq(struct udd_device *udd, rtdm_event_t *done) 34
		6.4.3.3	udd_get_device(struct rtdm_fd *fd)
		6.4.3.4	udd_notify_event(struct udd_device *udd)
		6.4.3.5	udd_register_device(struct udd_device *udd)
		6.4.3.6	udd_unregister_device(struct udd_device *udd)
6.5	Threa	d state fla	ngs 37
	6.5.1	Detailed	Description
	6.5.2	Macro D	Definition Documentation
		6.5.2.1	XNHELD
		6.5.2.2	XNMIGRATE
		6.5.2.3	XNPEND
		6.5.2.4	XNREADY
		6.5.2.5	XNSUSP
		6.5.2.6	XNTRAPLB
6.6	Threa	d informa	tion flags
	6.6.1	Detailed	Description
6.7	CAN [Devices .	
	6.7.1	Detailed	Description
	6.7.2	Macro D	Definition Documentation
		6.7.2.1	CAN_CTRLMODE_3_SAMPLES 50
		6.7.2.2	CAN_CTRLMODE_LISTENONLY
		6.7.2.3	CAN_CTRLMODE_LOOPBACK
		6.7.2.4	CAN_ERR_LOSTARB_UNSPEC 50
		6.7.2.5	CAN_RAW_ERR_FILTER 50
		6.7.2.6	CAN_RAW_FILTER
		6.7.2.7	CAN_RAW_LOOPBACK

		6.7.2.8	CAN_RAW_RECV_OWN_MSGS	52
		6.7.2.9	RTCAN_RTIOC_RCV_TIMEOUT	52
		6.7.2.10	RTCAN_RTIOC_SND_TIMEOUT	53
		6.7.2.11	RTCAN_RTIOC_TAKE_TIMESTAMP	53
		6.7.2.12	SIOCGCANBAUDRATE	54
		6.7.2.13	SIOCGCANCTRLMODE	54
		6.7.2.14	SIOCGCANCUSTOMBITTIME	54
		6.7.2.15	SIOCGCANSTATE	55
		6.7.2.16	SIOCGIFINDEX	55
		6.7.2.17	SIOCSCANBAUDRATE	56
		6.7.2.18	SIOCSCANCTRLMODE	56
		6.7.2.19	SIOCSCANCUSTOMBITTIME	57
		6.7.2.20	SIOCSCANMODE	58
		6.7.2.21	SOL_CAN_RAW	58
	6.7.3	Typedef	Documentation	58
		6.7.3.1	can_filter_t	58
		6.7.3.2	can_frame_t	59
	6.7.4	Enumera	ation Type Documentation	59
		6.7.4.1	CAN_BITTIME_TYPE	59
		6.7.4.2	CAN_MODE	59
		6.7.4.3	CAN_STATE	59
6.8	RTDM	١		61
	6.8.1	Detailed	Description	62
	6.8.2	Macro D	efinition Documentation	62
		6.8.2.1	RTDM_TIMEOUT_INFINITE	62
		6.8.2.2	RTDM_TIMEOUT_NONE	62
	6.8.3	Typedef	Documentation	62
		6.8.3.1	nanosecs_abs_t	62
		6.8.3.2	nanosecs_rel_t	62
6.9	RTDM	User AP	l	63
	6.9.1	Detailed	Description	63
6.10	Serial	Devices		64
6.11	Testing	g Devices		66
6.12	Real-ti	ime IPC .		67
	6.12.1	Detailed	Description	69
	6.12.2		efinition Documentation	69
		6.12.2.1	BUFP_BUFSZ	69
			BUFP_LABEL	70
			IDDP_LABEL	71
		6.12.2.4	IDDP_POOLSZ	71

vi CONTENTS

6.12.2.5 SO_RCVTIMEO	72
6.12.2.6 SO_SNDTIMEO	72
6.12.2.7 XDDP_BUFSZ	72
6.12.2.8 XDDP_EVTDOWN	73
6.12.2.9 XDDP_EVTIN	73
6.12.2.10XDDP_EVTNOBUF	74
6.12.2.11XDDP_EVTOUT	74
6.12.2.12XDDP_LABEL	74
6.12.2.13XDDP_MONITOR	75
6.12.2.14XDDP_POOLSZ	75
6.12.3 Enumeration Type Documentation	76
6.12.3.1 anonymous enum	76
6.12.4 Function Documentation	77
6.12.4.1 bindAF_RTIPC(int sockfd, const struct sockaddr_ipc *addr, socklen_addrlen)	_
6.12.4.2 closeAF_RTIPC(int sockfd)	78
6.12.4.3 connectAF_RTIPC(int_sockfd, const_struct_sockaddr_ipc_*addrsocklen_t addrsocklen_t	
6.12.4.4 getpeernameAF_RTIPC(int_sockfd, struct_sockaddr_ipc_*addcsocklen_t *addrlen)	
6.12.4.5 getsocknameAF_RTIPC(int sockfd, struct sockaddr_ipc *addcsocklen_t *addrlen)	
6.12.4.6 getsockoptAF_RTIPC(int sockfd, int level, int optname, void *optva socklen_t *optlen)	
6.12.4.7 recvmsgAF_RTIPC(int sockfd, struct msghdr *msg, int flags)	80
6.12.4.8 sendmsgAF_RTIPC(int sockfd, const struct msghdr *msg, int flags)	80
6.12.4.9 setsockoptAF_RTIPC(int sockfd, int level, int optname, const vo *optval, socklen_t optlen)	
6.12.4.10socketAF_RTIPC(int_domain=AF_RTIPC, int_type=SOCK_DGRAM int protocol)	
6.13 Asynchronous Procedure Calls	83
6.13.1 Detailed Description	83
6.13.2 Function Documentation	83
6.13.2.1 xnapc_alloc(const char *name, void(*handler)(void *cookie), void *cook	<mark>kie</mark>) 83
6.13.2.2 xnapc_free(int apc)	84
6.13.2.3 xnapc_schedule(int apc)	84
6.14 In-kernel arithmetics	85
6.14.1 Detailed Description	85
6.14.2 Function Documentation	85
6.14.2.1 xnarch_generic_full_divmod64(unsigned long long a, unsigned long long b, unsigned long long *rem)	•
6.15 Buffer descriptor	86

6.15.1 Detailed Description	86
6.15.2 Function Documentation	88
6.15.2.1 xnbufd_copy_from_kmem(struct xnbufd *bufd, void *from, size_t len)	88
6.15.2.2 xnbufd_copy_to_kmem(void *ptr, struct xnbufd *bufd, size_t len)	89
6.15.2.3 xnbufd_invalidate(struct xnbufd *bufd)	90
6.15.2.4 xnbufd_map_kread(struct xnbufd *bufd, const void *ptr, size_t len)	90
6.15.2.5 xnbufd_map_kwrite(struct xnbufd *bufd, void *ptr, size_t len)	90
6.15.2.6 xnbufd_map_uread(struct xnbufd *bufd, const voiduser *ptr, size_t len)	91
6.15.2.7 xnbufd_map_uwrite(struct xnbufd *bufd, voiduser *ptr, size_t len)	91
6.15.2.8 xnbufd_reset(struct xnbufd *bufd)	91
6.15.2.9 xnbufd_unmap_kread(struct xnbufd *bufd)	91
6.15.2.10xnbufd_unmap_kwrite(struct xnbufd *bufd)	92
6.15.2.11xnbufd_unmap_uread(struct xnbufd *bufd)	92
6.15.2.12xnbufd_unmap_uwrite(struct xnbufd *bufd)	93
6.16 Clock services	94
6.16.1 Detailed Description	94
6.16.2 Function Documentation	94
6.16.2.1 xnclock_adjust(struct xnclock *clock, xnsticks_t delta)	94
6.16.2.2 xnclock_deregister(struct xnclock *clock)	95
6.16.2.3 xnclock_register(struct xnclock *clock, const cpumask_t *affinity)	96
6.16.2.4 xnclock_tick(struct xnclock *clock)	96
6.17 Debugging services	97
6.17.1 Detailed Description	97
6.18 Dynamic memory allocation services	98
6.18.1 Detailed Description	98
6.18.2 Function Documentation	99
6.18.2.1 xnheap_alloc(struct xnheap *heap, u32 size)	99
6.18.2.2 xnheap_destroy(struct xnheap *heap)	99
6.18.2.3 xnheap_free(struct xnheap *heap, void *block)	99
6.18.2.4 xnheap_init(struct xnheap *heap, void *membase, u32 size)	100
6.18.2.5 xnheap_set_name(struct xnheap *heap, const char *name,)	100
6.19 Cobalt	101
6.19.1 Detailed Description	
6.20 Cobalt kernel	102
6.20.1 Detailed Description	103
6.20.1.1 Dual kernel service tags	103
6.21 Interrupt management	
6.21.1 Detailed Description	105
6.21.2 Function Documentation	105
6.21.2.1 xnintr_affinity(struct xnintr *intr, cpumask_t cpumask)	105

viii CONTENTS

6.21.2.2 xnintr_attach(struct xnintr *intr, void *cookie)	106
6.21.2.3 xnintr_destroy(struct xnintr *intr)	106
6.21.2.4 xnintr_detach(struct xnintr *intr)	106
6.21.2.5 xnintr_disable(struct xnintr *intr)	107
6.21.2.6 xnintr_enable(struct xnintr *intr)	107
6.21.2.7 xnintr_init(struct xnintr *intr, const char *name, unsigned int irq, xnis	
isr, xniack_t iack, int flags)	
6.22 Locking services	
6.22.1 Detailed Description	
6.22.2 Macro Definition Documentation	
6.22.2.1 splexit	
6.22.2.2 splhigh	
6.22.2.3 spltest	110
6.23 Lightweight key-to-object mapping service	111
6.23.1 Detailed Description	111
6.23.2 Function Documentation	111
6.23.2.1 xnmap_create(int nkeys, int reserve, int offset)	111
6.23.2.2 xnmap_delete(struct xnmap *map)	112
6.23.2.3 xnmap_enter(struct xnmap *map, int key, void *objaddr)	112
6.23.2.4 xnmap_fetch(struct xnmap *map, int key)	113
6.23.2.5 xnmap_fetch_nocheck(struct xnmap *map, int key)	113
6.23.2.6 xnmap_remove(struct xnmap ∗map, int key)	114
6.24 Registry services	116
6.24.1 Detailed Description	116
6.24.2 Function Documentation	116
6.24.2.1 xnregistry_bind(const char *key, xnticks_t timeout, int timeout_mo xnhandle_t *phandle)	
6.24.2.2 xnregistry_enter(const_char *key, void *objaddr, xnhandle_t *phanostruct xnpnode *pnode)	
6.24.2.3 xnregistry_lookup(xnhandle_t handle, unsigned long *cstamp_r)	118
6.24.2.4 xnregistry_remove(xnhandle_t handle)	118
6.24.2.5 xnregistry_unlink(const char *key)	119
6.25 Driver programming interface	120
6.25.1 Detailed Description	120
6.26 Driver to driver services	121
6.26.1 Detailed Description	122
6.26.2 Function Documentation	122
6.26.2.1 rtdm_accept(int fd, struct sockaddr *addr, socklen_t *addrlen)	122
6.26.2.2 rtdm_bind(int fd, const struct sockaddr *my_addr, socklen_t addrlen)	123
6.26.2.3 rtdm_close(int fd)	123
6.26.2.4 rtdm_connect(int fd, const struct sockaddr *serv_addr, socklen_t addr	rlen) 124

	6.26.2.5 ftdm_getpeername(intid, struct sockadur *name, sockien_t *nameien) .	124
	6.26.2.6 rtdm_getsockname(int fd, struct sockaddr *name, socklen_t *namelen) .	125
	6.26.2.7 rtdm_getsockopt(int fd, int level, int optname, void *optval, socklen_ t *optlen)	125
	6.26.2.8 rtdm_ioctl(int fd, int request,)	126
	6.26.2.9 rtdm_listen(int fd, int backlog)	127
	6.26.2.10rtdm_open(const char *path, int oflag,)	127
	6.26.2.11rtdm_read(int fd, void *buf, size_t nbyte)	128
	6.26.2.12rtdm_recv(int fd, void *buf, size_t len, int flags)	128
	6.26.2.13rtdm_recvfrom(int fd, void *buf, size_t len, int flags, struct sockaddr *from, socklen_t *fromlen)	129
	6.26.2.14rtdm_recvmsg(int fd, struct user_msghdr *msg, int flags)	129
	6.26.2.15rtdm_send(int fd, const void *buf, size_t len, int flags)	130
	6.26.2.16rtdm_sendmsg(int fd, const struct user_msghdr *msg, int flags)	130
	6.26.2.17rtdm_sendto(int fd, const void *buf, size_t len, int flags, const struct sockaddr *to, socklen_t tolen)	131
	6.26.2.18rtdm_setsockopt(int fd, int level, int optname, const void *optval, socklen_t optlen)	132
	6.26.2.19rtdm_shutdown(int fd, int how)	132
	6.26.2.20rtdm_socket(int protocol_family, int socket_type, int protocol)	133
	6.26.2.21rtdm_write(int fd, const void *buf, size_t nbyte)	
6.27 Device	e Profiles	134
6.27.1	Detailed Description	135
6.27.2	Macro Definition Documentation	136
	6.27.2.1 RTIOC_DEVICE_INFO	136
	6.27.2.2 RTIOC_PURGE	137
6.28 Device	e Registration Services	138
6.28.1	Detailed Description	139
6.28.2	Macro Definition Documentation	139
	6.28.2.1 RTDM_DEVICE_TYPE_MASK	139
	6.28.2.2 RTDM_EXCLUSIVE	139
	6.28.2.3 RTDM_FIXED_MINOR	139
	6.28.2.4 RTDM_MAX_MINOR	139
	6.28.2.5 RTDM_NAMED_DEVICE	140
	6.28.2.6 RTDM_PROTOCOL_DEVICE	140
6.28.3	Function Documentation	140
	6.28.3.1 rtdm_close_handler(struct rtdm_fd *fd)	140
	6.28.3.2 rtdm_dev_register(struct rtdm_device *dev)	140
	6.28.3.3 rtdm_dev_unregister(struct rtdm_device *dev)	141
	6.28.3.4 rtdm_get_unmapped_area_handler(struct rtdm_fd *fd, unsigned long len, unsigned long pgoff, unsigned long flags)	141

X CONTENTS

	6.28.3.5 rtdm_ioctl_handler(struct rtdm_fd *fd, unsigned int request, voiduser *arg)	1
	6.28.3.6 rtdm_mmap_handler(struct rtdm_fd *fd, struct vm_area_struct *vma)	14
	6.28.3.7 rtdm_open_handler(struct rtdm_fd *fd, int oflags)	1
	6.28.3.8 rtdm_read_handler(struct rtdm_fd *fd, voiduser *buf, size_t size)	1
	6.28.3.9 rtdm_recvmsg_handler(struct rtdm_fd *fd, struct user_msghdr *msg, int flags)	1.
	6.28.3.10rtdm_select_handler(struct rtdm_fd *fd, struct xnselector *selector, unsigned int type, unsigned int index)	1.
	6.28.3.11rtdm_sendmsg_handler(struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)	1
	6.28.3.12rtdm_socket_handler(struct rtdm_fd *fd, int protocol)	14
	6.28.3.13rtdm_write_handler(struct rtdm_fd *fd, const voiduser *buf, size_t size)	1
6.29 Clock	Services	1
6.29.1	Detailed Description	1.
6.29.2	Function Documentation	1
	6.29.2.1 rtdm_clock_read(void)	1
	6.29.2.2 rtdm_clock_read_monotonic(void)	1
6.30 Task S	Services	1
6.30.1	Detailed Description	1
6.30.2	Typedef Documentation	1
	6.30.2.1 rtdm_task_proc_t	1
6.30.3	Function Documentation	1
	6.30.3.1 rtdm_task_busy_sleep(nanosecs_rel_t delay)	1
	6.30.3.2 rtdm_task_busy_wait(bool condition, nanosecs_rel_t spin_ns, nanosecs _ rel_t sleep_ns)	
	6.30.3.3 rtdm_task_current(void)	1
	6.30.3.4 rtdm_task_destroy(rtdm_task_t *task)	1
	6.30.3.5 rtdm_task_init(rtdm_task_t *task, const char *name, rtdm_task_proc_ ← t task_proc, void *arg, int priority, nanosecs_rel_t period)	1
	6.30.3.6 rtdm_task_join(rtdm_task_t *task)	1
	6.30.3.7 rtdm_task_set_period(rtdm_task_t *task, nanosecs_abs_t start_date, nanosecs_rel_t period)	1:
	6.30.3.8 rtdm_task_set_priority(rtdm_task_t *task, int priority)	1
	6.30.3.9 rtdm_task_should_stop(void)	1
	6.30.3.10rtdm_task_sleep(nanosecs_rel_t delay)	1
	6.30.3.11rtdm_task_sleep_abs(nanosecs_abs_t_wakeup_time, enum_rtdm_← timer_mode mode)	1
	6.30.3.12rtdm_task_sleep_until(nanosecs_abs_t wakeup_time)	1
	6.30.3.13rtdm_task_unblock(rtdm_task_t *task)	1
	6.30.3.14rtdm_task_wait_period(unsigned long *overruns_r)	1
6.31 Timer	Services	1

CONTENTS xi

6.31.1 [Detailed Description	155
6.31.2	Typedef Documentation	155
6	6.31.2.1 rtdm_timer_handler_t	155
6.31.3 E	Enumeration Type Documentation	156
6	6.31.3.1 rtdm_timer_mode	156
6.31.4 F	Function Documentation	156
6	6.31.4.1 rtdm_timer_destroy(rtdm_timer_t *timer)	156
6	6.31.4.2 rtdm_timer_init(rtdm_timer_t *timer, rtdm_timer_handler_t handler, const char *name)	156
6	6.31.4.3 rtdm_timer_start(rtdm_timer_t ∗timer, nanosecs_abs_t expiry, nanosecs⇔ _rel_t interval, enum rtdm_timer_mode mode)	156
6	6.31.4.4 rtdm_timer_start_in_handler(rtdm_timer_t *timer, nanosecs_abs_t expiry, nanosecs_rel_t interval, enum rtdm_timer_mode mode)	157
6	6.31.4.5 rtdm_timer_stop(rtdm_timer_t *timer)	157
6	6.31.4.6 rtdm_timer_stop_in_handler(rtdm_timer_t *timer)	158
6.32 Synchro	onisation Services	160
6.32.1 [Detailed Description	161
6.32.2 E	Enumeration Type Documentation	161
(6.32.2.1 rtdm_selecttype	161
6.32.3 F	Function Documentation	161
(6.32.3.1 rtdm_for_each_waiter(rtdm_task_t pos, struct rtdm_wait_queue *wq)	161
(6.32.3.2 rtdm_for_each_waiter_safe(rtdm_task_t pos, rtdm_task_t tmp, struct rtdm_wait_queue *wq)	163
6	6.32.3.3 rtdm_timedwait(struct rtdm_wait_queue *wq, nanosecs_rel_t timeout, rtdm_toseq_t *toseq)	163
6	6.32.3.4 rtdm_timedwait_condition(struct rtdm_wait_queue *wq, C_expr condition, nanosecs_rel_t timeout, rtdm_toseq_t *toseq)	164
6	6.32.3.5 rtdm_timedwait_condition_locked(struct rtdm_wait_queue *wq, C_expr condition, nanosecs_rel_t timeout, rtdm_toseq_t *toseq)	
6	6.32.3.6 rtdm_timedwait_locked(struct rtdm_wait_queue *wq, nanosecs_rel_ t timeout, rtdm_toseq_t *toseq)	165
6	6.32.3.7 rtdm_toseq_init(rtdm_toseq_t *timeout_seq, nanosecs_rel_t timeout)	166
6	6.32.3.8 rtdm_wait(struct rtdm_wait_queue *wq)	166
6	6.32.3.9 rtdm_wait_condition(struct rtdm_wait_queue *wq, C_expr condition)	167
6	6.32.3.10rtdm_wait_condition_locked(struct rtdm_wait_queue *wq, C_expr condition)	167
6	6.32.3.11rtdm_wait_locked(struct rtdm_wait_queue *wq)	168
6	6.32.3.12rtdm_waitqueue_broadcast(struct rtdm_wait_queue *wq)	168
6	6.32.3.13rtdm_waitqueue_destroy(struct rtdm_waitqueue *wq)	169
6	6.32.3.14rtdm_waitqueue_flush(struct rtdm_wait_queue *wq)	169
6	6.32.3.15rtdm_waitqueue_init(struct rtdm_waitqueue *wq)	169
6	6.32.3.16rtdm_waitqueue_lock(struct rtdm_wait_queue *wq, rtdm_lockctx_t context)169
6	6.32.3.17rtdm_waitqueue_signal(struct rtdm_wait_queue *wq)	170

xii CONTENTS

6.32.3.18rtdm_waitqueue_unlock(struct_rtdm_wait_queue_*wq, rtdm_lockctx_← t context)
6.32.3.19rtdm_waitqueue_wakeup(struct rtdm_wait_queue *wq, rtdm_task_t waiter)17
6.33 Event Services
6.33.1 Detailed Description
6.33.2 Function Documentation
6.33.2.1 rtdm_event_clear(rtdm_event_t *event)
6.33.2.2 rtdm_event_destroy(rtdm_event_t *event)
6.33.2.3 rtdm_event_init(rtdm_event_t *event, unsigned long pending) 17
6.33.2.4 rtdm_event_pulse(rtdm_event_t *event)
6.33.2.5 rtdm_event_select(rtdm_event_t *event, rtdm_selector_t *selector, enum rtdm_selecttype type, unsigned int fd_index)
6.33.2.6 rtdm_event_signal(rtdm_event_t *event)
6.33.2.7 rtdm_event_timedwait(rtdm_event_t *event, nanosecs_rel_t timeout, rtdm_toseq_t *timeout_seq)
6.33.2.8 rtdm_event_wait(rtdm_event_t *event)
6.34 Semaphore Services
6.34.1 Detailed Description
6.34.2 Function Documentation
6.34.2.1 rtdm_sem_destroy(rtdm_sem_t *sem)
6.34.2.2 rtdm_sem_down(rtdm_sem_t *sem)
6.34.2.3 rtdm_sem_init(rtdm_sem_t *sem, unsigned long value)
6.34.2.4 rtdm_sem_select(rtdm_sem_t *sem, rtdm_selector_t *selector, enum rtdm_selecttype type, unsigned int fd_index)
6.34.2.5 rtdm_sem_timeddown(rtdm_sem_t *sem, nanosecs_rel_t timeout, rtdm_toseq_t *timeout_seq)
6.34.2.6 rtdm_sem_up(rtdm_sem_t *sem)
6.35 Mutex services
6.35.1 Detailed Description
6.35.2 Function Documentation
6.35.2.1 rtdm_mutex_destroy(rtdm_mutex_t *mutex)
6.35.2.2 rtdm_mutex_init(rtdm_mutex_t *mutex)
6.35.2.3 rtdm_mutex_lock(rtdm_mutex_t *mutex)
6.35.2.4 rtdm_mutex_timedlock(rtdm_mutex_t *mutex, nanosecs_rel_t timeout, rtdm_toseq_t *timeout_seq)
6.35.2.5 rtdm_mutex_unlock(rtdm_mutex_t *mutex)
6.36 Interrupt Management Services
6.36.1 Detailed Description
6.36.2 Macro Definition Documentation
6.36.2.1 rtdm_irq_get_arg
6.36.3 Typedef Documentation
6.36.3.1 rtdm_irq_handler_t18

CONTENTS xiii

6.36.4 Fund	ction Documentation	183
6.36	.4.1 rtdm_irq_disable(rtdm_irq_t *irq_handle)	183
6.36	.4.2 rtdm_irq_enable(rtdm_irq_t *irq_handle)	184
6.36	.4.3 rtdm_irq_free(rtdm_irq_t *irq_handle)	184
6.36	.4.4 rtdm_irq_request(rtdm_irq_t *irq_handle, unsigned int irq_no, rtdm_irq⊷ _handler_t handler, unsigned long flags, const char *device_name, void *arg)	185
6.37 Non-Real-T	ime Signalling Services	186
6.37.1 Deta	illed Description	186
6.37.2 Type	edef Documentation	186
6.37	.2.1 rtdm_nrtsig_handler_t	186
6.37.3 Fund	ction Documentation	187
6.37	.3.1 rtdm_nrtsig_destroy(rtdm_nrtsig_t *nrt_sig)	187
6.37	.3.2 rtdm_nrtsig_init(rtdm_nrtsig_t *nrt_sig, rtdm_nrtsig_handler_t handler, void *arg)	187
6.37	.3.3 rtdm_nrtsig_pend(rtdm_nrtsig_t *nrt_sig)	187
6.37	.3.4 rtdm_schedule_nrt_work(struct work_struct *lostage_work)	188
6.38 Utility Servi	ces	190
6.38.1 Deta	illed Description	191
6.38.2 Fund	ction Documentation	191
6.38	.2.1 rtdm_copy_from_user(struct rtdm_fd *fd, void *dst, const voiduser *src, size_t size)	191
6.38	.2.2 rtdm_copy_to_user(struct rtdm_fd *fd, voiduser *dst, const void *src, size_t size)	191
6.38	.2.3 rtdm_free(void *ptr)	192
6.38	.2.4 rtdm_in_rt_context(void)	192
6.38	.2.5 rtdm_iomap_to_user(struct rtdm_fd *fd, phys_addr_t src_addr, size_ t len, int prot, void **pptr, struct vm_operations_struct *vm_ops, void *vm_private_data)	192
6 38	.2.6 rtdm_malloc(size_t size)	
	.2.7 rtdm_mmap_iomem(struct vm_area_struct *vma, phys_addr_t pa)	
	.2.8 rtdm mmap kmem(struct vm area struct *vma, void *va)	
	.2.9 rtdm_mmap_to_user(struct rtdm_fd *fd, void *src_addr, size_t len, int	134
0.50	prot, void **pptr, struct vm_operations_struct *vm_ops, void *vm_↔ private_data)	194
6.38	.2.10rtdm_mmap_vmem(struct vm_area_struct *vma, void *va)	195
6.38	.2.11rtdm_munmap(void *ptr, size_t len)	196
6.38	.2.12rtdm_printk(const char *format,)	196
6.38	.2.13rtdm_printk_ratelimited(const char *format,)	196
6.38	.2.14rtdm_ratelimit(struct rtdm_ratelimit_state *rs, const char *func)	197
6.38	.2.15rtdm_read_user_ok(struct rtdm_fd *fd, const voiduser *ptr, size_t size)	197
6.38	.2.16rtdm_rt_capable(struct rtdm_fd *fd)	197
6.38	.2.17rtdm_rw_user_ok(struct rtdm_fd *fd, const voiduser *ptr, size_t size) .	198

XIV CONTENTS

6.38.2.18rtdm_safe_copy_from_user(struct rtdm_fd *fd, void *dst, const void← user *src, size_t size)	. 198
6.38.2.19rtdm_safe_copy_to_user(struct rtdm_fd *fd, voiduser *dst, const void *src, size_t size)	
6.38.2.20rtdm_strncpy_from_user(struct rtdm_fd *fd, char *dst, const charuser	
6.39 SCHED_QUOTA scheduling policy	
6.39.1 Detailed Description	201
6.40 Thread scheduling control	202
6.40.1 Detailed Description	202
6.40.2 Function Documentation	202
6.40.2.1 xnsched_rotate(struct xnsched ∗sched, struct xnsched_class ∗sched_⇔ class, const union xnsched_policy_param ∗sched_param)	202
6.40.2.2 xnsched_run(void)	203
6.41 Synchronous I/O multiplexing	204
6.41.1 Detailed Description	204
6.41.2 Function Documentation	205
6.41.2.1 xnselect(struct xnselector *selector, fd_set *out_fds[XNSELECT_MAX ← _ TYPES], fd_set *in_fds[XNSELECT_MAX_TYPES], int nfds, xnticks_t timeout, xntmode_t timeout_mode)	. 205
6.41.2.2 xnselect_bind(struct xnselect *select_block, struct xnselect_binding *binding, struct xnselector *selector, unsigned type, unsigned index, unsigned state)	. 205
6.41.2.3 xnselect_destroy(struct xnselect *select_block)	206
6.41.2.4 xnselect_init(struct xnselect *select_block)	206
6.41.2.5 xnselect_signal(struct xnselect *select_block, unsigned int state)	206
6.41.2.6 xnselector_destroy(struct xnselector *selector)	207
6.41.2.7 xnselector_init(struct xnselector *selector)	207
6.42 Thread synchronization services	208
6.42.1 Detailed Description	208
6.42.2 Function Documentation	208
6.42.2.1 xnsynch_acquire(struct xnsynch *synch, xnticks_t timeout, xntmode_← t timeout_mode)	208
6.42.2.2 xnsynch_destroy(struct xnsynch *synch)	209
6.42.2.3 xnsynch_flush(struct xnsynch *synch, int reason)	209
6.42.2.4 xnsynch_init(struct xnsynch *synch, int flags, atomic_t *fastlock)	210
6.42.2.5 xnsynch_peek_pendq(struct xnsynch *synch)	211
6.42.2.6 xnsynch_release(struct xnsynch *synch, struct xnthread *thread)	211
6.42.2.7 xnsynch_sleep_on(struct xnsynch *synch, xnticks_t timeout, xntmode_t timeout_mode)	. 212
6.42.2.8 xnsynch_try_acquire(struct xnsynch *synch)	212
6.42.2.9 xnsynch_wakeup_one_sleeper(struct xnsynch *synch)	213

CONTENTS xv

6.42.2.10xnsyncn_wakeup_tnis_sleeper(struct_xnsyncn_*syncn, struct_xntnread	
*sleeper)	
6.43 Thread services	215
6.43.1 Detailed Description	216
6.43.2 Function Documentation	216
6.43.2.1 xnthread_cancel(struct xnthread *thread)	216
6.43.2.2 xnthread_current(void)	217
6.43.2.3 xnthread_from_task(struct task_struct *p)	217
6.43.2.4 xnthread_harden(void)	217
6.43.2.5 xnthread_init(struct xnthread *thread, const struct xnthread_init_attr *attr, struct xnsched_class *sched_class, const union xnsched_policy_param *sched_param)	217
6.43.2.6 xnthread_join(struct xnthread *thread, bool uninterruptible)	219
6.43.2.7 xnthread_map(struct xnthread *thread, struct completion *done)	219
6.43.2.8 xnthread_migrate(int cpu)	220
6.43.2.9 xnthread_relax(int notify, int reason)	220
6.43.2.10xnthread_resume(struct xnthread *thread, int mask)	221
6.43.2.11xnthread_set_mode(int clrmask, int setmask)	221
6.43.2.12xnthread_set_periodic(struct xnthread *thread, xnticks_t idate, xntmode t timeout_mode, xnticks_t period)	
6.43.2.13xnthread_set_schedparam(struct xnthread ∗thread, struct xnsched_← class ∗sched_class, const union xnsched_policy_param ∗sched_param).	223
6.43.2.14xnthread_set_slice(struct xnthread *thread, xnticks_t quantum)	224
6.43.2.15xnthread_start(struct xnthread *thread, const struct xnthread_start_attr *attr)	224
6.43.2.16xnthread_suspend(struct xnthread *thread, int mask, xnticks_t timeout, xntmode_t timeout_mode, struct xnsynch *wchan)	
6.43.2.17xnthread_test_cancel(void)	226
6.43.2.18xnthread_unblock(struct xnthread *thread)	226
6.43.2.19xnthread_wait_period(unsigned long *overruns_r)	227
6.44 Timer services	228
6.44.1 Detailed Description	228
6.44.2 Function Documentation	229
6.44.2.1xntimer_migrate(struct xntimer *timer, struct xnsched *sched)	229
6.44.2.2 program_htick_shot(unsigned long delay, struct clock_event_device *cde	<mark>v)</mark> 229
6.44.2.3 switch_htick_mode(enum clock_event_mode mode, struct clock_event ←device ∗cdev)	229
6.44.2.4 xntimer_destroy(struct xntimer *timer)	230
6.44.2.5 xntimer_get_date(struct xntimer *timer)	230
6.44.2.6 xntimer_get_overruns(struct xntimer *timer, xnticks_t now)	231
6.44.2.7 xntimer_get_timeout(struct xntimer *timer)	232
6.44.2.8 xntimer_grab_hardware(void)	232

xvi CONTENTS

6.44.2.9 xntimer_init(struct xntimer *timer, struct xnclock *clock, void(*handler)(struct xnsched *sched, int flags)	
6.44.2.10xntimer_interval(struct xntimer *timer)	
6.44.2.11xntimer_release_hardware(void)	
6.44.2.12xntimer_start(struct xntimer *timer, xnticks_t value, xnticks_t interval, xntmode t mode)	
6.44.2.13xntimer_stop(struct xntimer *timer)	
6.45 Virtual file services	
6.45.1 Detailed Description	
6.45.2 Function Documentation	
6.45.2.1 xnvfile destroy(struct xnvfile *vfile)	. 237
6.45.2.2 xnvfile_get_blob(struct xnvfile_input *input, void *data, size_t size)	. 238
6.45.2.3 xnvfile_get_integer(struct xnvfile_input *input, long *valp)	
6.45.2.4 xnvfile_get_string(struct xnvfile_input *input, char *s, size_t maxlen)	. 239
6.45.2.5 xnvfile_init_dir(const char *name, struct xnvfile_directory *vdir, struct xnvfile_directory *parent)	
6.45.2.6 xnvfile_init_link(const char *from, const char *to, struct xnvfile_link *vlink, struct xnvfile_directory *parent)	
6.45.2.7 xnvfile_init_regular(const char *name, struct xnvfile_regular *vfile, struct xnvfile_directory *parent)	
6.45.2.8 xnvfile_init_snapshot(const char *name, struct xnvfile_snapshot *vfile, struct xnvfile_directory *parent)	
6.45.3 Variable Documentation	. 242
6.45.3.1 cobalt_vfroot	. 242
6.45.3.2 cobalt_vfroot	. 242
6.46 Analogy framework	. 243
6.46.1 Detailed Description	. 243
6.47 Driver API	. 244
6.47.1 Detailed Description	. 244
6.48 Driver management services	. 245
6.48.1 Detailed Description	. 245
6.48.2 Function Documentation	. 245
6.48.2.1 a4l_register_drv(struct a4l_driver *drv)	. 245
6.48.2.2 a4l_unregister_drv(struct a4l_driver *drv)	. 246
6.49 Subdevice management services	. 247
6.49.1 Detailed Description	. 248
6.49.2 Function Documentation	. 249
6.49.2.1 a4l_add_subd(struct a4l_device *dev, struct a4l_subdevice *subd)	. 249
6.49.2.2 a4l_alloc_subd(int sizeof_priv, void(*setup)(struct a4l_subdevice *))	. 249
6.49.2.3 a4l_get_subd(struct a4l_device *dev, int idx)	. 249
6.50 Buffer management services	. 251
6.50.1 Detailed Description	. 252

CONTENTS xvii

6.50.2 Function Documentation	. 252
6.50.2.1 a4l_buf_commit_absget(struct a4l_subdevice *subd, unsigned long coun	t)252
6.50.2.2 a4l_buf_commit_absput(struct a4l_subdevice *subd, unsigned long coun	t)253
6.50.2.3 a4l_buf_commit_get(struct a4l_subdevice *subd, unsigned long count) .	. 253
6.50.2.4 a4l_buf_commit_put(struct a4l_subdevice *subd, unsigned long count) .	. 254
6.50.2.5 a4l_buf_count(struct a4l_subdevice *subd)	. 254
6.50.2.6 a4l_buf_evt(struct a4l_subdevice *subd, unsigned long evts)	. 254
6.50.2.7 a4l_buf_get(struct a4l_subdevice *subd, void *bufdata, unsigned long count)	
6.50.2.8 a4I_buf_prepare_absget(struct a4I_subdevice *subd, unsigned long coun	<mark>1t)</mark> 255
6.50.2.9 a4I_buf_prepare_absput(struct a4I_subdevice *subd, unsigned long coun	ıt)255
6.50.2.10a4l_buf_prepare_get(struct a4l_subdevice *subd, unsigned long count) .	. 256
6.50.2.11a4l_buf_prepare_put(struct a4l_subdevice *subd, unsigned long count) .	. 256
6.50.2.12a4l_buf_put(struct a4l_subdevice *subd, void *bufdata, unsigned long count)	
6.50.2.13a4l_get_chan(struct a4l_subdevice *subd)	. 258
6.50.2.14a4l_get_cmd(struct a4l_subdevice *subd)	. 258
6.51 Interrupt management services	. 259
6.51.1 Detailed Description	. 259
6.51.2 Function Documentation	. 259
6.51.2.1 a4l_free_irq(struct a4l_device *dev, unsigned int irq)	. 259
6.51.2.2 a4l_get_irq(struct a4l_device *dev)	. 259
6.51.2.3 a4l_request_irq(struct a4l_device ∗dev, unsigned int irq, a4l_irq_hdlr_↔ t handler, unsigned long flags, void ∗cookie)	
6.52 Misc services	
6.52.1 Detailed Description	. 262
6.52.2 Function Documentation	. 262
6.52.2.1 a4l_get_time(void)	. 262
6.53 Clocks and timers	. 263
6.53.1 Detailed Description	. 263
6.53.2 Function Documentation	. 264
6.53.2.1 clock_getres(clockid_t clock_id, struct timespec *tp)	. 264
6.53.2.2 clock_gettime(clockid_t clock_id, struct timespec *tp)	. 264
6.53.2.3 clock_nanosleep(clockid_t clock_id, int flags, const struct timespec *rqtp, struct timespec *rmtp)	. 265
6.53.2.4 clock_settime(clockid_t clock_id, const struct timespec ∗tp)	266
6.53.2.5 nanosleep(const struct timespec *rqtp, struct timespec *rmtp)	266
6.53.2.6 timer_create(clockid_t clockid, const struct sigevent *restrict evp, timer_t *restrict timerid)	. 268
6.53.2.7 timer_delete(timer_t timerid)	. 269
6.53.2.8 timer_getoverrun(timer_t timerid)	269

xviii CONTENTS

6.53.2.9 timer_gettime(timer_t timerid, struct itimerspec *value)	. 270
6.53.2.10timer_settime(timer_t timerid, int flags, const struct itimerspec ∗↔ restrict value, struct itimerspec ∗restrict ovalue)	
6.54 Condition variables	. 272
6.54.1 Detailed Description	. 272
6.54.2 Function Documentation	. 273
6.54.2.1 pthread_cond_broadcast(pthread_cond_t *cond)	. 273
6.54.2.2 pthread_cond_destroy(pthread_cond_t *cond)	. 273
6.54.2.3 pthread_cond_init(pthread_cond_t *cond, const pthread_condattr_t *attr	274
6.54.2.4 pthread_cond_signal(pthread_cond_t *cond)	. 275
6.54.2.5 pthread_cond_timedwait(pthread_cond_t *cond, pthread_mutex_← t *mutex, const struct timespec *abstime)	
6.54.2.6 pthread_cond_wait(pthread_cond_t *cond, pthread_mutex_t *mutex) .	. 277
6.54.2.7 pthread_condattr_destroy(pthread_condattr_t *attr)	. 277
6.54.2.8 pthread_condattr_getclock(const_pthread_condattr_t_*attr,_clockid_← t *clk_id)	
6.54.2.9 pthread_condattr_getpshared(const pthread_condattr_t *attr, int *pshare	<mark>d)</mark> 278
6.54.2.10pthread_condattr_init(pthread_condattr_t *attr)	. 279
6.54.2.11pthread_condattr_setclock(pthread_condattr_t *attr, clockid_t clk_id)	. 280
6.54.2.12pthread_condattr_setpshared(pthread_condattr_t *attr, int pshared)	. 281
6.55 POSIX interface	. 282
6.55.1 Detailed Description	. 283
6.56 Message queues	. 284
6.56.1 Detailed Description	. 284
6.56.2 Function Documentation	
6.56.2.1 mq_close(mqd_t mqd)	. 285
6.56.2.2 mq_getattr(mqd_t mqd, struct mq_attr *attr)	. 285
6.56.2.3 mq_notify(mqd_t mqd, const struct sigevent *evp)	. 286
6.56.2.4 mq_open(const char *name, int oflags,)	. 286
6.56.2.5 mq_receive(mqd_t q, char *buffer, size_t len, unsigned *prio)	. 288
6.56.2.6 mq_send(mqd_t q, const char *buffer, size_t len, unsigned prio)	. 288
6.56.2.7 mq_setattr(mqd_t mqd, const struct mq_attr *restrict attr, struct mq_attr *restrict oattr)	
6.56.2.8 mq_timedreceive(mqd_t q, char *restrict buffer, size_t len, unsigned *restrict prio, const struct timespec *restrict timeout)	
6.56.2.9 mq_timedsend(mqd_t q, const char *buffer, size_t len, unsigned prio, const struct timespec *timeout)	
6.56.2.10mq_unlink(const char *name)	. 291
6.57 Mutual exclusion	. 292
6.57.1 Detailed Description	. 293
6.57.2 Function Documentation	. 293
6.57.2.1 pthread_mutex_destroy(pthread_mutex_t *mutex)	. 293

CONTENTS xix

	6.57.2.2	pthread_mutex_init(pthread_mutex_t *mutex, const pthread_mutexattr-	
		_t *attr)	
		pthread_mutex_lock(pthread_mutex_t *mutex)	295
	6.57.2.4	pthread_mutex_timedlock(pthread_mutex_t *mutex, const struct time-spec *to)	296
	6 57 2 5	pthread_mutex_trylock(pthread_mutex_t *mutex)	
		pthread_mutex_unlock(pthread_mutex_t *mutex)	
		pthread_mutexattr_destroy(pthread_mutexattr_t *attr)	
		pthread_mutexattr_getprotocol(const pthread_mutexattr_t *attr, int *proto)	
		pthread_mutexattr_getpshared(const pthread_mutexattr_t *attr, int *pshared)	
	6 57 2 10	Opthread_mutexattr_gettype(const pthread_mutexattr_t *attr, int *type)	
		1pthread_mutexattr_init(pthread_mutexattr_t *attr)	
		2pthread_mutexattr_setprotocol(pthread_mutexattr_t *attr, int proto)	
		3pthread_mutexattr_setpshared(pthread_mutexattr_t *attr, int pshared)	
		4pthread_mutexattr_settype(pthread_mutexattr_t *attr, int type)	
6 58 Proces		lling	
		Description	
		Documentation	
		sched_get_priority_max(int policy)	
		sched_get_priority_max_ex(int policy)	
		sched_get_priority_min(int policy)	
		sched get priority min ex(int policy)	
		sched_getconfig_np(int cpu, int policy, union sched_config *config, size t *len r)	
	6.58.2.6	sched_getscheduler(pid_t pid)	
		sched_getscheduler_ex(pid_t pid, int *policy_r, struct sched_param_ex *param_ex)	
	6.58.2.8	sched_setconfig_np(int cpu, int policy, const union sched_config *config,	
		size_t len)	308
	6.58.2.9	sched_setscheduler(pid_t pid, int policy, const struct sched_param *param)310
	6.58.2.10	Osched_setscheduler_ex(pid_t pid, int policy, const struct sched_param _ex *param_ex)	311
	6.58.2.1	1sched_yield(void)	312
6.59 Sema	ohores .		313
6.59.1	Detailed	Description	313
6.59.2	Function	Documentation	313
	6.59.2.1	sem_close(sem_t *sem)	313
	6.59.2.2	sem_destroy(sem_t *sem)	315
	6.59.2.3	sem_init(sem_t *sem, int pshared, unsigned int value)	316
	6.59.2.4	sem_post(sem_t *sem)	316
	6.59.2.5	sem_timedwait(sem_t *sem, const struct timespec *abs_timeout)	317

6.59.2.6 sem_trywait(sem_t *sem)	. 318
6.59.2.7 sem_unlink(const char ∗name)	. 318
6.59.2.8 sem_wait(sem_t *sem)	. 319
6.60 Thread management	. 320
6.60.1 Detailed Description	. 320
6.60.2 Function Documentation	. 320
6.60.2.1 pthread_create(pthread_t *ptid_r, const pthread_attr_t *attr, void *(*start)(void *), void *arg)	
6.60.2.2 pthread_join(pthread_t thread, void **retval)	. 321
6.60.2.3 pthread_kill(pthread_t thread, int sig)	. 322
6.60.2.4 pthread_setmode_np(int clrmask, int setmask, int *mode_r)	. 323
6.60.2.5 pthread_setname_np(pthread_t thread, const char *name)	. 324
6.61 Scheduling management	. 325
6.61.1 Detailed Description	. 325
6.61.2 Function Documentation	. 325
6.61.2.1 pthread_getschedparam(pthread_t thread, int *restrict policy, struct sched_param *restrict param)	
6.61.2.2 pthread_getschedparam_ex(pthread_t thread, int *restrict policy_r, struct sched_param_ex *restrict param_ex)	. 326
6.61.2.3 pthread_setschedparam(pthread_t thread, int policy, const struct sched_param *param)	. 326
6.61.2.4 pthread_setschedparam_ex(pthread_t thread, int policy, const struct sched_param_ex *param_ex)	. 328
6.61.2.5 pthread_yield(void)	
6.62 Smokey API	
6.63 Asynchronous acquisition API	
6.63.1 Detailed Description	
6.63.2 Function Documentation	
6.63.2.1 a4l_get_bufsize(a4l_desc_t *dsc, unsigned int idx_subd, unsigned long *size)	. 335
6.63.2.2 a4l_mark_bufrw(a4l_desc_t *dsc, unsigned int idx_subd, unsigned long cur, unsigned long *new)	. 335
6.63.2.3 a4l_mmap(a4l_desc_t *dsc, unsigned int idx_subd, unsigned long size, void **ptr)	. 336
6.63.2.4 a4l_poll(a4l_desc_t *dsc, unsigned int idx_subd, unsigned long ms_ timeout)	. 336
6.63.2.5 a4l_set_bufsize(a4l_desc_t *dsc, unsigned int idx_subd, unsigned long size)	
6.63.2.6 a4l_snd_cancel(a4l_desc_t *dsc, unsigned int idx_subd)	. 337
6.63.2.7 a4l_snd_command(a4l_desc_t *dsc, a4l_cmd_t *cmd)	. 338
6.64 Asynchronous acquisition API	. 339
6.64.1 Detailed Description	. 339
6.64.2 Function Documentation	. 339

CONTENTS xxi

		6.64.2.1	a4l_async_read(a4l_desc_t *dsc, void *buf, size_t nbyte, unsigned long ms_timeout)	339
		6.64.2.2	a4l_async_write(a4l_desc_t *dsc, void *buf, size_t nbyte, unsigned long ms_timeout)	340
6.65	Softwa	re calibra	tion API	341
			Description	
			Documentation	
			a4l_dcaltoraw(a4l_chinfo_t *chan, void *dst, double *src, int cnt, struct a4l_polynomial *converter)	
		6.65.2.2	a4l_get_softcal_converter(struct a4l_polynomial *converter, int subd, int chan, int range, struct a4l_calibration_data *data)	342
		6.65.2.3	$a4l_rawtodcal(a4l_chinfo_t *chan, \ double *dst, \ void *src, \ int \ cnt, \ struct \\ a4l_polynomial *converter) \ \dots \ $	343
		6.65.2.4	$a4l_read_calibration_file(char *name, struct \ a4l_calibration_data *data) \ \ .$	343
6.66	Descri	ptor Sysc	all API	344
	6.66.1	Detailed	Description	344
	6.66.2	Function	Documentation	344
		6.66.2.1	a4l_sys_desc(int fd, a4l_desc_t *dsc, int pass)	344
6.67	Descri	ptor API		346
	6.67.1	Detailed	Description	346
	6.67.2	Function	Documentation	346
		6.67.2.1	a4l_close(a4l_desc_t *dsc)	346
		6.67.2.2	a4l_fill_desc(a4l_desc_t *dsc)	347
		6.67.2.3	a4l_get_chinfo(a4l_desc_t *dsc, unsigned int subd, unsigned int chan, a4l_chinfo_t **info)	347
		6.67.2.4	a4l_get_rnginfo(a4l_desc_t *dsc, unsigned int subd, unsigned int chan, unsigned int rng, a4l_rnginfo_t **info)	347
		6.67.2.5	a4l_get_subdinfo(a4l_desc_t *dsc, unsigned int subd, a4l_sbinfo_t **info)	348
		6.67.2.6	a4l_open(a4l_desc_t *dsc, const char *fname)	348
6.68	Math A	ΝPI		349
	6.68.1	Detailed	Description	349
	6.68.2	Function	Documentation	349
		6.68.2.1	a4l_math_mean(double *pmean, double *val, unsigned nr)	349
		6.68.2.2	a4l_math_polyfit(unsigned r_dim, double *r, double orig, const unsigned dim, double *x, double *y)	349
		6.68.2.3	a4l_math_stddev(double *pstddev, double mean, double *val, unsigned nr	350
		6.68.2.4	a4l_math_stddev_of_mean(double *pstddevm, double mean, double *val, unsigned nr)	350
6.69	Range	/ convers	sion API	351
	6.69.1	Detailed	Description	351
	6.69.2	Function	Documentation	351
		6.69.2.1	$a4l_dtoraw(a4l_chinfo_t *chan, a4l_rnginfo_t *rng, void *dst, double *src, int cnt) \\ \dots $	351

xxii CONTENTS

6.69.2.2 a4l_find_range(a4l_desc_t *dsc, unsigned int idx_subd, unsigned int idx_chan, unsigned long unit, double min, double max, a4l_rnginfo_t **rng)352
6.69.2.3 a4l_ftoraw(a4l_chinfo_t *chan, a4l_rnginfo_t *rng, void *dst, float *src, int cnt)	352
6.69.2.4 a4l_rawtod(a4l_chinfo_t *chan, a4l_rnginfo_t *rng, double *dst, void *src, int cnt)	353
6.69.2.5 a4l_rawtof(a4l_chinfo_t *chan, a4l_rnginfo_t *rng, float *dst, void *src, int cnt)	353
6.69.2.6 a4l_rawtoul(a4l_chinfo_t *chan, unsigned long *dst, void *src, int cnt)	354
6.69.2.7 a4l_sizeof_chan(a4l_chinfo_t *chan)	354
6.69.2.8 a4l_sizeof_subd(a4l_sbinfo_t *subd)	354
6.69.2.9 a4l_ultoraw(a4l_chinfo_t *chan, void *dst, unsigned long *src, int cnt)	355
6.70 Level 1 API	356
6.70.1 Detailed Description	356
6.71 Synchronous acquisition API	357
6.71.1 Detailed Description	359
6.71.2 Function Documentation	359
6.71.2.1 a4l_snd_insn(a4l_desc_t *dsc, a4l_insn_t *arg)	359
6.71.2.2 a4l_snd_insnlist(a4l_desc_t *dsc, a4l_insnlst_t *arg)	359
6.72 Level 2 API	361
6.72.1 Detailed Description	361
6.73 Synchronous acquisition API	362
6.73.1 Detailed Description	362
6.73.2 Function Documentation	362
6.73.2.1 a4l_config_subd(a4l_desc_t *dsc, unsigned int idx_subd, unsigned int type,)	362
6.73.2.2 a4l_sync_dio(a4l_desc_t *dsc, unsigned int idx_subd, void *mask, void *buf)	363
6.73.2.3 a4l_sync_read(a4l_desc_t *dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void *buf, size_t nbyte)	363
6.73.2.4 a4l_sync_write(a4l_desc_t *dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void *buf, size_t nbyte)	364
6.74 Analogy user API	365
6.74.1 Detailed Description	365
6.75 Level 0 API	366
6.75.1 Detailed Description	366
6.76 Basic Syscall API	367
6.76.1 Detailed Description	367
6.76.2 Function Documentation	367
6.76.2.1 a4l_sys_close(int fd)	367
6.76.2.2 a4l_sys_open(const char *fname)	367
6.76.2.3 a4l_sys_read(int fd, void *buf, size_t nbyte)	368

CONTENTS xxiii

6.76.2.4 a4l_sys_write(int fd, void *buf, size_t nbyte)	368
6.77 Attach / detach Syscall API	369
6.77.1 Detailed Description	369
6.77.2 Function Documentation	369
6.77.2.1 a4l_sys_attach(int fd, a4l_lnkdesc_t *arg)	369
6.77.2.2 a4l_sys_bufcfg(int fd, unsigned int idx_subd, unsigned long size)	369
6.77.2.3 a4l_sys_detach(int fd)	370
6.78 Alarm services	371
6.78.1 Detailed Description	371
6.78.2 Function Documentation	371
6.78.2.1 rt_alarm_create(RT_ALARM *alarm, const char *name, void(*handler)(voi *arg), void *arg)	
6.78.2.2 rt_alarm_delete(RT_ALARM *alarm)	372
6.78.2.3 rt_alarm_inquire(RT_ALARM *alarm, RT_ALARM_INFO *info)	372
6.78.2.4 rt_alarm_start(RT_ALARM *alarm, RTIME value, RTIME interval)	373
6.78.2.5 rt_alarm_stop(RT_ALARM *alarm)	373
6.79 Buffer services	375
6.79.1 Detailed Description	376
6.79.2 Macro Definition Documentation	376
6.79.2.1 B_PRIO	376
6.79.3 Function Documentation	376
6.79.3.1 rt_buffer_bind(RT_BUFFER *bf, const char *name, RTIME timeout)	376
6.79.3.2 rt_buffer_clear(RT_BUFFER *bf)	377
6.79.3.3 rt_buffer_create(RT_BUFFER *bf, const char *name, size_t bufsz, int mode)	377
6.79.3.4 rt_buffer_delete(RT_BUFFER *bf)	378
6.79.3.5 rt_buffer_inquire(RT_BUFFER *bf, RT_BUFFER_INFO *info)	378
6.79.3.6 rt_buffer_read(RT_BUFFER *bf, void *ptr, size_t size, RTIME timeout)	379
6.79.3.7 rt_buffer_read_timed(RT_BUFFER *bf, void *ptr, size_t size, const struct timespec *abs_timeout)	379
6.79.3.8 rt_buffer_read_until(RT_BUFFER *bf, void *ptr, size_t size, RTIME timeou	t)380
6.79.3.9 rt_buffer_unbind(RT_BUFFER *bf)	381
6.79.3.10rt_buffer_write(RT_BUFFER *bf, const void *ptr, size_t size, RTIME time-out)	381
6.79.3.11rt_buffer_write_timed(RT_BUFFER *bf, const void *ptr, size_t size, const struct timespec *abs_timeout)	381
6.79.3.12rt_buffer_write_until(RT_BUFFER *bf, const void *ptr, size_t size, RTI ME timeout)	382
6.80 Condition variable services	384
6.80.1 Detailed Description	384
6.80.2 Function Documentation	385
6.80.2.1 rt_cond_bind(RT_COND *cond, const char *name, RTIME timeout)	385

xxiv CONTENTS

6.80.2.2 rt_cond_broadcast(RT_COND *cond)	. 385
6.80.2.3 rt_cond_create(RT_COND *cond, const char *name)	. 386
6.80.2.4 rt_cond_delete(RT_COND *cond)	. 387
6.80.2.5 rt_cond_inquire(RT_COND *cond, RT_COND_INFO *info)	. 387
6.80.2.6 rt_cond_signal(RT_COND *cond)	. 387
6.80.2.7 rt_cond_unbind(RT_COND *cond)	. 388
6.80.2.8 rt_cond_wait(RT_COND *cond, RT_MUTEX *mutex, RTIME timeout)	. 388
6.80.2.9 rt_cond_wait_timed(RT_COND *cond, RT_MUTEX *mutex, const struct timespec *abs_timeout)	
6.80.2.10rt_cond_wait_until(RT_COND ∗cond, RT_MUTEX ∗mutex, RTIME timeou	ı <mark>t)</mark> 389
6.81 Event flag group services	. 390
6.81.1 Detailed Description	. 391
6.81.2 Macro Definition Documentation	. 391
6.81.2.1 EV_ANY	. 391
6.81.2.2 EV_PRIO	. 391
6.81.3 Function Documentation	. 391
6.81.3.1 rt_event_bind(RT_EVENT *event, const char *name, RTIME timeout)	. 391
6.81.3.2 rt_event_clear(RT_EVENT *event, unsigned int mask, unsigned int *mask_r)	
6.81.3.3 rt_event_create(RT_EVENT *event, const char *name, unsigned int ivalue, int mode)	
6.81.3.4 rt_event_delete(RT_EVENT *event)	. 393
6.81.3.5 rt_event_inquire(RT_EVENT *event, RT_EVENT_INFO *info)	. 393
6.81.3.6 rt_event_signal(RT_EVENT *event, unsigned int mask)	. 394
6.81.3.7 rt_event_unbind(RT_EVENT *event)	. 394
6.81.3.8 rt_event_wait(RT_EVENT *event, unsigned int mask, unsigned int *mask_r, int mode, RTIME timeout)	
6.81.3.9 rt_event_wait_timed(RT_EVENT *event, unsigned int mask, unsigned int *mask_r, int mode, const struct timespec *abs_timeout)	
6.81.3.10rt_event_wait_until(RT_EVENT *event, unsigned int mask, unsigned int *mask_r, int mode, RTIME timeout)	
6.82 Heap management services	. 398
6.82.1 Detailed Description	. 399
6.82.2 Macro Definition Documentation	. 399
6.82.2.1 H_PRIO	. 399
6.82.3 Function Documentation	. 399
6.82.3.1 rt_heap_alloc(RT_HEAP *heap, size_t size, RTIME timeout, void **block	<mark>p)</mark> 399
6.82.3.2 rt_heap_alloc_timed(RT_HEAP *heap, size_t size, const struct timespec *abs_timeout, void **blockp)	
6.82.3.3 rt_heap_alloc_until(RT_HEAP *heap, size_t size, RTIME timeout, void **blockp)	
6.82.3.4 rt_heap_bind(RT_HEAP *heap, const char *name, RTIME timeout)	. 400

	P ∗heap, const char ∗name, size_t heapsize, int	Λ 1
,	······································	
	heap, void *block)	
, _		
	P *heap, RT_HEAP_INFO *info)	
	P *heap)	
•		
· ·		
· ·		
, , _	JTEX *mutex, RTIME timeout) 40	J8
*abs_timeout)	RT_MUTEX *mutex, const struct timespec40	
6.84.2.3 rt_mutex_acquire_until(R	T_MUTEX *mutex, RTIME timeout) 40	09
6.84.2.4 rt_mutex_bind(RT_MUTE	X *mutex, const char *name, RTIME timeout) . 40	09
\ _	ΓEX ∗mutex, const char ∗name) 41	
6.84.2.6 rt_mutex_delete(RT_MUT	ΓEX ∗mutex)	10
6.84.2.7 rt_mutex_inquire(RT_MU	TEX *mutex, RT_MUTEX_INFO *info) 41	11
6.84.2.8 rt_mutex_release(RT_MU	JTEX ∗mutex) 41	11
6.84.2.9 rt_mutex_unbind(RT_MU	TEX *mutex)	12
6.85 Message pipe services		13
6.85.1 Detailed Description		13
6.85.2 Macro Definition Documentation .		14
6.85.2.1 P_MINOR_AUTO		14
6.85.2.2 P_URGENT		14
6.85.3 Function Documentation		14
6.85.3.1 rt_pipe_bind(RT_PIPE *p	ipe, const char *name, RTIME timeout) 41	14
	*pipe, const char *name, int minor, size_t pool-	
,		
_, , _ , _	*pipe)	
_, _ , _ ,	ipe, void *buf, size_t size, RTIME timeout) 41	16
	PIPE *pipe, void *buf, size_t size, const struct	17
6.85.3.6 rt_pipe_read_until(RT_PI	PE *pipe, void *buf, size_t size, RTIME timeout) 41	18
6.85.3.7 rt_pipe_stream(RT_PIPE	*pipe, const void *buf, size_t size) 41	19
6.85.3.8 rt_pipe_unbind(RT_PIPE	*pipe)	19
6.85.3.9 rt_pipe_write(RT_PIPE *F	pipe, const void *buf, size_t size, int mode) 42	20
6.86 Message queue services		21
6.86.1 Detailed Description		22
6.86.2 Macro Definition Documentation .		22

xxvi CONTENTS

6.86.2.1 Q_PRIO	22
6.86.3 Function Documentation	22
6.86.3.1 rt_queue_alloc(RT_QUEUE *queue, size_t size)	22
6.86.3.2 rt_queue_bind(RT_QUEUE *queue, const char *name, RTIME timeout) . 42	23
6.86.3.3 rt_queue_create(RT_QUEUE *queue, const char *name, size_t poolsize, size_t qlimit, int mode)	23
6.86.3.4 rt_queue_delete(RT_QUEUE *queue)	24
6.86.3.5 rt_queue_flush(RT_QUEUE *queue) 42	25
6.86.3.6 rt_queue_free(RT_QUEUE *queue, void *buf)	25
6.86.3.7 rt_queue_inquire(RT_QUEUE *queue, RT_QUEUE_INFO *info) 42	26
6.86.3.8 rt_queue_read(RT_QUEUE *queue, void *buf, size_t size, RTIME timeout)42	26
6.86.3.9 rt_queue_read_timed(RT_QUEUE *queue, void *buf, size_t size, const struct timespec *abs_timeout)	26
6.86.3.10rt_queue_read_until(RT_QUEUE *queue, void *buf, size_t size, RTIME timeout)	27
6.86.3.11rt_queue_receive(RT_QUEUE *queue, void **bufp, RTIME timeout) 42	28
6.86.3.12rt_queue_receive_timed(RT_QUEUE *queue, void **bufp, const struct timespec *abs_timeout)	28
6.86.3.13rt_queue_receive_until(RT_QUEUE *queue, void **bufp, RTIME timeout) 42	29
6.86.3.14rt_queue_send(RT_QUEUE *queue, const void *buf, size_t size, int mode)42	29
6.86.3.15rt_queue_unbind(RT_QUEUE *queue)	30
6.87 Semaphore services	31
6.87.1 Detailed Description	32
6.87.2 Macro Definition Documentation	32
6.87.2.1 S_PRIO	32
6.87.3 Function Documentation	32
6.87.3.1 rt_sem_bind(RT_SEM *sem, const char *name, RTIME timeout) 43	32
6.87.3.2 rt_sem_broadcast(RT_SEM *sem)	33
6.87.3.3 rt_sem_create(RT_SEM *sem, const char *name, unsigned long icount, int mode)	33
6.87.3.4 rt_sem_delete(RT_SEM *sem)	34
6.87.3.5 rt_sem_inquire(RT_SEM *sem, RT_SEM_INFO *info)	34
6.87.3.6 rt_sem_p(RT_SEM *sem, RTIME timeout)	35
6.87.3.7 rt_sem_p_timed(RT_SEM *sem, const struct timespec *abs_timeout) 43	35
6.87.3.8 rt_sem_p_until(RT_SEM *sem, RTIME timeout)	36
6.87.3.9 rt_sem_unbind(RT_SEM *sem)	36
6.87.3.10rt_sem_v(RT_SEM *sem)	36
6.88 Task management services	37
6.88.1 Detailed Description	38
6.88.2 Macro Definition Documentation	
6.88.2.1 T_LOCK	39

CONTENTS xxvii

6.88	3.2.2 T_LOPRIO	439
6.88	3.2.3 T_WARNSW	439
6.88.3 Fun	ction Documentation	439
6.88	3.3.1 rt_task_bind(RT_TASK *task, const char *name, RTIME timeout)	439
6.88	3.3.2 rt_task_create(RT_TASK *task, const char *name, int stksize, int prio, int mode)	440
6.88	3.3.3 rt_task_delete(RT_TASK *task)	441
6.88	3.3.4 rt_task_inquire(RT_TASK *task, RT_TASK_INFO *info)	441
6.88	3.3.5 rt_task_join(RT_TASK ∗task)	442
6.88	3.3.6 rt_task_receive(RT_TASK_MCB *mcb_r, RTIME timeout)	443
6.88	3.3.7 rt_task_receive_timed(RT_TASK_MCB *mcb_r, const struct timespec *abs_timeout)	443
6.88	3.3.8 rt_task_receive_until(RT_TASK_MCB *mcb_r, RTIME timeout)	444
6.88	3.3.9 rt_task_reply(int flowid, RT_TASK_MCB *mcb_s)	444
6.88	3.3.10rt_task_resume(RT_TASK *task)	445
6.88	3.3.11rt_task_same(RT_TASK *task1, RT_TASK *task2)	446
6.88	3.3.12rt_task_self(void)	446
6.88	3.3.13rt_task_send(RT_TASK ∗task, RT_TASK_MCB ∗mcb_s, RT_TASK_M↔ CB ∗mcb_r, RTIME timeout)	446
6.88	3.3.14rt_task_send_timed(RT_TASK *task, RT_TASK_MCB *mcb_s, RT_T⇔ ASK_MCB *mcb_r, const struct timespec *abs_timeout)	447
6.88	3.3.15rt_task_send_until(RT_TASK *task, RT_TASK_MCB *mcb_s, RT_TA⇔ SK_MCB *mcb_r, RTIME timeout)	448
6.88	3.3.16rt_task_set_affinity(RT_TASK *task, const cpu_set_t *cpus)	448
6.88	3.3.17rt_task_set_mode(int clrmask, int setmask, int *mode_r)	449
6.88	3.3.18rt_task_set_periodic(RT_TASK *task, RTIME idate, RTIME period)	450
6.88	3.3.19rt_task_set_priority(RT_TASK *task, int prio)	451
6.88	3.3.20rt_task_shadow(RT_TASK *task, const char *name, int prio, int mode) .	451
6.88	3.3.21rt_task_sleep(RTIME delay)	453
6.88	3.3.22rt_task_sleep_until(RTIME date)	453
6.88	3.3.23rt_task_slice(RT_TASK *task, RTIME quantum)	454
6.88	3.3.24rt_task_spawn(RT_TASK *task, const char *name, int stksize, int prio, int mode, void(*entry)(void *arg), void *arg)	454
6.88	3.3.25rt_task_start(RT_TASK *task, void(*entry)(void *arg), void *arg)	455
6.88	3.3.26rt_task_suspend(RT_TASK *task)	455
6.88	3.3.27rt_task_unbind(RT_TASK *task)	456
6.88	3.3.28rt_task_unblock(RT_TASK *task)	456
6.88	3.3.29rt_task_wait_period(unsigned long *overruns_r)	457
6.88	3.3.30rt_task_yield(void)	457
6.89 Timer mana	agement services	459
6.89.1 Deta	ailed Description	459
6.89.2 Type	edef Documentation	459

xxviii CONTENTS

			6.89.2.1	RT_TIMER_INFO	459
		6.89.3	Function	Documentation	460
			6.89.3.1	rt_timer_inquire(RT_TIMER_INFO *info)	460
			6.89.3.2	rt_timer_ns2ticks(SRTIME ns)	460
			6.89.3.3	rt_timer_read(void)	460
			6.89.3.4	rt_timer_spin(RTIME ns)	461
			6.89.3.5	rt_timer_ticks2ns(SRTIME ticks)	461
	6.90	VxWo	rks® emu	lator	462
	6.91	pSOS	® emulate	or	463
	6.92	Transi	tion Kit .		464
		6.92.1	Detailed	Description	464
		6.92.2	Function	Documentation	464
			6.92.2.1	${\tt COMPAT_rt_alarm_create(RT_ALARM * alarm, const \ char * name)} \ . \ . \ .$	464
			6.92.2.2	COMPATrt_event_clear(RT_EVENT *event, unsigned long mask, unsigned long *mask_r)	465
			6.92.2.3	$\label{lem:compatible} COMPAT__rt_event_create(RT_EVENT *event, const char *name, unsigned long ivalue, int mode)$	
			6.92.2.4	${\tt COMPAT_rt_event_signal(RT_EVENT * event, unsigned long mask)} \ \ . \ \ .$	466
			6.92.2.5	COMPATrt_pipe_create(RT_PIPE *pipe, const char *name, int minor, size_t poolsize)	
			6.92.2.6	COMPATrt_task_create(RT_TASK *task, const char *name, int stk-size, int prio, int mode)	468
			6.92.2.7	COMPATrt_task_set_periodic(RT_TASK *task, RTIME idate, RTIME period)	469
			6.92.2.8	pthread_make_periodic_np(pthread_t thread, struct timespec *starttp, struct timespec *periodtp)	470
			6.92.2.9	pthread_wait_np(unsigned long *overruns_r)	470
			6.92.2.10	Ort_alarm_wait(RT_ALARM ∗alarm)	471
7	Data	Struc	ture Docu	umentation	473
	7.1	a4l_ch	annel Str	uct Reference	473
		7.1.1	Detailed	Description	473
		7.1.2	Field Do	cumentation	473
			7.1.2.1	flags	473
			7.1.2.2	nb_bits	473
	7.2	a4l_ch	annels_d	esc Struct Reference	473
		7.2.1	Detailed	Description	474
		7.2.2	Field Do	cumentation	474
			7.2.2.1	chans	474
			7.2.2.2	length	474
			7.2.2.3	mode	474
	7.3	a4l_cr	nd_desc S	Struct Reference	474

CONTENTS xxix

	7.3.1	Detailed Description
	7.3.2	Field Documentation
		7.3.2.1 data_len
		7.3.2.2 idx_subd
7.4	a4l_de	escriptor Struct Reference
	7.4.1	Detailed Description
	7.4.2	Field Documentation
		7.4.2.1 board_name
		7.4.2.2 driver_name
		7.4.2.3 fd
		7.4.2.4 idx_read_subd
		7.4.2.5 idx_write_subd
		7.4.2.6 magic
		7.4.2.7 nb_subd
		7.4.2.8 sbdata
		7.4.2.9 sbsize
7.5	a4l_dr	river Struct Reference
	7.5.1	Detailed Description
7.6	a4l_in	struction Struct Reference
	7.6.1	Detailed Description
	7.6.2	Field Documentation
		7.6.2.1 idx_subd
7.7	a4l_in	struction_list Struct Reference
	7.7.1	Detailed Description
7.8	a4l_ra	inge Struct Reference
	7.8.1	Detailed Description
	7.8.2	Field Documentation
		7.8.2.1 flags
		7.8.2.2 max
		7.8.2.3 min
7.9	a4l_su	ubdevice Struct Reference
	7.9.1	Detailed Description
7.10	atomic	c_t Struct Reference
	7.10.1	Detailed Description
7.11	can_b	ittime Struct Reference
	7.11.1	Detailed Description
7.12	can_b	ittime_btr Struct Reference
	7.12.1	Detailed Description
7.13	can_b	ittime_std Struct Reference
	7.13.1	Detailed Description

7.14 can_filter Struct Reference
7.14.1 Detailed Description
7.14.2 Field Documentation
7.14.2.1 can_id
7.14.2.2 can_mask
7.15 can_frame Struct Reference
7.15.1 Detailed Description
7.15.2 Field Documentation
7.15.2.1 can_id
7.16 can_ifreq Struct Reference
7.16.1 Detailed Description
7.17 macb_dma_desc Struct Reference
7.17.1 Detailed Description
7.18 macb_tx_skb Struct Reference
7.18.1 Detailed Description
7.19 RT_ALARM_INFO Struct Reference
7.19.1 Detailed Description
7.20 RT_BUFFER_INFO Struct Reference
7.20.1 Detailed Description
7.21 RT_COND_INFO Struct Reference
7.21.1 Detailed Description
7.22 RT_EVENT_INFO Struct Reference
7.22.1 Detailed Description
7.23 RT_HEAP_INFO Struct Reference
7.23.1 Detailed Description
7.23.2 Field Documentation
7.23.2.1 heapsize
7.23.2.2 usablemem
7.23.2.3 usedmem
7.24 RT_MUTEX_INFO Struct Reference
7.24.1 Detailed Description
7.24.2 Field Documentation
7.24.2.1 owner
7.25 RT_QUEUE_INFO Struct Reference
7.25.1 Detailed Description
7.26 RT_SEM_INFO Struct Reference
7.26.1 Detailed Description
7.27 RT_TASK_INFO Struct Reference
7.27.1 Detailed Description
7.28 rt_timer_info Struct Reference

CONTENTS xxxi

7.28.1 Detailed Description
7.28.2 Field Documentation
7.28.2.1 date
7.29 rtdm_dev_context Struct Reference
7.29.1 Detailed Description
7.29.2 Field Documentation
7.29.2.1 device
7.30 rtdm_device Struct Reference
7.30.1 Detailed Description
7.30.2 Field Documentation
7.30.2.1 "@11
7.30.2.2 driver
7.30.2.3 label
7.30.2.4 minor
7.31 rtdm_device_info Struct Reference
7.31.1 Detailed Description
7.32 rtdm_driver Struct Reference
7.32.1 Detailed Description
7.32.2 Field Documentation
7.32.2.1 device_count
7.32.2.2 device_flags
7.32.2.3 profile_info
7.33 rtdm_fd_ops Struct Reference
7.33.1 Detailed Description
7.33.2 Field Documentation
7.33.2.1 close
7.33.2.2 get_unmapped_area
7.33.2.3 ioctl_nrt
7.33.2.4 ioctl_rt
7.33.2.5 mmap
7.33.2.6 open
7.33.2.7 read_nrt
7.33.2.8 read_rt
7.33.2.9 recvmsg_nrt
7.33.2.10recvmsg_rt
7.33.2.11select
7.33.2.12sendmsg_nrt
7.33.2.13sendmsg_rt
7.33.2.15write_nrt

xxxii CONTENTS

7.33.2.16write_rt
7.34 rtdm_sm_ops Struct Reference
7.34.1 Detailed Description
7.35 rtipc_port_label Struct Reference
7.35.1 Detailed Description
7.35.2 Field Documentation
7.35.2.1 label
7.36 rtser_config Struct Reference
7.36.1 Detailed Description
7.37 rtser_event Struct Reference
7.37.1 Detailed Description
7.38 rtser_status Struct Reference
7.38.1 Detailed Description
7.39 sockaddr_can Struct Reference
7.39.1 Detailed Description
7.39.2 Field Documentation
7.39.2.1 can_ifindex
7.40 sockaddr_ipc Struct Reference
7.40.1 Detailed Description
7.40.2 Field Documentation
7.40.2.1 sipc_port
7.41 udd_device Struct Reference
7.41.1 Detailed Description
7.41.2 Field Documentation
7.41.2.1 close
7.41.2.2 device_flags
7.41.2.3 device_subclass
7.41.2.4 interrupt
7.41.2.5 ioctl
7.41.2.6 irq
7.41.2.7 mem_regions
7.41.2.8 mmap
7.41.2.9 open
7.42 udd_memregion Struct Reference
7.42.1 Detailed Description
7.42.2 Field Documentation
7.42.2.1 addr
7.42.2.2 len
7.42.2.3 type
7.43 udd_device::udd_reserved Struct Reference

CONTENTS xxxiii

7.43.1 Detailed Description
7.44 udd_signotify Struct Reference
7.44.1 Detailed Description
7.44.2 Field Documentation
7.44.2.1 pid
7.44.2.2 sig
7.45 xnheap::xnbucket Struct Reference
7.45.1 Detailed Description
7.46 xnsched Struct Reference
7.46.1 Detailed Description
7.46.2 Field Documentation
7.46.2.1 cpu
7.46.2.2 curr
7.46.2.3 htimer
7.46.2.4 inesting
7.46.2.5 lflags
7.46.2.6 resched
7.46.2.7 rrbtimer
7.46.2.8 rt
7.46.2.9 status
7.47 xnvfile_lock_ops Struct Reference
7.47.1 Detailed Description
7.47.2 Field Documentation
7.47.2.1 get
7.47.2.2 put
7.48 xnvfile_regular_iterator Struct Reference
7.48.1 Detailed Description
7.48.2 Field Documentation
7.48.2.1 pos
7.48.2.2 private
7.48.2.3 seq
7.48.2.4 vfile
7.49 xnvfile_regular_ops Struct Reference
7.49.1 Detailed Description
7.49.2 Field Documentation
7.49.2.1 begin
7.49.2.2 end
7.49.2.3 next
7.49.2.4 rewind
7.49.2.5 show

XXXIV

			7.49.2.6	store										 		 	518
	7.50	xnvfile	_rev_tag	Struct F	Refere	nce .								 		 	518
		7.50.1	Detailed	Descrip	otion .									 		 	518
		7.50.2	Field Doo	cument	ation .									 		 	519
			7.50.2.1	rev .										 		 	519
	7.51	xnvfile	_snapsho	t Struct	Refer	rence								 		 	519
		7.51.1	Detailed	Descrip	otion .									 		 	519
	7.52	xnvfile	_snapsho	t_iterate	or Stru	uct Re	eferen	ce .						 		 	519
		7.52.1	Detailed	Descrip	otion .									 		 	520
		7.52.2	Field Doo	cument	ation .									 		 	520
			7.52.2.1	databu	ı f									 		 	520
			7.52.2.2	endfn										 		 	520
			7.52.2.3	nrdata										 		 	521
			7.52.2.4	private										 		 	521
			7.52.2.5	seq .										 		 	521
			7.52.2.6	vfile .										 		 	521
	7.53	xnvfile	_snapsho	t_ops S	Struct I	Refere	ence							 		 	521
		7.53.1	Detailed	Descrip	otion .									 		 	521
		7.53.2	Field Doo	cument	ation .									 		 	521
			7.53.2.1	begin										 		 	521
			7.53.2.2	end .										 		 	522
			7.53.2.3	next .										 		 	522
			7.53.2.4	rewind										 		 	523
			7.53.2.5	show										 		 	523
			7.53.2.6	store										 		 	524
8	File	Docum	entation														525
	8.1		e/cobalt/ke	ernel/rto	dm/an	alogy/	/chan	nel r	ange	.h Fil	e Re	fere	nce	 		 	
		8.1.1	Detailed						_								
	8.2	include	e/cobalt/ke	ernel/rto	dm/an:	alogy/	/drive	r.h Fil	le Re	ferer	ice .			 		 	528
		8.2.1	Detailed	Descrip	otion									 		 	528
	8.3	include	e/cobalt/ke	ernel/rto	dm/dri	ver.h	File R	Refere	ence					 		 	529
		8.3.1	Detailed	Descrip	otion .									 		 	533
		8.3.2	Macro De	efinition	ı Docu	ıment	ation							 		 	533
			8.3.2.1	RTDM	_CLAS	SS_M	IAGIC							 		 	533
			8.3.2.2	RTDM	_PRO	FILE_	_INFC)						 		 	534
		8.3.3	Function	Docum	nentati	on								 		 	534
			8.3.3.1	rtdm_f	d_dev	ice(st	ruct rt	tdm_f	fd *fd)				 		 	534
			8.3.3.2	rtdm_f	d_is_ι	ıser(s	truct	rtdm_	_fd *fo	d) .				 		 	534
			8.3.3.3	rtdm_f	d_to_r	orivate	e(stru	ct rtd	m_fd	*fd)				 		 	535

		8.3.3.4 rtdm_private_to_fd(void *dev_private)	35
8.4	include	cobalt/kernel/rtdm/analogy/subdevice.h File Reference 53	35
	8.4.1	Detailed Description	36
8.5	include	rtdm/can.h File Reference	37
	8.5.1	Detailed Description	37
8.6	include	r/rtdm/uapi/can.h File Reference	38
	8.6.1	Detailed Description	14
8.7	include	cobalt/kernel/rtdm/fd.h File Reference	14
	8.7.1	Detailed Description	15
	8.7.2	Function Documentation	15
		8.7.2.1 rtdm_fd_get(int ufd, unsigned int magic)	15
		8.7.2.2 rtdm_fd_lock(struct rtdm_fd *fd)	16
		8.7.2.3 rtdm_fd_put(struct rtdm_fd *fd)	16
		8.7.2.4 rtdm_fd_select(int ufd, struct xnselector *selector, unsigned int type) 54	17
		8.7.2.5 rtdm_fd_unlock(struct rtdm_fd *fd)	18
8.8	include	rtdm/uapi/ipc.h File Reference	18
	8.8.1	Detailed Description	51
8.9	include	r/rtdm/rtdm.h File Reference	51
	8.9.1	Detailed Description	52
8.10	include	rtdm/uapi/rtdm.h File Reference	52
	8.10.1	Detailed Description	53
8.11	include	rtdm/serial.h File Reference	54
	8.11.1	Detailed Description	54
8.12	include	rtdm/uapi/serial.h File Reference	55
	8.12.1	Detailed Description	59
	8.12.2	Macro Definition Documentation	59
		8.12.2.1 RTSER_RTIOC_BREAK_CTL	59
		8.12.2.2 RTSER_RTIOC_GET_CONFIG	59
		8.12.2.3 RTSER_RTIOC_GET_CONTROL	30
		8.12.2.4 RTSER_RTIOC_GET_STATUS	31
		8.12.2.5 RTSER_RTIOC_SET_CONFIG	31
		8.12.2.6 RTSER_RTIOC_SET_CONTROL	32
		8.12.2.7 RTSER_RTIOC_WAIT_EVENT	32
8.13	include	r/rtdm/testing.h File Reference	32
	8.13.1	Detailed Description	33
8.14	include	r/rtdm/uapi/testing.h File Reference	33
	8.14.1	Detailed Description	35
8.15	include	c/cobalt/kernel/rtdm/udd.h File Reference	35
	8.15.1	Detailed Description	37
8.16	include	r/rtdm/uapi/udd.h File Reference	37

xxxvi **CONTENTS**

		8.16.1 Detailed Description	568
	8.17	include/rtdm/analogy.h File Reference	568
		8.17.1 Detailed Description	569
	8.18	include/rtdm/uapi/analogy.h File Reference	569
		8.18.1 Detailed Description	574
		8.18.2 Macro Definition Documentation	574
		8.18.2.1 A4L_RNG_FACTOR	574
	8.19	lib/analogy/calibration.h File Reference	574
		8.19.1 Detailed Description	574
	8.20	lib/analogy/internal.h File Reference	575
		8.20.1 Detailed Description	575
	8.21	lib/analogy/async.c File Reference	576
		8.21.1 Detailed Description	576
	8.22	lib/analogy/calibration.c File Reference	577
		8.22.1 Detailed Description	577
	8.23	lib/analogy/descriptor.c File Reference	578
		8.23.1 Detailed Description	578
	8.24	lib/analogy/range.c File Reference	579
		8.24.1 Detailed Description	580
	8.25	lib/analogy/root_leaf.h File Reference	580
		8.25.1 Detailed Description	580
	8.26	lib/analogy/sync.c File Reference	581
		8.26.1 Detailed Description	581
	8.27	lib/analogy/sys.c File Reference	582
		8.27.1 Detailed Description	582
9	Fyar	mple Documentation	583
	9.1		
	9.2	bufp-readwrite.c	
	9.3	can-rtt.c	
	9.4	cross-link.c	
	9.5	iddp-label.c	
	9.6	iddp-sendrecv.c	
	9.7	rtcanconfig.c	
	9.8	rtcanrecv.c	
	9.9	rtcansend.c	
	9.10	xddp-echo.c	
		xddp-label.c	
		xddp-stream.c	
Inc	lex		623

Chapter 1

API service tags

All services from the Cobalt/POSIX library, or which belong to APIs based on the Copperplate library may be restricted to particular calling contexts, or entail specific side-effects.

Therefore, the information below applies to all application-oriented APIs available with Xenomai, such as the Cobalt/POSIX library, the Alchemy API, and to all RTOS emulators as well. To describe this information, each service documented by this section bears a set of tags when applicable.

The table below matches the tags used throughout the documentation with the description of their meaning for the caller.

Attention

By Xenomai thread, we mean any thread created by a Xenomai API service, including real-time Cobalt/POSIX threads in dual kernel mode. By regular POSIX thread, we mean any thread directly created by the standard *glibc-based* POSIX service over Mercury (i.e. NPTL/linuxthreads pt/read_create()), excluding such threads which have been promoted to the real-time domain afterwards (aka "shadowed") over Cobalt.

Context tags

Tag	Context on entry
xthread-only	Must be called from a Xenomai thread
xhandler-only	Must be called from a Xenomai handler. See
	note.
xcontext	May be called from any Xenomai context
	(thread or handler).
pthread-only	Must be called from a regular POSIX thread
thread-unrestricted	May be called from a Xenomai or regular
	POSIX thread indifferently
xthread-nowait	May be called from a Xenomai thread
	unrestricted, or from a regular thread as a
	non-blocking service only. See note.
unrestricted	May be called from any context previously
	described

Note

A Xenomai handler is used for callback-based notifications from Copperplate-based APIs, such as timeouts. This context is *NOT* mapped to a regular Linux signal handler, it is actually underlaid by a special thread context, so that async-unsafe POSIX services may be invoked internally by the API implementation when running on behalf of such handler. Therefore, calling Xenomai API services from asynchronous regular signal handlers is fundamentally unsafe.

2 API service tags

Possible side-effects when running the application over the Cobalt core (i.e. dual kernel configuration)

Tag	Description
switch-primary	the caller may switch to primary mode
switch-secondary	the caller may switch to secondary mode

Note

As a rule of thumb, any service which might block the caller, causes a switch to primary mode if invoked from secondary mode. This rule might not apply in case the service can complete fully from user-space without any syscall entailed, due to a particular optimization (e.g. fast acquisition of semaphore resources directly from user-space in the non-contended case). Therefore, the switch-{primary, secondary} tags denote either services which will always switch the caller to the mode mentioned, or might have to do so, depending on the context. The absence of such tag indicates that such services can complete in either modes and as such will entail no switch.

Chapter 2

Deprecated List

globalScope> Global COMPAT__rt_alarm_create (RT_ALARM *alarm, const char *name)

This is a compatibility service from the Transition Kit.

globalScope> Global COMPAT__rt_event_clear (RT_EVENT *event, unsigned long mask, unsigned long *mask_r)

This is a compatibility service from the Transition Kit.

globalScope> Global COMPAT__rt_event_create (RT_EVENT *event, const char *name, unsigned long ivalue, int mode)

This is a compatibility service from the Transition Kit.

globalScope> Global COMPAT__rt_event_signal (RT_EVENT *event, unsigned long mask)
This is a compatibility service from the Transition Kit.

globalScope> Global COMPAT__rt_task_create (RT_TASK *task, const char *name, int stksize, int prio, int mode)

This is a compatibility service from the Transition Kit.

globalScope> Global COMPAT__rt_task_set_periodic (RT_TASK *task, RTIME idate, RTIME period)

This is a compatibility service from the Transition Kit.

Module IOCTLs

Passing struct ifreqas a request descriptor for CAN IOCTLs is still accepted for backward compatibility, however it is recommended to switch to struct can_ifreqat the first opportunity.

Module IOCTLs

Passing struct ifreqas a request descriptor for CAN IOCTLs is still accepted for backward compatibility, however it is recommended to switch to struct can_ifreqat the first opportunity.

globalScope> Global pthread_make_periodic_np (pthread_t thread, struct timespec *starttp, struct timespec *periodtp)

This service is a non-portable extension of the Xenomai 2.x POSIX interface, not available with Xenomai 3.x. Instead, Cobalt-based applications should set up a periodic timer using the timer_create(), timer_settime() call pair, then wait for release points via sigwaitinfo(). Overruns can be detected by looking at the siginfo.

si_overrun field. Alternatively, applications may obtain a file descriptor referring to a Cobalt timer via the timerfd() call, and read() from it to wait for timeouts.

globalScope> Global pthread_wait_np (unsigned long *overruns_r)

This service is a non-portable extension of the Xenomai 2.x POSIX interface, not available with Xenomai 3.x. Instead, Cobalt-based applications should set up a

4 Deprecated List

periodic timer using the timer_create(), timer_settime() call pair, then wait for release points via sigwaitinfo(). Overruns can be detected by looking at the siginfo. ⇔ si_overrun field. Alternatively, applications may obtain a file descriptor referring to a Cobalt timer via the timerfd() call, and read() from it to wait for timeouts.

globalScope> Global rt_alarm_wait (RT_ALARM *alarm)

This is a compatibility service from the Transition Kit.

globalScope> Global RTDM_EXECUTE_ATOMICALLY (code_block)

This construct will be phased out in Xenomai 3.0. Please use rtdm_waitqueue services instead.

globalScope> Global rtdm_task_sleep_until (nanosecs_abs_t wakeup_time)

Use rtdm_task_sleep_abs instead!

Generated by Doxygen

Chapter 3

Module Index

3.1 Modules

lere is a list of all modules:
RTDM
RTDM User API
Driver programming interface
Driver to driver services
Device Registration Services
Clock Services
Task Services
Timer Services
Synchronisation Services
Big dual kernel lock
Spinlock with preemption deactivation
Event Services
Semaphore Services
Mutex services
Interrupt Management Services
Non-Real-Time Signalling Services
Utility Services
Device Profiles
User-space driver core
CAN Devices
Serial Devices
Testing Devices
Real-time IPC
Cobalt
Cobalt kernel
Asynchronous Procedure Calls
In-kernel arithmetics
Buffer descriptor
Clock services
Debugging services
Dynamic memory allocation services
Interrupt management
Locking services
Lightweight key-to-object mapping service
Registry services
Thread scheduling control
OOLIED OLIOTA sales I l'assaults

6 Module Index

· · · · · · · · · · · · · · · · · · ·	
•	
Driver API	
Driver management services	
Analogy user API	
Level 1 API	
Asynchronous acquisition API .	
· · · · · · · · · · · · · · · · · · ·	
•	
<u> </u>	
•	
•	
•	
•	
	37:
	373
•	
•	
<u> </u>	
•	
<u> </u>	
<u> </u>	
•	
nanomoniam	

Chapter 4

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

a4l_channel
Structure describing some channel's characteristics
a4l_channels_desc
Structure describing a channels set
a4I_cmd_desc
Structure describing the asynchronous instruction
a4l_descriptor
Structure containing device-information useful to users
a4l_driver
Structure containing driver declaration data
a4l_instruction
Structure describing the synchronous instruction
a4l_instruction_list
Structure describing the list of synchronous instructions
a4l_range
Structure describing a (unique) range
a4l_subdevice
Structure describing the subdevice
atomic_t
Copyright © 2011 Gilles Chanteperdrix gilles.chanteperdrix@xenomai.org 483
can_bittime
Custom CAN bit-time definition
can_bittime_btr
Hardware-specific BTR bit-times
can_bittime_std
Standard bit-time parameters according to Bosch
can_filter Filter for reception of CAN messages
can_frame Raw CAN frame
can_ifreq CAN interface request descriptor
macb dma desc
Hardware DMA descriptor
macb tx skb
Data about an skb which is being transmitted
RT ALARM INFO
Alarm status descriptor
/ iiai iii dialad addoiipidi

8 Data Structure Index

RT_BUFFER_INFO
Buffer status descriptor
RT_COND_INFO
Condition variable status descriptor
Event status descriptor
RT_HEAP_INFO
Heap status descriptor
RT_MUTEX_INFO Mutex status descriptor
RT_QUEUE_INFO
Queue status descriptor
RT_SEM_INFO Semaphore status descriptor
RT_TASK_INFO
Task status descriptor
rt_timer_info Timer status descriptor
rtdm_dev_context
Device context
rtdm_device RTDM device
rtdm device info
Device information
rtdm_driver RTDM driver
rtdm_fd_ops
RTDM file operation descriptor
rtdm_sm_ops RTDM state management handlers
RTDM state management handlers
Port label information structure
rtser_config
Serial device configuration
Additional information about serial device events
rtser_status
Serial device status
Socket address structure for the CAN address family
sockaddr_ipc
Socket address structure for the RTIPC address family
udd_memregion
udd_device::udd_reserved
Reserved to the UDD core
UDD event notification descriptor
xnheap::xnbucket
Log2 bucket list
Scheduling information structure
xnvfile_lock_ops
Vfile locking operations
xnvfile_regular_iterator Regular vfile iterator
xnvfile_regular_ops
Regular vfile operation descriptor

4.1 Data Structures 9

vfile_rev_tag	
Snapshot revision tag	518
vfile_snapshot	
Snapshot vfile descriptor	519
vfile_snapshot_iterator	
Snapshot-driven vfile iterator	519
vfile_snapshot_ops	
Snapshot vfile operation descriptor	521

10 Data Structure Index

Chapter 5

File Index

5.1 File List

Here is a list of all documented files with brief descriptions:

include/alchemy/alarm.h	
include/alchemy/buffer.h	
include/alchemy/compat.h	_
include/alchemy/cond.h	
include/alchemy/event.h	-
include/alchemy/heap.h	_
include/alchemy/mutex.h	-
include/alchemy/pipe.h	-
include/alchemy/queue.h	_
include/alchemy/sem.h	_
include/alchemy/task.h	-
include/alchemy/timer.h	-
include/boilerplate/ancillaries.h	_
include/boilerplate/atomic.h	-
include/boilerplate/compiler.h	
include/boilerplate/debug.h	
include/boilerplate/hash.h	_
include/boilerplate/ libc.h	
include/boilerplate/list.h	-
include/boilerplate/lock.h	_
include/boilerplate/obstack.h	-
include/boilerplate/private-list.h	-
include/boilerplate/scope.h	_
include/boilerplate/setup.h	-
include/boilerplate/shared-list.h	_
include/boilerplate/time.h	_
include/boilerplate/tunables.h	_
include/cobalt/arith.h	
include/cobalt/fcntl.h	
include/cobalt/mqueue.h	-
include/cobalt/pthread.h	_
include/cobalt/sched.h	
include/cobalt/semaphore.h	
include/cobalt/signal.h	-
include/cobalt/stdio.h	
include/cobalt/stdlib.h	
include/cobalt/syslog.h	
include/cobalt/ticks.h	?

12 File Index

include/cobalt/time.h	
include/cobalt/ trace.h	. ??
include/cobalt/ tunables.h	
include/cobalt/ unistd.h	
include/cobalt/wrappers.h	
include/cobalt/boilerplate/ limits.h	
include/cobalt/boilerplate/ sched.h	
include/cobalt/boilerplate/ signal.h	
include/cobalt/boilerplate/ trace.h	
include/cobalt/boilerplate/ wrappers.h	
include/cobalt/kernel/ ancillaries.h	
include/cobalt/kernel/ apc.h	
include/cobalt/kernel/ arith.h	
include/cobalt/kernel/ assert.h	
include/cobalt/kernel/ bheap.h	
include/cobalt/kernel/ bufd.h	
include/cobalt/kernel/ clock.h	
include/cobalt/kernel/ compat.h	
include/cobalt/kernel/ heap.h	
include/cobalt/kernel/ init.h	
include/cobalt/kernel/ intr.h	
include/cobalt/kernel/ list.h	
include/cobalt/kernel/ lock.h	
include/cobalt/kernel/ map.h	
include/cobalt/kernel/ pipe.h	
include/cobalt/kernel/ ppd.h	
include/cobalt/kernel/ registry.h	
include/cobalt/kernel/ sched-idle.h	
include/cobalt/kernel/ sched-quota.h	
include/cobalt/kernel/ sched-rt.h	
include/cobalt/kernel/ sched-sporadic.h	
include/cobalt/kernel/ sched-tp.h	
include/cobalt/kernel/ sched-weak.h	
include/cobalt/kernel/ sched.h	
include/cobalt/kernel/ schedparam.h	
include/cobalt/kernel/ schedqueue.h	. ??
include/cobalt/kernel/ select.h	. ??
include/cobalt/kernel/ stat.h	. ??
include/cobalt/kernel/ synch.h	. ??
include/cobalt/kernel/ thread.h	. ??
include/cobalt/kernel/ timer.h	. ??
include/cobalt/kernel/ trace.h	. ??
include/cobalt/kernel/ tree.h	. ??
include/cobalt/kernel/ vdso.h	. ??
include/cobalt/kernel/ vfile.h	. ??
include/cobalt/kernel/rtdm/ autotune.h	. ??
include/cobalt/kernel/rtdm/ can.h	. ??
include/cobalt/kernel/rtdm/ cobalt.h	. ??
include/cobalt/kernel/rtdm/ compat.h	. ??
include/cobalt/kernel/rtdm/driver.h	
Real-Time Driver Model for Xenomai, driver API header	. 529
include/cobalt/kernel/rtdm/fd.h	. 544
include/cobalt/kernel/rtdm/ ipc.h	. ??
include/cobalt/kernel/rtdm.h	. ??
include/cobalt/kernel/rtdm/ serial.h	. ??
include/cobalt/kernel/rtdm/ testing.h	. ??
include/cobalt/kernel/rtdm/udd.h	
Copyright (C) 2014 Philippe Gerum rpm@xenomai.org	. 565

5.1 File List

include/cobalt/kernel/rtdm/analogy/ buffer.h
include/cobalt/kernel/rtdm/analogy/channel_range.h
Analogy for Linux, channel, range related features
include/cobalt/kernel/rtdm/analogy/command.h
include/cobalt/kernel/rtdm/analogy/context.h
include/cobalt/kernel/rtdm/analogy/device.h
include/cobalt/kernel/rtdm/analogy/driver.h
Analogy for Linux, driver facilities
include/cobalt/kernel/rtdm/analogy/instruction.h
include/cobalt/kernel/rtdm/analogy/rtdm helpers.h
include/cobalt/kernel/rtdm/analogy/subdevice.h
Analogy for Linux, subdevice related features
include/cobalt/kernel/rtdm/analogy/ transfer.h
include/cobalt/sys/cobalt.h
include/cobalt/sys/ioctl.h
include/cobalt/sys/ mman.h
include/cobalt/sys/ select.h
include/cobalt/sys/ socket.h ??
include/cobalt/sys/time.h
include/cobalt/sys/timerfd.h
include/cobalt/uapi/ cond.h
include/cobalt/uapi/ corectl.h
include/cobalt/uapi/ event.h
include/cobalt/uapi/ monitor.h
include/cobalt/uapi/ mutex.h
include/cobalt/uapi/ sched.h ??
5 - 1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 -
5 · · · · · · · · · · · · · · · · · · ·
include/cobalt/uapi/kernel/ limits.h
include/cobalt/uapi/kernel/ pipe.h
include/cobalt/uapi/kernel/ synch.h
include/cobalt/uapi/kernel/thread.h???
include/cobalt/uapi/kernel/trace.h
include/cobalt/uapi/kernel/types.h
include/cobalt/uapi/kernel/ urw.h
include/cobalt/uapi/kernel/vdso.h???
include/copperplate/clockobj.h
include/copperplate/cluster.h
include/copperplate/debug.h
include/copperplate/eventobj.h
include/copperplate/heapobj.h
include/copperplate/reference.h
include/copperplate/registry-obstack.h??
include/copperplate/registry.h
include/copperplate/semobj.h
include/copperplate/syncobj.h
include/copperplate/threadobj.h
include/copperplate/timerobj.h??
include/copperplate/traceobj.h??
include/copperplate/tunables.h
include/copperplate/wrappers.h

14 File Index

include/mercury/ pthread.h	??
include/mercury/boilerplate/ limits.h	??
include/mercury/boilerplate/ sched.h	??
include/mercury/boilerplate/ signal.h	??
include/mercury/boilerplate/ trace.h	
include/mercury/boilerplate/ wrappers.h	??
include/psos/ psos.h	??
include/rtdm/analogy.h	
Analogy for Linux, library facilities	568
include/rtdm/autotune.h	??
include/rtdm/can.h	537
include/rtdm/ ipc.h	??
include/rtdm/rtdm.h	551
include/rtdm/serial.h	
Real-Time Driver Model for Xenomai, serial device profile header	554
include/rtdm/testing.h	
Real-Time Driver Model for Xenomai, testing device profile header	562
include/rtdm/ udd.h	??
include/rtdm/uapi/analogy.h	
Analogy for Linux, UAPI bits	569
include/rtdm/uapi/ autotune.h	??
include/rtdm/uapi/can.h	
Real-Time Driver Model for RT-Socket-CAN, CAN device profile header	538
include/rtdm/uapi/ <mark>ipc.h</mark>	
This file is part of the Xenomai project	548
include/rtdm/uapi/rtdm.h	
Real-Time Driver Model for Xenomai, user API header	552
include/rtdm/uapi/serial.h	
Real-Time Driver Model for Xenomai, serial device profile header	555
include/rtdm/uapi/testing.h	
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header	
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h	563
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project	563 567
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project	563 567 ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project	563 567 ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h	563 567 ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h	563 567 ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h	563 567 ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h	563 567 ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h	563 567 ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/heap.h	563 567 ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/hative/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h	563 567 ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/mutex.h	563 567 ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/mutex.h include/trank/native/pipe.h	563 567 ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/event.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/pipe.h include/trank/native/pipe.h include/trank/native/pipe.h	563 567 ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/ewent.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/mutex.h include/trank/native/pipe.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/queue.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/mutex.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/sem.h include/trank/native/sem.h include/trank/native/sem.h include/trank/native/sem.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/event.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/sem.h include/trank/native/sem.h include/trank/native/sem.h include/trank/native/task.h include/trank/native/task.h include/trank/native/timer.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/hative/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/pipe.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/sem.h include/trank/native/task.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/types.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/pipe.h include/trank/native/queue.h include/trank/native/sem.h include/trank/native/task.h include/trank/native/task.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/types.h include/trank/native/types.h include/trank/posix/pthread.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/sem.h include/trank/native/sem.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/types.h include/trank/posix/pthread.h include/trank/rtdm/rtcan.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/pipe.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/task.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/types.h include/trank/posix/pthread.h include/trank/rtdm/rtdm.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/gipe.h include/trank/native/queue.h include/trank/native/task.h include/trank/native/task.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/types.h include/trank/native/types.h include/trank/posix/pthread.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/trank.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/cond.h include/trank/native/event.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/queue.h include/trank/native/gipe.h include/trank/native/sem.h include/trank/native/sem.h include/trank/native/task.h include/trank/native/types.h include/trank/native/types.h include/trank/posix/pthread.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/event.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/queue.h include/trank/native/jupe.h include/trank/native/types.h include/trank/native/task.h include/trank/native/types.h include/trank/native/types.h include/trank/native/types.h include/trank/posix/pthread.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/udd.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/smokey/smokey.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/heap.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/pipe.h include/trank/native/queue.h include/trank/native/queue.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/timer.h include/trank/native/types.h include/trank/native/types.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtto.h include/trank/rtdm/rttserial.h include/trank/rtdm/rttesting.h include/trank/rtdm/rttesting.h include/vxworks/errnoLib.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??
include/rtdm/uapi/testing.h Real-Time Driver Model for Xenomai, testing device profile header include/rtdm/uapi/udd.h This file is part of the Xenomai project include/smokey/smokey.h include/trank/rtdk.h include/trank/rtdk.h include/trank/native/alarm.h include/trank/native/buffer.h include/trank/native/event.h include/trank/native/event.h include/trank/native/misc.h include/trank/native/misc.h include/trank/native/mutex.h include/trank/native/queue.h include/trank/native/jupe.h include/trank/native/types.h include/trank/native/task.h include/trank/native/types.h include/trank/native/types.h include/trank/native/types.h include/trank/posix/pthread.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtcan.h include/trank/rtdm/rtdm.h include/trank/rtdm/rtdm.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h include/trank/rtdm/rttgc.h	563 567 ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ?? ??

5.1 File List

include/vxworks/lstLib.h	??
include/vxworks/memPartLib.h	??
include/vxworks/msgQLib.h	??
include/vxworks/rngLib.h	??
include/vxworks/semLib.h	??
include/vxworks/ sysLib.h	??
include/vxworks/taskHookLib.h	??
include/vxworks/taskInfo.h	??
include/vxworks/taskLib.h	??
include/vxworks/tickLib.h	??
include/vxworks/types.h	??
include/vxworks/wdLib.h	??
include/xenomai/ init.h	??
include/xenomai/ tunables.h	??
include/xenomai/ version.h	??
kernel/cobalt/ debug.h	??
kernel/cobalt/ procfs.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/ calibration.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/ features.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/ fptest.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/ machine.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/ syscall.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/ syscall32.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/thread.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/wrappers.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/uapi/ arith.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/uapi/ features.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/uapi/fptest.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/uapi/ syscall.h	??
kernel/cobalt/arch/arm/include/asm/xenomai/uapi/ tsc.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/calibration.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/features.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/fptest.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/ machine.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/syscall.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/syscall32.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/ thread.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/wrappers.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/uapi/ arith.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/uapi/features.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/uapi/ fptest.h	??
kernel/cobalt/arch/blackfin/include/asm/xenomai/uapi/syscall.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/ calibration.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/fptest.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/ machine.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/syscall.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/syscall32.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/thread.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/wrappers.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/uapi/ arith.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/uapi/ features.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/uapi/fptest.h	??
kernel/cobalt/arch/powerpc/include/asm/xenomai/uapi/syscall.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ c1e.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ calibration.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ features.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ fptest.h	??
•	

16 File Index

kernel/cobalt/arch/x86/include/asm/xenomai/ machine.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ smi.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ syscall.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/syscall32-table.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ syscall32.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/thread.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/ wrappers.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/uapi/ arith.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/uapi/features.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/uapi/fptest.h	??
kernel/cobalt/arch/x86/include/asm/xenomai/uapi/ syscall.h	??
kernel/cobalt/include/asm-generic/xenomai/ machine.h	??
kernel/cobalt/include/asm-generic/xenomai/mayday.h	??
kernel/cobalt/include/asm-generic/xenomai/ pci_ids.h	??
kernel/cobalt/include/asm-generic/xenomai/syscall.h	??
kernel/cobalt/include/asm-generic/xenomai/syscall32.h	??
kernel/cobalt/include/asm-generic/xenomai/thread.h	??
kernel/cobalt/include/asm-generic/xenomai/wrappers.h	??
kernel/cobalt/include/ipipe/thread_info.h	??
kernel/cobalt/posix/ clock.h	??
kernel/cobalt/posix/cond.h	??
kernel/cobalt/posix/corectl.h	??
kernel/cobalt/posix/event.h	??
kernel/cobalt/posix/ extension.h	??
kernel/cobalt/posix/internal.h	??
kernel/cobalt/posix/io.h	??
kernel/cobalt/posix/memory.h	??
kernel/cobalt/posix/monitor.h	??
kernel/cobalt/posix/mqueue.h	??
kernel/cobalt/posix/mutex.h	??
kernel/cobalt/posix/ process.h	??
kernel/cobalt/posix/ sched.h	??
kernel/cobalt/posix/ sem.h	??
kernel/cobalt/posix/ signal.h	??
kernel/cobalt/posix/ syscall.h	??
kernel/cobalt/posix/ syscall32.h	??
kernel/cobalt/posix/thread.h	??
kernel/cobalt/posix/timer.h	??
kernel/cobalt/posix/timerfd.h	??
kernel/cobalt/rtdm/internal.h	??
kernel/cobalt/trace/cobalt-core.h	??
kernel/cobalt/trace/cobalt-posix.h	?? ??
kernel/cobalt/trace/ cobalt-rtdm.h	??
5, 1	??
kernel/drivers/analogy/intel/8255.h	??
kernel/drivers/analogy/national_instruments/mite.h	??
kernel/drivers/analogy/national_instruments/ ni_mio.h	??
kernel/drivers/analogy/national_instruments/ ni_stc.h	??
kernel/drivers/analogy/national_instruments/ ni_tio.h	??
kernel/drivers/can/ rtcan_dev.n	??
kernel/drivers/can/ rtcan_internal.n kernel/drivers/can/ rtcan_list.h	??
kernel/drivers/can/ rtcan_rist.n	??
kernel/drivers/can/ rtcan_raw.n kernel/drivers/can/ rtcan_socket.h	??
kernel/drivers/can/ rtcan_socket.n	??
kernel/drivers/can/mscan/rtcan mscan.h	??
kernel/drivers/can/mscan/rtcan mscan regs.h	??
kernel/drivers/can/sja1000/ rtcan sja1000.h	??
10011101/01010101010101110111111111111	

5.1 File List

kernel/drivers/can/sja1000/rtcan_sja1000_regs.h
kernel/drivers/ipc/internal.h
kernel/drivers/net/drivers/rt_at91_ether.h
kernel/drivers/net/drivers/rt_eth1394.h
kernel/drivers/net/drivers/rt_fec.h
kernel/drivers/net/drivers/rt_macb.h
kernel/drivers/net/drivers/rt_smc91111.h
kernel/drivers/net/drivers/e1000/e1000.h
kernel/drivers/net/drivers/e1000/e1000_hw.h
kernel/drivers/net/drivers/e1000/e1000_osdep.h
kernel/drivers/net/drivers/e1000/kcompat.h
kernel/drivers/net/drivers/e1000e/ defines.h
kernel/drivers/net/drivers/e1000e/e1000.h
kernel/drivers/net/drivers/e1000e/ hw.h
kernel/drivers/net/drivers/experimental/e1000/e1000.h
kernel/drivers/net/drivers/experimental/e1000/e1000_80003es2lan.h
kernel/drivers/net/drivers/experimental/e1000/e1000_82541.h
kernel/drivers/net/drivers/experimental/e1000/e1000_82543.h
kernel/drivers/net/drivers/experimental/e1000/e1000_82571.h
kernel/drivers/net/drivers/experimental/e1000/e1000_api.h
kernel/drivers/net/drivers/experimental/e1000/e1000_defines.h
kernel/drivers/net/drivers/experimental/e1000/e1000_hw.h
·
kernel/drivers/net/drivers/experimental/e1000/e1000_manage.h
kernel/drivers/net/drivers/experimental/e1000/e1000_nsdep.h
kernel/drivers/net/drivers/experimental/e1000/e1000_bhy.h
kernel/drivers/net/drivers/experimental/e1000/e1000_regs.h
kernel/drivers/net/drivers/experimental/e1000/kcompat.h
kernel/drivers/net/drivers/experimental/rt2500/rt2500pci.h
kernel/drivers/net/drivers/experimental/rt2500/ rt2x00.h
kernel/drivers/net/drivers/igb/e1000_82575.h
kernel/drivers/net/drivers/igb/e1000_defines.h
kernel/drivers/net/drivers/igb/e1000 hw.h
kernel/drivers/net/drivers/igb/e1000_i210.h
kernel/drivers/net/drivers/igb/e1000 mac.h
kernel/drivers/net/drivers/igb/e1000_mbx.h
kernel/drivers/net/drivers/igb/e1000_nvm.h
kernel/drivers/net/drivers/igb/e1000_phy.h
kernel/drivers/net/drivers/igb/e1000_regs.h
kernel/drivers/net/drivers/igb/igb.h
kernel/drivers/net/drivers/mpc52xx_fec/rt_mpc52xx_fec.h
kernel/drivers/net/drivers/tulip/ tulip.h
kernel/drivers/net/stack/include/ipv4_chrdev.h
kernel/drivers/net/stack/include/ nomac_chrdev.h
kernel/drivers/net/stack/include/ rtcfg_chrdev.h
kernel/drivers/net/stack/include/ rtdev.h
kernel/drivers/net/stack/include/ rtdev_mgr.h
kernel/drivers/net/stack/include/rtmac.h
kernel/drivers/net/stack/include/ rtnet.h
kernel/drivers/net/stack/include/rtnet_chrdev.h
kernel/drivers/net/stack/include/rtnet_internal.h
kernel/drivers/net/stack/include/ rtnet_iovec.h
— ·
kernel/drivers/net/stack/include/ rtnet_socket.h
Remei/direcollievolaciviniciude/Haru-III

18 File Index

	?
	?
	?
_ 5	?
—	?
	?
	?
	?
	?
	?
	?
	?
	?
	?
kernel/drivers/net/stack/include/ipv4/route.h	
kernel/drivers/net/stack/include/ipv4/tcp.h	
kernel/drivers/net/stack/include/ipv4/ udp.h	
kernel/drivers/net/stack/include/rtcfg/ rtcfg.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_client_event.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_conn_event.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_event.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_file.h	
kernel/drivers/net/stack/include/rtcfg/ rtcfg_frame.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_ioctl.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_proc.h	
kernel/drivers/net/stack/include/rtcfg/rtcfg_timer.h	
kernel/drivers/net/stack/include/rtmac/rtmac_disc.h	
kernel/drivers/net/stack/include/rtmac/rtmac_proc.h	
kernel/drivers/net/stack/include/rtmac/rtmac_proto.h	
kernel/drivers/net/stack/include/rtmac/rtmac_vnic.h	
kernel/drivers/net/stack/include/rtmac/nomac/nomac.h	
kernel/drivers/net/stack/include/rtmac/nomac/nomac_dev.h	
kernel/drivers/net/stack/include/rtmac/nomac/nomac_ioctl.h	
kernel/drivers/net/stack/include/rtmac/nomac/nomac_proto.h	
kernel/drivers/net/stack/include/rtmac/tdma/tdma.h	
kernel/drivers/net/stack/include/rtmac/tdma/tdma_dev.h	
	?
kernel/drivers/net/stack/include/rtmac/tdma/tdma_proto.h	
	?
and the second of the second o	?
	?
	?
	?
	?
	?
	?
	?
	?
	?
	?
	?
y 1, 1,	?
	?
	?
	?
	?
lib/analogy/async.c	,,
Analogy for Linux, command, transfer, etc	О

5.1 File List

lib/analogy/calibration.c
Analogy for Linux, device, subdevice, etc
lib/analogy/calibration.h
Analogy for Linux, internal calibration declarations
lib/analogy/descriptor.c
Analogy for Linux, descriptor related features
lib/analogy/internal.h
Analogy for Linux, internal declarations
lib/analogy/range.c
Analogy for Linux, range related features
lib/analogy/root_leaf.h
Analogy for Linux, root / leaf system
lib/analogy/sync.c
Analogy for Linux, instruction related features
lib/analogy/sys.c
Analogy for Linux, descriptor related features
lib/cobalt/current.h
lib/cobalt/internal.h
lib/cobalt/umm.h
lib/cobalt/arch/arm/include/asm/xenomai/features.h
lib/cobalt/arch/arm/include/asm/xenomai/syscall.h
lib/cobalt/arch/arm/include/asm/xenomai/tsc.h
lib/cobalt/arch/blackfin/include/asm/xenomai/features.h
lib/cobalt/arch/blackfin/include/asm/xenomai/syscall.h
lib/cobalt/arch/blackfin/include/asm/xenomai/tsc.h
lib/cobalt/arch/powerpc/include/asm/xenomai/features.h
lib/cobalt/arch/powerpc/include/asm/xenomai/syscall.h
lib/cobalt/arch/powerpc/include/asm/xenomai/tsc.h
lib/cobalt/arch/x86/include/asm/xenomai/features.h
lib/cobalt/arch/x86/include/asm/xenomai/syscall.h
lib/cobalt/arch/x86/include/asm/xenomai/tsc.h
lib/copperplate/internal.h
lib/copperplate/regd/sysregfs.h
lib/psos/internal.h
lib/psos/ pt.h
lib/psos/queue.h??
lib/psos/reference.h
lib/psos/ rn.h
lib/psos/ sem.h
lib/psos/task.h
lib/psos/ tm.h
lib/trank/internal.h
lib/vxworks/memPartLib.h
lib/vxworks/msgQLib.h
lib/vxworks/reference.h
lib/vxworks/rngLib.h
lib/vxworks/semLib.h
lib/vxworks/taskHookLib.h
lib/vxworks/taskLib.h
lib/vxworks/tickLib.h
lib/vxworks/ wdLib.h

20 File Index


Chapter 6

Module Documentation

6.1 Channels and ranges

Channels.

Collaboration diagram for Channels and ranges:



Data Structures

- struct a4l_channel
 - Structure describing some channel's characteristics.
- struct a4l_channels_desc
 - Structure describing a channels set.
- struct a4l_range
 - Structure describing a (unique) range.

Macros

- #define A4L_CHAN_GLOBAL 0x10
 - Internal use flag (must not be used by driver developer)
- #define A4L_RNG_GLOBAL 0x8
 - Internal use flag (must not be used by driver developer)
- #define RANGE(x, y)
 - Macro to declare a (unique) range with no unit defined.
- #define RANGE_V(x, y)
 - Macro to declare a (unique) range in Volt.
- #define RANGE_mA(x, y)
 - Macro to declare a (unique) range in milliAmpere.

22 Module Documentation

#define RANGE_ext(x, y)

Macro to declare a (unique) range in some external reference.

• #define A4L RNG GLOBAL RNGDESC 0

Constant to define a ranges descriptor as global (inter-channel)

#define A4L_RNG_PERCHAN_RNGDESC 1

Constant to define a ranges descriptor as specific for a channel.

• #define RNG_GLOBAL(x)

Macro to declare a ranges global descriptor in one line.

Channel reference

Flags to define the channel's reference

#define A4L_CHAN_AREF_GROUND 0x1

Ground reference.

#define A4L_CHAN_AREF_COMMON 0x2

Common reference.

• #define A4L_CHAN_AREF_DIFF 0x4

Differential reference.

#define A4L CHAN AREF OTHER 0x8

Misc reference.

Channels declaration mode

Constant to define whether the channels in a descriptor are identical

• #define A4L CHAN GLOBAL CHANDESC 0

Global declaration, the set contains channels with similar characteristics.

#define A4L_CHAN_PERCHAN_CHANDESC 1

Per channel declaration, the decriptor gathers differents channels.

6.1.1 Detailed Description

Channels.

According to the Analogy nomenclature, the channel is the elementary acquisition entity. One channel is supposed to acquire one data at a time. A channel can be:

- · an analog input or an analog ouput;
- · a digital input or a digital ouput;

Channels are defined by their type and by some other characteristics like:

- their resolutions for analog channels (which usually ranges from 8 to 32 bits);
- · their references;

Such parameters must be declared for each channel composing a subdevice. The structure a4l_channel (struct a4l_channel) is used to define one channel.

Another structure named a4l_channels_desc (struct a4l_channels_desc) gathers all channels for a specific subdevice. This latter structure also stores:

- the channels count;
- the channels declaration mode (A4L_CHAN_GLOBAL_CHANDESC or A4L_CHAN_PERCHAN
 _CHANDESC): if all the channels composing a subdevice are identical, there is no need to declare
 the parameters for each channel; the global declaration mode eases the structure composition.

Usually the channels descriptor looks like this:

Ranges

So as to perform conversion from logical values acquired by the device to physical units, some range structure(s) must be declared on the driver side.

Such structures contain:

- the physical unit type (Volt, Ampere, none);
- the minimal and maximal values:

These range structures must be associated with the channels at subdevice registration time as a channel can work with many ranges. At configuration time (thanks to an Analogy command), one range will be selected for each enabled channel.

Consequently, for each channel, the developer must declare all the possible ranges in a structure called struct a4l_rngtab. Here is an example:

```
struct a41_rngtab example_tab = {
   length: 2,
   rngs: {
        RANGE_V(-5,5),
        RANGE_V(-10,10),
   },
};
```

For each subdevice, a specific structure is designed to gather all the ranges tabs of all the channels. In this structure, called struct a4l_rngdesc, three fields must be filled:

- the declaration mode (A4L_RNG_GLOBAL_RNGDESC or A4L_RNG_PERCHAN_RNGDESC);
- the number of ranges tab;
- the tab of ranges tabs pointers;

Most of the time, the channels which belong to the same subdevice use the same set of ranges. So, there is no need to declare the same ranges for each channel. A macro is defined to prevent redundant declarations: RNG_GLOBAL().


Here is an example:

```
struct a4l_rngdesc example_rng = RNG_GLOBAL(example_tab);
```

24 Module Documentation

6.2 Big dual kernel lock

Collaboration diagram for Big dual kernel lock:



Macros

• #define cobalt_atomic_enter(__context)

Enter atomic section (dual kernel only)

#define cobalt_atomic_leave(__context)

Leave atomic section (dual kernel only)

#define RTDM_EXECUTE_ATOMICALLY(code_block)

Execute code block atomically (DEPRECATED)

6.2.1 Detailed Description

6.2.2 Macro Definition Documentation

```
6.2.2.1 #define cobalt_atomic_enter( __context )
```

Value:

Enter atomic section (dual kernel only)

This call opens a fully atomic section, serializing execution with respect to all interrupt handlers (including for real-time IRQs) and Xenomai threads running on all CPUs.

Parameters

context	name of local variable to store the context in. This variable updated by the real-time
	core will hold the information required to leave the atomic section properly.

Note

Atomic sections may be nested. The caller is allowed to sleep on a blocking Xenomai service from primary mode within an atomic section delimited by cobalt_atomic_enter/cobalt_atomic_eleave calls. On the contrary, sleeping on a regular Linux kernel service while holding such lock is NOT valid.

Since the strongest lock is acquired by this service, it can be used to synchronize real-time and non-real-time contexts.

Warning

This service is not portable to the Mercury core, and should be restricted to Cobalt-specific use cases, mainly for the purpose of porting existing dual-kernel drivers which still depend on the obsolete RTDM_EXECUTE_ATOMICALLY() construct.

```
6.2.2.2 #define cobalt atomic leave( context )
```

Value:

Leave atomic section (dual kernel only)

This call closes an atomic section previously opened by a call to cobalt_atomic_enter(), restoring the preemption and interrupt state which prevailed prior to entering the exited section.

Parameters

```
__context | name of local variable which stored the context.
```

Warning

This service is not portable to the Mercury core, and should be restricted to Cobalt-specific use cases.

```
6.2.2.3 #define RTDM EXECUTE ATOMICALLY( code block )
```

Value:

Execute code block atomically (DEPRECATED)

Generally, it is illegal to suspend the current task by calling rtdm_event_wait(), etc. while holding a spinlock. In contrast, this macro allows to combine several operations including a potentially rescheduling call to an atomic code block with respect to other RTDM_EXECUTE_ATOMICALLY() blocks. The macro is a light-weight alternative for protecting code blocks via mutexes, and it can even be used to synchronise real-time and non-real-time contexts.

Parameters

```
code_block | Commands to be executed atomically
```

Note

It is not allowed to leave the code block explicitly by using break, return, goto, etc. This would leave the global lock held during the code block execution in an inconsistent state. Moreover, do not embed complex operations into the code bock. Consider that they will be executed under preemption lock with interrupts switched-off. Also note that invocation of rescheduling calls may break the atomicity until the task gains the CPU again.

Tags

unrestricted

26 Module Documentation

Deprecated This construct will be phased out in Xenomai 3.0. Please use rtdm_waitqueue services instead.

See also

cobalt_atomic_enter().

6.3 Spinlock with preemption deactivation

Collaboration diagram for Spinlock with preemption deactivation:



Macros

- #define RTDM_LOCK_UNLOCKED(__name) IPIPE_SPIN_LOCK_UNLOCKED
 Static lock initialisation.
- #define rtdm_lock_get_irqsave(__lock, __context) ((__context) = __rtdm_lock_get_irqsave(__ ← lock))

Acquire lock and disable preemption, by stalling the head domain.

- #define rtdm_lock_irqsave(__context) splhigh(__context)
 - Disable preemption locally.
- #define rtdm_lock_irqrestore(__context) splexit(__context)

Restore preemption state.

Typedefs

- typedef ipipe_spinlock_t rtdm_lock_t
 - Lock variable.
- typedef unsigned long rtdm_lockctx_t

Variable to save the context while holding a lock.

Functions

- static void rtdm_lock_init (rtdm_lock_t *lock)
 - Dynamic lock initialisation.
- static void rtdm_lock_get (rtdm_lock_t *lock)

Acquire lock from non-preemptible contexts.

- static void rtdm_lock_put (rtdm_lock_t *lock)
 - Release lock without preemption restoration.
- static void rtdm_lock_put_irqrestore (rtdm_lock_t *lock, rtdm_lockctx_t context)

Release lock and restore preemption state.

6.3.1 Detailed Description

6.3.2 Macro Definition Documentation

28 Module Documentation

```
6.3.2.1 #define rtdm_lock_get_irqsave( __lock, __context ) ((__context) = __rtdm_lock_get_irqsave(__lock))
```

Acquire lock and disable preemption, by stalling the head domain.

Parameters

lock	Address of lock variable
context	name of local variable to store the context in

Tags

unrestricted

Referenced by rtdm_ratelimit().

6.3.2.2 #define rtdm_lock_irgrestore(__context) splexit(__context)

Restore preemption state.

Parameters

context	name of local variable which stored the context

Tags

unrestricted

6.3.2.3 #define rtdm_lock_irqsave(__context) splhigh(__context)

Disable preemption locally.

Parameters

context	name of local variable to store the context in
---------	--

Tags

unrestricted

6.3.3 Function Documentation

6.3.3.1 static void rtdm_lock_get (rtdm_lock_t * lock) [inline], [static]

Acquire lock from non-preemptible contexts.

Parameters

```
lock Address of lock variable
```

Tags

unrestricted

References spltest.

6.3.3.2 static void rtdm_lock_init (rtdm_lock_t * lock) [inline], [static]

Dynamic lock initialisation.

Parameters

lock	Address of lock variable

Tags

task-unrestricted

```
6.3.3.3 static void rtdm_lock_put ( rtdm_lock_t * lock ) [inline], [static]
```

Release lock without preemption restoration.

Parameters

Tags

unrestricted, might-switch

Release lock and restore preemption state.

Parameters

lock	Address of lock variable
context	name of local variable which stored the context


Tags

unrestricted

Referenced by rtdm_ratelimit().

6.4 User-space driver core

This profile includes all mini-drivers sitting on top of the User-space Device Driver framework (UDD). Collaboration diagram for User-space driver core:



Data Structures

- struct udd_memregion
- struct udd device
- struct udd device::udd reserved

Reserved to the UDD core.

struct udd_signotify

UDD event notification descriptor.

Functions

• int udd_register_device (struct udd_device *udd)

Register a UDD device.

• int udd unregister device (struct udd device *udd)

Unregister a UDD device.

struct udd_device * udd_get_device (struct rtdm_fd *fd)

RTDM file descriptor to target UDD device.

void udd_notify_event (struct udd_device *udd)

Notify an IRQ event for an unmanaged interrupt.

void udd_enable_irq (struct udd_device *udd, rtdm_event_t *done)

Enable the device IRQ line.

void udd_disable_irq (struct udd_device *udd, rtdm_event_t *done)

Disable the device IRQ line.

• #define UDD_IRQ_NONE 0

No IRQ managed.

#define UDD_IRQ_CUSTOM (-1)

IRQ directly managed from the mini-driver on top of the UDD core.

Memory types for mapping

Types of memory for mapping

The UDD core implements a default ->mmap() handler which first attempts to hand over the request to the corresponding handler defined by the mini-driver. If not present, the UDD core establishes the mapping automatically, depending on the memory type defined for the region.

Module Documentation

• #define UDD_MEM_NONE 0

No memory region.

• #define UDD MEM PHYS 1

Physical I/O memory region.

#define UDD MEM LOGICAL 2

Kernel logical memory region (e.g.

• #define UDD MEM VIRTUAL 3

Virtual memory region with no direct physical mapping (e.g.

UDD IOCTL

IOCTL requests

• #define UDD_RTIOC_IRQEN_IO(RTDM_CLASS_UDD, 0)

Enable the interrupt line.

#define UDD_RTIOC_IRQDIS_IO(RTDM_CLASS_UDD, 1)

Disable the interrupt line.

• #define UDD RTIOC IRQSIG IOW(RTDM CLASS UDD, 2, struct udd signotify)

Enable/Disable signal notification upon interrupt event.

6.4.1 Detailed Description

This profile includes all mini-drivers sitting on top of the User-space Device Driver framework (UDD).

The generic UDD core driver enables interrupt control and I/O memory access interfaces to user-space device drivers, as defined by the mini-drivers when registering.

A mini-driver supplements the UDD core with ancillary functions for dealing with memory mappings and interrupt control for a particular I/O card/device.

UDD-compliant mini-drivers only have to provide the basic support for dealing with the interrupt sources present in the device, so that most part of the device requests can be handled from a Xenomai application running in user-space. Typically, a mini-driver would handle the interrupt top-half, and the user-space application would handle the bottom-half.

This profile is reminiscent of the UIO framework available with the Linux kernel, adapted to the dual kernel Cobalt environment.

6.4.2 Macro Definition Documentation

```
6.4.2.1 #define UDD IRQ CUSTOM (-1)
```

IRQ directly managed from the mini-driver on top of the UDD core.

The mini-driver is in charge of attaching the handler(s) to the IRQ(s) it manages, notifying the Cobalt threads waiting for IRQ events by calling the udd notify event() service.

Referenced by $udd_disable_irq()$, $udd_enable_irq()$, $udd_register_device()$, and $udd_unregister_device()$.

6.4.2.2 #define UDD_IRQ_NONE 0

No IRQ managed.

Special IRQ values for udd_device.irq Passing this code implicitly disables all interrupt-related services, including control (disable/enable) and notification.

Referenced by udd_disable_irq(), udd_enable_irq(), udd_register_device(), and udd_unregister_ device().

6.4.2.3 #define UDD_MEM_LOGICAL 2

Kernel logical memory region (e.g.

kmalloc()). By default, the UDD core maps such memory to a virtual user range by calling the rtdm_\circ} mmap kmem() service.

6.4.2.4 #define UDD_MEM_NONE 0

No memory region.

Use this type code to disable an entry in the array of memory mappings, i.e. udd_device.mem_regions[]. Referenced by udd_register_device(), and udd_unregister_device().

6.4.2.5 #define UDD MEM PHYS 1

Physical I/O memory region.

By default, the UDD core maps such memory to a virtual user range by calling the rtdm_mmap_iomem() service.

6.4.2.6 #define UDD MEM VIRTUAL 3

Virtual memory region with no direct physical mapping (e.g.

vmalloc()). By default, the UDD core maps such memory to a virtual user range by calling the rtdm_\circ} mmap_vmem() service.

6.4.2.7 #define UDD RTIOC IRQDIS IO(RTDM CLASS UDD, 1)

Disable the interrupt line.

The UDD-class mini-driver should handle this request when received through its ->ioctl() handler if provided. Otherwise, the UDD core disables the interrupt line in the interrupt controller before returning to the caller.

Note

The mini-driver must handle the UDD_RTIOC_IRQEN request for a custom IRQ from its ->ioctl() handler, otherwise such request receives -EIO from the UDD core.

6.4.2.8 #define UDD RTIOC IRQEN IO(RTDM CLASS UDD, 0)

Enable the interrupt line.

The UDD-class mini-driver should handle this request when received through its ->ioctl() handler if provided. Otherwise, the UDD core enables the interrupt line in the interrupt controller before returning to the caller.

34 Module Documentation

6.4.2.9 #define UDD_RTIOC_IRQSIG_IOW(RTDM_CLASS_UDD, 2, struct udd_signotify)

Enable/Disable signal notification upon interrupt event.

A valid notification descriptor must be passed along with this request, which is handled by the UDD core directly.

Note

The mini-driver must handle the UDD_RTIOC_IRQDIS request for a custom IRQ from its ->ioctl() handler, otherwise such request receives -EIO from the UDD core.

6.4.3 Function Documentation

6.4.3.1 void udd disable irq (struct udd device * udd, rtdm event t * done)

Disable the device IRQ line.

This service issues a request to the regular kernel for disabling the IRQ line registered by the driver. If the caller runs in primary mode, the request is scheduled but deferred until the current CPU leaves the real-time domain (see note). Otherwise, the request is immediately handled.

Parameters

uc	dd	The UDD driver handling the IRQ to disable. If no IRQ was registered by the driver at the UDD core, this routine has no effect.
dor	- 1	Optional event to signal upon completion. If non-NULL, done will be posted by a call
		to rtdm_event_signal() after the interrupt line is disabled.

Tags

unrestricted

Note

The deferral is required as some interrupt management code involved in disabling interrupt lines may not be safely executed from primary mode. By passing a valid *done* object address, the caller can wait for the request to complete, by sleeping on rtdm_event_wait().

References udd device::irg, UDD IRQ CUSTOM, and UDD IRQ NONE.

6.4.3.2 void udd enable irg (struct udd device * udd, rtdm event t * done)

Enable the device IRQ line.

This service issues a request to the regular kernel for enabling the IRQ line registered by the driver. If the caller runs in primary mode, the request is scheduled but deferred until the current CPU leaves the real-time domain (see note). Otherwise, the request is immediately handled.

Parameters

udd	The UDD driver handling the IRQ to disable. If no IRQ was registered by the driver
	at the UDD core, this routine has no effect.
done	Optional event to signal upon completion. If non-NULL, done will be posted by a call
	to rtdm_event_signal() after the interrupt line is enabled.

Tags

unrestricted

Note

The deferral is required as some interrupt management code involved in enabling interrupt lines may not be safely executed from primary mode. By passing a valid *done* object address, the caller can wait for the request to complete, by sleeping on rtdm_event_wait().

References udd_device::irq, UDD_IRQ_CUSTOM, and UDD_IRQ_NONE.

6.4.3.3 struct udd device* udd get device (struct rtdm fd * fd)

RTDM file descriptor to target UDD device.

Retrieves the UDD device from a RTDM file descriptor.

Parameters

fd	File descriptor received by an ancillary I/O handler from a mini-driver based on the
	UDD core.

Returns

A pointer to the UDD device to which fd refers to.

Note

This service is intended for use by mini-drivers based on the UDD core exclusively. Passing file descriptors referring to other RTDM devices will certainly lead to invalid results.

Tags

mode-unrestricted

References rtdm device::driver, rtdm driver::profile info, and rtdm fd device().

```
6.4.3.4 void udd_notify_event ( struct udd_device * udd )
```

Notify an IRQ event for an unmanaged interrupt.

When the UDD core shall hand over the interrupt management for a device to the mini-driver (see U → DD_IRQ_CUSTOM), the latter should notify the UDD core when IRQ events are received by calling this service.

As a result, the UDD core wakes up any Cobalt thread waiting for interrupts on the device via a read(2) or select(2) call.

Parameters

udd UDD device descriptor receiving the IRQ.
--

Tags

coreirq-only

Note

In case the IRQ handler from the mini-driver requested the UDD core not to re-enable the interrupt line, the application may later request the unmasking by issuing the UDD_RTIOC_IRQEN ioctl(2) command. Writing a non-zero integer to the device via the write(2) system call has the same effect.

References rtdm_event_signal().

Module Documentation

6.4.3.5 int udd_register_device (struct udd_device * udd)

Register a UDD device.

This routine registers a mini-driver at the UDD core.

Parameters

udd UDD device descriptor which should describe the new device properties.

Returns

Zero is returned upon success, otherwise a negative error code is received, from the set of error codes defined by rtdm_dev_register(). In addition, the following error codes can be returned:

- -EINVAL, some of the memory regions declared in the udd_device.mem_regions[] array have invalid properties, i.e. bad type, NULL name, zero length or address. Any undeclared region entry from the array must bear the UDD MEM NONE type.
- -EINVAL, if udd_device.irq is different from UDD_IRQ_CUSTOM and UDD_IRQ_NONE but invalid, causing rtdm_irq_request() to fail.
- -EINVAL, if udd device.device flags contains invalid flags.
- -ENXIO can be received if this service is called while the Cobalt kernel is disabled.

Tags

secondary-only

References rtdm_driver::context_size, rtdm_driver::device_count, udd_device::device_flags, rtdm_ cdriver::device_flags, rtdm_device::device_flags, rtdm_device::device_flags, rtdm_device::label, udd_device::mem_regions, rtdm_fd_ops::open, rtdm_driver::ops, rtdm_driver::profile_info, rtdm_devc_register(), rtdm_dev_unregister(), rtdm_event_init(), rtdm_irq_request(), RTDM_NAMED_DEVICE, RTDM_PROTOCOL_DEVICE, udd_memregion::type, UDD_IRQ_CUSTOM, UDD_IRQ_NONE, and UDD_MEM_NONE.

6.4.3.6 int udd_unregister_device (struct udd_device * udd)

Unregister a UDD device.

This routine unregisters a mini-driver from the UDD core. This routine waits until all connections to *udd* have been closed prior to unregistering.

Parameters

udd UDD device descriptor

Returns

Zero is returned upon success, otherwise -ENXIO is received if this service is called while the Cobalt kernel is disabled.

Tags

secondary-only

References udd_device::irq, udd_device::mem_regions, rtdm_dev_unregister(), rtdm_event_destroy(), rtdm_irq_free(), udd_memregion::type, UDD_IRQ_CUSTOM, UDD_IRQ_NONE, and UDD_MEM_N ONE.

6.5 Thread state flags

Bits reporting permanent or transient states of threads.

Collaboration diagram for Thread state flags:



Macros

#define XNSUSP 0x00000001

Suspended.

• #define XNPEND 0x00000002

Sleep-wait for a resource.

#define XNDELAY 0x00000004

Delayed.

#define XNREADY 0x00000008

Linked to the ready queue.

#define XNDORMANT 0x00000010

Not started yet.

• #define XNZOMBIE 0x00000020

Zombie thread in deletion process.

• #define XNMAPPED 0x00000040

Thread is mapped to a linux task.

• #define XNRELAX 0x00000080

Relaxed shadow thread (blocking bit)
• #define XNMIGRATE 0x00000100

Thread is currently migrating to another CPU.

• #define XNHELD 0x00000200

Thread is held to process emergency.

• #define XNBOOST 0x00000400

Undergoes a PIP boost.

• #define XNSSTEP 0x00000800

Single-stepped by debugger.

• #define XNLOCK 0x00001000

Scheduler lock control (pseudo-bit, not in -> state)

• #define XNRRB 0x00002000

Undergoes a round-robin scheduling.

• #define XNWARN 0x00004000

Issue SIGDEBUG on error detection.

#define XNFPU 0x00008000

Thread uses FPU.

• #define XNROOT 0x00010000

Root thread (that is, Linux/IDLE)

• #define XNWEAK 0x00020000

Non real-time shadow (from the WEAK class)

#define XNUSER 0x00040000

Shadow thread running in userland.

#define XNJOINED 0x00080000

Another thread waits for joining this thread.

• #define XNTRAPLB 0x00100000

Trap lock break (i.e.

#define XNDEBUG 0x00200000

User-level debugging enabled.

6.5.1 Detailed Description

Bits reporting permanent or transient states of threads.

6.5.2 Macro Definition Documentation

6.5.2.1 #define XNHELD 0x00000200

Thread is held to process emergency.

Referenced by xnthread resume(), and xnthread suspend().

6.5.2.2 #define XNMIGRATE 0x00000100

Thread is currently migrating to another CPU.

6.5.2.3 #define XNPEND 0x00000002

Sleep-wait for a resource.

Referenced by xnsynch_acquire(), xnsynch_flush(), xnsynch_sleep_on(), xnsynch_wakeup_one_← sleeper(), xnsynch_wakeup_this_sleeper(), xnthread_resume(), and xnthread_unblock().

6.5.2.4 #define XNREADY 0x00000008

Linked to the ready queue.

Referenced by xnthread_resume(), and xnthread_suspend().

6.5.2.5 #define XNSUSP 0x00000001

Suspended.

Referenced by xnthread_init(), xnthread_start(), and xnthread_suspend().

6.5.2.6 #define XNTRAPLB 0x00100000

Trap lock break (i.e.


may not sleep with sched lock)

Referenced by xnthread_suspend().

6.6 Thread information flags

Bits reporting events notified to threads.

Collaboration diagram for Thread information flags:



Macros

#define XNTIMEO 0x00000001

Woken up due to a timeout condition.

• #define XNRMID 0x00000002

Pending on a removed resource.

• #define XNBREAK 0x00000004

Forcibly awaken from a wait state.

#define XNKICKED 0x00000008

Forced out of primary mode.

• #define XNWAKEN 0x00000010

Thread waken up upon resource availability.

• #define XNROBBED 0x00000020

Robbed from resource ownership.

• #define XNCANCELD 0x00000040

Cancellation request is pending.

#define XNPIALERT 0x00000080

Priority inversion alert (SIGDEBUG sent)

• #define XNMOVED 0x00000001

CPU migration in primary mode occurred.

#define XNLBALERT 0x00000002

Scheduler lock break alert (SIGDEBUG sent)

6.6.1 Detailed Description

Bits reporting events notified to threads.

40 Module Documentation

6.7 CAN Devices

This is the common interface a RTDM-compliant CAN device has to provide.

Collaboration diagram for CAN Devices:



Data Structures

struct can_bittime_std

Standard bit-time parameters according to Bosch.

struct can_bittime_btr

Hardware-specific BTR bit-times.

• struct can_bittime

Custom CAN bit-time definition.

struct can_filter

Filter for reception of CAN messages.

struct sockaddr_can

Socket address structure for the CAN address family.

struct can_frame

Raw CAN frame.

struct can_ifreq

CAN interface request descriptor.

Macros

#define AF CAN 29

CAN address family.

#define PF_CAN AF_CAN

CAN protocol family.

#define SOL CAN RAW 103

CAN socket levels.

Typedefs

typedef uint32 t can id t

Type of CAN id (see CAN_xxx_MASK and CAN_xxx_FLAG)

• typedef can_id_t can_err_mask_t

Type of CAN error mask.

typedef uint32_t can_baudrate_t

Baudrate definition in bits per second.

typedef enum CAN_BITTIME_TYPE can_bittime_type_t

See CAN_BITTIME_TYPE.

typedef enum CAN_MODE can_mode_t

See CAN MODE.

typedef int can_ctrlmode_t

See CAN CTRLMODE.

typedef enum CAN_STATE can_state_t

See CAN_STATE.

typedef struct can_filter can_filter_t

Filter for reception of CAN messages.

typedef struct can_frame can_frame_t

Raw CAN frame.

Enumerations

enum CAN_BITTIME_TYPE { CAN_BITTIME_STD, CAN_BITTIME_BTR }
 Supported CAN bit-time types.

CAN ID masks

Bit masks for masking CAN IDs

• #define CAN_EFF_MASK 0x1FFFFFFF

Bit mask for extended CAN IDs.

• #define CAN_SFF_MASK 0x000007FF

Bit mask for standard CAN IDs.

CAN ID flags

Flags within a CAN ID indicating special CAN frame attributes

#define CAN_EFF_FLAG 0x80000000

Extended frame.

• #define CAN RTR FLAG 0x40000000

Remote transmission frame.

• #define CAN_ERR_FLAG 0x20000000

Error frame (see Errors), not valid in struct can_filter.

#define CAN_INV_FILTER CAN_ERR_FLAG

Invert CAN filter definition, only valid in struct can filter.

Particular CAN protocols

Possible protocols for the PF_CAN protocol family Currently only the RAW protocol is supported.

• #define CAN RAW 1

Raw protocol of PF_CAN, applicable to socket type SOCK_RAW.

42 Module Documentation

CAN operation modes

Modes into which CAN controllers can be set

• enum CAN MODE { CAN MODE STOP = 0, CAN MODE START, CAN MODE SLEEP }

CAN controller modes

Special CAN controllers modes, which can be or'ed together.

Note

These modes are hardware-dependent. Please consult the hardware manual of the CAN controller for more detailed information.

- #define CAN CTRLMODE LISTENONLY 0x1
- #define CAN CTRLMODE LOOPBACK 0x2
- #define CAN_CTRLMODE_3_SAMPLES 0x4

CAN controller states

States a CAN controller can be in.

```
    enum CAN_STATE {
        CAN_STATE_ERROR_ACTIVE = 0, CAN_STATE_ACTIVE = 0, CAN_STATE_ERROR_WAR
        NING = 1, CAN_STATE_BUS_WARNING = 1,
        CAN_STATE_ERROR_PASSIVE = 2, CAN_STATE_BUS_PASSIVE = 2, CAN_STATE_BUS_
        OFF, CAN_STATE_SCANNING_BAUDRATE,
        CAN_STATE_STOPPED, CAN_STATE_SLEEPING }
```

Timestamp switches

Arguments to pass to RTCAN RTIOC TAKE TIMESTAMP

- #define RTCAN_TAKE_NO_TIMESTAMPS 0
 Switch off taking timestamps.
- #define RTCAN_TAKE_TIMESTAMPS 1
 Do take timestamps.

RAW socket options

Setting and getting CAN RAW socket options.

- #define CAN_RAW_FILTER 0x1
 - CAN filter definition.
- #define CAN_RAW_ERR_FILTER 0x2

CAN error mask.

- #define CAN_RAW_LOOPBACK 0x3
 - CAN TX loopback.
- #define CAN_RAW_RECV_OWN_MSGS 0x4

CAN receive own messages.

IOCTLs

CAN device IOCTLs

- #define SIOCGIFINDEX defined_by_kernel_header_file

 Get CAN interface index by name.
- #define SIOCSCANBAUDRATE _IOW(RTIOC_TYPE_CAN, 0x01, struct can_ifreq)
 Set baud rate.
- #define SIOCGCANBAUDRATE _IOWR(RTIOC_TYPE_CAN, 0x02, struct can_ifreq)
 Get baud rate.
- #define SIOCSCANCUSTOMBITTIME _IOW(RTIOC_TYPE_CAN, 0x03, struct can_ifreq) Set custom bit time parameter.
- #define SIOCGCANCUSTOMBITTIME _IOWR(RTIOC_TYPE_CAN, 0x04, struct can_ifreq)
 Get custom bit-time parameters.
- #define SIOCSCANMODE _IOW(RTIOC_TYPE_CAN, 0x05, struct can_ifreq)
 Set operation mode of CAN controller.
- #define SIOCGCANSTATE _IOWR(RTIOC_TYPE_CAN, 0x06, struct can_ifreq)
 Get current state of CAN controller.
- #define SIOCSCANCTRLMODE _IOW(RTIOC_TYPE_CAN, 0x07, struct can_ifreq)
 Set special controller modes.
- #define SIOCGCANCTRLMODE _IOWR(RTIOC_TYPE_CAN, 0x08, struct can_ifreq)
 Get special controller modes.
- #define RTCAN_RTIOC_TAKE_TIMESTAMP_IOW(RTIOC_TYPE_CAN, 0x09, int)

 Enable or disable storing a high precision timestamp upon reception of a CAN frame.
- #define RTCAN_RTIOC_RCV_TIMEOUT _IOW(RTIOC_TYPE_CAN, 0x0A, nanosecs_rel_t) Specify a reception timeout for a socket.
- #define RTCAN_RTIOC_SND_TIMEOUT_IOW(RTIOC_TYPE_CAN, 0x0B, nanosecs_rel_t)
 Specify a transmission timeout for a socket.

Error mask

Error class (mask) in can_id field of struct can_frame to be used with CAN_RAW_ERR_FILTER.

Note: Error reporting is hardware dependent and most CAN controllers report less detailed error conditions than the SJA1000.

Note: In case of a bus-off error condition (CAN_ERR_BUSOFF), the CAN controller is **not** restarted automatically. It is the application's responsibility to react appropriately, e.g. calling CAN_MODE_STA⊷ RT.

Note: Bus error interrupts (CAN_ERR_BUSERROR) are enabled when an application is calling a Recv function on a socket listening on bus errors (using CAN_RAW_ERR_FILTER). After one bus error has occured, the interrupt will be disabled to allow the application time for error processing and to efficiently avoid bus error interrupt flooding.

- #define CAN_ERR_TX_TIMEOUT 0x00000001U
 TX timeout (netdevice driver)
- #define CAN_ERR_LOSTARB 0x00000002U
 - Lost arbitration (see data[0])
- #define CAN ERR CRTL 0x00000004U

Controller problems (see data[1])

• #define CAN_ERR_PROT 0x00000008U

Protocol violations (see data[2], data[3])

#define CAN_ERR_TRX 0x00000010U

Transceiver status (see data[4])

#define CAN_ERR_ACK 0x00000020U

Received no ACK on transmission.

- #define CAN_ERR_BUSOFF 0x00000040U
 Bus off.
- #define CAN_ERR_BUSERROR 0x00000080U
 Bus error (may flood!)
- #define CAN_ERR_RESTARTED 0x00000100U
 Controller restarted.
- #define CAN_ERR_MASK 0x1FFFFFFFU
 Omit EFF, RTR, ERR flags.

Arbitration lost error

Error in the data[0] field of struct can_frame.

 #define CAN_ERR_LOSTARB_UNSPEC 0x00 unspecified

Controller problems

Error in the data[1] field of struct can_frame.

- #define CAN_ERR_CRTL_UNSPEC 0x00
 unspecified
- #define CAN_ERR_CRTL_RX_OVERFLOW 0x01
 RX buffer overflow.
- #define CAN_ERR_CRTL_TX_OVERFLOW 0x02
 TX buffer overflow.
- #define CAN_ERR_CRTL_RX_WARNING 0x04
 reached warning level for RX errors
- #define CAN_ERR_CRTL_TX_WARNING 0x08
 reached warning level for TX errors
- #define CAN_ERR_CRTL_RX_PASSIVE 0x10
 reached passive level for RX errors
- #define CAN_ERR_CRTL_TX_PASSIVE 0x20
 reached passive level for TX errors

Protocol error type

Error in the data[2] field of struct can_frame.

- #define CAN_ERR_PROT_UNSPEC 0x00
 unspecified
- #define CAN_ERR_PROT_BIT 0x01

single bit error

#define CAN_ERR_PROT_FORM 0x02

frame format error

 #define CAN_ERR_PROT_STUFF 0x04 bit stuffing error

#define CAN_ERR_PROT_BIT0 0x08

unable to send dominant bit

#define CAN_ERR_PROT_BIT1 0x10

unable to send recessive bit

 #define CAN_ERR_PROT_OVERLOAD 0x20 bus overload

#define CAN_ERR_PROT_ACTIVE 0x40
 active error announcement

#define CAN ERR PROT TX 0x80

error occured on transmission

Protocol error location

Error in the data[4] field of struct can_frame.

- #define CAN_ERR_PROT_LOC_UNSPEC 0x00 unspecified
- #define CAN_ERR_PROT_LOC_SOF 0x03
 start of frame
- #define CAN_ERR_PROT_LOC_ID28_21 0x02
 ID bits 28 21 (SFF: 10 3)
- #define CAN_ERR_PROT_LOC_ID20_18 0x06
 ID bits 20 18 (SFF: 2 0)
- #define CAN_ERR_PROT_LOC_SRTR 0x04 substitute RTR (SFF: RTR)
- #define CAN_ERR_PROT_LOC_IDE 0x05
 identifier extension
- #define CAN_ERR_PROT_LOC_ID17_13 0x07
 ID bits 17-13.
- #define CAN_ERR_PROT_LOC_ID12_05 0x0F
 ID bits 12-5.
- #define CAN_ERR_PROT_LOC_ID04_00 0x0E
 ID bits 4-0.
- #define CAN_ERR_PROT_LOC_RTR 0x0C
 RTR.
- #define CAN_ERR_PROT_LOC_RES1 0x0D
 reserved bit 1
- #define CAN_ERR_PROT_LOC_RES0 0x09
 reserved bit 0
- #define CAN_ERR_PROT_LOC_DLC 0x0B data length code
- #define CAN_ERR_PROT_LOC_DATA 0x0A data section
- #define CAN_ERR_PROT_LOC_CRC_SEQ 0x08 CRC sequence.

- #define CAN_ERR_PROT_LOC_CRC_DEL 0x18
 CRC delimiter.
- #define CAN_ERR_PROT_LOC_ACK 0x19
 ACK slot.
- #define CAN_ERR_PROT_LOC_ACK_DEL 0x1B ACK delimiter.
- #define CAN_ERR_PROT_LOC_EOF 0x1A
 end of frame
- #define CAN_ERR_PROT_LOC_INTERM 0x12 intermission
- #define CAN_ERR_TRX_UNSPEC 0x00 0000 0000
- #define CAN_ERR_TRX_CANH_NO_WIRE 0x04 0000 0100
- #define CAN_ERR_TRX_CANH_SHORT_TO_BAT 0x05 0000 0101
- #define CAN_ERR_TRX_CANH_SHORT_TO_VCC 0x06 0000 0110
- #define CAN_ERR_TRX_CANH_SHORT_TO_GND 0x07 0000 0111
- #define CAN_ERR_TRX_CANL_NO_WIRE 0x40 0100 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_BAT 0x50
 0101 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_VCC 0x60 0110 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_GND 0x70 0111 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_CANH 0x80 1000 0000

6.7.1 Detailed Description

This is the common interface a RTDM-compliant CAN device has to provide.

Feel free to report bugs and comments on this profile to the "Socketcan" mailing list (Socketcan-core@lists. ← berlios.de) or directly to the authors (wg@grandegger.com or Sebastian.Smolorz@stud. ← uni-hannover.de).

Profile Revision: 2

Device Characteristics

Device Flags: RTDM_PROTOCOL_DEVICE

Protocol Family: PF_CAN

Socket Type: SOCK_RAW

Device Class: RTDM_CLASS_CAN

Supported Operations

Socket

Tags

secondary-only

Specific return values:

• -EPROTONOSUPPORT (Protocol is not supported by the driver. See CAN protocols for possible protocols.)

Close

Blocking calls to any of the Send or Receive functions will be unblocked when the socket is closed and return with an error.

Tags

secondary-only

Specific return values: none

IOCTL

Tags

task-unrestricted. see below Specific return values: see below

Bind

Binds a socket to one or all CAN devices (see struct sockaddr_can). If a filter list has been defined with setsockopt (see Sockopts), it will be used upon reception of CAN frames to decide whether the bound socket will receive a frame. If no filter has been defined, the socket will receive all CAN frames on the specified interface(s).

Binding to special interface index 0 will make the socket receive CAN frames from all CAN interfaces.

Binding to an interface index is also relevant for the Send functions because they will transmit a message over the interface the socket is bound to when no socket address is given to them.

Tags

secondary-only

Specific return values:

- -EFAULT (It was not possible to access user space memory area at the specified address.)
- -ENOMEM (Not enough memory to fulfill the operation)
- -EINVAL (Invalid address family, or invalid length of address structure)
- -ENODEV (Invalid CAN interface index)
- -ENOSPC (No enough space for filter list)

- -EBADF (Socket is about to be closed)
- -EAGAIN (Too many receivers. Old binding (if any) is still active. Close some sockets and try again.)

Setsockopt, Getsockopt

These functions allow to set and get various socket options. Currently, only CAN raw sockets are supported.

Supported Levels and Options:

- Level SOL_CAN_RAW : CAN RAW protocol (see CAN_RAW)
 - Option CAN RAW FILTER: CAN filter list
 - Option CAN_RAW_ERR_FILTER: CAN error mask
 - Option CAN_RAW_LOOPBACK : CAN TX loopback to local sockets

Tags

task-unrestricted Specific return values: see links to options above.

Recv, Recvfrom, Recvmsg

These functions receive CAN messages from a socket. Only one message per call can be received, so only one buffer with the correct length must be passed. For SOCK_RAW, this is the size of struct can_frame.

Unlike a call to one of the <u>Send</u> functions, a Recv function will not return with an error if an interface is down (due to bus-off or setting of stop mode) or in sleep mode. Moreover, in such a case there may still be some CAN messages in the socket buffer which could be read out successfully.

It is possible to receive a high precision timestamp with every CAN message. The condition is a former instruction to the socket via RTCAN_RTIOC_TAKE_TIMESTAMP. The timestamp will be copied to the msg_control buffer of struct msghdr if it points to a valid memory location with size of nanosecs abs t. If this is a NULL pointer the timestamp will be discarded silently.

Note: A msg_controllen of 0 upon completion of the function call indicates that no timestamp is available for that message.

Supported Flags [in]:

- MSG_DONTWAIT (By setting this flag the operation will only succeed if it would not block, i.e.
 if there is a message in the socket buffer. This flag takes precedence over a timeout specified
 by RTCAN_RTIOC_RCV_TIMEOUT.)
- MSG_PEEK (Receive a message but leave it in the socket buffer. The next receive operation will get that message again.)

Supported Flags [out]: none

Tags

mode-unrestricted

Specific return values:

• Non-negative value (Indicating the successful reception of a CAN message. For SOCK_RAW, this is the size of struct can_frame regardless of the actual size of the payload.)

- -EFAULT (It was not possible to access user space memory area at one of the specified addresses.)
- -EINVAL (Unsupported flag detected, or invalid length of socket address buffer, or invalid length of message control buffer)
- -EMSGSIZE (Zero or more than one iovec buffer passed, or buffer too small)
- -EAGAIN (No data available in non-blocking mode)
- -EBADF (Socket was closed.)
- -EINTR (Operation was interrupted explicitly or by signal.)
- -ETIMEDOUT (Timeout)

Send, Sendto, Sendmsg

These functions send out CAN messages. Only one message per call can be transmitted, so only one buffer with the correct length must be passed. For SOCK_RAW, this is the size of struct can frame.

The following only applies to SOCK_RAW: If a socket address of struct sockaddr_can is given, only can_ifindex is used. It is also possible to omit the socket address. Then the interface the socket is bound to will be used for sending messages.

If an interface goes down (due to bus-off or setting of stop mode) all senders that were blocked on this interface will be woken up.

Supported Flags:

 MSG_DONTWAIT (By setting this flag the transmit operation will only succeed if it would not block. This flag takes precedence over a timeout specified by RTCAN_RTIOC_SND_TIME ← OUT.)

Tags

mode-unrestricted

Specific return values:

- Non-negative value equal to given buffer size (Indicating the successful completion of the function call. See also note.)
- -EOPNOTSUPP (MSG_OOB flag is not supported.)
- -EINVAL (Unsupported flag detected *or:* Invalid length of socket address *or:* Invalid address family *or:* Data length code of CAN frame not between 0 and 15 *or:* CAN standard frame has got an ID not between 0 and 2031)
- -EMSGSIZE (Zero or more than one buffer passed or invalid size of buffer)
- -EFAULT (It was not possible to access user space memory area at one of the specified addresses.)
- -ENXIO (Invalid CAN interface index 0 is not allowed here or socket not bound or rather bound to all interfaces.)
- -ENETDOWN (Controller is bus-off or in stopped state.)
- -ECOMM (Controller is sleeping)
- -EAGAIN (Cannot transmit without blocking but a non-blocking call was requested.)
- -EINTR (Operation was interrupted explicitly or by signal)
- -EBADF (Socket was closed.)
- -ETIMEDOUT (Timeout)

Note: A successful completion of the function call does not implicate a successful transmission of the message.

6.7.2 Macro Definition Documentation

6.7.2.1 #define CAN_CTRLMODE_3_SAMPLES 0x4

Triple sampling mode

In this mode the CAN controller uses Triple sampling.

6.7.2.2 #define CAN CTRLMODE LISTENONLY 0x1

Listen-Only mode

In this mode the CAN controller would give no acknowledge to the CAN-bus, even if a message is received successfully and messages would not be transmitted. This mode might be useful for busmonitoring, hot-plugging or throughput analysis.

Examples:

rtcanconfig.c.

6.7.2.3 #define CAN_CTRLMODE_LOOPBACK 0x2

Loopback mode

In this mode the CAN controller does an internal loop-back, a message is transmitted and simultaneously received. That mode can be used for self test operation.

Examples:

rtcanconfig.c.

6.7.2.4 #define CAN_ERR_LOSTARB_UNSPEC 0x00

unspecified

else bit number in bitstream

6.7.2.5 #define CAN RAW ERR FILTER 0x2

CAN error mask.

A CAN error mask (see Errors) can be set with setsockopt. This mask is then used to decide if error frames are delivered to this socket in case of error condidtions. The error frames are marked with the CAN_ERR_FLAG of CAN_xxx_FLAG and must be handled by the application properly. A detailed description of the errors can be found in the can_id and the data fields of struct can_frame (see Errors for futher details).

Parameters

in level SOL_CAN_RAW	in	level	SOL_CAN_RAW
----------------------	----	-------	-------------

in	optname	CAN_RAW_ERR_FILTER
in	optval	Pointer to error mask of type can_err_mask_t.
in	optlen	Size of error mask: sizeof(can_err_mask_t).

Tags

task-unrestricted

Specific return values:

- -EFAULT (It was not possible to access user space memory area at the specified address.)
- -EINVAL (Invalid length "optlen")

Examples:

rtcanrecv.c.

6.7.2.6 #define CAN RAW FILTER 0x1

CAN filter definition.

A CAN raw filter list with elements of struct can_filter can be installed with setsockopt. This list is used upon reception of CAN frames to decide whether the bound socket will receive a frame. An empty filter list can also be defined using optlen = 0, which is recommanded for write-only sockets. If the socket was already bound with Bind, the old filter list gets replaced with the new one. Be aware that already received, but not read out CAN frames may stay in the socket buffer.

Parameters

in	level	SOL_CAN_RAW
in	optname	CAN_RAW_FILTER
in	optval	Pointer to array of struct can_filter.
in	optlen	Size of filter list: count * sizeof(struct can_filter).

Tags

task-unrestricted

Specific return values:

- -EFAULT (It was not possible to access user space memory area at the specified address.)
- -ENOMEM (Not enough memory to fulfill the operation)
- -EINVAL (Invalid length "optlen")
- -ENOSPC (No space to store filter list, check RT-Socket-CAN kernel parameters)

Examples:

can-rtt.c, rtcanrecv.c, and rtcansend.c.

6.7.2.7 #define CAN_RAW_LOOPBACK 0x3

CAN TX loopback.

The TX loopback to other local sockets can be selected with this setsockopt.

52 Module Documentation

Note

The TX loopback feature must be enabled in the kernel and then the loopback to other local TX sockets is enabled by default.

Parameters

in	level	SOL_CAN_RAW
in	optname	CAN_RAW_LOOPBACK
in	optval	Pointer to integer value.
in	optlen	Size of int: sizeof(int).

Tags

task-unrestricted

Specific return values:

- -EFAULT (It was not possible to access user space memory area at the specified address.)
- -EINVAL (Invalid length "optlen")
- -EOPNOTSUPP (not supported, check RT-Socket-CAN kernel parameters).

Examples:

rtcansend.c.

6.7.2.8 #define CAN_RAW_RECV_OWN_MSGS 0x4

CAN receive own messages.

Not supported by RT-Socket-CAN, but defined for compatibility with Socket-CAN.

Specify a reception timeout for a socket.

Defines a timeout for all receive operations via a socket which will take effect when one of the receive functions is called without the MSG_DONTWAIT flag set.

The default value for a newly created socket is an infinite timeout.

Note

The setting of the timeout value is not done atomically to avoid locks. Please set the value before receiving messages from the socket.

Parameters

in	arg	Pointer to nanosecs_rel_t variable. The value is interpreted as relative
		timeout in nanoseconds in case of a positive value. See Timeouts for
		special timeouts.

Returns

0 on success, otherwise:

• -EFAULT: It was not possible to access user space memory area at the specified address.

Tags

task-unrestricted

Examples:

rtcanrecv.c.

6.7.2.10 #define RTCAN_RTIOC_SND_TIMEOUT_IOW(RTIOC_TYPE_CAN, 0x0B, nanosecs rel t)

Specify a transmission timeout for a socket.

Defines a timeout for all send operations via a socket which will take effect when one of the send functions is called without the MSG_DONTWAIT flag set.

The default value for a newly created socket is an infinite timeout.

Note

The setting of the timeout value is not done atomically to avoid locks. Please set the value before sending messages to the socket.

Parameters

in	arg	Pointer to nanosecs_rel_t variable. The value is interpreted as relative
		timeout in nanoseconds in case of a positive value. See Timeouts for
		special timeouts.

Returns

0 on success, otherwise:

• -EFAULT: It was not possible to access user space memory area at the specified address.

Tags

task-unrestricted

Examples:

rtcansend.c.

6.7.2.11 #define RTCAN RTIOC TAKE TIMESTAMP IOW(RTIOC TYPE CAN, 0x09, int)

Enable or disable storing a high precision timestamp upon reception of a CAN frame.

A newly created socket takes no timestamps by default.

Parameters

in	arg	int variable, see Timestamp switches

Returns

0 on success.

Tags

task-unrestricted

Note

Activating taking timestamps only has an effect on newly received CAN messages from the bus. Frames that already are in the socket buffer do not have timestamps if it was deactivated before. See Receive for more details.

Examples:

rtcanrecv.c.

6.7.2.12 #define SIOCGCANBAUDRATE _IOWR(RTIOC_TYPE_CAN, 0x02, struct can_ifreq)

Get baud rate.

Parameters

in,out	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr←
		_name must hold a valid CAN interface name, ifr_ifru will be filled
		with an instance of can_baudrate_t.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EINVAL: No baud rate was set yet.

Tags

task-unrestricted

6.7.2.13 #define SIOCGCANCTRLMODE _IOWR(RTIOC_TYPE_CAN, 0x08, struct can_ifreq)

Get special controller modes.

Parameters

in	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr↔
		_name must hold a valid CAN interface name, ifr_ifru must be filled
		with an instance of can_ctrlmode_t.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EINVAL: No baud rate was set yet.

Tags

task-unrestricted, might-switch

6.7.2.14 #define SIOCGCANCUSTOMBITTIME _IOWR(RTIOC_TYPE_CAN, 0x04, struct can_ifreq)

Get custom bit-time parameters.

Parameters

in,out	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr←
		_name must hold a valid CAN interface name, ifr_ifru will be filled
		with an instance of struct can_bittime.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EINVAL: No baud rate was set yet.

Tags

task-unrestricted

6.7.2.15 #define SIOCGCANSTATE _IOWR(RTIOC_TYPE_CAN, 0x06, struct can_ifreq)

Get current state of CAN controller.

States are divided into main states and additional error indicators. A CAN controller is always in exactly one main state. CAN bus errors are registered by the CAN hardware and collected by the driver. There is one error indicator (bit) per error type. If this IOCTL is triggered the error types which occured since the last call of this IOCTL are reported and thereafter the error indicators are cleared. See also CAN controller states.

Parameters

in,out	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr↔
		_name must hold a valid CAN interface name, ifr_ifru will be filled
		with an instance of can_mode_t.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.

Tags

task-unrestricted, might-switch

6.7.2.16 #define SIOCGIFINDEX defined_by_kernel_header_file

Get CAN interface index by name.

Parameters

in,out	arg	Pointer to interface request structure buffer (struct can_ifreq). If
		ifr_name holds a valid CAN interface name ifr_ifindex will be filled
		with the corresponding interface index.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.

Tags

task-unrestricted

Examples:

can-rtt.c, rtcanconfig.c, rtcanrecv.c, and rtcansend.c.

6.7.2.17 #define SIOCSCANBAUDRATE _IOW(RTIOC_TYPE_CAN, 0x01, struct can_ifreq)

Set baud rate.

The baudrate must be specified in bits per second. The driver will try to calculate resonable CAN bit-timing parameters. You can use SIOCSCANCUSTOMBITTIME to set custom bit-timing.

Parameters

in	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr⊷
		_name must hold a valid CAN interface name, ifr_ifru must be filled
		with an instance of can_baudrate_t.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EINVAL: No valid baud rate, see can_baudrate_t.
- -EDOM : Baud rate not possible.
- -EAGAIN: Request could not be successully fulfilled. Try again.

Tags

task-unrestricted, might-switch

Note

Setting the baud rate is a configuration task. It should be done deliberately or otherwise CAN messages will likely be lost.

Examples:

rtcanconfig.c.

6.7.2.18 #define SIOCSCANCTRLMODE _IOW(RTIOC_TYPE_CAN, 0x07, struct can_ifreq)

Set special controller modes.

Various special controller modes could be or'ed together (see CAN CTRLMODE for further information).

Parameters

in	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr←
		_name must hold a valid CAN interface name, ifr_ifru must be filled
		with an instance of can_ctrlmode_t.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EINVAL: No valid baud rate, see can baudrate t.
- -EAGAIN: Request could not be successully fulfilled. Try again.

Tags

task-unrestricted, might-switch

Note

Setting special controller modes is a configuration task. It should be done deliberately or otherwise CAN messages will likely be lost.

Examples:

rtcanconfig.c.

6.7.2.19 #define SIOCSCANCUSTOMBITTIME _IOW(RTIOC_TYPE_CAN, 0x03, struct can_ifreq)

Set custom bit time parameter.

Custem-bit time could be defined in various formats (see struct can_bittime).

Parameters

in	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr↔
		_name must hold a valid CAN interface name, ifr_ifru must be filled
		with an instance of struct can_bittime.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EINVAL: No valid baud rate, see can_baudrate_t.
- -EAGAIN: Request could not be successully fulfilled. Try again.

Tags

task-unrestricted, might-switch

Note

Setting the bit-time is a configuration task. It should be done deliberately or otherwise CAN messages will likely be lost.

Examples:

rtcanconfig.c.

6.7.2.20 #define SIOCSCANMODE _IOW(RTIOC_TYPE_CAN, 0x05, struct can_ifreq)

Set operation mode of CAN controller.

See CAN controller modes for available modes.

Parameters

in	arg	Pointer to interface request structure buffer (struct can_ifreq). ifr↔
		_name must hold a valid CAN interface name, ifr_ifru must be filled
		with an instance of can_mode_t.

Returns

0 on success, otherwise:

- -EFAULT: It was not possible to access user space memory area at the specified address.
- -ENODEV: No device with specified name exists.
- -EAGAIN: (CAN_MODE_START, CAN_MODE_STOP) Could not successfully set mode, hardware is busy. Try again.
- -EINVAL: (CAN_MODE_START) Cannot start controller, set baud rate first.
- -ENETDOWN: (CAN_MODE_SLEEP) Cannot go into sleep mode because controller is stopped or bus off.
- -EOPNOTSUPP: unknown mode

Tags

task-unrestricted, might-switch

Note

Setting a CAN controller into normal operation after a bus-off can take some time (128 occurrences of 11 consecutive recessive bits). In such a case, although this IOCTL will return immediately with success and SIOCGCANSTATE will report CAN_STATE_ACTIVE, bus-off recovery may still be in progress.

If a controller is bus-off, setting it into stop mode will return no error but the controller remains bus-off.

Examples:

rtcanconfig.c.

6.7.2.21 #define SOL_CAN_RAW 103

CAN socket levels.

Used for Sockopts for the particular protocols.

Examples:

can-rtt.c, rtcanrecv.c, and rtcansend.c.

6.7.3 Typedef Documentation

6.7.3.1 typedef struct can filter can filter t

Filter for reception of CAN messages.

This filter works as follows: A received CAN ID is AND'ed bitwise with can_mask and then compared to can_id. This also includes the CAN_EFF_FLAG and CAN_RTR_FLAG of CAN_xxx_FLAG. If this comparison is true, the message will be received by the socket. The logic can be inverted with the can_id flag CAN_INV_FILTER:

```
1 if (can_id & CAN_INV_FILTER) {
2    if ((received_can_id & can_mask) != (can_id & ~CAN_INV_FILTER))
3         accept-message;
4 } else {
5    if ((received_can_id & can_mask) == can_id)
6         accept-message;
7 }
```

Multiple filters can be arranged in a filter list and set with Sockopts. If one of these filters matches a CAN ID upon reception of a CAN frame, this frame is accepted.

6.7.3.2 typedef struct can_frame can_frame_t

Raw CAN frame.

Central structure for receiving and sending CAN frames.

Examples:

rtcanrecv.c.

6.7.4 Enumeration Type Documentation

6.7.4.1 enum CAN_BITTIME_TYPE

Supported CAN bit-time types.

Enumerator

CAN_BITTIME_STD Standard bit-time definition according to Bosch. **CAN BITTIME BTR** Hardware-specific BTR bit-time definition.

6.7.4.2 enum CAN_MODE

Enumerator

CAN_MODE_STOP Set controller in Stop mode (no reception / transmission possible)

CAN MODE START Set controller into normal operation.

Coming from stopped mode or bus off, the controller begins with no errors in CAN_STATE_← ACTIVE.

CAN_MODE_SLEEP Set controller into Sleep mode.

This is only possible if the controller is not stopped or bus-off.

Notice that sleep mode will only be entered when there is no bus activity. If the controller detects bus activity while "sleeping" it will go into operating mode again.

To actively leave sleep mode again trigger CAN_MODE_START.

6.7.4.3 enum CAN_STATE

Enumerator

CAN_STATE_ERROR_ACTIVE CAN controller is error active.

60 Module Documentation

CAN_STATE_ACTIVE CAN controller is active.

CAN_STATE_ERROR_WARNING CAN controller is error active, warning level is reached.

CAN STATE BUS WARNING CAN controller is error active, warning level is reached.

CAN_STATE_ERROR_PASSIVE CAN controller is error passive.

CAN_STATE_BUS_PASSIVE CAN controller is error passive.

CAN_STATE_BUS_OFF CAN controller went into Bus Off.

CAN STATE SCANNING BAUDRATE CAN controller is scanning to get the baudrate.

CAN_STATE_STOPPED CAN controller is in stopped mode.


CAN_STATE_SLEEPING CAN controller is in Sleep mode.

6.8 RTDM 61

6.8 RTDM

The Real-Time Driver Model (RTDM) provides a unified interface to both users and developers of real-time device drivers.

Collaboration diagram for RTDM:



Modules

RTDM User API

Application interface to RTDM services.

• Driver programming interface

RTDM driver programming interface.

• Device Profiles

Pre-defined classes of real-time devices.

Typedefs

• typedef uint64_t nanosecs_abs_t

RTDM type for representing absolute dates.

typedef int64_t nanosecs_rel_t

RTDM type for representing relative intervals.

API Versioning

• #define RTDM API VER 9

Common user and driver API version.

• #define RTDM_API_MIN_COMPAT_VER 9

Minimum API revision compatible with the current release.

RTDM TIMEOUT xxx

Special timeout values

Module Documentation

#define RTDM_TIMEOUT_INFINITE 0
 Block forever.

• #define RTDM TIMEOUT NONE (-1)

Any negative timeout means non-blocking.

6.8.1 Detailed Description

The Real-Time Driver Model (RTDM) provides a unified interface to both users and developers of real-time device drivers.

Specifically, it addresses the constraints of mixed RT/non-RT systems like Xenomai. RTDM conforms to POSIX semantics (IEEE Std 1003.1) where available and applicable.

API Revision: 8

62

6.8.2 Macro Definition Documentation

6.8.2.1 #define RTDM TIMEOUT INFINITE 0

Block forever.

6.8.2.2 #define RTDM_TIMEOUT_NONE (-1)

Any negative timeout means non-blocking.

6.8.3 Typedef Documentation

6.8.3.1 typedef uint64_t nanosecs_abs_t

RTDM type for representing absolute dates.

Its base type is a 64 bit unsigned integer. The unit is 1 nanosecond.

Examples:

rtcanrecv.c.

6.8.3.2 typedef int64 t nanosecs rel t

RTDM type for representing relative intervals.

Its base type is a 64 bit signed integer. The unit is 1 nanosecond. Relative intervals can also encode the special timeouts "infinite" and "non-blocking", see RTDM_TIMEOUT_xxx.

Examples:

rtcanrecv.c.

6.9 RTDM User API

6.9 RTDM User API

Application interface to RTDM services.

Collaboration diagram for RTDM User API:



Files

• file rtdm.h

Real-Time Driver Model for Xenomai, user API header.

6.9.1 Detailed Description

Application interface to RTDM services.

This is the upper interface of RTDM provided to application programs both in kernel and user space. Note that certain functions may not be implemented by every device. Refer to the Device Profiles for precise information.

6.10 Serial Devices

This is the common interface a RTDM-compliant serial device has to provide.

Collaboration diagram for Serial Devices:



This is the common interface a RTDM-compliant serial device has to provide.

Feel free to comment on this profile via the Xenomai mailing list xenomai@xenomai.org or directly to the author jan.kiszka@web.de.

Profile Revision: 3

Device Characteristics

Device Flags: RTDM_NAMED_DEVICE, RTDM_EXCLUSIVE

Device Class: RTDM_CLASS_SERIAL

Device Name: "/dev/rtdm/rtser<N>", N>=0

Supported Operations

Open

Tags

secondary-only Specific return values: none

Close

Tags

secondary-only Specific return values: none

IOCTL

Tags

task-unrestricted. See below Specific return values: see below

Read

6.10 Serial Devices 65

Tags

mode-unrestricted Specific return values:

- -ETIMEDOUT
- -EINTR (interrupted explicitly or by signal)
- -EAGAIN (no data available in non-blocking mode)
- -EBADF (device has been closed while reading)
- -EIO (hardware error or broken bit stream)

Write

Tags

mode-unrestricted Specific return values:

- -ETIMEDOUT
- -EINTR (interrupted explicitly or by signal)
- -EAGAIN (no data written in non-blocking mode)
- -EBADF (device has been closed while writing)

6.11 Testing Devices

This group of devices is intended to provide in-kernel testing results.

Collaboration diagram for Testing Devices:



This group of devices is intended to provide in-kernel testing results.

Feel free to comment on this profile via the Xenomai mailing list xenomai@xenomai.org or directly to the author jan.kiszka@web.de.

Profile Revision: 2

Device Characteristics

Device Flags: RTDM_NAMED_DEVICE

Device Class: RTDM_CLASS_TESTING

Supported Operations

Open

Tags

secondary-only Specific return values: none

Close

Tags

secondary-only Specific return values: none

IOCTL

Tags

task-unrestricted. See TSTIOCTLs below Specific return values: see TSTIOCTLs below

6.12 Real-time IPC 67

6.12 Real-time IPC

Profile Revision: 1

Collaboration diagram for Real-time IPC:



Data Structures

struct rtipc_port_label

Port label information structure.

struct sockaddr_ipc

Socket address structure for the RTIPC address family.

Typedefs

• typedef int16_t rtipc_port_t

Port number type for the RTIPC address family.

Supported operations

Standard socket operations supported by the RTIPC protocols.

- int socket__AF_RTIPC (int domain=AF_RTIPC, int type=SOCK_DGRAM, int protocol)

 Create an endpoint for communication in the AF_RTIPC domain.
- int close__AF_RTIPC (int sockfd)

Close a RTIPC socket descriptor.

- int bind__AF_RTIPC (int sockfd, const struct sockaddr_ipc *addr, socklen_t addrlen)

 Bind a RTIPC socket to a port.
- int connect__AF_RTIPC (int sockfd, const struct sockaddr_ipc *addr, socklen_t addrlen)

 Initiate a connection on a RTIPC socket.
- int setsockopt__AF_RTIPC (int sockfd, int level, int optname, const void *optval, socklen_t optlen) Set options on RTIPC sockets.
- int getsockopt__AF_RTIPC (int sockfd, int level, int optname, void *optval, socklen_t *optlen)

 Get options on RTIPC sockets.
- ssize_t sendmsg__AF_RTIPC (int sockfd, const struct msghdr *msg, int flags)
 Send a message on a RTIPC socket.
- ssize_t recvmsg__AF_RTIPC (int sockfd, struct msghdr *msg, int flags)
 - Receive a message from a RTIPC socket.
- int getsockname__AF_RTIPC (int sockfd, struct sockaddr_ipc *addr, socklen_t *addrlen)

Get socket name.

int getpeername__AF_RTIPC (int sockfd, struct sockaddr_ipc *addr, socklen_t *addrlen)
 Get socket peer.

RTIPC protocol list

protocols for the PF_RTIPC protocol family

enum { IPCPROTO_IPC = 0, IPCPROTO_XDDP = 1, IPCPROTO_IDDP = 2, IPCPROTO_BUFP = 3 }

XDDP socket options

Setting and getting XDDP socket options.

• #define XDDP LABEL 1

XDDP label assignment.

• #define XDDP_POOLSZ 2

XDDP local pool size configuration.

• #define XDDP BUFSZ 3

XDDP streaming buffer size configuration.

#define XDDP_MONITOR 4

XDDP monitoring callback.

XDDP events

Specific events occurring on XDDP channels, which can be monitored via the XDDP_MONITOR socket option.

• #define XDDP EVTIN 1

Monitor writes to the non real-time endpoint.

#define XDDP_EVTOUT 2

Monitor reads from the non real-time endpoint.

• #define XDDP EVTDOWN 3

Monitor close from the non real-time endpoint.

• #define XDDP EVTNOBUF 4

Monitor memory shortage for non real-time datagrams.

IDDP socket options

Setting and getting IDDP socket options.

• #define IDDP LABEL 1

IDDP label assignment.

• #define IDDP POOLSZ 2

IDDP local pool size configuration.

6.12 Real-time IPC 69

BUFP socket options

Setting and getting BUFP socket options.

#define BUFP_LABEL 1
 BUFP label assignment.

#define BUFP_BUFSZ 2

BUFP buffer size configuration.

Socket level options

Setting and getting supported standard socket level options.

- #define SO_SNDTIMEO defined_by_kernel_header_file
 IPCPROTO_IDDP and IPCPROTO_BUFP protocols support the standard SO_SNDTIMEO socket option, from the SOL_SOCKET level.
- #define SO_RCVTIMEO defined_by_kernel_header_file
 All RTIPC protocols support the standard SO_RCVTIMEO socket option, from the SOL_SOCKET level.

6.12.1 Detailed Description

Profile Revision: 1

Device Characteristics

Device Flags: RTDM_PROTOCOL_DEVICE

Protocol Family: PF_RTIPC

Socket Type: SOCK_DGRAM

Device Class: RTDM_CLASS_RTIPC

6.12.2 Macro Definition Documentation

6.12.2.1 #define BUFP_BUFSZ 2

BUFP buffer size configuration.

All messages written to a BUFP socket are buffered in a single per-socket memory area. Configuring the size of such buffer prior to binding the socket to a destination port is mandatory.

It is not allowed to configure a buffer size after the socket was bound. However, multiple configuration calls are allowed prior to the binding; the last value set will be used.

Note

: the buffer memory is obtained from the host allocator by the bind call.

Parameters

in	level	SOL_BUFP
in	optname	BUFP_BUFSZ
in	optval	Pointer to a variable of type size_t, containing the required size of the buffer to reserve at binding time
in	optlen	sizeof(size_t)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EALREADY (socket already bound)
- -EINVAL (optlen is invalid or *optval is zero)

Calling context:

RT/non-RT

Examples:

bufp-label.c, and bufp-readwrite.c.

6.12.2.2 #define BUFP_LABEL 1

BUFP label assignment.

ASCII label strings can be attached to BUFP ports, in order to connect sockets to them in a more descriptive way than using plain numeric port values.

When available, this label will be registered when binding, in addition to the port number (see BUFP port binding).

It is not allowed to assign a label after the socket was bound. However, multiple assignment calls are allowed prior to the binding; the last label set will be used.

Parameters

in	level	SOL_BUFP
in	optname	BUFP_LABEL
in	optval	Pointer to struct rtipc_port_label
in	optlen	sizeof(struct rtipc_port_label)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EALREADY (socket already bound)
- -EINVAL (optlen is invalid)

Calling context:

RT/non-RT

Examples:

bufp-label.c.

6.12 Real-time IPC 71

6.12.2.3 #define IDDP_LABEL 1

IDDP label assignment.

ASCII label strings can be attached to IDDP ports, in order to connect sockets to them in a more descriptive way than using plain numeric port values.

When available, this label will be registered when binding, in addition to the port number (see IDDP port binding).

It is not allowed to assign a label after the socket was bound. However, multiple assignment calls are allowed prior to the binding; the last label set will be used.

Parameters

in	level	SOL_IDDP
in	optname	IDDP_LABEL
in	optval	Pointer to struct rtipc_port_label
in	optlen	sizeof(struct rtipc_port_label)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EALREADY (socket already bound)
- -EINVAL (optlen is invalid)

Calling context:

RT/non-RT

Examples:

iddp-label.c.

6.12.2.4 #define IDDP_POOLSZ 2

IDDP local pool size configuration.

By default, the memory needed to convey the data is pulled from Xenomai's system pool. Setting a local pool size overrides this default for the socket.

If a non-zero size was configured, a local pool is allocated at binding time. This pool will provide storage for pending datagrams.

It is not allowed to configure a local pool size after the socket was bound. However, multiple configuration calls are allowed prior to the binding; the last value set will be used.

Note

: the pool memory is obtained from the host allocator by the bind call.

Parameters

in	level	SOL_IDDP
in	optname	IDDP_POOLSZ
in	optval	Pointer to a variable of type size_t, containing the required size of the
		local pool to reserve at binding time
in	optlen	sizeof(size_t)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EALREADY (socket already bound)
- -EINVAL (optlen is invalid or *optval is zero)

Calling context:

RT/non-RT

Examples:

iddp-sendrecv.c.

6.12.2.5 #define SO_RCVTIMEO defined_by_kernel_header_file

All RTIPC protocols support the standard SO_RCVTIMEO socket option, from the SOL_SOCKET level.

See also

setsockopt(), getsockopt() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399/

Examples:

xddp-label.c.

Referenced by rt pipe read timed().

6.12.2.6 #define SO_SNDTIMEO defined_by_kernel_header_file

IPCPROTO_IDDP and IPCPROTO_BUFP protocols support the standard SO_SNDTIMEO socket option, from the SOL_SOCKET level.

See also

setsockopt(), getsockopt() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399/

6.12.2.7 #define XDDP_BUFSZ 3

XDDP streaming buffer size configuration.

In addition to sending datagrams, real-time threads may stream data in a byte-oriented mode through the port as well. This increases the bandwidth and reduces the overhead, when the overall data to send to the Linux domain is collected by bits, and keeping the message boundaries is not required.

This feature is enabled when a non-zero buffer size is set for the socket. In that case, the real-time data accumulates into the streaming buffer when MSG_MORE is passed to any of the send functions, until:

6.12 Real-time IPC 73

- the receiver from the Linux domain wakes up and consumes it,
- a different source port attempts to send data to the same destination port,
- MSG_MORE is absent from the send flags,
- the buffer is full,

whichever comes first.

Setting *optval to zero disables the streaming buffer, in which case all sendings are conveyed in separate datagrams, regardless of MSG_MORE.

Note

only a single streaming buffer exists per socket. When this buffer is full, the real-time data stops accumulating and sending operations resume in mere datagram mode. Accumulation may happen again after some or all data in the streaming buffer is consumed from the Linux domain endpoint.

The streaming buffer size may be adjusted multiple times during the socket lifetime; the latest configuration change will take effect when the accumulation resumes after the previous buffer was flushed.

Parameters

in	level	SOL_XDDP
in	optname	XDDP_BUFSZ
in	optval	Pointer to a variable of type size_t, containing the required size of the streaming buffer
in	optlen	sizeof(size_t)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -ENOMEM (Not enough memory)
- -EINVAL (optlen is invalid)

Calling context:

RT/non-RT

Examples:

xddp-stream.c.

Referenced by rt_pipe_create().

6.12.2.8 #define XDDP_EVTDOWN 3

Monitor close from the non real-time endpoint.

XDDP_EVTDOWN is sent when the non real-time endpoint is closed. The argument is always 0.

6.12.2.9 #define XDDP_EVTIN 1

Monitor writes to the non real-time endpoint.

XDDP_EVTIN is sent when data is written to the non real-time endpoint the socket is bound to (i.e. via /dev/rtpN), which means that some input is pending for the real-time endpoint. The argument is the size of the incoming message.

6.12.2.10 #define XDDP_EVTNOBUF 4

74

Monitor memory shortage for non real-time datagrams.

XDDP_EVTNOBUF is sent when no memory is available from the pool to hold the message currently sent from the non real-time endpoint. The argument is the size of the failed allocation. Upon return from the callback, the caller will block and retry until enough space is available from the pool; during that process, the callback might be invoked multiple times, each time a new attempt to get the required memory fails.

6.12.2.11 #define XDDP_EVTOUT 2

Monitor reads from the non real-time endpoint.

XDDP_EVTOUT is sent when the non real-time endpoint successfully reads a complete message (i.e. via /dev/rtpN). The argument is the size of the outgoing message.

6.12.2.12 #define XDDP_LABEL 1

XDDP label assignment.

ASCII label strings can be attached to XDDP ports, so that opening the non-RT endpoint can be done by specifying this symbolic device name rather than referring to a raw pseudo-device entry (i.e. /dev/rtpN).

When available, this label will be registered when binding, in addition to the port number (see XDDP port binding).

It is not allowed to assign a label after the socket was bound. However, multiple assignment calls are allowed prior to the binding; the last label set will be used.

Parameters

in	level	SOL_XDDP
in	optname	XDDP_LABEL
in	optval	Pointer to struct rtipc_port_label
in	optlen	sizeof(struct rtipc_port_label)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EALREADY (socket already bound)
- -EINVAL (optlen invalid)

Calling context:

RT/non-RT

Examples:

xddp-label.c.

Referenced by rt_pipe_create().

6.12 Real-time IPC 75

6.12.2.13 #define XDDP_MONITOR 4

XDDP monitoring callback.

Other RTDM drivers may install a user-defined callback via the rtdm_setsockopt call from the inter-driver API, in order to collect particular events occurring on the channel.

This notification mechanism is particularly useful to monitor a channel asynchronously while performing other tasks.

The user-provided routine will be passed the RTDM file descriptor of the socket receiving the event, the event code, and an optional argument. Four events are currently defined, see XDDP_EVENTS.

The XDDP_EVTIN and XDDP_EVTOUT events are fired on behalf of a fully atomic context; therefore, care must be taken to keep their overhead low. In those cases, the Xenomai services that may be called from the callback are restricted to the set allowed to a real-time interrupt handler.

Parameters

in	level	SOL_XDDP
in	optname	XDDP_MONITOR
in	optval	Pointer to a pointer to function of type int (*)(int fd, int event, long arg), containing the address of the user-defined callback. Passing a NULL callback pointer in <i>optval</i> disables monitoring.
in	optlen	sizeof(int (*)(int fd, int event, long arg))

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EPERM (Operation not allowed from user-space)
- -EINVAL (optlen is invalid)

Calling context:

RT/non-RT, kernel space only

6.12.2.14 #define XDDP POOLSZ 2

XDDP local pool size configuration.

By default, the memory needed to convey the data is pulled from Xenomai's system pool. Setting a local pool size overrides this default for the socket.

If a non-zero size was configured, a local pool is allocated at binding time. This pool will provide storage for pending datagrams.

It is not allowed to configure a local pool size after the socket was bound. However, multiple configuration calls are allowed prior to the binding; the last value set will be used.

Note

: the pool memory is obtained from the host allocator by the bind call.

Parameters

in	level	SOL_XDDP
in	optname	XDDP_POOLSZ
in	optval	Pointer to a variable of type size_t, containing the required size of the local pool to reserve at binding time
in	optlen	sizeof(size_t)

Returns

0 is returned upon success. Otherwise:

- -EFAULT (Invalid data address given)
- -EALREADY (socket already bound)
- -EINVAL (optlen invalid or *optval is zero)

Calling context:

RT/non-RT

Examples:

xddp-echo.c.

Referenced by rt pipe create().

6.12.3 Enumeration Type Documentation

6.12.3.1 anonymous enum

Enumerator

IPCPROTO IPC Default protocol (IDDP)

IPCPROTO_XDDP Cross-domain datagram protocol (RT <-> non-RT). Real-time Xenomai threads and regular Linux threads may want to exchange data in a way that does not require the former to leave the real-time domain (i.e. primary mode). The RTDM-based XDDP protocol is available for this purpose.

On the Linux domain side, pseudo-device files named /dev/rtp<minor> give regular POSIX threads access to non real-time communication endpoints, via the standard character-based I/O interface. On the Xenomai domain side, sockets may be bound to XDDP ports, which act as proxies to send and receive data to/from the associated pseudo-device files. Ports and pseudo-device minor numbers are paired, meaning that e.g. socket port 7 will proxy the traffic to/from /dev/rtp7.

All data sent through a bound/connected XDDP socket via sendto(2) or write(2) will be passed to the peer endpoint in the Linux domain, and made available for reading via the standard read(2) system call. Conversely, all data sent using write(2) through the non real-time endpoint will be conveyed to the real-time socket endpoint, and made available to the recvfrom(2) or read(2) system calls.

IPCPROTO_IDDP Intra-domain datagram protocol (RT <-> RT). The RTDM-based IDDP protocol enables real-time threads to exchange datagrams within the Xenomai domain, via socket endpoints.

IPCPROTO_BUFP Buffer protocol (RT <-> RT, byte-oriented). The RTDM-based BUFP protocol implements a lightweight, byte-oriented, one-way Producer-Consumer data path. All messages written are buffered into a single memory area in strict FIFO order, until read by the consumer.

This protocol always prevents short writes, and only allows short reads when a potential dead-lock situation arises (i.e. readers and writers waiting for each other indefinitely).

6.12 Real-time IPC

6.12.4 Function Documentation

6.12.4.1 int bind__AF_RTIPC (int sockfd, const struct **sockaddr_ipc** * addr, socklen_t addrlen)

Bind a RTIPC socket to a port.

Bind the socket to a destination port.

Parameters

in	sockfd	The RTDM file descriptor obtained from the socket creation call.
in	addr	The address to bind the socket to (see struct sockaddr_ipc). The
		meaning of such address depends on the RTIPC protocol in use for the socket:

• IPCPROTO XDDP

This action creates an endpoint for channelling traffic between the Xenomai and Linux domains. sipc_family must be AF_RTIPC, sipc_port is either -1, or a valid free port number between 0 and CONFIG_XENO_OPT_PIPE_NRDEV-1.

If sipc port is -1, a free port will be assigned automatically.

Upon success, the pseudo-device /dev/rtpN will be reserved for this communication channel, where N is the assigned port number. The non real-time side shall open this device to exchange data over the bound socket.

If a label was assigned (see XDDP_LABEL) prior to binding the socket to a port, a registry link referring to the created pseudo-device will be automatically set up as /proc/xenomai/registry/rtipc/xddp/label, where label is the label string passed to setsockopt() for the XDDP_LABEL option.

IPCPROTO_IDDP

This action creates an endpoint for exchanging datagrams within the Xenomai domain.

sipc_family must be AF_RTIPC, sipc_port is either -1, or a valid free port number between 0 and CONFIG_XENO_OPT_IDDP_NRPORT-1.

If *sipc_port* is -1, a free port will be assigned automatically. The real-time peer shall connect to the same port for exchanging data over the bound socket.

If a label was assigned (see IDDP_LABEL) prior to binding the socket to a port, a registry link referring to the assigned port number will be automatically set up as /proc/xenomai/registry/rtipc/iddp/label, where label is the label string passed to setsockopt() for the IDDP_LABEL option.

• IPCPROTO BUFP

This action creates an endpoint for a one-way byte stream within the Xenomai domain.

sipc_family must be AF_RTIPC, sipc_port is either -1, or a valid free port number between 0 and CONFIG_XENO_OPT_BUFP_NRPORT-1.

If *sipc_port* is -1, an available port will be assigned automatically. The real-time peer shall connect to the same port for exchanging data over the bound socket.

If a label was assigned (see BUFP_LABEL) prior to binding the socket to a port, a registry link referring to the assigned port number will be automatically set up as /proc/xenomai/registry/rtipc/bufp/label, where label is the label string passed to setsockopt() for the BUFP LABEL option.

Parameters

78

in	addrlen	The size in bytes of the structure pointed to by addr.
----	---------	--

Returns

In addition to the standard error codes for bind(2), the following specific error code may be returned:

- -EFAULT (Invalid data address given)
- -ENOMEM (Not enough memory)
- -EINVAL (Invalid parameter)
- -EADDRINUSE (Socket already bound to a port, or no port available)

Calling context:

non-RT

6.12.4.2 int close__AF_RTIPC (int sockfd)

Close a RTIPC socket descriptor.

Blocking calls to any of the sendmsg or recvmsg functions will be unblocked when the socket is closed and return with an error.

Parameters

in sockfo	The socket descriptor to close.
-----------	---------------------------------

Returns

In addition to the standard error codes for close(2), the following specific error code may be returned: none

Calling context:

non-RT

6.12.4.3 int connect__AF_RTIPC (int sockfd, const struct **sockaddr_ipc** * addr, socklen_t addrlen)

Initiate a connection on a RTIPC socket.

Parameters

in	sockfd	The RTDM file descriptor obtained from the socket creation call.
in	addr	The address to connect the socket to (see struct sockaddr_ipc).

- If sipc_port is a valid port for the protocol, it is used verbatim and the connection succeeds immediately, regardless of whether the destination is bound at the time of the call.
- If sipc_port is -1 and a label was assigned to the socket, connect() blocks for the requested amount
 of time (see SO_RCVTIMEO) until a socket is bound to the same label via bind(2) (see XDDP

 _LABEL, IDDP_LABEL, BUFP_LABEL), in which case a connection is established between both
 endpoints.
- If sipc_port is -1 and no label was assigned to the socket, the default destination address is cleared, meaning that any subsequent write to the socket will return -EDESTADDRREQ, until a valid destination address is set via connect(2) or bind(2).

6.12 Real-time IPC 79

Parameters

in	addrlen	The size in bytes of the structure pointed to by addr.
----	---------	--

Returns

In addition to the standard error codes for connect(2), the following specific error code may be returned: none.

Calling context:

RT/non-RT

6.12.4.4 int getpeername__AF_RTIPC (int sockfd, struct **sockaddr_ipc** * addr, socklen_t * addrlen)

Get socket peer.

The name of the remote endpoint for the socket is copied back (see struct sockaddr_ipc). This is the default destination address for messages sent on the socket. It can be set either explicitly via connect(2), or implicitly via bind(2) if no connect(2) was called prior to binding the socket to a port, in which case both the local and remote names are equal.

Returns

In addition to the standard error codes for getpeername(2), the following specific error code may be returned: none.

Calling context:

RT/non-RT

6.12.4.5 int getsockname__AF_RTIPC (int sockfd, struct **sockaddr_ipc** * addr, socklen_t * addrlen)

Get socket name.

The name of the local endpoint for the socket is copied back (see struct sockaddr ipc).

Returns

In addition to the standard error codes for <code>getsockname(2)</code>, the following specific error code may be returned: none.

Calling context:

RT/non-RT

6.12.4.6 int getsockopt__AF_RTIPC (int sockfd, int level, int optname, void * optval, socklen_t * optlen)

Get options on RTIPC sockets.

These functions allow to get various socket options. Supported Levels and Options:

Level SOL_SOCKET

- Level SOL_XDDP
- Level SOL IDDP
- Level SOL_BUFP

Returns

In addition to the standard error codes for getsockopt(2), the following specific error code may be returned: follow the option links above.

Calling context:

RT/non-RT

6.12.4.7 ssize_t recvmsg__AF_RTIPC (int sockfd, struct msghdr * msg, int flags)

Receive a message from a RTIPC socket.

Parameters

in	sockfd	The RTDM file descriptor obtained from the socket creation call.
out	msg	The address the message header will be copied at.
in	flags	Operation flags:

MSG_DONTWAIT Non-blocking I/O operation. The caller will not be blocked whenever no message is immediately available for receipt at the time of the call, but will rather return with -EWOU

LDBLOCK.

Note

IPCPROTO_BUFP does not allow for short reads and always returns the requested amount of bytes, except in one situation: whenever some writer is waiting for sending data upon a buffer full condition, while the caller would have to wait for receiving a complete message. This is usually the sign of a pathological use of the BUFP socket, like defining an incorrect buffer size via BUFP_B ∪ UFSZ. In that case, a short read is allowed to prevent a deadlock.

Returns

In addition to the standard error codes for recvmsg(2), the following specific error code may be returned: none.

Calling context:

RT

6.12.4.8 ssize_t sendmsg__AF_RTIPC (int sockfd, const struct msghdr * msg, int flags)

Send a message on a RTIPC socket.

Parameters

6.12 Real-time IPC 81

in	sockfd	The RTDM file descriptor obtained from the socket creation call.
in	msg	The address of the message header conveying the datagram.
in	flags	Operation flags:

- MSG_OOB Send out-of-band message. For all RTIPC protocols except IPCPROTO_BUFP, sending out-of-band data actually means pushing them to the head of the receiving queue, so that the reader will always receive them before normal messages. IPCPROTO_BUFP does not support out-of-band sending.
- MSG_DONTWAIT Non-blocking I/O operation. The caller will not be blocked whenever the message cannot be sent immediately at the time of the call (e.g. memory shortage), but will rather return with -EWOULDBLOCK. Unlike other RTIPC protocols, IPCPROTO_XDDP accepts but never considers MSG_DONTWAIT since writing to a real-time XDDP endpoint is inherently a non-blocking operation.
- MSG_MORE Accumulate data before sending. This flag is accepted by the IPCPROTO_XDDP
 protocol only, and tells the send service to accumulate the outgoing data into an internal streaming
 buffer, instead of issuing a datagram immediately for it. See XDDP BUFSZ for more.

Note

No RTIPC protocol allows for short writes, and only complete messages are sent to the peer.

Returns

In addition to the standard error codes for sendmsg(2), the following specific error code may be returned: none.

Calling context:

RT

6.12.4.9 int setsockopt__AF_RTIPC (int sockfd, int level, int optname, const void * optval, socklen_t optlen)

Set options on RTIPC sockets.

These functions allow to set various socket options. Supported Levels and Options:

- Level SOL SOCKET
- Level SOL_XDDP
- Level SOL IDDP
- Level SOL BUFP

Returns

In addition to the standard error codes for setsockopt(2), the following specific error code may be returned: follow the option links above.

Calling context:

non-RT

6.12.4.10 int socket AF RTIPC (int domain = AF_RTIPC, int type = SOCK_DGRAM, int protocol)

Create an endpoint for communication in the AF_RTIPC domain.

Parameters

in	domain	The communication domain. Must be AF_RTIPC.
in	type	The socket type. Must be SOCK_DGRAM.
in	protocol	Any of IPCPROTO_XDDP, IPCPROTO_IDDP, or IPCPROTO_BUFP.
		IPCPROTO_IPC is also valid, and refers to the default RTIPC protocol,
		namely IPCPROTO_IDDP.

Returns

In addition to the standard error codes for socket(2), the following specific error code may be returned:

• -ENOPROTOOPT (Protocol is known, but not compiled in the RTIPC driver). See RTIPC protocols for available protocols.


Calling context:

non-RT

6.13 Asynchronous Procedure Calls

Services for scheduling function calls in the Linux domain.

Collaboration diagram for Asynchronous Procedure Calls:



Functions

- int xnapc_alloc (const char *name, void(*handler)(void *cookie), void *cookie)
 Allocate an APC slot.
- void xnapc_free (int apc)

Releases an APC slot.

• static void xnapc_schedule (int apc)

Schedule an APC invocation.

6.13.1 Detailed Description

Services for scheduling function calls in the Linux domain.

APC is the acronym for Asynchronous Procedure Call, a mean by which activities from the Xenomai domain can schedule deferred invocations of handlers to be run into the Linux domain, as soon as possible when the Linux kernel gets back in control.

Up to BITS PER LONG APC slots can be active at any point in time.

APC support is built upon the interrupt pipeline's virtual interrupt support.

6.13.2 Function Documentation

6.13.2.1 int xnapc_alloc (const char * name, void(*)(void *cookie) handler, void * cookie)

Allocate an APC slot.

APC is the acronym for Asynchronous Procedure Call, a mean by which activities from the Xenomai domain can schedule deferred invocations of handlers to be run into the Linux domain, as soon as possible when the Linux kernel gets back in control. Up to BITS_PER_LONG APC slots can be active at any point in time. APC support is built upon the interrupt pipeline's virtual interrupt support.

Any Linux kernel service which is callable from a regular Linux interrupt handler is in essence available to APC handlers.

Parameters

84

name	is a symbolic name identifying the APC which will get reported through the /proc/xenomai/apc interface. Passing NULL to create an anonymous APC is allowed.
handler	The address of the fault handler to call upon exception condition. The handle will be
	passed the <i>cookie</i> value unmodified.
cookie	A user-defined opaque pointer the APC handler receives as its sole argument.

Returns

a valid APC identifier is returned upon success, or a negative error code otherwise:

- -EINVAL is returned if handler is invalid.
- -EBUSY is returned if no more APC slots are available.

Tags

unrestricted

6.13.2.2 void xnapc_free (int apc)

Releases an APC slot.

This service deallocates an APC slot obtained by xnapc_alloc().

Parameters

apc The APC id. to release, as returned by a successful call to the xnapc_alloc() servic
--

Tags

unrestricted

6.13.2.3 static inline int xnapc_schedule (int apc) [inline], [static]

Schedule an APC invocation.

This service marks the APC as pending for the Linux domain, so that its handler will be called as soon as possible, when the Linux domain gets back in control.

When posted from the Linux domain, the APC handler is fired as soon as the interrupt mask is explicitly cleared by some kernel code. When posted from the Xenomai domain, the APC handler is fired as soon as the Linux domain is resumed, i.e. after Xenomai has completed all its pending duties.

Parameters

apc The APC id. to schedule.

This service can be called from:


• Any domain context, albeit the usual calling place is from the Xenomai domain.

6.14 In-kernel arithmetics

A collection of helpers performing arithmetics not implicitly available from kernel context via GC

C helpers.

Collaboration diagram for In-kernel arithmetics:



Functions

• unsigned long long xnarch_generic_full_divmod64 (unsigned long long a, unsigned long long b, unsigned long long *rem)

Architecture-independent div64 operation with remainder.

6.14.1 Detailed Description

A collection of helpers performing arithmetics not implicitly available from kernel context via $GC \leftarrow C$ helpers.

Many of these routines enable 64bit arithmetics on 32bit systems. Xenomai architecture ports normally implement the performance critical ones in hand-crafted assembly code (see kernel/cobalt/arch/<arch>/include/asm/xenomai/uapi/arith.h).

6.14.2 Function Documentation

6.14.2.1 unsigned long long xnarch_generic_full_divmod64 (unsigned long long a, unsigned long long * rem)

Architecture-independent div64 operation with remainder.

Parameters

а	dividend
b	divisor
rem	if non-NULL, a pointer to a 64bit variable for collecting the remainder from the divi-
	sion.

6.15 Buffer descriptor

Abstraction for copying data to/from different address spaces.

Collaboration diagram for Buffer descriptor:



Functions

- static void xnbufd_map_uread (struct xnbufd *bufd, const void __user *ptr, size_t len)
 Initialize a buffer descriptor for reading from user memory.
- static void xnbufd_map_uwrite (struct xnbufd *bufd, void __user *ptr, size_t len)
 Initialize a buffer descriptor for writing to user memory.
- ssize t xnbufd unmap uread (struct xnbufd *bufd)

Finalize a buffer descriptor obtained from xnbufd_map_uread().

ssize_t xnbufd_unmap_uwrite (struct xnbufd *bufd)

Finalize a buffer descriptor obtained from xnbufd map uwrite().

static void xnbufd_map_kread (struct xnbufd *bufd, const void *ptr, size_t len)

Initialize a buffer descriptor for reading from kernel memory.

static void xnbufd map kwrite (struct xnbufd *bufd, void *ptr, size t len)

Initialize a buffer descriptor for writing to kernel memory.

ssize_t xnbufd_unmap_kread (struct xnbufd *bufd)

Finalize a buffer descriptor obtained from xnbufd_map_kread().

ssize_t xnbufd_unmap_kwrite (struct xnbufd *bufd)

Finalize a buffer descriptor obtained from xnbufd map kwrite().

ssize_t xnbufd_copy_to_kmem (void *ptr, struct xnbufd *bufd, size_t len)

Copy memory covered by a buffer descriptor to kernel memory.

ssize_t xnbufd_copy_from_kmem (struct xnbufd *bufd, void *from, size_t len)

Copy kernel memory to the area covered by a buffer descriptor.

void xnbufd_invalidate (struct xnbufd *bufd)

Invalidate a buffer descriptor.

• static void xnbufd reset (struct xnbufd *bufd)

Reset a buffer descriptor.

6.15.1 Detailed Description

Abstraction for copying data to/from different address spaces.

A buffer descriptor is a simple abstraction dealing with copy operations to/from memory buffers which may belong to different address spaces.

To this end, the buffer descriptor library provides a small set of copy routines which are aware of address space restrictions when moving data, and a generic container type which can hold a reference to - or

cover - a particular memory area, either present in kernel space, or in any of the existing user memory contexts.

The goal of the buffer descriptor abstraction is to hide address space specifics from Xenomai services dealing with memory areas, allowing them to operate on multiple address spaces seamlessly.

The common usage patterns are as follows:

 Implementing a Xenomai syscall returning a bulk of data to the caller, which may have to be copied back to either kernel or user space:

```
[Syscall implementation]
ssize_t rt_bulk_read_inner(struct xnbufd *bufd)
    ssize_t ret;
    size_t len;
    void *bulk;
    bulk = get_next_readable_bulk(&len);
    ret = xnbufd_copy_from_kmem(bufd, bulk, min(bufd->b_len, len));
    free_bulk(bulk);
    ret = this_may_fail();
    if (ret)
             xnbufd_invalidate(bufd);
    return ret;
}
[Kernel wrapper for in-kernel calls]
int rt_bulk_read(void *ptr, size_t len)
    struct xnbufd bufd;
    ssize_t ret;
    xnbufd_map_kwrite(&bufd, ptr, len);
ret = rt_bulk_read_inner(&bufd);
    xnbufd_unmap_kwrite(&bufd);
    return ret;
}
[Userland trampoline for user syscalls]
int __rt_bulk_read(struct pt_regs *regs)
    struct xnbufd bufd;
    void __user *ptr;
    ssize_t ret;
    size_t len;
    ptr = (void __user *)__xn_reg_arg1(regs);
    len = __xn_reg_arg2(regs);
    xnbufd map uwrite(&bufd. ptr. len):
    ret = rt_bulk_read_inner(&bufd);
    xnbufd_unmap_uwrite(&bufd);
    return ret;
```

• Implementing a Xenomai syscall receiving a bulk of data from the caller, which may have to be read from either kernel or user space:

```
[Syscall implementation]
ssize_t rt_bulk_write_inner(struct xnbufd *bufd)
{
    void *bulk = get_free_bulk(bufd->b_len);
    return xnbufd_copy_to_kmem(bulk, bufd, bufd->b_len);
}
[Kernel wrapper for in-kernel calls]
int rt_bulk_write(const void *ptr, size_t len)
{
    struct xnbufd bufd;
    ssize_t ret;
    xnbufd_map_kread(&bufd, ptr, len);
    ret = rt_bulk_write_inner(&bufd);
    xnbufd_unmap_kread(&bufd);
```

```
return ret;
}
[Userland trampoline for user syscalls]
int __rt_bulk_write(struct pt_regs *regs)
{
    struct xnbufd bufd;
    void __user *ptr;
    ssize_t ret;
    size_t len;

    ptr = (void __user *)__xn_reg_arg1(regs);
    len = __xn_reg_arg2(regs);

    xnbufd_map_uread(&bufd, ptr, len);
    ret = rt_bulk_write_inner(&bufd);
    xnbufd_unmap_uread(&bufd);
    return ret;
}
```

6.15.2 Function Documentation

```
6.15.2.1 ssize t xnbufd copy from kmem ( struct xnbufd * bufd, void * from, size t len )
```

Copy kernel memory to the area covered by a buffer descriptor.

This routine copies *len* bytes from the kernel memory starting at *from* to the area referred to by the buffer descriptor *bufd*. xnbufd_copy_from_kmem() tracks the write offset within the destination memory internally, so that it may be called several times in a loop, until the entire memory area is stored.

The destination address space is dealt with, according to the following rules:

- if bufd refers to a writable kernel area (i.e. see xnbufd_map_kwrite()), the copy is immediatly and fully performed with no restriction.
- if bufd refers to a writable user area (i.e. see xnbufd_map_uwrite()), the copy is performed only if that area lives in the currently active address space, and only if the caller may sleep Linux-wise to process any potential page fault which may arise while writing to that memory.
- if bufd refers to a user area which may not be immediately written to from the current context, the copy is postponed until xnbufd_unmap_uwrite() is invoked for ubufd, at which point the copy will take place. In such a case, the source memory is transferred to a carry over buffer allocated internally; this operation may lead to request dynamic memory from the nucleus heap if len is greater than 64 bytes.

Parameters

bufd	The address of the buffer descriptor covering the user memory to copy data to.
from	The start address of the kernel memory to copy from.
len	The length of the kernel memory to copy to bufd.

Returns

The number of bytes written so far to the memory area covered by ubufd. Otherwise,

• -ENOMEM is returned when no memory is available from the nucleus heap to allocate the carry over buffer.

Tags

unrestricted

Note

Calling this routine while holding the nklock and/or running with interrupts disabled is invalid, and doing so will trigger a debug assertion.

This routine may switch the caller to secondary mode if a page fault occurs while reading from the user area. For that reason, xnbufd_copy_to_kmem() may only be called from a preemptible section (Linux-wise).

```
6.15.2.2 ssize t xnbufd copy to kmem (void * to, struct xnbufd * bufd, size t len )
```

Copy memory covered by a buffer descriptor to kernel memory.

This routine copies *len* bytes from the area referred to by the buffer descriptor *bufd* to the kernel memory area *to.* xnbufd_copy_to_kmem() tracks the read offset within the source memory internally, so that it may be called several times in a loop, until the entire memory area is loaded.

The source address space is dealt with, according to the following rules:

- if bufd refers to readable kernel area (i.e. see xnbufd_map_kread()), the copy is immediately and fully performed with no restriction.
- if bufd refers to a readable user area (i.e. see xnbufd_map_uread()), the copy is performed only if that area lives in the currently active address space, and only if the caller may sleep Linux-wise to process any potential page fault which may arise while reading from that memory.
- any attempt to read from *bufd* from a non-suitable context is considered as a bug, and will raise a panic assertion when the nucleus is compiled in debug mode.

Parameters

to	The start address of the kernel memory to copy to.
bufd	The address of the buffer descriptor covering the user memory to copy data from.
len	The length of the user memory to copy from bufd.

Returns

The number of bytes read so far from the memory area covered by *ubufd*. Otherwise:

• -EINVAL is returned upon attempt to read from the user area from an invalid context. This error is only returned when the debug mode is disabled; otherwise a panic assertion is raised.

Tags

task-unrestricted

Note

Calling this routine while holding the nklock and/or running with interrupts disabled is invalid, and doing so will trigger a debug assertion.

This routine may switch the caller to secondary mode if a page fault occurs while reading from the user area. For that reason, xnbufd_copy_to_kmem() may only be called from a preemptible section (Linux-wise).

6.15.2.3 void xnbufd_invalidate (struct xnbufd * bufd)

Invalidate a buffer descriptor.

The buffer descriptor is invalidated, making it unusable for further copy operations. If an outstanding carry over buffer was allocated by a previous call to xnbufd_copy_from_kmem(), it is immediately freed so that no data transfer will happen when the descriptor is finalized.

The only action that may subsequently be performed on an invalidated descriptor is calling the relevant unmapping routine for it. For that reason, xnbufd_invalidate() should be invoked on the error path when data may have been transferred to the carry over buffer.

Parameters

bufd	The address of the buffer descriptor to invalidate.

Tags

unrestricted

6.15.2.4 void xnbufd_map_kread (struct xnbufd * bufd, const void * ptr, size_t len) [inline], [static]

Initialize a buffer descriptor for reading from kernel memory.

The new buffer descriptor may be used to copy data from kernel memory. This routine should be used in pair with xnbufd_unmap_kread().

Parameters

bufd	The address of the buffer descriptor which will map a len bytes kernel memory area,
	starting from <i>ptr</i> .
ptr	The start of the kernel buffer to map.
len	The length of the kernel buffer starting at ptr.

Tags

unrestricted

6.15.2.5 void xnbufd_map_kwrite (struct xnbufd * bufd, void * ptr, size_t len) [inline], [static]

Initialize a buffer descriptor for writing to kernel memory.

The new buffer descriptor may be used to copy data to kernel memory. This routine should be used in pair with xnbufd unmap kwrite().

Parameters

bufd	The address of the buffer descriptor which will map a <i>len</i> bytes kernel memory area,
	starting from ptr.
ptr	The start of the kernel buffer to map.
len	The length of the kernel buffer starting at ptr.

Tags

unrestricted

```
6.15.2.6 void xnbufd_map_uread ( struct xnbufd * bufd, const void __user * ptr, size_t len ) [inline], [static]
```

Initialize a buffer descriptor for reading from user memory.

The new buffer descriptor may be used to copy data from user memory. This routine should be used in pair with xnbufd_unmap_uread().

Parameters

bufd	The address of the buffer descriptor which will map a <i>len</i> bytes user memory area, starting from <i>ptr. ptr</i> is never dereferenced directly, since it may refer to a buffer that lives in another address space.
ptr	The start of the user buffer to map.
len	The length of the user buffer starting at ptr.

Tags

task-unrestricted

Initialize a buffer descriptor for writing to user memory.

The new buffer descriptor may be used to copy data to user memory. This routine should be used in pair with xnbufd_unmap_uwrite().

Parameters

bufd	The address of the buffer descriptor which will map a <i>len</i> bytes user memory area,
	starting from <i>ptr. ptr</i> is never dereferenced directly, since it may refer to a buffer that
	lives in another address space.
ptr	The start of the user buffer to map.
len	The length of the user buffer starting at ptr.

Tags

task-unrestricted

```
6.15.2.8 void xnbufd_reset ( struct xnbufd * bufd ) [inline], [static]
```

Reset a buffer descriptor.

The buffer descriptor is reset, so that all data already copied is forgotten. Any carry over buffer allocated is kept, though.

Parameters

bufd The address of the buffer descriptor to reset.	
---	--

Tags

unrestricted

```
6.15.2.9 ssize_t xnbufd_unmap_kread ( struct xnbufd * bufd )
```

Finalize a buffer descriptor obtained from xnbufd_map_kread().

This routine finalizes a buffer descriptor previously initialized by a call to xnbufd_map_kread(), to read data from a kernel area.

Parameters

bufd The address of the buffer descriptor to finalize.

Returns

The number of bytes read so far from the memory area covered by ubufd.

Tags

task-unrestricted

6.15.2.10 ssize_t xnbufd_unmap_kwrite (struct xnbufd * bufd)

Finalize a buffer descriptor obtained from xnbufd_map_kwrite().

This routine finalizes a buffer descriptor previously initialized by a call to xnbufd_map_kwrite(), to write data to a kernel area.

Parameters

bufd The address of the buffer descriptor to finalize.

Returns

The number of bytes written so far to the memory area covered by ubufd.

Tags

task-unrestricted

6.15.2.11 ssize t xnbufd unmap uread (struct xnbufd * bufd)

Finalize a buffer descriptor obtained from xnbufd map uread().

This routine finalizes a buffer descriptor previously initialized by a call to xnbufd_map_uread(), to read data from a user area.

Parameters

bufd | The address of the buffer descriptor to finalize.

Returns

The number of bytes read so far from the memory area covered by ubufd.

Tags

task-unrestricted

Note

Calling this routine while holding the nklock and/or running with interrupts disabled is invalid, and doing so will trigger a debug assertion.

6.15.2.12 ssize_t xnbufd_unmap_uwrite (struct xnbufd * bufd)

Finalize a buffer descriptor obtained from xnbufd_map_uwrite().

This routine finalizes a buffer descriptor previously initialized by a call to xnbufd_map_uwrite(), to write data to a user area.

The main action taken is to write the contents of the kernel memory area passed to xnbufd_copy_from _kmem() whenever the copy operation was postponed at that time; the carry over buffer is eventually released as needed. If xnbufd_copy_from_kmem() was allowed to copy to the destination user memory at once, then xnbufd_unmap_uwrite() leads to a no-op.

Parameters

bufd	The address of the buffer descriptor to finalize.

Returns

The number of bytes written so far to the memory area covered by ubufd.

Tags

task-unrestricted

Note

Calling this routine while holding the nklock and/or running with interrupts disabled is invalid, and doing so will trigger a debug assertion.

6.16 Clock services

Collaboration diagram for Clock services:



Functions

int xnclock_register (struct xnclock *clock, const cpumask_t *affinity)

Register a Xenomai clock.

void xnclock_deregister (struct xnclock *clock)

Deregister a Xenomai clock.

void xnclock_tick (struct xnclock *clock)

Process a clock tick.

void xnclock_adjust (struct xnclock *clock, xnsticks_t delta)

Adjust a clock time.

6.16.1 Detailed Description

6.16.2 Function Documentation

6.16.2.1 void xnclock_adjust (struct xnclock * clock, xnsticks_t delta)

Adjust a clock time.

This service changes the epoch for the given clock by applying the specified tick delta on its wallclock offset.

Parameters

clock	clock The clock to adjust.	
delta The adjustment value expressed in nanoseconds.		

Tags

task-unrestricted, atomic-entry

Note

Xenomai tracks the system time in *nkclock*, as a monotonously increasing count of ticks since the epoch. The epoch is initially the same as the underlying machine time.

6.16 Clock services 95

6.16.2.2 void xnclock_deregister (struct xnclock * clock)

Deregister a Xenomai clock.

This service uninstalls a Xenomai clock previously registered with xnclock_register().

This service may be called once all timers driven by *clock* have been stopped.

Parameters

clock	The clock to deregister.
-------	--------------------------

Tags

secondary-only

6.16.2.3 int xnclock_register (struct xnclock * clock, const cpumask_t * affinity)

Register a Xenomai clock.

This service installs a new clock which may be used to drive Xenomai timers.

Parameters

clock	The new clock to register.
affinity The set of CPUs we may expect the backing clock device to tick on.	

Tags

secondary-only

6.16.2.4 void xnclock_tick (struct xnclock * clock)

Process a clock tick.

This routine processes an incoming *clock* event, firing elapsed timers as appropriate.

Parameters

clock	The clock for which a new event was received.

Tags

coreirq-only, atomic-entry

Note

The current CPU must be part of the real-time affinity set, otherwise weird things may happen.

References xnsched::htimer, xnsched::lflags, and xnsched::status.

6.17 Debugging services

Collaboration diagram for Debugging services:




6.17.1 Detailed Description

6.18 Dynamic memory allocation services

The implementation of the memory allocator follows the algorithm described in a USENIX 1988 paper called "Design of a General Purpose Memory Allocator for the 4.3BSD Unix Kernel" by Marshall K.

Collaboration diagram for Dynamic memory allocation services:



Data Structures

struct xnheap::xnbucket

log2 bucket list

Functions

- int xnheap_init (struct xnheap *heap, void *membase, u32 size)
 Initialize a memory heap.
- void xnheap_set_name (struct xnheap *heap, const char *name,...)
 Set the heap's name string.
- void xnheap_destroy (struct xnheap *heap)

Destroys a memory heap.

• void * xnheap_alloc (struct xnheap *heap, u32 size)

Allocate a memory block from a memory heap.

void xnheap_free (struct xnheap *heap, void *block)

Release a block to a memory heap.

6.18.1 Detailed Description

The implementation of the memory allocator follows the algorithm described in a USENIX 1988 paper called "Design of a General Purpose Memory Allocator for the 4.3BSD Unix Kernel" by Marshall K.

McKusick and Michael J. Karels. You can find it at various locations on the net, including http://docs. ← FreeBSD.org/44doc/papers/kernmalloc.pdf.

Implementation constraints

- Minimum page size is 2 ** XNHEAP_MINLOG2 (must be large enough to hold a pointer).
- Maximum page size is 2 ** XNHEAP_MAXLOG2.
- Requested block size is rounded up to XNHEAP MINLOG2.

 Requested block size larger than 2 times the XNHEAP_PAGESZ is rounded up to the next page boundary and obtained from the free page list. So we need a bucket for each power of two between XNHEAP_MINLOG2 and XNHEAP_MAXLOG2 inclusive, plus one to honor requests ranging from the maximum page size to twice this size.

6.18.2 Function Documentation

6.18.2.1 void * xnheap alloc (struct xnheap * heap, u32 size)

Allocate a memory block from a memory heap.

Allocates a contiguous region of memory from an active memory heap. Such allocation is guaranteed to be time-bounded.

Parameters

heap	The descriptor address of the heap to get memory from.	
size	size The size in bytes of the requested block. Sizes lower or equal to the page size a	
	rounded either to the minimum allocation size if lower than this value, or to the min-	
	imum alignment size if greater or equal to this value. In the current implementation,	
	with MINALLOC = 8 and MINALIGN = 16, a 7 bytes request will be rounded to 8	
	bytes, and a 17 bytes request will be rounded to 32.	

Returns

The address of the allocated region upon success, or NULL if no memory is available from the specified heap.

Tags

unrestricted

6.18.2.2 void xnheap_destroy (struct xnheap * heap)

Destroys a memory heap.

Destroys a memory heap.

Parameters

heap	The heap descriptor.

Tags

secondary-only

6.18.2.3 void xnheap_free (struct xnheap * heap, void * block)

Release a block to a memory heap.

Releases a memory block to a heap.

Parameters

heap	The heap descriptor.
block	The block to be returned to the heap.

Tags

unrestricted

6.18.2.4 int xnheap_init (struct xnheap * heap, void * membase, u32 size)

Initialize a memory heap.

Initializes a memory heap suitable for time-bounded allocation requests of dynamic memory.

Parameters

heap	The address of a heap descriptor to initialize.	
membase	The address of the storage area.	
size	The size in bytes of the storage area. size must be a multiple of PAGE_SIZE and	
	smaller than 2 Gb in the current implementation.	

Returns

0 is returned upon success, or:

- -EINVAL is returned if size is either:
 - not aligned on PAGE_SIZE
 - smaller than 2 * PAGE_SIZE
 - greater than 2 Gb (XNHEAP_MAXHEAPSZ)
- -ENOMEM is returned upon failure of allocating the meta-data area used internally to maintain the heap.

Tags

secondary-only

6.18.2.5 void xnheap_set_name (struct xnheap * heap, const char * name, ...)

Set the heap's name string.

Set the heap name that will be used in statistic outputs.

Parameters

	heap	The address of a heap descriptor.
ĺ	name	Name displayed in statistic outputs. This parameter can be a printk()-like format
		argument list.

Tags


task-unrestricted

6.19 Cobalt 101

6.19 Cobalt

Cobalt supplements the native Linux kernel in dual kernel configurations.

Collaboration diagram for Cobalt:



Modules

Cobalt kernel

The Cobalt core is a co-kernel which supplements the Linux kernel for delivering real-time services with very low latency.

Analogy framework

A RTDM-based interface for implementing DAQ card drivers.

POSIX interface

The Cobalt/POSIX interface is an implementation of a subset of the Single Unix specification over the Cobalt core.

6.19.1 Detailed Description

Cobalt supplements the native Linux kernel in dual kernel configurations.


It deals with all time-critical activities, such as handling interrupts, and scheduling real-time threads. The Cobalt kernel has higher priority over all the native kernel activities.

Cobalt provides an implementation of the POSIX and RTDM interfaces based on a set of generic RTOS building blocks.

6.20 Cobalt kernel

The Cobalt core is a co-kernel which supplements the Linux kernel for delivering real-time services with very low latency.

Collaboration diagram for Cobalt kernel:



Modules

• Asynchronous Procedure Calls

6.20 Cobalt kernel 103

Services for scheduling function calls in the Linux domain.

In-kernel arithmetics

A collection of helpers performing arithmetics not implicitly available from kernel context via GCC helpers.

Buffer descriptor

Abstraction for copying data to/from different address spaces.

- Clock services
- Debugging services
- · Dynamic memory allocation services

The implementation of the memory allocator follows the algorithm described in a USENIX 1988 paper called "Design of a General Purpose Memory Allocator for the 4.3BSD Unix Kernel" by Marshall K.

- Interrupt management
- · Locking services

The Xenomai core deals with concurrent activities from two distinct kernels running side-by-side.

Lightweight key-to-object mapping service

A map is a simple indexing structure which associates unique integer keys with pointers to objects.

Registry services

The registry provides a mean to index object descriptors on unique alphanumeric keys.

- Thread scheduling control
- Synchronous I/O multiplexing

This module implements the services needed for implementing the POSIX select() service, or any other event multiplexing services.

- Thread synchronization services
- Thread services
- Timer services

The Xenomai timer facility depends on a clock source (xnclock) for scheduling the next activation times.

Virtual file services

Virtual files provide a mean to export Xenomai object states to user-space, based on common kernel interfaces.

6.20.1 Detailed Description

The Cobalt core is a co-kernel which supplements the Linux kernel for delivering real-time services with very low latency.

It implements a set of generic RTOS building blocks, which the Cobalt/POSIX and Cobalt/RTDM APIs are based on. Cobalt has higher priority over the Linux kernel activities.

6.20.1.1 Dual kernel service tags

The Cobalt kernel services may be restricted to particular calling contexts, or entail specific side-effects.

To describe this information, each service documented by this section bears a set of tags when applicable.

The table below matches the tags used throughout the documentation with the description of their meaning for the caller.

Context tags

Tag	Context on entry
primary-only	Must be called from a Cobalt task in primary
	mode

coreirq-only	Must be called from a Cobalt IRQ handler
secondary-only	Must be called from a Cobalt task in
	secondary mode or regular Linux task
rtdm-task	Must be called from a RTDM driver task
mode-unrestricted	Must be called from a Cobalt task in either
	primary or secondary mode
task-unrestricted	May be called from a Cobalt or regular Linux
	task indifferently
unrestricted	May be called from any context previously
	described
atomic-entry	Caller must currently hold the big Cobalt
	kernel lock (nklock)

Possible side-effects

Tag	Description
might-switch	The Cobalt kernel may switch context

6.21 Interrupt management

Collaboration diagram for Interrupt management:



Functions

void xnintr_destroy (struct xnintr *intr)

Destroy an interrupt descriptor.

• int xnintr attach (struct xnintr *intr, void *cookie)

Attach an interrupt descriptor.

void xnintr_detach (struct xnintr *intr)

Detach an interrupt descriptor.

void xnintr_enable (struct xnintr *intr)

Enable an interrupt line.

void xnintr_disable (struct xnintr *intr)

Disable an interrupt line.

void xnintr_affinity (struct xnintr *intr, cpumask_t cpumask)

Set processor affinity of interrupt.

• int xnintr_init (struct xnintr *intr, const char *name, unsigned int irq, xnisr_t isr, xniack_t iack, int flags)

Initialize an interrupt descriptor.

6.21.1 Detailed Description

6.21.2 Function Documentation

6.21.2.1 void xnintr_affinity (struct xnintr * intr, cpumask_t cpumask)

Set processor affinity of interrupt.

Restricts the IRQ line associated with the interrupt descriptor *intr* to be received only on processors which bits are set in *cpumask*.

Parameters

intr	The address of the interrupt descriptor.
cpumask	The new processor affinity.

Note

Depending on architectures, setting more than one bit in *cpumask* could be meaningless.

Tags

secondary-only

6.21.2.2 int xnintr_attach (struct xnintr * intr, void * cookie)

Attach an interrupt descriptor.

Attach an interrupt descriptor previously initialized by xnintr_init(). This operation registers the descriptor at the interrupt pipeline, but does not enable the interrupt line yet. A call to xnintr_enable() is required to start receiving IRQs from the interrupt line associated to the descriptor.

Parameters

intr	The address of the interrupt descriptor to attach.
cookie	A user-defined opaque value which is stored into the descriptor for further retrieval
	by the interrupt handler.

Returns

0 is returned on success. Otherwise:

- -EINVAL is returned if an error occurred while attaching the descriptor.
- -EBUSY is returned if the descriptor was already attached.

Note

The caller **must not** hold nklock when invoking this service, this would cause deadlocks.

Tags

secondary-only

Note

Attaching an interrupt descriptor resets the tracked number of IRQ receipts to zero.

Referenced by rtdm irg request().

6.21.2.3 void xnintr destroy (struct xnintr * intr)

Destroy an interrupt descriptor.

Destroys an interrupt descriptor previously initialized by xnintr_init(). The descriptor is automatically detached by a call to xnintr_detach(). No more IRQs will be received through this descriptor after this service has returned.

Parameters

intr The address of the interrupt descriptor to destroy.
--

Tags

secondary-only

References xnintr_detach().

Referenced by rtdm_irq_request(), and xntimer_release_hardware().

6.21.2.4 void xnintr detach (struct xnintr * intr)

Detach an interrupt descriptor.

This call unregisters an interrupt descriptor previously attached by xnintr_attach() from the interrupt pipeline. Once detached, the associated interrupt line is disabled, but the descriptor remains valid. The descriptor can be attached anew by a call to xnintr_attach().

Parameters

intr | The address of the interrupt descriptor to detach.

Note

The caller must not hold nklock when invoking this service, this would cause deadlocks.

Tags

secondary-only

Referenced by xnintr_destroy().

6.21.2.5 void xnintr disable (struct xnintr * intr)

Disable an interrupt line.

Disables the interrupt line associated with an interrupt descriptor.

Parameters

intr | The address of the interrupt descriptor.

Tags

secondary-only

6.21.2.6 void xnintr_enable (struct xnintr * intr)

Enable an interrupt line.

Enables the interrupt line associated with an interrupt descriptor.

Parameters

intr The address of the interrupt descriptor.

Tags

secondary-only

Referenced by rtdm_irq_request().

6.21.2.7 int xnintr_init (struct xnintr * intr, const char * name, unsigned int irq, xnisr_t isr, xniack_t iack, int flags)

Initialize an interrupt descriptor.

When an interrupt occurs on the given *irq* line, the interrupt service routine *isr* is fired in order to deal with the hardware event. The interrupt handler may call any non-blocking service from the Cobalt core.

Upon receipt of an IRQ, the interrupt handler *isr* is immediately called on behalf of the interrupted stack context, the rescheduling procedure is locked, and the interrupt line is masked in the system interrupt controller chip. Upon return, the status of the interrupt handler is checked for the following bits:

XN_IRQ_HANDLED indicates that the interrupt request was successfully handled.

• XN_IRQ_NONE indicates the opposite to XN_IRQ_HANDLED, meaning that no interrupt source could be identified for the ongoing request by the handler.

In addition, one of the following bits may be present in the status:

- XN_IRQ_DISABLE tells the Cobalt core to disable the interrupt line before returning from the interrupt context.
- XN_IRQ_PROPAGATE propagates the IRQ event down the interrupt pipeline to Linux. Using this flag is strongly discouraged, unless you fully understand the implications of such propagation.

Warning

The handler should not use these bits if it shares the interrupt line with other handlers in the real-time domain. When any of these bits is detected, the interrupt line is left masked.

A count of interrupt receipts is tracked into the interrupt descriptor, and reset to zero each time such descriptor is attached. Since this count could wrap around, it should be used as an indication of interrupt activity only.

Parameters

intr	The address of a descriptor the Cobalt core will use to store the interrupt-specific
	data.
name	An ASCII string standing for the symbolic name of the interrupt or NULL.
irq	The IRQ line number associated with the interrupt descriptor. This value is
	architecture-dependent. An interrupt descriptor must be attached to the system
	by a call to xnintr_attach() before <i>irq</i> events can be received.
isr	The diagnost of the mineral property and the diagnost of the mineral property
	descriptor receiving the IRQ.
iack	in the distance of the opening materials and an experimental and experimental experimental and experimental experi
	default one. Only very specific situations actually require to override the default
	setting for this parameter, like having to acknowledge non-standard PIC hardware.
	iack should return a non-zero value to indicate that the interrupt has been properly
	acknowledged. If <i>iack</i> is NULL, the default routine will be used instead.
flags	A set of creation flags affecting the operation. The valid flags are:

- XN IRQTYPE SHARED enables IRQ-sharing with other interrupt objects.
- XN_IRQTYPE_EDGE is an additional flag need to be set together with XN_IRQTYPE_SHARED to enable IRQ-sharing of edge-triggered interrupts.

Returns

0 is returned on success. Otherwise, -EINVAL is returned if *irg* is not a valid interrupt number.

Tags

secondary-only

Referenced by rtdm_irq_request(), and xntimer_grab_hardware().

6.22 Locking services

The Xenomai core deals with concurrent activities from two distinct kernels running side-by-side. Collaboration diagram for Locking services:



Macros

- #define splhigh(x) ((x) = ipipe_test_and_stall_head() & 1)
 Hard disable interrupts on the local processor, saving previous state.
- #define splexit(x) ipipe_restore_head(x & 1)

Restore the saved hard interrupt state on the local processor.

- #define splmax() ipipe_stall_head()
 - Hard disable interrupts on the local processor.
- #define splnone() ipipe_unstall_head()

Hard enable interrupts on the local processor.

#define spltest() ipipe_test_head()

Test hard interrupt state on the local processor.

6.22.1 Detailed Description

The Xenomai core deals with concurrent activities from two distinct kernels running side-by-side.

When interrupts are involved, the services from this section control the **hard** interrupt state exclusively, for protecting against processor-local or SMP concurrency.

Note

In a dual kernel configuration, *hard interrupts* are gated by the CPU. When enabled, hard interrupts are immediately delivered to the Xenomai core if they belong to a real-time source, or deferred until enabled by a second-stage virtual interrupt mask, if they belong to regular Linux devices/sources.

6.22.2 Macro Definition Documentation

6.22.2.1 #define splexit(x) ipipe_restore_head(x & 1)

Restore the saved hard interrupt state on the local processor.

Parameters

in	X	The context variable previously updated by splhigh()
	, ,	in the second random provided by aparation by aparation by

6.22.2.2 #define splhigh(x) ((x) = ipipe_test_and_stall_head() & 1)

Hard disable interrupts on the local processor, saving previous state.

Parameters

out	X	An unsigned long integer context variable
-----	---	---

6.22.2.3 #define spltest() ipipe_test_head()

Test hard interrupt state on the local processor.


Returns

Zero if the local processor currently accepts interrupts, non-zero otherwise.

Referenced by rtdm_fd_select(), and rtdm_lock_get().

6.23 Lightweight key-to-object mapping service

A map is a simple indexing structure which associates unique integer keys with pointers to objects. Collaboration diagram for Lightweight key-to-object mapping service:



Functions

- struct xnmap * xnmap_create (int nkeys, int reserve, int offset)
 Create a map.
- void xnmap_delete (struct xnmap *map)

Delete a map.

• int xnmap_enter (struct xnmap *map, int key, void *objaddr)

Index an object into a map.

int xnmap_remove (struct xnmap *map, int key)

Remove an object reference from a map.

static void * xnmap_fetch_nocheck (struct xnmap *map, int key)

Search an object into a map - unchecked form.

static void * xnmap_fetch (struct xnmap *map, int key)

Search an object into a map.

6.23.1 Detailed Description

A map is a simple indexing structure which associates unique integer keys with pointers to objects.

The current implementation supports reservation, for naming/indexing objects, either on a fixed, user-provided integer (i.e. a reserved key value), or by drawing the next available key internally if the caller did not specify any fixed key. For instance, in some given map, the key space ranging from 0 to 255 could be reserved for fixed keys, whilst the range from 256 to 511 could be available for drawing free keys dynamically.

A maximum of 1024 unique keys per map is supported on 32bit machines.

(This implementation should not be confused with C++ STL maps, which are dynamically expandable and allow arbitrary key types; Xenomai maps don't).

6.23.2 Function Documentation

6.23.2.1 struct xnmap * xnmap_create (int nkeys, int reserve, int offset)

Create a map.

Allocates a new map with the specified addressing capabilities. The memory is obtained from the Xenomai system heap.

Parameters

nkeys	The maximum number of unique keys the map will be able to hold. This value cannot exceed the static limit represented by XNMAP_MAX_KEYS, and must be a power of two.
reserve	The number of keys which should be kept for reservation within the index space. Reserving a key means to specify a valid key to the xnmap_enter() service, which will then attempt to register this exact key, instead of drawing the next available key from the unreserved index space. When reservation is in effect, the unreserved index space will hold key values greater than <i>reserve</i> , keeping the low key values for the reserved space. For instance, passing <i>reserve</i> = 32 would cause the index range [0 31] to be kept for reserved keys. When non-zero, <i>reserve</i> is rounded to the next multiple of BITS_PER_LONG. If <i>reserve</i> is zero no reservation will be available from the map.
offset	The lowest key value xnmap_enter() will return to the caller. Key values will be in the range [0 + offset nkeys + offset - 1]. Negative offsets are valid.

Returns

the address of the new map is returned on success; otherwise, NULL is returned if *nkeys* is invalid.

Tags

task-unrestricted

6.23.2.2 void xnmap_delete (struct xnmap * map)

Delete a map.

Deletes a map, freeing any associated memory back to the Xenomai system heap.

Parameters

map	The address of the map to delete.

Tags

task-unrestricted

6.23.2.3 int xnmap_enter (struct xnmap * map, int key, void * objaddr)

Index an object into a map.

Insert a new object into the given map.

Parameters

тар	The address of the map to insert into.
key	The key to index the object on. If this key is within the valid index range [0 - offset
	nkeys - offset - 1], then an attempt to reserve this exact key is made. If <i>key</i> has an out-of-range value lower or equal to 0 - offset - 1, then an attempt is made to draw a free key from the unreserved index space.

objaddr	The address of the object to index on the key. This value will be returned by a
	successful call to xnmap_fetch() with the same key.

Returns

a valid key is returned on success, either key if reserved, or the next free key. Otherwise:

- -EEXIST is returned upon attempt to reserve a busy key.
- -ENOSPC when no more free key is available.

Tags

unrestricted

6.23.2.4 void xnmap_fetch (struct xnmap * map, int key) [inline], [static]

Search an object into a map.

Retrieve an object reference from the given map by its index key.

Parameters

тар	The address of the map to retrieve from.
key	The key to be searched for in the map index.

Returns

The indexed object address is returned on success, otherwise NULL is returned when *key* is invalid or no object is currently indexed on it.

Tags

unrestricted

6.23.2.5 void xnmap_fetch_nocheck (struct xnmap * map, int key) [inline], [static]

Search an object into a map - unchecked form.

Retrieve an object reference from the given map by its index key, but does not perform any sanity check on the provided key.

Parameters

тар	The address of the map to retrieve from.
key	The key to be searched for in the map index.

Returns

The indexed object address is returned on success, otherwise NULL is returned when no object is currently indexed on *key*.

Tags

unrestricted

6.23.2.6 int xnmap_remove (struct xnmap * map, int key)

Remove an object reference from a map.

Removes an object reference from the given map, releasing the associated key.

Parameters

тар	The address of the map to remove from.
key	The key the object reference to be removed is indexed on.

Returns

0 is returned on success. Otherwise:

• -ESRCH is returned if key is invalid.

Tags

unrestricted

6.24 Registry services

The registry provides a mean to index object descriptors on unique alphanumeric keys.

Collaboration diagram for Registry services:



Functions

- int xnregistry_enter (const char *key, void *objaddr, xnhandle_t *phandle, struct xnpnode *pnode)

 Register a real-time object.
- int xnregistry_bind (const char *key, xnticks_t timeout, int timeout_mode, xnhandle_t *phandle)

 Bind to a real-time object.
- int xnregistry_remove (xnhandle_t handle)

Forcibly unregister a real-time object.

- static void * xnregistry_lookup (xnhandle_t handle, unsigned long *cstamp_r)
 Find a real-time object into the registry.
- int xnregistry_unlink (const char *key)

Turn a named object into an anonymous object.

6.24.1 Detailed Description

The registry provides a mean to index object descriptors on unique alphanumeric keys.

When labeled this way, an object is globally exported; it can be searched for, and its descriptor returned to the caller for further use; the latter operation is called a "binding". When no object has been registered under the given name yet, the registry can be asked to set up a rendez-vous, blocking the caller until the object is eventually registered.

6.24.2 Function Documentation

6.24.2.1 int xnregistry_bind (const char * key, xnticks_t timeout, int timeout_mode, xnhandle_t * phandle)

Bind to a real-time object.

This service retrieves the registry handle of a given object identified by its key. Unless otherwise specified, this service will block the caller if the object is not registered yet, waiting for such registration to occur.

Parameters

key	A valid NULL-terminated string which identifies the object to bind to.
timeout	The timeout which may be used to limit the time the thread wait for the object to be
	registered. This value is a wait time given as a count of nanoseconds. It can either
	be relative, absolute monotonic (XN_ABSOLUTE), or absolute adjustable (XN_RE↔
	ALTIME) depending on timeout_mode. Passing XN_INFINITE and setting timeout⊷
	_mode to XN_RELATIVE specifies an unbounded wait. Passing XN_NONBLO
	CK causes the service to return immediately without waiting if the object is not
	registered on entry. All other values are used as a wait limit.
timeout_mode	The mode of the <i>timeout</i> parameter. It can either be set to XN_RELATIVE, XN_A ←
	BSOLUTE, or XN_REALTIME (see also xntimer_start()).
phandle	A pointer to a memory location which will be written upon success with the generic
	handle defined by the registry for the retrieved object. Contents of this memory is
	undefined upon failure.

Returns

0 is returned upon success. Otherwise:

- -EINVAL is returned if key is NULL.
- -EINTR is returned if xnthread_unblock() has been called for the waiting thread before the retrieval has completed.
- -EWOULDBLOCK is returned if timeout is equal to XN_NONBLOCK and the searched object is not registered on entry. As a special exception, this error is also returned if this service should block, but was called from a context which cannot sleep (e.g. interrupt, non-realtime or scheduler locked).
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.

Tags

primary-only, might-switch

Note

xnregistry_bind() only returns the index portion of a handle, which might include other fixed bits to be complete (e.g. XNSYNCH_PSHARED). The caller is responsible for completing the handle returned with those bits if applicable, depending on the context.

References XNBREAK, xnsynch_sleep_on(), and XNTIMEO.

6.24.2.2 int xnregistry_enter (const char * key, void * objaddr, xnhandle_t * phandle, struct xnpnode * pnode)

Register a real-time object.

This service allocates a new registry slot for an associated object, and indexes it by an alphanumeric key for later retrieval.

Parameters

key	A valid NULL-terminated string by which the object will be indexed and later retrieved
	in the registry. Since it is assumed that such key is stored into the registered object,
	it will not be copied but only kept by reference in the registry. Pass an empty or
	NULL string if the object shall only occupy a registry slot for handle-based lookups.

objaddr	An opaque pointer to the object to index by <i>key</i> .
phandle	A pointer to a generic handle defined by the registry which will uniquely identify the
	indexed object, until the latter is unregistered using the xnregistry_remove() service.
pnode	A pointer to an optional /proc node class descriptor. This structure provides the in-
	formation needed to export all objects from the given class through the /proc filesys-
	tem, under the /proc/xenomai/registry entry. Passing NULL indicates that no /proc
	support is available for the newly registered object.

Returns

0 is returned upon success. Otherwise:

- -EINVAL is returned if objaddr is NULL, or if key is non-NULL and contains an invalid '/' character.
- -ENOMEM is returned if the system fails to get enough dynamic memory from the global real-time heap in order to register the object.
- -EEXIST is returned if the key is already in use.

Tags

unrestricted, might-switch, atomic-entry

References xnsched run().

Referenced by rtdm_dev_register().

Find a real-time object into the registry.

This service retrieves an object from its handle into the registry and returns the memory address of its descriptor. Optionally, it also copies back the object's creation stamp which is unique across object registration calls.

Parameters

handle	The generic handle of the object to fetch.
cstamp_r	If not-NULL, the object's creation stamp will be copied to this memory area.

Returns

The memory address of the object's descriptor is returned on success. Otherwise, NULL is returned if *handle* does not reference a registered object.

Tags

unrestricted

6.24.2.4 int xnregistry remove (xnhandle thandle)

Forcibly unregister a real-time object.

This service forcibly removes an object from the registry. The removal is performed regardless of the current object's locking status.

Parameters

handle	The generic handle of the object to remove.
--------	---

Returns

0 is returned upon success. Otherwise:

• -ESRCH is returned if handle does not reference a registered object.

Tags

unrestricted

Referenced by rtdm_dev_register(), and rtdm_dev_unregister().

```
6.24.2.5 int xnregistry_unlink ( const char * key )
```

Turn a named object into an anonymous object.


Tags

unrestricted

6.25 Driver programming interface

RTDM driver programming interface.

Collaboration diagram for Driver programming interface:



Modules

- Driver to driver services
 - Inter-driver interface.
- Device Registration Services
- Clock Services
- Task Services
- Timer Services
- Synchronisation Services
- Interrupt Management Services
- Non-Real-Time Signalling Services

These services provide a mechanism to request the execution of a specified handler in non-real-time context.

Utility Services


6.25.1 Detailed Description

RTDM driver programming interface.

6.26 Driver to driver services

Inter-driver interface.

Collaboration diagram for Driver to driver services:



Functions

• int rtdm_open (const char *path, int oflag,...)

Open a device.

• int rtdm_socket (int protocol_family, int socket_type, int protocol)

Create a socket.

int rtdm_close (int fd)

Close a device or socket.

int rtdm_ioctl (int fd, int request,...)

Issue an IOCTL.

• ssize t rtdm read (int fd, void *buf, size t nbyte)

Read from device.

• ssize_t rtdm_write (int fd, const void *buf, size_t nbyte)

Write to device.

ssize_t rtdm_recvmsg (int fd, struct user_msghdr *msg, int flags)

Receive message from socket.

ssize_t rtdm_recvfrom (int fd, void *buf, size_t len, int flags, struct sockaddr *from, socklen_
 t *fromlen)

Receive message from socket.

ssize_t rtdm_recv (int fd, void *buf, size_t len, int flags)

Receive message from socket.

• ssize_t rtdm_sendmsg (int fd, const struct user_msghdr *msg, int flags)

Transmit message to socket.

ssize_t rtdm_sendto (int fd, const void *buf, size_t len, int flags, const struct sockaddr *to, socklen
 _t tolen)

Transmit message to socket.

• ssize t rtdm send (int fd, const void *buf, size t len, int flags)

Transmit message to socket.

• int rtdm_bind (int fd, const struct sockaddr *my_addr, socklen_t addrlen)

Bind to local address.

• int rtdm_connect (int fd, const struct sockaddr *serv_addr, socklen_t addrlen)

Connect to remote address.

int rtdm_listen (int fd, int backlog)

Listen to incoming connection requests.

int rtdm_accept (int fd, struct sockaddr *addr, socklen_t *addrlen)

Accept a connection request.

• int rtdm_shutdown (int fd, int how)

Shut down parts of a connection.

• int rtdm_getsockopt (int fd, int level, int optname, void *optval, socklen_t *optlen)

Get socket option.

int rtdm_setsockopt (int fd, int level, int optname, const void *optval, socklen_t optlen)
 Set socket option.

• int rtdm_getsockname (int fd, struct sockaddr *name, socklen_t *namelen)

• int rtdm_getpeername (int fd, struct sockaddr *name, socklen_t *namelen)

Get socket destination address.

Get local socket address.

6.26.1 Detailed Description

Inter-driver interface.

6.26.2 Function Documentation

6.26.2.1 int rtdm_accept (int fd, struct sockaddr * addr, socklen_t * addrlen)

Accept a connection request.

Accept connection requests.

Refer to rtdm_accept() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
out	addr	Buffer for remote address
in,out	addrlen	Address buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

accept() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.2 int rtdm_bind (int fd, const struct sockaddr * my_addr, socklen_t addrlen)

Bind to local address.

Refer to rtdm_bind() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	my_addr	Address buffer
in	addrlen	Address buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

bind() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.3 int rtdm_close (int fd)

Close a device or socket.

Refer to rtdm_close() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

secondary-only, might-switch

Parameters

_			
	in	fd	File descriptor as returned by rtdm_open() or rtdm_socket()

Returns

0 on success, otherwise a negative error code.

Note

If the matching rtdm_open() or rtdm_socket() call took place in non-real-time context, rtdm_close() must be issued within non-real-time as well. Otherwise, the call will fail.

Action depends on driver implementation, see Device Profiles.

See also

124

close() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

secondary-only, might-switch

6.26.2.4 int rtdm connect (int fd, const struct sockaddr * serv addr, socklen t addrlen)

Connect to remote address.

Refer to rtdm_connect() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	serv_addr	Address buffer
in	addrlen	Address buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

connect() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.5 int rtdm_getpeername (int fd, struct sockaddr * name, socklen_t * namelen)

Get socket destination address.

Refer to rtdm_getpeername() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()

out	name	Address buffer
in,out	namelen	Address buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

getpeername() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

task-unrestricted, might-switch

6.26.2.6 int rtdm_getsockname (int fd, struct sockaddr * name, socklen_t * namelen)

Get local socket address.

Refer to rtdm_getsockname() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
out	name	Address buffer
in,out	namelen	Address buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

getsockname() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

task-unrestricted, might-switch

6.26.2.7 int rtdm_getsockopt (int fd, int level, int optname, void * optval, socklen_t * optlen)

Get socket option.

Refer to rtdm_getsockopt() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	level	Addressed stack level
in	optname	Option name ID
out	optval	Value buffer
in,out	optlen	Value buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

```
getsockopt() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

Tags

task-unrestricted, might-switch

6.26.2.8 int rtdm_ioctl (int fd, int request, ...)

Issue an IOCTL.

Refer to rtdm_ioctl() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_open() or rtdm_socket()
in	request	IOCTL code
		Optional third argument, depending on IOCTL function (void * or
		unsigned long)

Returns

Positiv value on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

```
ioctl() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

Tags

task-unrestricted, might-switch

6.26.2.9 int rtdm_listen (int fd, int backlog)

Listen to incoming connection requests.

Listen for incomming connection requests.

Refer to rtdm_listen() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	backlog	Maximum queue length

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

listen() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

task-unrestricted, might-switch

6.26.2.10 int rtdm_open (const char * path, int oflag, ...)

Open a device.

Refer to rtdm_open() for parameters and return values

Tags

secondary-only, might-switch

Parameters

in	path	Device name
in	oflag	Open flags
		Further parameters will be ignored.

Returns

Positive file descriptor value on success, otherwise a negative error code.

Action depends on driver implementation, see Device Profiles.

See also

open() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

secondary-only, might-switch

```
6.26.2.11 ssize_t rtdm_read ( int fd, void * buf, size_t nbyte )
```

Read from device.

Refer to rtdm_read() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

128

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_open()
out	buf	Input buffer
in	nbyte	Number of bytes to read

Returns

Number of bytes read, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

```
read() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

Tags

mode-unrestricted, might-switch

```
6.26.2.12 ssize_t rtdm_recv ( int fd, void * buf, size_t len, int flags )
```

Receive message from socket.

Refer to rtdm_recv() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
out	buf	Message buffer
in	len	Message buffer size
in	flags	Message flags

Returns

Number of bytes received, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

```
recv() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

Tags

mode-unrestricted, might-switch

6.26.2.13 ssize_t rtdm_recvfrom (int fd, void * buf, size_t len, int flags, struct sockaddr * from, socklen_t * fromlen)

Receive message from socket.

Refer to rtdm_recvfrom() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
out	buf	Message buffer
in	len	Message buffer size
in	flags	Message flags
out	from	Buffer for message sender address
in,out	fromlen	Address buffer size

Returns

Number of bytes received, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

recvfrom() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.14 ssize_t rtdm_recvmsg (int fd, struct user_msghdr * msg, int flags)

Receive message from socket.

Refer to rtdm_recvmsg() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in,out	msg	Message descriptor
in	flags	Message flags

Returns

Number of bytes received, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

recvmsg() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.15 ssize t rtdm send (int fd, const void * buf, size t len, int flags)

Transmit message to socket.

Refer to rtdm_send() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	buf	Message buffer
in	len	Message buffer size
in	flags	Message flags

Returns

Number of bytes sent, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

send() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.16 ssize_t rtdm_sendmsg (int fd, const struct user_msghdr * msg, int flags)

Transmit message to socket.

Refer to rtdm_sendmsg() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	msg	Message descriptor
in	flags	Message flags

Returns

Number of bytes sent, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

sendmsg() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.17 ssize_t rtdm_sendto (int fd, const void * buf, size_t len, int flags, const struct sockaddr * to, socklen_t tolen)

Transmit message to socket.

Refer to rtdm_sendto() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	buf	Message buffer
in	len	Message buffer size
in	flags	Message flags
in	to	Buffer for message destination address
in	tolen	Address buffer size

Returns

Number of bytes sent, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

sendto() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

mode-unrestricted, might-switch

6.26.2.18 int rtdm_setsockopt (int fd, int level, int optname, const void * optval, socklen_t optlen)

Set socket option.

Refer to rtdm_setsockopt() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

task-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	level	Addressed stack level
in	optname	Option name ID
in	optval	Value buffer
in	optlen	Value buffer size

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

setsockopt() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

task-unrestricted, might-switch

6.26.2.19 int rtdm_shutdown (int fd, int how)

Shut down parts of a connection.

Refer to rtdm_shutdown() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

secondary-only, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_socket()
in	how	Specifies the part to be shut down (SHUT_xxx)

Returns

0 on success, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

shutdown() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

Tags

secondary-only, might-switch

6.26.2.20 int rtdm_socket (int protocol_family, int socket_type, int protocol)

Create a socket.

Refer to rtdm_socket() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

secondary-only, might-switch

Parameters

in	protocol_family	Protocol family (PF_xxx)
in	socket_type	Socket type (SOCK_xxx)
in	protocol	Protocol ID, 0 for default

Returns

Positive file descriptor value on success, otherwise a negative error code.

Action depends on driver implementation, see Device Profiles.

See also

```
socket() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

Tags

secondary-only, might-switch

```
6.26.2.21 ssize_t rtdm_write ( int fd, const void * buf, size_t nbyte )
```

Write to device.

Refer to rtdm_write() for parameters and return values. Action depends on driver implementation, see Device Profiles.

Tags

mode-unrestricted, might-switch

Parameters

in	fd	File descriptor as returned by rtdm_open()
in	buf	Output buffer
in	nbyte	Number of bytes to write

Returns

Number of bytes written, otherwise negative error code

Action depends on driver implementation, see Device Profiles.

See also

```
write() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```


Tags

mode-unrestricted, might-switch

6.27 Device Profiles

Pre-defined classes of real-time devices.

Collaboration diagram for Device Profiles:



Modules

• User-space driver core

This profile includes all mini-drivers sitting on top of the User-space Device Driver framework (UDD).

CAN Devices

This is the common interface a RTDM-compliant CAN device has to provide.

Serial Devices

This is the common interface a RTDM-compliant serial device has to provide.

Testing Devices

This group of devices is intended to provide in-kernel testing results.

• Real-time IPC

Profile Revision: 1

Data Structures

struct rtdm_device_info

Device information.

Typedefs

typedef struct rtdm_device_info rtdm_device_info_t
 Device information.

6.27 Device Profiles

RTDM CLASS xxx

Device classes

- #define RTDM CLASS PARPORT 1
- #define RTDM_CLASS_SERIAL 2
- #define RTDM_CLASS_CAN 3
- #define RTDM_CLASS_NETWORK 4
- #define RTDM CLASS RTMAC 5
- #define RTDM CLASS TESTING 6
- #define RTDM CLASS RTIPC 7
- #define RTDM_CLASS_COBALT 8
- #define RTDM CLASS UDD 9
- #define RTDM_CLASS_MEMORY 10
- #define RTDM CLASS MISC 223
- #define RTDM CLASS EXPERIMENTAL 224
- #define RTDM_CLASS_MAX 255

Device Naming

Maximum length of device names (excluding the final null character)

• #define RTDM MAX DEVNAME LEN 31

RTDM PURGE xxx BUFFER

Flags selecting buffers to be purged

- #define RTDM PURGE RX BUFFER 0x0001
- #define RTDM_PURGE_TX_BUFFER 0x0002

Common IOCTLs

The following IOCTLs are common to all device rtdm_profiles.

- #define RTIOC_DEVICE_INFO _IOR(RTIOC_TYPE_COMMON, 0x00, struct rtdm_device_info)
 Retrieve information about a device or socket.
- #define RTIOC PURGE IOW(RTIOC TYPE COMMON, 0x10, int)

Purge internal device or socket buffers.

6.27.1 Detailed Description

Pre-defined classes of real-time devices.

Device profiles define which operation handlers a driver of a certain class of devices has to implement, which name or protocol it has to register, which IOCTLs it has to provide, and further details. Sub-classes can be defined in order to extend a device profile with more hardware-specific functions.

- 6.27.2 Macro Definition Documentation
- 6.27.2.1 #define RTIOC_DEVICE_INFO _IOR(RTIOC_TYPE_COMMON, 0x00, struct rtdm_device_info)

Retrieve information about a device or socket.

6.27 Device Profiles 137

Parameters

out	arg	Pointer to information buffer (struct rtdm_device_info)
-----	-----	---

6.27.2.2 #define RTIOC_PURGE_IOW(RTIOC_TYPE_COMMON, 0x10, int)


Purge internal device or socket buffers.

Parameters

in	arg	Purge mask, see RTDM_PURGE_xxx_BUFFER
----	-----	---------------------------------------

6.28 Device Registration Services

Collaboration diagram for Device Registration Services:



Data Structures

struct rtdm_fd_ops

RTDM file operation descriptor.

Macros

#define RTDM_MAX_MINOR 256

Maximum number of named devices per driver.

Functions

• int rtdm_open_handler (struct rtdm_fd *fd, int oflags)

Open handler for named devices.

• int rtdm_socket_handler (struct rtdm_fd *fd, int protocol)

Socket creation handler for protocol devices.

void rtdm_close_handler (struct rtdm_fd *fd)

Close handler.

int rtdm_ioctl_handler (struct rtdm_fd *fd, unsigned int request, void __user *arg)

IOCTL handler.

ssize_t rtdm_read_handler (struct rtdm_fd *fd, void __user *buf, size_t size)

Read handler.

• ssize_t rtdm_write_handler (struct rtdm_fd *fd, const void __user *buf, size_t size)

Write handler.

ssize t rtdm recvmsg handler (struct rtdm fd *fd, struct user msghdr *msg, int flags)

Receive message handler.

• ssize_t rtdm_sendmsg_handler (struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)

Transmit message handler.

• int rtdm_select_handler (struct rtdm_fd *fd, struct xnselector *selector, unsigned int type, unsigned int index)

Select handler.

• int rtdm_mmap_handler (struct rtdm_fd *fd, struct vm_area_struct *vma)

Memory mapping handler.

• unsigned long rtdm_get_unmapped_area_handler (struct rtdm_fd *fd, unsigned long len, unsigned long pgoff, unsigned long flags)

Allocate mapping region in address space.

• int rtdm_dev_register (struct rtdm_device *dev)

Register a RTDM device.

void rtdm_dev_unregister (struct rtdm_device *dev)

Unregister a RTDM device.

Device Flags

Static flags describing a RTDM device

• #define RTDM EXCLUSIVE 0x0001

If set, only a single instance of the device can be requested by an application.

#define RTDM FIXED MINOR 0x0002

Use fixed minor provided in the rtdm_device description for registering.

• #define RTDM NAMED DEVICE 0x0010

If set, the device is addressed via a clear-text name.

#define RTDM_PROTOCOL_DEVICE 0x0020

If set, the device is addressed via a combination of protocol ID and socket type.

#define RTDM_DEVICE_TYPE_MASK 0x00F0

Mask selecting the device type.

#define RTDM SECURE DEVICE 0x80000000

Flag indicating a secure variant of RTDM (not supported here)

- 6.28.1 Detailed Description
- 6.28.2 Macro Definition Documentation
- 6.28.2.1 #define RTDM_DEVICE_TYPE_MASK 0x00F0

Mask selecting the device type.

6.28.2.2 #define RTDM_EXCLUSIVE 0x0001

If set, only a single instance of the device can be requested by an application.

6.28.2.3 #define RTDM_FIXED_MINOR 0x0002

Use fixed minor provided in the rtdm_device description for registering.

If this flag is absent, the RTDM core assigns minor numbers to devices managed by a driver in order of registration.

Referenced by rtdm_dev_register().

6.28.2.4 #define RTDM_MAX_MINOR 256

Maximum number of named devices per driver.

Referenced by rtdm_dev_register().

6.28.2.5 #define RTDM_NAMED_DEVICE 0x0010

If set, the device is addressed via a clear-text name.

Referenced by rtdm dev register(), rtdm dev unregister(), and udd register device().

6.28.2.6 #define RTDM_PROTOCOL_DEVICE 0x0020

If set, the device is addressed via a combination of protocol ID and socket type.

Referenced by udd_register_device().

6.28.3 Function Documentation

6.28.3.1 void rtdm_close_handler (struct rtdm_fd * fd)

Close handler.

Parameters

in	fd	File descriptor associated with opened device instance.
----	----	---

See also

close() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

6.28.3.2 int rtdm_dev_register (struct rtdm_device * dev)

Register a RTDM device.

Registers a device in the RTDM namespace.

Parameters

in	dev	Device descriptor.

Returns

0 is returned upon success. Otherwise:

- -EINVAL is returned if the descriptor contains invalid entries. RTDM_PROFILE_INFO() must appear in the list of initializers for the driver properties.
- -EEXIST is returned if the specified device name of protocol ID is already in use.
- -ENOMEM is returned if a memory allocation failed in the process of registering the device.
- -EAGAIN is returned if no registry slot is available (check/raise CONFIG_XENO_OPT_REGIST
 — RY NRSLOTS).

Tags

secondary-only

References rtdm_fd_ops::close, rtdm_driver::device_count, rtdm_driver::device_flags, rtdm_device ::driver, rtdm_device::label, rtdm_device::minor, rtdm_fd_ops::open, rtdm_driver::ops, rtdm_driver ::protocol_family, RTDM_FIXED_MINOR, RTDM_MAX_MINOR, RTDM_NAMED_DEVICE, rtdm_fd_cops::socket, rtdm_driver::socket_type, xnregistry_enter(), and xnregistry_remove().

Referenced by udd_register_device().

6.28.3.3 void rtdm_dev_unregister (struct rtdm_device * dev)

Unregister a RTDM device.

Removes the device from the RTDM namespace. This routine waits until all connections to *device* have been closed prior to unregistering.

Parameters

in	dev	Device descriptor.

Tags

secondary-only

References rtdm_driver::device_flags, rtdm_device::driver, rtdm_device::minor, RTDM_NAMED_DEV LCE, and xnregistry_remove().

Referenced by udd register device(), and udd unregister device().

6.28.3.4 unsigned long rtdm_get_unmapped_area_handler (struct rtdm_fd * fd, unsigned long len, unsigned long pgoff, unsigned long flags)

Allocate mapping region in address space.

When present, this optional handler should return the start address of a free region in the process's address space, large enough to cover the ongoing mmap() operation. If unspecified, the default architecture-defined handler is invoked.

Most drivers can omit this handler, except on MMU-less platforms (see second note).

Parameters

in	fd	File descriptor
in	len	Length of the requested region
in	pgoff	Page frame number to map to (see second note).
in	flags	Requested mapping flags

Returns

The start address of the mapping region on success. On failure, a negative error code should be returned, with -ENOSYS meaning that the driver does not want to provide such information, in which case the ongoing mmap() operation will fail.

Note

The address hint passed to the mmap() request is deliberately ignored by RTDM, and therefore not passed to this handler.

On MMU-less platforms, this handler is required because RTDM issues mapping requests over a shareable character device internally. In such context, the RTDM core may pass a null *pgoff* argument to the handler, for probing for the logical start address of the memory region to map to. Otherwise, when *pgoff* is non-zero, pgoff << PAGE_SHIFT is usually returned.

6.28.3.5 int rtdm_ioctl_handler (struct rtdm_fd * fd, unsigned int request, void __user * arg)

IOCTL handler.

Parameters

	in	fd	File descriptor
Ī	in	request	Request number as passed by the user
Ī	in,out	arg	Request argument as passed by the user

Returns

A positive value or 0 on success. On failure return either -ENOSYS, to request that the function be called again from the opposite realtime/non-realtime context, or another negative error code.

See also

```
ioctl() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

6.28.3.6 int rtdm mmap handler (struct rtdm fd * fd, struct vm area struct * vma)

Memory mapping handler.

Parameters

in	fd	File descriptor
in	vma	Virtual memory area descriptor

Returns

0 on success. On failure, a negative error code is returned.

See also

```
mmap() in POSIX.1-2001, http://pubs.opengroup.org/onlinepubs/7908799/xsh/mmap.html
```

Note

The address hint passed to the mmap() request is deliberately ignored by RTDM.

```
6.28.3.7 int rtdm_open_handler ( struct rtdm_fd * fd, int oflags )
```

Open handler for named devices.

Parameters

in	fd	File descriptor associated with opened device instance
in	oflags	Open flags as passed by the user

The file descriptor carries a device minor information which can be retrieved by a call to rtdm_fd_← minor(fd). The minor number can be used for distinguishing devices managed by a driver.

Returns

0 on success. On failure, a negative error code is returned.

See also

```
open() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399
```

6.28.3.8 ssize_t rtdm_read_handler (struct rtdm_fd * fd, void __user * buf, size_t size)

Read handler.

Parameters

in	fd	File descriptor
out	buf	Input buffer as passed by the user
in	size	Number of bytes the user requests to read

Returns

On success, the number of bytes read. On failure return either -ENOSYS, to request that this handler be called again from the opposite realtime/non-realtime context, or another negative error code.

See also

read() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

6.28.3.9 ssize_t rtdm_recvmsg_handler (struct rtdm_fd * fd, struct user_msghdr * msg, int flags)

Receive message handler.

Parameters

in	fd	File descriptor
in,out	msg	Message descriptor as passed by the user, automatically mirrored to
		safe kernel memory in case of user mode call
in	flags	Message flags as passed by the user

Returns

On success, the number of bytes received. On failure return either -ENOSYS, to request that this handler be called again from the opposite realtime/non-realtime context, or another negative error code.

See also

recvmsg() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

6.28.3.10 int rtdm_select_handler (struct rtdm_fd * fd, struct xnselector * selector, unsigned int type, unsigned int index)

Select handler.

Parameters

in	fd	File descriptor
	selector	Pointer to the selector structure
	type	Type of events (XNSELECT_READ, XNSELECT_WRITE, or XNSE LECT_EXCEPT)
	index	Index of the file descriptor

Returns

0 on success. On failure, a negative error code is returned.

See also

select() in POSIX.1-2001, http://pubs.opengroup.org/onlinepubs/007908799/xsh/select.← html

6.28.3.11 ssize_t rtdm_sendmsg_handler (struct rtdm_fd * fd, const struct user_msghdr * msg, int flags)

Transmit message handler.

in	fd	File descriptor
in	msg	Message descriptor as passed by the user, automatically mirrored to
		safe kernel memory in case of user mode call
in	flags	Message flags as passed by the user

Returns

On success, the number of bytes transmitted. On failure return either -ENOSYS, to request that this handler be called again from the opposite realtime/non-realtime context, or another negative error code.

See also

sendmsg() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

6.28.3.12 int rtdm socket handler (struct rtdm fd * fd, int protocol)

Socket creation handler for protocol devices.

Parameters

in	fd	File descriptor associated with opened device instance
in	protocol	Protocol number as passed by the user

Returns

0 on success. On failure, a negative error code is returned.

See also

socket() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

6.28.3.13 ssize_t rtdm_write_handler (struct rtdm_fd * fd, const void __user * buf, size_t size)

Write handler.

Parameters

in	fd	File descriptor
in	buf	Output buffer as passed by the user
in	size	Number of bytes the user requests to write

Returns


On success, the number of bytes written. On failure return either -ENOSYS, to request that this handler be called again from the opposite realtime/non-realtime context, or another negative error code.

See also

write() in IEEE Std 1003.1, http://www.opengroup.org/onlinepubs/009695399

6.29 Clock Services

Collaboration diagram for Clock Services:



Functions

146

- nanosecs_abs_t rtdm_clock_read (void)
 Get system time.
- nanosecs_abs_t rtdm_clock_read_monotonic (void)
 Get monotonic time.

6.29.1 Detailed Description

6.29.2 Function Documentation

6.29.2.1 **nanosecs_abs_t** rtdm_clock_read (void)

Get system time.

Returns

The system time in nanoseconds is returned

Note

The resolution of this service depends on the system timer. In particular, if the system timer is running in periodic mode, the return value will be limited to multiples of the timer tick period. The system timer may have to be started to obtain valid results. Whether this happens automatically (as on Xenomai) or is controlled by the application depends on the RTDM host environment.

Tags

unrestricted

Referenced by a4l_get_time(), and rtdm_ratelimit().

6.29.2.2 **nanosecs_abs_t** rtdm_clock_read_monotonic (void)

Get monotonic time.

Returns

The monotonic time in nanoseconds is returned

6.29 Clock Services 147

Note


The resolution of this service depends on the system timer. In particular, if the system timer is running in periodic mode, the return value will be limited to multiples of the timer tick period. The system timer may have to be started to obtain valid results. Whether this happens automatically (as on Xenomai) or is controlled by the application depends on the RTDM host environment.

Tags

unrestricted

6.30 Task Services

Collaboration diagram for Task Services:



Typedefs

typedef void(* rtdm_task_proc_t) (void *arg)
 Real-time task procedure.

Functions

int rtdm_task_init (rtdm_task_t *task, const char *name, rtdm_task_proc_t task_proc, void *arg, int priority, nanosecs_rel_t period)

Initialise and start a real-time task.

void rtdm_task_destroy (rtdm_task_t *task)

Destroy a real-time task.

int rtdm_task_should_stop (void)

Check for pending termination request.

void rtdm_task_set_priority (rtdm_task_t *task, int priority)

Adjust real-time task priority.

• int rtdm_task_set_period (rtdm_task_t *task, nanosecs_abs_t start_date, nanosecs_rel_t period)

Adjust real-time task period.

int rtdm_task_wait_period (unsigned long *overruns_r)

Wait on next real-time task period.

• int rtdm task unblock (rtdm task t *task)

Activate a blocked real-time task.

rtdm task t * rtdm task current (void)

Get current real-time task.

• int rtdm_task_sleep (nanosecs_rel_t delay)

Sleep a specified amount of time.

int rtdm_task_sleep_until (nanosecs_abs_t wakeup_time)

Sleep until a specified absolute time.

• int rtdm_task_sleep_abs (nanosecs_abs_t wakeup_time, enum rtdm_timer_mode mode)

Sleep until a specified absolute time.

• int rtdm_task_busy_wait (bool condition, nanosecs_rel_t spin_ns, nanosecs_rel_t sleep_ns) Safe busy waiting.

• void rtdm_task_join (rtdm_task_t *task)

Wait on a real-time task to terminate.

void rtdm_task_busy_sleep (nanosecs_rel_t delay)

Busy-wait a specified amount of time.

6.30 Task Services 149

Task Priority Range

Maximum and minimum task priorities

- #define RTDM_TASK_LOWEST_PRIORITY 0
- #define RTDM_TASK_HIGHEST_PRIORITY 99

Task Priority Modification

Raise or lower task priorities by one level

- #define RTDM_TASK_RAISE_PRIORITY (+1)
- #define RTDM_TASK_LOWER_PRIORITY (-1)
- 6.30.1 Detailed Description
- 6.30.2 Typedef Documentation
- 6.30.2.1 typedef void(* rtdm_task_proc_t) (void *arg)

Real-time task procedure.

Parameters

in,out	arg	argument as passed to rtdm_task_init()
--------	-----	--

6.30.3 Function Documentation

6.30.3.1 void rtdm_task_busy_sleep (nanosecs_rel_t delay)

Busy-wait a specified amount of time.

This service does not schedule out the caller, but rather spins in a tight loop, burning CPU cycles until the timeout elapses.

Parameters

in	delay	Delay in nanoseconds. Note that a zero delay does not have the mean-
		ing of RTDM_TIMEOUT_INFINITE here.

Note

The caller must not be migratable to different CPUs while executing this service. Otherwise, the actual delay will be undefined.

Tags

unrestricted

6.30.3.2 int rtdm_task_busy_wait (bool condition, nanosecs_rel_t spin_ns, nanosecs_rel_t sleep_ns)

Safe busy waiting.

This service alternates active spinning and sleeping within a wait loop, until a condition is satisfied. While sleeping, a task is scheduled out and does not consume any CPU time.

rtdm_task_busy_wait() is particularly useful for waiting for a state change reading an I/O register, which usually happens shortly after the wait starts, without incurring the adverse effects of long busy waiting if it doesn't.

Parameters

in	condition	The C expression to be tested for detecting completion.
in	spin_ns	The time to spin on <i>condition</i> before sleeping, expressed as a count of
		nanoseconds.
in	sleep_ns	The time to sleep for before spinning again, expressed as a count of nanoseconds.

Returns

0 on success if *condition* is satisfied, otherwise:

- -EINTR is returned if the calling task has been unblocked by a Linux signal or explicitly via rtdm

 task_unblock().
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

```
6.30.3.3 rtdm task t* rtdm task current (void)
```

Get current real-time task.

Returns

Pointer to task handle

Tags

mode-unrestricted

```
6.30.3.4 void rtdm_task_destroy ( rtdm_task_t * task )
```

Destroy a real-time task.

This call sends a termination request to *task*, then waits for it to exit. All RTDM task should check for pending termination requests by calling rtdm_task_should_stop() from their work loop.

If task is current, rtdm task destroy() terminates the current context, and does not return to the caller.

Parameters

in,out	task	Task handle as returned by rtdm_task_init()
--------	------	---

Note

Passing the same task handle to RTDM services after the completion of this function is not allowed.

Tags

secondary-only, might-switch

6.30 Task Services

6.30.3.5 int rtdm_task_init (rtdm_task_t * task, const char * name, rtdm_task_proc_t task_proc, void * arg, int priority, nanosecs_rel_t period)

Initialise and start a real-time task.

After initialising a task, the task handle remains valid and can be passed to RTDM services until either rtdm_task_destroy() or rtdm_task_join() was invoked.

Parameters

in,out	task	Task handle
in	name	Optional task name
in	task_proc	Procedure to be executed by the task
in	arg	Custom argument passed to task_proc() on entry
in	priority	Priority of the task, see also Task Priority Range
in	period	Period in nanoseconds of a cyclic task, 0 for non-cyclic mode. Waiting for the first and subsequent periodic events is done using rtdm_task.
		_wait_period().

Returns

0 on success, otherwise negative error code

Tags

secondary-only, might-switch

References xnthread_cancel(), xnthread_init(), xnthread_set_periodic(), and xnthread_start().

6.30.3.6 void rtdm task join (rtdm task t * task)

Wait on a real-time task to terminate.

Parameters

in,out	task	Task handle as returned by rtdm_task_init()

Note

Passing the same task handle to RTDM services after the completion of this function is not allowed. This service does not trigger the termination of the targeted task. The user has to take of this, otherwise rtdm_task_join() will never return.

Tags

mode-unrestricted

References xnthread_join().

6.30.3.7 int rtdm_task_set_period (rtdm_task_t * task, nanosecs_abs_t start_date, nanosecs_rel_t period)

Adjust real-time task period.

Parameters

in,out	task	Task handle as returned by rtdm_task_init(), or NULL for referring to
		the current RTDM task or Cobalt thread.
in	start_date	The initial (absolute) date of the first release point, expressed in
		nanoseconds. task will be delayed by the first call to rtdm_task_←
		<pre>wait_period() until this point is reached. If start_date is zero, the first</pre>
		release point is set to <i>period</i> nanoseconds after the current date.
in	period	New period in nanoseconds of a cyclic task, zero to disable cyclic mode
		for task.

Tags

task-unrestricted

6.30.3.8 void rtdm_task_set_priority (rtdm_task_t * task, int priority)

Adjust real-time task priority.

Parameters

in,out	task	Task handle as returned by rtdm_task_init()
in	priority	New priority of the task, see also Task Priority Range

Tags

task-unrestricted, might-switch

6.30.3.9 int rtdm_task_should_stop (void)

Check for pending termination request.

Check whether a termination request was received by the current RTDM task. Termination requests are sent by calling rtdm_task_destroy().

Returns

Non-zero indicates that a termination request is pending, in which case the caller should wrap up and exit.

Tags

rtdm-task, might-switch

6.30.3.10 int rtdm_task_sleep (nanosecs_rel_t delay)

Sleep a specified amount of time.

Parameters

in delay Delay in nanoseconds, see RTDM_TIMEOUT_xxx for special values.	
---	--

6.30 Task Services

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

6.30.3.11 int rtdm_task_sleep_abs (nanosecs_abs_t wakeup_time, enum rtdm_timer_mode mode)

Sleep until a specified absolute time.

Parameters

in	wakeup_time	Absolute timeout in nanoseconds
in	mode	Selects the timer mode, see RTDM_TIMERMODE_xxx for details

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().
- -EPERM may be returned if an illegal invocation environment is detected.
- -EINVAL is returned if an invalid parameter was passed.

Tags

primary-only, might-switch

6.30.3.12 int rtdm_task_sleep_until (nanosecs_abs_t wakeup_time)

Sleep until a specified absolute time.

Deprecated Use rtdm_task_sleep_abs instead!

Parameters

in	wakeup_time	Absolute timeout in nanoseconds

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

```
6.30.3.13 int rtdm_task_unblock ( rtdm_task_t * task )
```

Activate a blocked real-time task.

Returns

Non-zero is returned if the task was actually unblocked from a pending wait state, 0 otherwise.

Tags

unrestricted, might-switch

```
6.30.3.14 int rtdm_task_wait_period ( unsigned long * overruns_r )
```

Wait on next real-time task period.

Parameters

in	overruns_r	Address of a long word receiving the count of overruns if -ETIMEDO ←
		UT is returned, or NULL if the caller don't need that information.

Returns

0 on success, otherwise:

- -EINVAL is returned if calling task is not in periodic mode.
- -ETIMEDOUT is returned if a timer overrun occurred, which indicates that a previous release point has been missed by the calling task.


Tags

primary-only, might-switch

6.31 Timer Services 155

6.31 Timer Services

Collaboration diagram for Timer Services:



Typedefs

typedef void(* rtdm_timer_handler_t) (rtdm_timer_t *timer)
 Timer handler.

Functions

- int rtdm_timer_init (rtdm_timer_t *timer, rtdm_timer_handler_t handler, const char *name)

 Initialise a timer.
- void rtdm_timer_destroy (rtdm_timer_t *timer)

Destroy a timer.

• int rtdm_timer_start (rtdm_timer_t *timer, nanosecs_abs_t expiry, nanosecs_rel_t interval, enum rtdm timer mode mode)

Start a timer.

void rtdm_timer_stop (rtdm_timer_t *timer)

Stop a timer.

• int rtdm_timer_start_in_handler (rtdm_timer_t *timer, nanosecs_abs_t expiry, nanosecs_rel_t interval, enum rtdm_timer_mode mode)

Start a timer from inside a timer handler.

void rtdm_timer_stop_in_handler (rtdm_timer_t *timer)

Stop a timer from inside a timer handler.

RTDM TIMERMODE xxx

Timer operation modes

enum rtdm_timer_mode { RTDM_TIMERMODE_RELATIVE = XN_RELATIVE, RTDM_TIMERM
 ODE_ABSOLUTE = XN_ABSOLUTE, RTDM_TIMERMODE_REALTIME = XN_REALTIME }

6.31.1 Detailed Description

6.31.2 Typedef Documentation

6.31.2.1 typedef void(* rtdm_timer_handler_t) (rtdm_timer_t *timer)

Timer handler.

in	timer	Timer handle as returned by rtdm_timer_init()

6.31.3 Enumeration Type Documentation

6.31.3.1 enum rtdm timer mode

Enumerator

RTDM_TIMERMODE_RELATIVE Monotonic timer with relative timeout. **RTDM_TIMERMODE_ABSOLUTE** Monotonic timer with absolute timeout. **RTDM_TIMERMODE_REALTIME** Adjustable timer with absolute timeout.

6.31.4 Function Documentation

6.31.4.1 void rtdm_timer_destroy (rtdm_timer_t * timer)

Destroy a timer.

Parameters

in,out	timer	Timer handle as returned by rtdm_timer_init()
--------	-------	---

Tags

task-unrestricted

References xntimer destroy().

6.31.4.2 int rtdm_timer_init (rtdm_timer_t * timer, rtdm_timer_handler_t handler, const char * name)

Initialise a timer.

Parameters

in,out	timer	Timer handle
in	handler	Handler to be called on timer expiry
in	name	Optional timer name

Returns

0 on success, otherwise negative error code

Tags

task-unrestricted

6.31.4.3 int rtdm_timer_start (rtdm_timer_t * timer, nanosecs_abs_t expiry, nanosecs_rel_t interval, enum rtdm_timer_mode mode)

Start a timer.

6.31 Timer Services 157

Parameters

in,out	timer	Timer handle as returned by rtdm_timer_init()
in	expiry	Firing time of the timer, mode defines if relative or absolute
in	interval	Relative reload value, > 0 if the timer shall work in periodic mode with
		the specific interval, 0 for one-shot timers
in	mode	Defines the operation mode, see RTDM_TIMERMODE_xxx for possi-
		ble values

Returns

0 on success, otherwise:

• -ETIMEDOUT is returned if expiry describes an absolute date in the past. In such an event, the timer is nevertheless armed for the next shot in the timeline if *interval* is non-zero.

Tags

unrestricted

References xntimer_start().

6.31.4.4 int rtdm_timer_start_in_handler (rtdm_timer_t * timer, nanosecs_abs_t expiry, nanosecs_rel_t interval, enum rtdm_timer_mode mode)

Start a timer from inside a timer handler.

Parameters

in,out	timer	Timer handle as returned by rtdm_timer_init()
in	expiry	Firing time of the timer, mode defines if relative or absolute
in	interval	Relative reload value, > 0 if the timer shall work in periodic mode with
		the specific interval, 0 for one-shot timers
in	mode	Defines the operation mode, see RTDM_TIMERMODE_xxx for possi-
		ble values

Returns

0 on success, otherwise:

• -ETIMEDOUT is returned if expiry describes an absolute date in the past.

Tags

coreirq-only

6.31.4.5 void rtdm_timer_stop (rtdm_timer_t * timer)

Stop a timer.

Parameters

in,out	timer	Timer handle as returned by rtdm_timer_init()

Tags

unrestricted

References xntimer_stop().

6.31.4.6 void rtdm_timer_stop_in_handler (rtdm_timer_t * timer)

Stop a timer from inside a timer handler.

6.31 Timer Services 159

Parameters


in,out	timer	Timer handle as returned by rtdm_timer_init()
--------	-------	---

Tags

coreirq-only

6.32 Synchronisation Services

Collaboration diagram for Synchronisation Services:



Modules

- Big dual kernel lock
- · Spinlock with preemption deactivation
- Event Services
- Semaphore Services
- Mutex services

Functions

- void rtdm_waitqueue_init (struct rtdm_waitqueue *wq)
 Initialize a RTDM wait queue.
- void rtdm_waitqueue_destroy (struct rtdm_waitqueue *wq)

Deletes a RTDM wait queue.

rtdm_timedwait_condition_locked (struct rtdm_wait_queue *wq, C_expr condition, nanosecs_rel
 _t timeout, rtdm_toseq_t *toseq)

Timed sleep on a locked waitqueue until a condition gets true.

• rtdm wait condition locked (struct rtdm wait queue *wq, C expr condition)

Sleep on a locked waitqueue until a condition gets true.

 rtdm_timedwait_condition (struct rtdm_wait_queue *wq, C_expr condition, nanosecs_rel_t timeout, rtdm_toseq_t *toseq)

Timed sleep on a waitqueue until a condition gets true.

- void rtdm_timedwait (struct rtdm_wait_queue *wq, nanosecs_rel_t timeout, rtdm_toseq_t *toseq)

 Timed sleep on a waitqueue unconditionally.
- void rtdm_timedwait_locked (struct rtdm_wait_queue *wq, nanosecs_rel_t timeout, rtdm_toseq_t *toseq)

Timed sleep on a locked waitqueue unconditionally.

• rtdm_wait_condition (struct rtdm_wait_queue *wq, C_expr condition)

Sleep on a waitqueue until a condition gets true.

void rtdm wait (struct rtdm wait queue *wq)

Sleep on a waitqueue unconditionally.

void rtdm_wait_locked (struct rtdm_wait_queue *wq)

Sleep on a locked waitqueue unconditionally.

void rtdm_waitqueue_lock (struct rtdm_wait_queue *wq, rtdm_lockctx_t context)
 Lock a waitqueue.

• void rtdm_waitqueue_unlock (struct rtdm_wait_queue *wq, rtdm_lockctx_t context)

Unlock a waitqueue.

void rtdm_waitqueue_signal (struct rtdm_wait_queue *wq)

Signal a waitqueue.

void rtdm_waitqueue_broadcast (struct rtdm_wait_queue *wq)

Broadcast a waitqueue.

void rtdm_waitqueue_flush (struct rtdm_wait_queue *wq)

Flush a waitqueue.

void rtdm_waitqueue_wakeup (struct rtdm_wait_queue *wq, rtdm_task_t waiter)

Signal a particular waiter on a waitqueue.

rtdm_for_each_waiter (rtdm_task_t pos, struct rtdm_wait_queue *wq)

Simple iterator for waitqueues.

• rtdm_for_each_waiter_safe (rtdm_task_t pos, rtdm_task_t tmp, struct rtdm_wait_queue *wq) Safe iterator for waitqueues.

RTDM SELECTTYPE xxx

Event types select can bind to

 enum rtdm_selecttype { RTDM_SELECTTYPE_READ = XNSELECT_READ, RTDM_SELECT_ TYPE_WRITE = XNSELECT_WRITE, RTDM_SELECTTYPE_EXCEPT = XNSELECT_EXCEPT }

Timeout Sequence Management

• void rtdm_toseq_init (rtdm_toseq_t *timeout_seq, nanosecs_rel_t timeout)

Initialise a timeout sequence.

- 6.32.1 Detailed Description
- 6.32.2 Enumeration Type Documentation
- 6.32.2.1 enum rtdm_selecttype

Enumerator

RTDM_SELECTTYPE_READ Select input data availability events. **RTDM_SELECTTYPE_WRITE** Select ouput buffer availability events. **RTDM_SELECTTYPE_EXCEPT** Select exceptional events.

- 6.32.3 Function Documentation
- 6.32.3.1 rtdm_for_each_waiter (rtdm_task_t pos, struct rtdm_wait_queue * wq)

Simple iterator for waitqueues.

This construct traverses the wait list of a given waitqueue wq, assigning each RTDM task pointer to the cursor variable pos, which must be of type rtdm_task_t.

wq must have been locked by a call to rtdm_waitqueue_lock() prior to traversing its wait list.

pos	cursor variable holding a pointer to the RTDM task being fetched.	
wq	waitqueue to scan.	

Note

The waitqueue should not be signaled, broadcast or flushed during the traversal, unless the loop is aborted immediately after. Should multiple waiters be readied while iterating, the safe form rtdm_for_each_waiter_safe() must be used for traversal instead.

Tags

unrestricted

```
6.32.3.2 rtdm_for_each_waiter_safe ( rtdm_task_t pos, rtdm_task_t tmp, struct rtdm_wait_queue * wq )
```

Safe iterator for waitqueues.

This construct traverses the wait list of a given waitqueue *wq*, assigning each RTDM task pointer to the cursor variable *pos*, which must be of type rtdm_task_t.

Unlike with rtdm_for_each_waiter(), the waitqueue may be signaled, broadcast or flushed during the traversal.

wq must have been locked by a call to rtdm_waitqueue_lock() prior to traversing its wait list.

Parameters

pos	cursor variable holding a pointer to the RTDM task being fetched.
tmp	temporary cursor variable.
wq	waitqueue to scan.

Tags

unrestricted

```
6.32.3.3 void rtdm_timedwait ( struct rtdm_wait_queue * wq, nanosecs_rel_t timeout, rtdm_toseq_t * toseq )
```

Timed sleep on a waitqueue unconditionally.

The calling task is put to sleep until the waitqueue is signaled by either rtdm_waitqueue_signal() or rtdm_waitqueue_broadcast(), or flushed by a call to rtdm_waitqueue_flush(), or a timeout occurs.

Parameters

	wq	waitqueue to wait on.
	timeout	relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for special
		values.
in,out	toseq	handle of a timeout sequence as returned by rtdm_toseq_init() or N←
		ULL.

Returns

0 on success, otherwise:

• -EINTR is returned if the waitqueue has been flushed, or the calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().

 -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of time

Note

Passing RTDM_TIMEOUT_NONE to *timeout* makes no sense for such service, and might cause unexpected behavior.

Tags

primary-only, might-switch

```
6.32.3.4 rtdm_timedwait_condition ( struct rtdm_wait_queue * wq, C_expr condition, nanosecs_rel_t timeout, rtdm_toseq_t * toseq )
```

Timed sleep on a waitqueue until a condition gets true.

The calling task is put to sleep until *condition* evaluates to true or a timeout occurs. The condition is checked each time the waitqueue *wq* is signaled.

Parameters

	wq	waitqueue to wait on.
	condition	C expression for the event to wait for.
	timeout	relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for special
		values.
in,out	toseq	handle of a timeout sequence as returned by rtdm_toseq_init() or N←
		ULL.

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().
- -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of time.

Note

rtdm_waitqueue_signal() has to be called after changing any variable that could change the result of the wait condition.

Passing RTDM_TIMEOUT_NONE to *timeout* makes no sense for such service, and might cause unexpected behavior.

Tags

primary-only, might-switch

```
6.32.3.5 rtdm_timedwait_condition_locked ( struct rtdm_wait_queue * wq, C_expr condition, nanosecs_rel_t timeout, rtdm_toseq_t * toseq )
```

Timed sleep on a locked waitqueue until a condition gets true.

The calling task is put to sleep until *condition* evaluates to true or a timeout occurs. The condition is checked each time the waitqueue *wq* is signaled.

The waitqueue must have been locked by a call to rtdm_waitqueue_lock() prior to calling this service.

	wq	locked waitqueue to wait on. The waitqueue lock is dropped when
		sleeping, then reacquired before this service returns to the caller.
	condition	C expression for the event to wait for.
	timeout	relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for special
		values.
in,out	toseq	handle of a timeout sequence as returned by rtdm_toseq_init() or N→
		ULL.

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().
- -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of time.

Note

rtdm_waitqueue_signal() has to be called after changing any variable that could change the result of the wait condition.

Passing RTDM_TIMEOUT_NONE to *timeout* makes no sense for such service, and might cause unexpected behavior.

Tags

primary-only, might-switch

6.32.3.6 void rtdm_timedwait_locked (struct rtdm_wait_queue * wq, nanosecs_rel_t timeout, rtdm toseq t * toseq)

Timed sleep on a locked waitqueue unconditionally.

The calling task is put to sleep until the waitqueue is signaled by either rtdm_waitqueue_signal() or rtdm_waitqueue_broadcast(), or flushed by a call to rtdm_waitqueue_flush(), or a timeout occurs.

The waitqueue must have been locked by a call to rtdm waitqueue lock() prior to calling this service.

Parameters

	wq	locked waitqueue to wait on. The waitqueue lock is dropped when
		sleeping, then reacquired before this service returns to the caller.
	timeout	relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for special
		values.
in,out	toseq	handle of a timeout sequence as returned by rtdm_toseq_init() or N←
		ULL.

Returns

0 on success, otherwise:

- -EINTR is returned if the waitqueue has been flushed, or the calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().
- -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of time.

Note

Passing RTDM_TIMEOUT_NONE to *timeout* makes no sense for such service, and might cause unexpected behavior.

Tags

primary-only, might-switch

```
6.32.3.7 void rtdm toseq init ( rtdm toseq t * timeout seq, nanosecs rel t timeout )
```

Initialise a timeout sequence.

This service initialises a timeout sequence handle according to the given timeout value. Timeout sequences allow to maintain a continuous *timeout* across multiple calls of blocking synchronisation services. A typical application scenario is given below.

Parameters

in,out	timeout_seq	Timeout sequence handle
in	timeout	Relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for spe-
		cial values

Application Scenario:

```
1 int device_service_routine(...)
2 {
3
          rtdm_toseq_t timeout_seq;
4
          rtdm_toseq_init(&timeout_seq, timeout);
8
          while (received < requested) {
                   ret = rtdm_event_timedwait(&data_available, timeout, &timeout_seq);
10
                   if (ret < 0) // including -ETIMEDOUT
                            break;
11
                   // receive some data
14
15
           }
16
17 }
```

Using a timeout sequence in such a scenario avoids that the user-provided relative timeout is restarted on every call to rtdm_event_timedwait(), potentially causing an overall delay that is larger than specified by timeout. Moreover, all functions supporting timeout sequences also interpret special timeout values (infinite and non-blocking), disburdening the driver developer from handling them separately.

Tags

task-unrestricted

```
6.32.3.8 void rtdm wait ( struct rtdm wait queue * wq )
```

Sleep on a waitqueue unconditionally.

The calling task is put to sleep until the waitqueue is signaled by either rtdm_waitqueue_signal() or rtdm_waitqueue_broadcast(), or flushed by a call to rtdm_waitqueue_flush().

wa	waitqueue to wait on.
7	

Returns

0 on success, otherwise:

• -EINTR is returned if the waitqueue has been flushed, or the calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().

Tags

primary-only, might-switch

```
6.32.3.9 rtdm_wait_condition ( struct rtdm_wait_queue * wq, C_expr condition )
```

Sleep on a waitqueue until a condition gets true.

The calling task is put to sleep until *condition* evaluates to true. The condition is checked each time the waitqueue *wq* is signaled.

Parameters

wq	waitqueue to wait on
condition	C expression for the event to wait for.

Returns

0 on success, otherwise:

• -EINTR is returned if calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().

Note

rtdm_waitqueue_signal() has to be called after changing any variable that could change the result of the wait condition.

Tags

primary-only, might-switch

```
6.32.3.10 rtdm_wait_condition_locked ( struct rtdm_wait_queue * wq, C_expr condition )
```

Sleep on a locked waitqueue until a condition gets true.

The calling task is put to sleep until *condition* evaluates to true. The condition is checked each time the waitqueue *wg* is signaled.

The waitqueue must have been locked by a call to rtdm_waitqueue_lock() prior to calling this service.

Parameters

wq	locked waitqueue to wait on. The waitqueue lock is dropped when sleeping, then
	reacquired before this service returns to the caller.
condition	C expression for the event to wait for.

Returns

0 on success, otherwise:

• -EINTR is returned if calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().

Note

rtdm_waitqueue_signal() has to be called after changing any variable that could change the result of the wait condition.

Tags

primary-only, might-switch

```
6.32.3.11 void rtdm_wait_locked ( struct rtdm_wait_queue * wq )
```

Sleep on a locked waitqueue unconditionally.

The calling task is put to sleep until the waitqueue is signaled by either rtdm_waitqueue_signal() or rtdm_waitqueue broadcast(), or flushed by a call to rtdm_waitqueue flush().

The waitqueue must have been locked by a call to rtdm_waitqueue_lock() prior to calling this service.

Parameters

wq	locked waitqueue to wait on. The waitqueue lock is dropped when sleeping, then
	reacquired before this service returns to the caller.

Returns

0 on success, otherwise:

• -EINTR is returned if the waitqueue has been flushed, or the calling task has received a Linux signal or has been forcibly unblocked by a call to rtdm_task_unblock().

Tags

primary-only, might-switch

```
6.32.3.12 void rtdm_waitqueue_broadcast ( struct rtdm_wait_queue * wq )
```

Broadcast a waitqueue.

Broadcast the waitqueue *wq*, waking up all waiters. Each readied task may assume to have received the wake up event.

wq waitqueue to broadcast.

Returns

non-zero if at least one task has been readied as a result of this call, zero otherwise.

Tags

unrestricted, might-switch

6.32.3.13 void rtdm_waitqueue_destroy (struct rtdm_waitqueue * wq)

Deletes a RTDM wait queue.

Dismantles a wait queue structure, releasing all resources attached to it.

Parameters

wq waitqueue to delete.

Tags

task-unrestricted

6.32.3.14 void rtdm_waitqueue_flush (struct rtdm_wait_queue * wq)

Flush a waitqueue.

Flushes the waitqueue wq, unblocking all waiters with an error status (-EINTR).

Parameters

wq waitqueue to flush.

Returns

non-zero if at least one task has been readied as a result of this call, zero otherwise.

Tags

unrestricted, might-switch

6.32.3.15 void rtdm_waitqueue_init (struct rtdm_waitqueue * wq)

Initialize a RTDM wait queue.

Sets up a wait queue structure for further use.

Parameters

wq waitqueue to initialize.

Tags

task-unrestricted

6.32.3.16 void rtdm_waitqueue_lock (struct rtdm_wait_queue * wq, rtdm_lockctx_t context)

Lock a waitqueue.

Acquires the lock on the waitqueue wq.

Parameters

wq	waitqueue to lock.
context	name of local variable to store the context in.

Note

Recursive locking might lead to unexpected behavior, including lock up.

Tags

unrestricted

6.32.3.17 void rtdm_waitqueue_signal (struct rtdm_wait_queue * wq)

Signal a waitqueue.

Signals the waitqueue wq, waking up a single waiter (if any).

Parameters

wq	waitqueue to signal.
----	----------------------

Returns

non-zero if a task has been readied as a result of this call, zero otherwise.

Tags

unrestricted, might-switch

6.32.3.18 void rtdm_waitqueue_unlock (struct rtdm_wait_queue * wq, rtdm_lockctx_t context)

Unlock a waitqueue.

Releases the lock on the waitqueue wg.

Parameters

wq	waitqueue to unlock.
context	name of local variable to retrieve the context from.

Tags

unrestricted

6.32.3.19 void rtdm_waitqueue_wakeup (struct rtdm_wait_queue * wq, rtdm_task_t waiter)

Signal a particular waiter on a waitqueue.

Signals the waitqueue wq, waking up waiter waiter only, which must be currently sleeping on the waitqueue.

wq	waitqueue to signal.
waiter	RTDM task to wake up.

Tags

unrestricted, might-switch

6.33 Event Services

Collaboration diagram for Event Services:



Functions

172

• void rtdm_event_init (rtdm_event_t *event, unsigned long pending)

Initialise an event.

void rtdm_event_destroy (rtdm_event_t *event)

Destroy an event.

void rtdm_event_pulse (rtdm_event_t *event)

Signal an event occurrence to currently listening waiters.

void rtdm_event_signal (rtdm_event_t *event)

Signal an event occurrence.

int rtdm_event_wait (rtdm_event_t *event)

Wait on event occurrence.

int rtdm_event_timedwait (rtdm_event_t *event, nanosecs_rel_t timeout, rtdm_toseq_t *timeout
_seq)

Wait on event occurrence with timeout.

void rtdm_event_clear (rtdm_event_t *event)

Clear event state.

int rtdm_event_select (rtdm_event_t *event, rtdm_selector_t *selector, enum rtdm_selecttype type, unsigned int fd_index)

Bind a selector to an event.

6.33.1 Detailed Description

6.33.2 Function Documentation

6.33.2.1 void rtdm_event_clear (rtdm_event_t * event)

Clear event state.

Parameters

in,out	event	Event handle as returned by rtdm_event_init()

Tags

unrestricted

References xnselect_signal().

6.33 Event Services 173

6.33.2.2 void rtdm_event_destroy (rtdm_event_t * event)

Destroy an event.

in,out	event	Event handle as returned by rtdm_event_init()

Tags

task-unrestricted, might-switch

References XNRMID, and xnselect_destroy().

Referenced by udd_unregister_device().

6.33.2.3 void rtdm_event_init (rtdm_event_t * event, unsigned long pending)

Initialise an event.

Parameters

in,out	event	Event handle
in	pending	Non-zero if event shall be initialised as set, 0 otherwise

Tags

task-unrestricted

References xnselect_init(), and xnsynch_init().

Referenced by udd_register_device().

6.33.2.4 void rtdm event pulse (rtdm event t * event)

Signal an event occurrence to currently listening waiters.

This function wakes up all current waiters of the given event, but it does not change the event state. Subsequently callers of rtdm_event_wait() or rtdm_event_timedwait() will therefore be blocked first.

Parameters

in,out	event	Event handle as returned by rtdm_event_init()

Tags

unrestricted, might-switch

6.33.2.5 int rtdm_event_select (rtdm_event_t * event, rtdm_selector_t * selector, enum rtdm_selecttype type, unsigned int fd_index)

Bind a selector to an event.

This functions binds the given selector to an event so that the former is notified when the event state changes. Typically the select binding handler will invoke this service.

Parameters

ſ	in.out	event	Event handle as returned by rtdm_event_init()
Į	III, out	Ovont	Event nariale as retarned by rtam_event_int()

6.33 Event Services 175

in,out	selector	Selector as passed to the select binding handler
in	type	Type of the bound event as passed to the select binding handler
in	fd_index	File descriptor index as passed to the select binding handler

Returns

0 on success, otherwise:

- -ENOMEM is returned if there is insufficient memory to establish the dynamic binding.
- -EINVAL is returned if type or fd_index are invalid.

Tags

task-unrestricted

References xnselect_bind().

```
6.33.2.6 void rtdm_event_signal ( rtdm_event_t * event )
```

Signal an event occurrence.

This function sets the given event and wakes up all current waiters. If no waiter is presently registered, the next call to rtdm_event_wait() or <a href="rtdm_event_timedwait() will return immediately.

Parameters

in,out	event	Event handle as returned by rtdm_event_init()
--------	-------	---

Tags

unrestricted, might-switch

References xnsched_run(), xnselect_signal(), and xnsynch_flush().

Referenced by udd_notify_event().

6.33.2.7 int rtdm_event_timedwait (rtdm_event_t * event, nanosecs_rel_t timeout, rtdm_toseq_t * timeout_seq)

Wait on event occurrence with timeout.

This function waits or tests for the occurrence of the given event, taking the provided timeout into account. On successful return, the event is reset.

Parameters

in,out	event	Event handle as returned by rtdm_event_init()
in	timeout	Relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for spe-
		cial values
in,out	timeout_seq	Handle of a timeout sequence as returned by rtdm_toseq_init() or N←
		ULL

Returns

0 on success, otherwise:

 -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of time.

• -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().

- -EIDRM is returned if event has been destroyed.
- -EPERM may be returned if an illegal invocation environment is detected.
- -EWOULDBLOCK is returned if a negative timeout (i.e., non-blocking operation) has been specified.

Tags

primary-only, might-switch

References XNRMID, xnselect_signal(), xnsynch_sleep_on(), xnthread_current(), and XNTIMEO. Referenced by rtdm_event_wait().

```
6.33.2.8 int rtdm_event_wait ( rtdm_event_t * event )
```

Wait on event occurrence.

This is the light-weight version of rtdm_event_timedwait(), implying an infinite timeout.

Parameters

in,out	event	Event handle as returned by rtdm_event_init()
--------	-------	---

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().
- -EIDRM is returned if event has been destroyed.
- -EPERM may be returned if an illegal invocation environment is detected.


Tags

primary-only, might-switch

References rtdm_event_timedwait().

6.34 Semaphore Services

Collaboration diagram for Semaphore Services:



Functions

void rtdm_sem_init (rtdm_sem_t *sem, unsigned long value)
 Initialise a semaphore.

void rtdm_sem_destroy (rtdm_sem_t *sem)

Destroy a semaphore.

int rtdm_sem_down (rtdm_sem_t *sem)

Decrement a semaphore.

Decrement a semaphore with timeout.

void rtdm_sem_up (rtdm_sem_t *sem)

Increment a semaphore.

• int rtdm_sem_select (rtdm_sem_t *sem, rtdm_selector_t *selector, enum rtdm_selecttype type, unsigned int fd_index)

Bind a selector to a semaphore.

6.34.1 Detailed Description

6.34.2 Function Documentation

6.34.2.1 void rtdm_sem_destroy (rtdm_sem_t * sem)

Destroy a semaphore.

Parameters

	in,out	sem	Semaphore handle as returned by rtdm_sem_init()
--	--------	-----	---

Tags

task-unrestricted, might-switch

References XNRMID, and xnselect_destroy().

6.34.2.2 int rtdm_sem_down (rtdm_sem_t * sem)

Decrement a semaphore.

This is the light-weight version of rtdm_sem_timeddown(), implying an infinite timeout.

Parameters

in,out	sem	Semaphore handle as returned by rtdm_sem_init()
--------	-----	---

Returns

0 on success, otherwise:

- -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().
- -EIDRM is returned if sem has been destroyed.
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

References rtdm_sem_timeddown().

6.34.2.3 void rtdm_sem_init (rtdm_sem_t * sem, unsigned long value)

Initialise a semaphore.

Parameters

in,out	sem	Semaphore handle
in	value	Initial value of the semaphore

Tags

task-unrestricted

References xnselect_init(), and xnsynch_init().

6.34.2.4 int rtdm_sem_select (rtdm_sem_t * sem, rtdm_selector_t * selector, enum rtdm selecttype type, unsigned int fd index)

Bind a selector to a semaphore.

This functions binds the given selector to the semaphore so that the former is notified when the semaphore state changes. Typically the select binding handler will invoke this service.

Parameters

in,out	sem	Semaphore handle as returned by rtdm_sem_init()
in,out	selector	Selector as passed to the select binding handler
in	type	Type of the bound event as passed to the select binding handler
in	fd_index	File descriptor index as passed to the select binding handler

Returns

0 on success, otherwise:

- -ENOMEM is returned if there is insufficient memory to establish the dynamic binding.
- -EINVAL is returned if type or fd_index are invalid.

Tags

task-unrestricted

References xnselect_bind().

6.34.2.5 int rtdm_sem_timeddown (rtdm_sem_t * sem, nanosecs_rel_t timeout, rtdm_toseq_t * timeout_seq)

Decrement a semaphore with timeout.

This function tries to decrement the given semphore's value if it is positive on entry. If not, the caller is blocked unless non-blocking operation was selected.

Parameters

in,out	sem	Semaphore handle as returned by rtdm_sem_init()
in	timeout	Relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for spe-
		cial values
in,out	timeout_seq	Handle of a timeout sequence as returned by rtdm_toseq_init() or N←
		ULL

Returns

0 on success, otherwise:

- -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of time.
- -EWOULDBLOCK is returned if timeout is negative and the semaphore value is currently not positive.
- -EINTR is returned if calling task has been unblock by a signal or explicitly via rtdm_task_unblock().
- -EIDRM is returned if sem has been destroyed.
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

References XNRMID, xnselect_signal(), xnsynch_sleep_on(), xnthread_current(), and XNTIMEO. Referenced by rtdm_sem_down().

```
6.34.2.6 void rtdm_sem_up ( rtdm_sem_t * sem )
```

Increment a semaphore.

This function increments the given semphore's value, waking up a potential waiter which was blocked upon rtdm sem down().

Parameters

in,out	sem	Semaphore handle as returned by rtdm_sem_init()

Tags

unrestricted, might-switch

References xnsched_run(), xnselect_signal(), and xnsynch_wakeup_one_sleeper().

6.35 Mutex services

Collaboration diagram for Mutex services:



Functions

180

• void rtdm_mutex_init (rtdm_mutex_t *mutex)

void rtdm_mutex_destroy (rtdm_mutex_t *mutex)

Destroy a mutex.

Initialise a mutex.

void rtdm_mutex_unlock (rtdm_mutex_t *mutex)

Release a mutex.

• int rtdm_mutex_lock (rtdm_mutex_t *mutex)

Request a mutex.

int rtdm_mutex_timedlock (rtdm_mutex_t *mutex, nanosecs_rel_t timeout, rtdm_toseq_

 t *timeout_seq)

Request a mutex with timeout.

6.35.1 Detailed Description

6.35.2 Function Documentation

6.35.2.1 void rtdm mutex destroy (rtdm mutex t * mutex)

Destroy a mutex.

Parameters

in,out	mutex	Mutex handle as returned by rtdm_mutex_init()

Tags

task-unrestricted, might-switch

References XNRMID.

6.35.2.2 void rtdm_mutex_init (rtdm_mutex_t * mutex)

Initialise a mutex.

This function initalises a basic mutex with priority inversion protection. "Basic", as it does not allow a mutex owner to recursively lock the same mutex again.

6.35 Mutex services 181

Parameters

in,out	mutex	Mutex handle
--------	-------	--------------

Tags

task-unrestricted

References xnsynch_init().

```
6.35.2.3 int rtdm_mutex_lock ( rtdm_mutex_t * mutex )
```

Request a mutex.

This is the light-weight version of rtdm_mutex_timedlock(), implying an infinite timeout.

Parameters

in,out	mutex	Mutex handle as returned by rtdm_mutex_init()
--------	-------	---

Returns

0 on success, otherwise:

- -EIDRM is returned if mutex has been destroyed.
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

References rtdm_mutex_timedlock().

```
6.35.2.4 int rtdm_mutex_timedlock ( rtdm_mutex_t * mutex, nanosecs_rel_t timeout, rtdm_toseq_t * timeout_seq )
```

Request a mutex with timeout.

This function tries to acquire the given mutex. If it is not available, the caller is blocked unless non-blocking operation was selected.

Parameters

in,out	mutex	Mutex handle as returned by rtdm_mutex_init()
in	timeout	Relative timeout in nanoseconds, see RTDM_TIMEOUT_xxx for special values
in,out	timeout_seq	Handle of a timeout sequence as returned by rtdm_toseq_init() or N ULL

Returns

0 on success, otherwise:

- -ETIMEDOUT is returned if the if the request has not been satisfied within the specified amount of
- -EWOULDBLOCK is returned if timeout is negative and the semaphore value is currently not positive.

- -EIDRM is returned if mutex has been destroyed.
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

primary-only, might-switch

References XNBREAK, xnsynch_acquire(), xnsynch_try_acquire(), xnthread_current(), and XNTIMEO. Referenced by rtdm_mutex_lock().

6.35.2.5 void rtdm_mutex_unlock (rtdm_mutex_t * mutex)

Release a mutex.

This function releases the given mutex, waking up a potential waiter which was blocked upon rtdm_← mutex_lock() or rtdm_mutex_timedlock().

Parameters

in,out	mutex	Mutex handle as returned by rtdm_mutex_init()


Tags

primary-only, might-switch

References xnsched_run(), and xnsynch_release().

6.36 Interrupt Management Services

Collaboration diagram for Interrupt Management Services:



Macros

#define rtdm_irq_get_arg(irq_handle, type) ((type *)irq_handle->cookie)
 Retrieve IRQ handler argument.

Typedefs

typedef int(* rtdm_irq_handler_t) (rtdm_irq_t *irq_handle)
 Interrupt handler.

Functions

• int rtdm_irq_request (rtdm_irq_t *irq_handle, unsigned int irq_no, rtdm_irq_handler_t handler, unsigned long flags, const char *device_name, void *arg)

Register an interrupt handler.

• int rtdm_irq_free (rtdm_irq_t *irq_handle)

Release an interrupt handler.

• int rtdm_irq_enable (rtdm_irq_t *irq_handle)

Enable interrupt line.

• int rtdm_irq_disable (rtdm_irq_t *irq_handle)

Disable interrupt line.

RTDM_IRQTYPE_xxx

Interrupt registrations flags

• #define RTDM IRQTYPE SHARED XN IRQTYPE SHARED

Enable IRQ-sharing with other real-time drivers.

• #define RTDM IRQTYPE EDGE XN IRQTYPE EDGE

Mark IRQ as edge-triggered, relevant for correct handling of shared edge-triggered IRQs.

RTDM IRQ xxx

Return flags of interrupt handlers

• #define RTDM_IRQ_NONE XN_IRQ_NONE

Unhandled interrupt.

• #define RTDM_IRQ_HANDLED XN_IRQ_HANDLED

Denote handled interrupt.

• #define RTDM IRQ DISABLE XN IRQ DISABLE

Request interrupt disabling on exit.

6.36.1 Detailed Description

6.36.2 Macro Definition Documentation

6.36.2.1 #define rtdm_irq_get_arg(irq_handle, type) ((type *)irq_handle->cookie)

Retrieve IRQ handler argument.

Parameters

irq_handle	handle IRQ handle	
type Type of the pointer to return		

Returns

The argument pointer registered on rtdm_irq_request() is returned, type-casted to the specified type.

Tags

unrestricted

6.36.3 Typedef Documentation

6.36.3.1 typedef int(* rtdm_irq_handler_t) (rtdm_irq_t *irq_handle)

Interrupt handler.

Parameters

in	irq_handle	IRQ handle as returned by rtdm_irq_request()

Returns

0 or a combination of RTDM_IRQ_xxx flags

6.36.4 Function Documentation

6.36.4.1 int rtdm_irq_disable (rtdm_irq_t * irq_handle)

Disable interrupt line.

in,out	irq_handle	IRQ handle as returned by rtdm_irq_request()
--------	------------	--

Returns

0 on success, otherwise negative error code

Note

This service is for exceptional use only. Drivers should always prefer interrupt masking at device level (via corresponding control registers etc.) over masking at line level. Keep in mind that the latter is incompatible with IRQ line sharing and can also be more costly as interrupt controller access requires broader synchronization. Also, such service is solely available from secondary mode. The caller is responsible for excluding such conflicts.

Tags

secondary-only

6.36.4.2 int rtdm_irq_enable (rtdm_irq_t * irq_handle)

Enable interrupt line.

Parameters

in,out	irq_handle	IRQ handle as returned by rtdm_irq_request()
--------	------------	--

Returns

0 on success, otherwise negative error code

Note

This service is for exceptional use only. Drivers should always prefer interrupt masking at device level (via corresponding control registers etc.) over masking at line level. Keep in mind that the latter is incompatible with IRQ line sharing and can also be more costly as interrupt controller access requires broader synchronization. Also, such service is solely available from secondary mode. The caller is responsible for excluding such conflicts.

Tags

secondary-only

6.36.4.3 int rtdm_irq_free (rtdm_irq_t * irq_handle)

Release an interrupt handler.

Parameters

in,out	irq_handle	IRQ handle as returned by rtdm_irq_request()

Returns

0 on success, otherwise negative error code

Note

The caller is responsible for shutting down the IRQ source at device level before invoking this service. In turn, rtdm_irq_free ensures that any pending event on the given IRQ line is fully processed on return from this service.

Tags

secondary-only

Referenced by udd_unregister_device().

6.36.4.4 int rtdm_irq_request (rtdm_irq_t * irq_handle, unsigned int irq_no, rtdm_irq_handler_t handler, unsigned long flags, const char * device_name, void * arg)

Register an interrupt handler.

This function registers the provided handler with an IRQ line and enables the line.

Parameters

in,out	irq_handle	IRQ handle
in	irq_no	Line number of the addressed IRQ
in	handler	Interrupt handler
in	flags	Registration flags, see RTDM_IRQTYPE_xxx for details
in	device_name	Device name to show up in real-time IRQ lists
in	arg	Pointer to be passed to the interrupt handler on invocation

Returns

0 on success, otherwise:

- -EINVAL is returned if an invalid parameter was passed.
- -EBUSY is returned if the specified IRQ line is already in use.

Tags

secondary-only

 $References\ xnintr_attach(),\ xnintr_destroy(),\ xnintr_enable(),\ and\ xnintr_init().$

Referenced by udd_register_device().

6.37 Non-Real-Time Signalling Services

These services provide a mechanism to request the execution of a specified handler in non-real-time context.

Collaboration diagram for Non-Real-Time Signalling Services:



Typedefs

• typedef void(* rtdm_nrtsig_handler_t) (rtdm_nrtsig_t *nrt_sig, void *arg)

Non-real-time signal handler.

Functions

- void rtdm_schedule_nrt_work (struct work_struct *lostage_work)
 - Put a work task in Linux non real-time global workqueue from primary mode.
- int rtdm_nrtsig_init (rtdm_nrtsig_t *nrt_sig, rtdm_nrtsig_handler_t handler, void *arg)

 Register a non-real-time signal handler.
- void rtdm_nrtsig_destroy (rtdm_nrtsig_t *nrt_sig)
 - Release a non-realtime signal handler.
- void rtdm_nrtsig_pend (rtdm_nrtsig_t *nrt_sig)

Trigger non-real-time signal.

6.37.1 Detailed Description

These services provide a mechanism to request the execution of a specified handler in non-real-time context.

The triggering can safely be performed in real-time context without suffering from unknown delays. The handler execution will be deferred until the next time the real-time subsystem releases the CPU to the non-real-time part.

6.37.2 Typedef Documentation

6.37.2.1 typedef void(* rtdm nrtsig handler t) (rtdm nrtsig t *nrt sig, void *arg)

Non-real-time signal handler.

in	nrt_sig	Signal handle pointer as passed to rtdm_nrtsig_init()
in	arg	Argument as passed to rtdm_nrtsig_init()

Note

The signal handler will run in soft-IRQ context of the non-real-time subsystem. Note the implications of this context, e.g. no invocation of blocking operations.

6.37.3 Function Documentation

6.37.3.1 void rtdm_nrtsig_destroy (rtdm_nrtsig_t * nrt_sig)

Release a non-realtime signal handler.

Parameters

in,out	nrt_sig	Signal handle

Tags

task-unrestricted

6.37.3.2 int rtdm_nrtsig_init (rtdm_nrtsig_t * nrt_sig, rtdm_nrtsig_handler_t handler, void * arg)

Register a non-real-time signal handler.

Parameters

in,out	nrt_sig	Signal handle
in	handler	Non-real-time signal handler
in	arg	Custom argument passed to handler() on each invocation

Returns

0 on success, otherwise:

• -EAGAIN is returned if no free signal slot is available.

Tags

task-unrestricted

6.37.3.3 void rtdm_nrtsig_pend (rtdm_nrtsig_t * nrt_sig)

Trigger non-real-time signal.

Parameters

in,out	nrt_sig	Signal handle

Tags

unrestricted

6.37.3.4 void rtdm_schedule_nrt_work (struct work_struct * lostage_work)

Put a work task in Linux non real-time global workqueue from primary mode.


Parameters

lostage_work

6.38 Utility Services 191

6.38 Utility Services

Collaboration diagram for Utility Services:



Functions

• int rtdm_mmap_to_user (struct rtdm_fd *fd, void *src_addr, size_t len, int prot, void **pptr, struct vm operations_struct *vm_ops, void *vm_private_data)

Map a kernel memory range into the address space of the user.

int rtdm_iomap_to_user (struct rtdm_fd *fd, phys_addr_t src_addr, size_t len, int prot, void **pptr, struct vm_operations_struct *vm_ops, void *vm_private_data)

Map an I/O memory range into the address space of the user.

int rtdm_mmap_kmem (struct vm_area_struct *vma, void *va)

Map a kernel logical memory range to a virtual user area.

int rtdm_mmap_vmem (struct vm_area_struct *vma, void *va)

Map a virtual memory range to a virtual user area.

int rtdm_mmap_iomem (struct vm_area_struct *vma, phys_addr_t pa)

Map an I/O memory range to a virtual user area.

int rtdm_munmap (void *ptr, size_t len)

Unmap a user memory range.

int rtdm_ratelimit (struct rtdm_ratelimit_state *rs, const char *func)

Enforces a rate limit.

void rtdm_printk_ratelimited (const char *format,...)

Real-time safe rate-limited message printing on kernel console.

void rtdm_printk (const char *format,...)

Real-time safe message printing on kernel console.

void * rtdm_malloc (size_t size)

Allocate memory block.

void rtdm_free (void *ptr)

Release real-time memory block.

• int rtdm read user ok (struct rtdm fd *fd, const void user *ptr, size t size)

Check if read access to user-space memory block is safe.

int rtdm_rw_user_ok (struct rtdm_fd *fd, const void __user *ptr, size_t size)

Check if read/write access to user-space memory block is safe.

int rtdm_copy_from_user (struct rtdm_fd *fd, void *dst, const void __user *src, size_t size)

Copy user-space memory block to specified buffer.

• int rtdm_safe_copy_from_user (struct rtdm_fd *fd, void *dst, const void __user *src, size_t size)

Check if read access to user-space memory block and copy it to specified buffer.

int rtdm copy to user (struct rtdm fd *fd, void user *dst, const void *src, size t size)

Copy specified buffer to user-space memory block.

• int rtdm_safe_copy_to_user (struct rtdm_fd *fd, void __user *dst, const void *src, size_t size)

Check if read/write access to user-space memory block is safe and copy specified buffer to it.

• int rtdm_strncpy_from_user (struct rtdm_fd *fd, char *dst, const char __user *src, size_t count) Copy user-space string to specified buffer.

• int rtdm_in_rt_context (void)

Test if running in a real-time task.

• int rtdm_rt_capable (struct rtdm_fd *fd)

Test if the caller is capable of running in real-time context.

6.38.1 Detailed Description

6.38.2 Function Documentation

6.38.2.1 int rtdm_copy_from_user (struct rtdm_fd * fd, void * dst, const void __user * src, size_t size)

Copy user-space memory block to specified buffer.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler
in	dst	Destination buffer address
in	src	Address of the user-space memory block
in	size	Size of the memory block

Returns

0 on success, otherwise:

· -EFAULT is returned if an invalid memory area was accessed.

Note

Before invoking this service, verify via rtdm_read_user_ok() that the provided user-space address can securely be accessed.

Tags

task-unrestricted

6.38.2.2 int rtdm_copy_to_user (struct rtdm_fd * fd, void __user * dst, const void * src, size_t size)

Copy specified buffer to user-space memory block.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler
in	dst	Address of the user-space memory block
in	src	Source buffer address

6.38 Utility Services 193

in	size	Size of the memory block

Returns

0 on success, otherwise:

· -EFAULT is returned if an invalid memory area was accessed.

Note

Before invoking this service, verify via rtdm_rw_user_ok() that the provided user-space address can securely be accessed.

Tags

task-unrestricted

```
6.38.2.3 void rtdm_free ( void * ptr )
```

Release real-time memory block.

Parameters

in	ptr	Pointer to memory block as returned by rtdm_malloc()
----	-----	--

Tags

unrestricted

```
6.38.2.4 int rtdm_in_rt_context (void)
```

Test if running in a real-time task.

Returns

Non-zero is returned if the caller resides in real-time context, 0 otherwise.

Tags

unrestricted

```
6.38.2.5 int rtdm_iomap_to_user ( struct rtdm_fd * fd, phys_addr_t src_addr, size_t len, int prot, void ** pptr, struct vm_operations_struct * vm_ops, void * vm_private_data )
```

Map an I/O memory range into the address space of the user.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler

in	src_addr	physical I/O address to be mapped
in	len	Length of the memory range
in	prot	Protection flags for the user's memory range, typically either PROT_← READ or PROT_READ PROT_WRITE
in,out	pptr	Address of a pointer containing the desired user address or NULL on entry and the finally assigned address on return
in	vm_ops	vm_operations to be executed on the vm_area of the user memory range or NULL
in	vm_private_← data	Private data to be stored in the vm_area, primarily useful for vm_← operation handlers

Returns

0 on success, otherwise (most common values):

- -EINVAL is returned if an invalid start address, size, or destination address was passed.
- -ENOMEM is returned if there is insufficient free memory or the limit of memory mapping for the user process was reached.
- -EAGAIN is returned if too much memory has been already locked by the user process.
- -EPERM may be returned if an illegal invocation environment is detected.

Note

RTDM supports two models for unmapping the memory area:

- manual unmapping via rtdm_munmap(), which may be issued from a driver in response to an IOCTL call, or by a call to the regular munmap() call from the application.
- automatic unmapping, triggered by the termination of the process which owns the mapping.
 To track the number of references pending on the resource mapped, the driver can pass the
 address of a close handler for the vm_area considered, in the vm_ops descriptor. See the
 relevant Linux kernel programming documentation (e.g. Linux Device Drivers book) on virtual
 memory management for details.

Tags

secondary-only

6.38.2.6 void* rtdm malloc (size t size)

Allocate memory block.

Parameters

in	size	Requested size of the memory	/ block

Returns

The pointer to the allocated block is returned on success, NULL otherwise.

Tags

unrestricted

Referenced by a4l_alloc_subd().

6.38 Utility Services 195

6.38.2.7 int rtdm_mmap_iomem (struct vm_area_struct * vma, phys_addr_t pa)

Map an I/O memory range to a virtual user area.

This routine is commonly used from a ->mmap() handler of a RTDM driver, for mapping an I/O memory area over the user address space referred to by *vma*.

Parameters

in	vma	The VMA descriptor to receive the mapping.
in	ра	The physical I/O address to be mapped.

Returns

0 on success, otherwise a negated error code is returned.

Note

To map a chunk of logical space obtained from kmalloc(), or a purely virtual area with no direct physical mapping to a VMA, call rtdm_mmap_kmem() or rtdm_mmap_vmem() respectively instead.

Tags

secondary-only

6.38.2.8 int rtdm mmap kmem (struct vm area struct * vma, void * va)

Map a kernel logical memory range to a virtual user area.

This routine is commonly used from a ->mmap() handler of a RTDM driver, for mapping a virtual memory area with a direct physical mapping over the user address space referred to by *vma*.

Parameters

in	vma	The VMA descriptor to receive the mapping.
in	va	The kernel logical address to be mapped.

Returns

0 on success, otherwise a negated error code is returned.

Note

This service works on memory regions allocated via kmalloc(). To map a chunk of virtual space with no direct physical mapping, or a physical I/O memory to a VMA, call rtdm_mmap_iomem() respectively instead.

Tags

secondary-only

6.38.2.9 int rtdm_mmap_to_user (struct rtdm_fd * fd, void * src_addr, size_t len, int prot, void ** pptr, struct vm_operations_struct * vm_ops, void * vm_private_data)

Map a kernel memory range into the address space of the user.

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler
in	src_addr	Kernel virtual address to be mapped
in	len	Length of the memory range
in	prot	Protection flags for the user's memory range, typically either PROT_←
		READ or PROT_READ PROT_WRITE
in,out	pptr	Address of a pointer containing the desired user address or NULL on
		entry and the finally assigned address on return
in	vm_ops	vm_operations to be executed on the vm_area of the user memory
		range or NULL
in	vm_private_ <i>←</i>	Private data to be stored in the vm_area, primarily useful for vm_←
	data	operation handlers

Returns

0 on success, otherwise (most common values):

- -EINVAL is returned if an invalid start address, size, or destination address was passed.
- -ENOMEM is returned if there is insufficient free memory or the limit of memory mapping for the user process was reached.
- -EAGAIN is returned if too much memory has been already locked by the user process.
- -EPERM may be returned if an illegal invocation environment is detected.

Note

This service only works on memory regions allocated via kmalloc() or vmalloc(). To map physical I/O memory to user-space use rtdm_iomap_to_user() instead.

RTDM supports two models for unmapping the memory area:

- manual unmapping via rtdm_munmap(), which may be issued from a driver in response to an IOCTL call, or by a call to the regular munmap() call from the application.
- automatic unmapping, triggered by the termination of the process which owns the mapping.
 To track the number of references pending on the resource mapped, the driver can pass the
 address of a close handler for the vm_area considered, in the vm_ops descriptor. See the
 relevant Linux kernel programming documentation (e.g. Linux Device Drivers book) on virtual
 memory management for details.

Tags

secondary-only

6.38.2.10 int rtdm_mmap_vmem (struct vm_area_struct * vma, void * va)

Map a virtual memory range to a virtual user area.

This routine is commonly used from a ->mmap() handler of a RTDM driver, for mapping a purely virtual memory area over the user address space referred to by *vma*.

Parameters

6.38 Utility Services 197

in	vma	The VMA descriptor to receive the mapping.
in	va	The virtual address to be mapped.

Returns

0 on success, otherwise a negated error code is returned.

Note

This service works on memory regions allocated via vmalloc(). To map a chunk of logical space obtained from kmalloc(), or a physical I/O memory to a VMA, call rtdm_mmap_kmem() or

Tags

secondary-only

6.38.2.11 int rtdm_munmap (void * ptr, size_t len)

Unmap a user memory range.

Parameters

in	ptr	User address or the memory range
in	len	Length of the memory range

Returns

0 on success, otherwise:

- -EINVAL is returned if an invalid address or size was passed.
- -EPERM may be returned if an illegal invocation environment is detected.

Tags

secondary-only

6.38.2.12 void rtdm_printk (const char * format, ...)

Real-time safe message printing on kernel console.

Parameters

in	format	Format string (conforming standard printf())
		Arguments referred by format

Returns

On success, this service returns the number of characters printed. Otherwise, a negative error code is returned.

Tags

unrestricted

6.38.2.13 void rtdm printk ratelimited (const char * format, ...)

Real-time safe rate-limited message printing on kernel console.

in	format	Format string (conforming standard printf())
		Arguments referred by format

Returns

On success, this service returns the number of characters printed. Otherwise, a negative error code is returned.

Tags

unrestricted

6.38.2.14 int rtdm_ratelimit (struct rtdm_ratelimit_state * rs, const char * func)

Enforces a rate limit.

This function enforces a rate limit: not more than rs->burst callbacks in every rs->interval.

Parameters

in,out	rs	rtdm_ratelimit_state data
in	func	name of calling function

Returns

0 means callback will be suppressed and 1 means go ahead and do it

Tags

unrestricted

References rtdm_clock_read(), rtdm_lock_get_irqsave, and rtdm_lock_put_irqrestore().

6.38.2.15 int rtdm_read_user_ok (struct rtdm_fd * fd, const void __user * ptr, size_t size)

Check if read access to user-space memory block is safe.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation handler
in	ptr	Address of the user-provided memory block
in	size	Size of the memory block

Returns

Non-zero is return when it is safe to read from the specified memory block, 0 otherwise.

Tags

task-unrestricted

6.38.2.16 int rtdm rt capable (struct rtdm fd * fd)

Test if the caller is capable of running in real-time context.

6.38 Utility Services 199

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler

Returns

Non-zero is returned if the caller is able to execute in real-time context (independent of its current execution mode), 0 otherwise.

Note

This function can be used by drivers that provide different implementations for the same service depending on the execution mode of the caller. If a caller requests such a service in non-real-time context but is capable of running in real-time as well, it might be appropriate for the driver to reject the request via -ENOSYS so that RTDM can switch the caller and restart the request in real-time context.

Tags

unrestricted

6.38.2.17 int rtdm_rw_user_ok (struct rtdm_fd * fd, const void __user * ptr, size_t size)

Check if read/write access to user-space memory block is safe.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation handler
in	ptr	Address of the user-provided memory block
in	size	Size of the memory block

Returns

Non-zero is return when it is safe to read from or write to the specified memory block, 0 otherwise.

Tags

task-unrestricted

6.38.2.18 int rtdm_safe_copy_from_user (struct rtdm_fd * fd, void * dst, const void __user * src, size t size)

Check if read access to user-space memory block and copy it to specified buffer.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler
in	dst	Destination buffer address
in	src	Address of the user-space memory block

2	_!	C:== = f + == ========== = = ==
1 n	SIZE	Size of the memory block
111	0,20	OLO OF THO HIGHIOTY BIOOK

Returns

0 on success, otherwise:

· -EFAULT is returned if an invalid memory area was accessed.

Note

This service is a combination of rtdm_read_user_ok and rtdm_copy_from_user.

Tags

task-unrestricted

```
6.38.2.19 int rtdm_safe_copy_to_user ( struct rtdm_fd * fd, void __user * dst, const void * src, size_t size )
```

Check if read/write access to user-space memory block is safe and copy specified buffer to it.

Parameters

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler
in	dst	Address of the user-space memory block
in	src	Source buffer address
in	size	Size of the memory block

Returns

0 on success, otherwise:

• -EFAULT is returned if an invalid memory area was accessed.

Note

This service is a combination of rtdm_rw_user_ok and rtdm_copy_to_user.

Tags

task-unrestricted

6.38.2.20 int rtdm_strncpy_from_user (struct rtdm_fd * fd, char * dst, const char __user * src, size_t count)

Copy user-space string to specified buffer.

Parameters

6.38 Utility Services 201

in	fd	RTDM file descriptor as passed to the invoked device operation han-
		dler
in	dst	Destination buffer address
in	src	Address of the user-space string
in	count	Maximum number of bytes to copy, including the trailing '0'

Returns

Length of the string on success (not including the trailing '0'), otherwise:

• -EFAULT is returned if an invalid memory area was accessed.

Note

This services already includes a check of the source address, calling rtdm_read_user_ok() for src explicitly is not required.


Tags

task-unrestricted

6.39 SCHED_QUOTA scheduling policy

The SCHED_QUOTA policy enforces a limitation on the CPU consumption of threads over a globally defined period, known as the quota interval.

Collaboration diagram for SCHED QUOTA scheduling policy:



6.39.1 Detailed Description

The SCHED_QUOTA policy enforces a limitation on the CPU consumption of threads over a globally defined period, known as the quota interval.

This is done by pooling threads with common requirements in groups, and giving each group a share of the global period (CONFIG_XENO_OPT_SCHED_QUOTA_PERIOD).

When threads have entirely consumed the quota allotted to the group they belong to, the latter is suspended as a whole, until the next quota interval starts. At this point, a new runtime budget is given to each group, in accordance with its share.

6.40 Thread scheduling control

Collaboration diagram for Thread scheduling control:



Modules

SCHED_QUOTA scheduling policy

The SCHED_QUOTA policy enforces a limitation on the CPU consumption of threads over a globally defined period, known as the quota interval.

Data Structures

struct xnsched

Scheduling information structure.

Functions

• static int xnsched_run (void)

The rescheduling procedure.

• static void xnsched_rotate (struct xnsched *sched, struct xnsched_class *sched_class, const union xnsched_policy_param *sched_param)

Rotate a scheduler runqueue.

6.40.1 Detailed Description

6.40.2 Function Documentation

6.40.2.1 void xnsched_rotate (struct **xnsched** * sched, struct xnsched_class * sched_class, const union xnsched_policy_param * sched_param) [inline], [static]

Rotate a scheduler runqueue.

The specified scheduling class is requested to rotate its runqueue for the given scheduler. Rotation is performed according to the scheduling parameter specified by *sched_param*.

Note

The nucleus supports round-robin scheduling for the members of the RT class.

	sched	The per-CPU scheduler hosting the target scheduling class.
Ī	sched_class	The scheduling class which should rotate its runqueue.
Ī	sched_param	The scheduling parameter providing rotation information to the specified scheduling
		class.

Tags

unrestricted, atomic-entry

```
6.40.2.2 int xnsched run (void) [inline], [static]
```

The rescheduling procedure.

This is the central rescheduling routine which should be called to validate and apply changes which have previously been made to the nucleus scheduling state, such as suspending, resuming or changing the priority of threads. This call performs context switches as needed. xnsched_run() schedules out the current thread if:

- the current thread is about to block.
- a runnable thread from a higher priority scheduling class is waiting for the CPU.
- the current thread does not lead the runnable threads from its own scheduling class (i.e. round-robin).

The Cobalt core implements a lazy rescheduling scheme so that most of the services affecting the threads state MUST be followed by a call to the rescheduling procedure for the new scheduling state to be applied.

In other words, multiple changes on the scheduler state can be done in a row, waking threads up, blocking others, without being immediately translated into the corresponding context switches. When all changes have been applied, xnsched_run() should be called for considering those changes, and possibly switching context.

As a notable exception to the previous principle however, every action which ends up suspending the current thread begets an implicit call to the rescheduling procedure on behalf of the blocking service.

Typically, self-suspension or sleeping on a synchronization object automatically leads to a call to the rescheduling procedure, therefore the caller does not need to explicitly issue xnsched_run() after such operations.

The rescheduling procedure always leads to a null-effect if it is called on behalf of an interrupt service routine. Any outstanding scheduler lock held by the outgoing thread will be restored when the thread is scheduled back in.

Calling this procedure with no applicable context switch pending is harmless and simply leads to a null-effect.

Returns

Non-zero is returned if a context switch actually happened, otherwise zero if the current thread was left running.

Tags

unrestricted

References xnsched::curr.

Referenced by rtdm_event_signal(), rtdm_mutex_unlock(), rtdm_sem_up(), xnregistry_enter(), xnselect_bind(), xnselect_destroy(), xnthread_cancel(), xnthread_migrate(), xnthread_set_mode(), and xnthread_start().

6.41 Synchronous I/O multiplexing

This module implements the services needed for implementing the POSIX select() service, or any other event multiplexing services.

Collaboration diagram for Synchronous I/O multiplexing:



Functions

• void xnselect_init (struct xnselect *select_block)

Initialize a struct xnselect structure.

static int xnselect_signal (struct xnselect *select_block, unsigned int state)

Signal a file descriptor state change.

void xnselect_destroy (struct xnselect *select_block)

Destroy the xnselect structure associated with a file descriptor.

int xnselector_init (struct xnselector *selector)

Initialize a selector structure.

int xnselect (struct xnselector *selector, fd_set *out_fds[XNSELECT_MAX_TYPES], fd_set *in_← fds[XNSELECT_MAX_TYPES], int nfds, xnticks_t timeout, xntmode_t timeout_mode)

Check the state of a number of file descriptors, wait for a state change if no descriptor is ready.

void xnselector_destroy (struct xnselector *selector)

Destroy a selector block.

int xnselect_bind (struct xnselect *select_block, struct xnselect_binding *binding, struct xnselector *selector, unsigned type, unsigned index, unsigned state)

Bind a file descriptor (represented by its xnselect structure) to a selector block.

6.41.1 Detailed Description

This module implements the services needed for implementing the POSIX select() service, or any other event multiplexing services.

Following the implementation of the posix select service, this module defines three types of events:

- XNSELECT_READ meaning that a file descriptor is ready for reading;
- XNSELECT_WRITE meaning that a file descriptor is ready for writing;
- XNSELECT_EXCEPT meaning that a file descriptor received an exceptional event.

It works by defining two structures:

- a struct xnselect structure, which should be added to every file descriptor for every event type (read, write, or except);
- a *struct xnselector* structure, the selection structure, passed by the thread calling the xnselect service, where this service does all its housekeeping.

6.41.2 Function Documentation

6.41.2.1 int xnselect (struct xnselector * selector, fd_set * out_fds[XNSELECT_MAX_TYPES], fd_set * in_fds[XNSELECT_MAX_TYPES], int nfds, xnticks_t timeout, xntmode_t timeout mode)

Check the state of a number of file descriptors, wait for a state change if no descriptor is ready.

Parameters

selector	structure to check for pending events
out_fds	The set of descriptors with pending events if a strictly positive number is returned,
	or the set of descriptors not yet bound if -ECHRNG is returned;
in_fds	the set of descriptors which events should be checked
nfds	the highest-numbered descriptor in any of the in_fds sets, plus 1;
timeout	the timeout, whose meaning depends on timeout_mode, note that xnselect() pass
	timeout and timeout_mode unchanged to xnsynch_sleep_on, so passing a relative
	value different from XN_INFINITE as a timeout with timeout_mode set to XN_RE↔
	LATIVE, will cause a longer sleep than expected if the sleep is interrupted.
timeout_mode	the mode of timeout.

Return values

-EINVAL	if <i>nfds</i> is negative;
-ECHRNG	if some of the descriptors passed in <i>in_fds</i> have not yet been registered
	with xnselect_bind(), out_fds contains the set of such descriptors;
-EINTR	if xnselect was interrupted while waiting;
0	in case of timeout.
the	number of file descriptors having received an event.

Tags

primary-only, might-switch

References XNBREAK, xnsynch_sleep_on(), and XNTIMEO.

6.41.2.2 int xnselect_bind (struct xnselect * select_block, struct xnselect_binding * binding, struct xnselector * selector, unsigned type, unsigned index, unsigned state)

Bind a file descriptor (represented by its *xnselect* structure) to a selector block.

Parameters

select_block	pointer to the struct xnselect to be bound;
binding	pointer to a newly allocated (using xnmalloc) struct xnselect_binding;
selector	pointer to the selector structure;
type	type of events (XNSELECT_READ, XNSELECT_WRITE, or XNSELECT_EXCEP⊷
	(<i>T</i>);
index	index of the file descriptor (represented by select_block) in the bit fields used by the
	selector structure;
state	current state of the file descriptor.

select_block must have been initialized with xnselect_init(), the xnselector structure must have been initialized with xnselector init(), binding may be uninitialized.

This service must be called with nklock locked, irqs off. For this reason, the *binding* parameter must have been allocated by the caller outside the locking section.

Return values

-EINVAL	if type or index is invalid;
0	otherwise.

Tags

task-unrestricted, might-switch, atomic-entry

References xnsched run().

Referenced by rtdm_event_select(), and rtdm_sem_select().

6.41.2.3 void xnselect_destroy (struct xnselect * select_block)

Destroy the *xnselect* structure associated with a file descriptor.

Any binding with a xnselector block is destroyed.

Parameters

aalaat blaak	pointer to the xnselect structure associated with a file descriptor
Select block	pointer to the <i>xhselect</i> structure associated with a nie descriptor

Tags

task-unrestricted, might-switch

References xnsched_run().

Referenced by rtdm_event_destroy(), and rtdm_sem_destroy().

6.41.2.4 void xnselect init (struct xnselect * select block)

Initialize a struct xnselect structure.

This service must be called to initialize a *struct xnselect* structure before it is bound to a selector by the means of xnselect_bind().

Parameters

select_block	pointer to the xnselect structure to be initialized

Tags

task-unrestricted

Referenced by rtdm_event_init(), and rtdm_sem_init().

6.41.2.5 static int xnselect_signal (struct **xnselect** * select_block, unsigned int state) [inline], [static]

Signal a file descriptor state change.

Parameters

select_block	pointer to an <i>xnselect</i> structure representing the file descriptor whose state changed;
state	new value of the state.

Return values

1	if rescheduling is needed;
0	otherwise.

Referenced by rtdm_event_clear(), rtdm_event_signal(), rtdm_event_timedwait(), rtdm_sem_ctimeddown(), and rtdm_sem_up().

6.41.2.6 void xnselector_destroy (struct xnselector * selector)

Destroy a selector block.

All bindings with file descriptor are destroyed.

Parameters

selector the selector block to be destroyed	
---	--

Tags

task-unrestricted

6.41.2.7 int xnselector_init (struct xnselector * selector)

Initialize a selector structure.

Parameters

selector	The selector structure to be initialized.
Return values	
	0


Tags

task-unrestricted

References xnsynch_init().

6.42 Thread synchronization services

Collaboration diagram for Thread synchronization services:



Functions

- void xnsynch_init (struct xnsynch *synch, int flags, atomic_t *fastlock)
 Initialize a synchronization object.
- int xnsynch_destroy (struct xnsynch *synch)
 Destroy a synchronization object.
- int xnsynch_sleep_on (struct xnsynch *synch, xnticks_t timeout, xntmode_t timeout_mode)

 Sleep on an ownerless synchronization object.
- struct xnthread * xnsynch_wakeup_one_sleeper (struct xnsynch *synch)

 Unblock the heading thread from wait.
- void xnsynch_wakeup_this_sleeper (struct xnsynch *synch, struct xnthread *sleeper)

 Unblock a particular thread from wait.
- int xnsynch_acquire (struct xnsynch *synch, xnticks_t timeout, xntmode_t timeout_mode)

 Acquire the ownership of a synchronization object.
- int xnsynch try acquire (struct xnsynch *synch)

Try acquiring the ownership of a synchronization object.

- struct xnthread * xnsynch_release (struct xnsynch *synch, struct xnthread *thread)
 Give the resource ownership to the next waiting thread.
- struct xnthread * xnsynch_peek_pendq (struct xnsynch *synch)

Access the thread leading a synch object wait queue.

• int xnsynch_flush (struct xnsynch *synch, int reason)

Unblock all waiters pending on a resource.

6.42.1 Detailed Description

6.42.2 Function Documentation

6.42.2.1 int xnsynch_acquire (struct xnsynch * synch, xnticks_t timeout, xntmode_t timeout_mode)

Acquire the ownership of a synchronization object.

This service should be called by upper interfaces wanting the current thread to acquire the ownership of the given resource. If the resource is already assigned to another thread, the caller is suspended.

This service must be used only with synchronization objects that track ownership (XNSYNCH_OWNER set.

Parameters

The descriptor address of the synchronization object to acquire.	
The timeout which may be used to limit the time the thread pends on the resource.	
This value is a wait time given as a count of nanoseconds. It can either be relative,	
absolute monotonic, or absolute adjustable depending on timeout_mode. Passing	
XN_INFINITE and setting <i>mode</i> to XN_RELATIVE specifies an unbounded wait. All	
other values are used to initialize a watchdog timer.	
The mode of the <i>timeout</i> parameter. It can either be set to XN_RELATIVE, XN_A	
BSOLUTE, or XN_REALTIME (see also xntimer_start()).	

Returns

A bitmask which may include zero or one information bit among XNRMID, XNTIMEO and XNB REAK, which should be tested by the caller, for detecting respectively: object deletion, timeout or signal/unblock conditions which might have happened while waiting.

Tags

primary-only, might-switch

Note

Unlike xnsynch_try_acquire(), this call does NOT check for invalid recursive locking request, which means that such request will always cause a deadlock for the caller.

References XNBOOST, XNBREAK, XNPEND, XNRMID, XNROBBED, xnthread_current(), xnthread_cu

Referenced by rtdm mutex timedlock().

6.42.2.2 int xnsynch_destroy (struct xnsynch * synch)

Destroy a synchronization object.

Destroys the synchronization object synch, unblocking all waiters with the XNRMID status.

Returns

XNSYNCH_RESCHED is returned if at least one thread is unblocked, which means the caller should invoke xnsched_run() for applying the new scheduling state. Otherwise, XNSYNCH_DO⊷ NE is returned.

Side effects

Same as xnsynch_flush().

Tags

task-unrestricted

References XNRMID, and xnsynch flush().

6.42.2.3 int xnsynch_flush (struct xnsynch * synch, int reason)

Unblock all waiters pending on a resource.

This service atomically releases all threads which currently sleep on a given resource.

This service should be called by upper interfaces under circumstances requiring that the pending queue of a given resource is cleared, such as before the resource is deleted.

synch	The descriptor address of the synchronization object to be flushed.		
reason	Some flags to set in the information mask of every unblocked thread. Zero is an		
	acceptable value. The following bits are pre-defined by the nucleus:		

- XNRMID should be set to indicate that the synchronization object is about to be destroyed (see xnthread_resume()).
- XNBREAK should be set to indicate that the wait has been forcibly interrupted (see xnthread_

 unblock()).

Returns

XNSYNCH_RESCHED is returned if at least one thread is unblocked, which means the caller should invoke xnsched_run() for applying the new scheduling state. Otherwise, XNSYNCH_DO⊷ NE is returned.

Side effects

- The effective priority of the previous resource owner might be lowered to its base priority value as a consequence of the priority inheritance boost being cleared.
- After this operation has completed, the synchronization object is not owned by any thread.

Tags

unrestricted

References XNPEND, and xnthread_resume().

Referenced by rtdm event signal(), and xnsynch destroy().

6.42.2.4 void xnsynch_init (struct xnsynch * synch, int flags, atomic_t * fastlock)

Initialize a synchronization object.

Initializes a synchronization object. Xenomai threads can wait on and signal such objects for serializing access to resources. This object has built-in support for priority inheritance.

Parameters

synch	The address of a synchronization object descriptor the nucleus will use to store the	
	object-specific data. This descriptor must always be valid while the object is active	
	therefore it must be allocated in permanent memory.	
flags	A set of creation flags affecting the operation. The valid flags are:	

- XNSYNCH_PRIO causes the threads waiting for the resource to pend in priority order. Otherwise, FIFO ordering is used (XNSYNCH_FIFO).
- XNSYNCH_OWNER indicates that the synchronization object shall track the resource ownership, allowing a single owner at most at any point in time. Note that setting this flag implies the use of xnsynch_acquire() and xnsynch_release() instead of xnsynch_sleep_on() and xnsynch_wakeup← _*().
- XNSYNCH_PIP enables priority inheritance when a priority inversion is detected among threads using this object. XNSYNCH_PIP enables XNSYNCH_OWNER and XNSYNCH_PRIO implicitly.

XNSYNCH_DREORD (Disable REORDering) tells the nucleus that the wait queue should not be
reordered whenever the priority of a blocked thread it holds is changed. If this flag is not specified,
changing the priority of a blocked thread using xnthread_set_schedparam() will cause this object's
wait queue to be reordered according to the new priority level, provided the synchronization object
makes the waiters wait by priority order on the awaited resource (XNSYNCH_PRIO).

Parameters

fastlock	Address of the fast lock word to be associated with a synchronization object with
	ownership tracking. Therefore, a valid fast-lock address is required if XNSYNCH_←
	OWNER is set in <i>flags</i> .

Tags

task-unrestricted

Referenced by rtdm_event_init(), rtdm_mutex_init(), rtdm_sem_init(), and xnselector_init().

6.42.2.5 struct xnthread * xnsynch peek pendq (struct xnsynch * synch)

Access the thread leading a synch object wait queue.

This services returns the descriptor address of to the thread leading a synchronization object wait queue.

Parameters

synch	The descriptor address of the target synchronization object.
-------	--

Returns

The descriptor address of the unblocked thread.

Tags

unrestricted

6.42.2.6 struct xnthread * xnsynch_release (struct xnsynch * synch, struct xnthread * thread)

Give the resource ownership to the next waiting thread.

This service releases the ownership of the given synchronization object. The thread which is currently leading the object's pending list, if any, is unblocked from its pending state. However, no reschedule is performed.

This service must be used only with synchronization objects that track ownership (XNSYNCH_OWNER set).

Parameters

synch	The descriptor address of the synchronization object whose ownership is changed.
thread	The descriptor address of the current owner.

Returns

The descriptor address of the unblocked thread.

Side effects

- The effective priority of the previous resource owner might be lowered to its base priority value as a consequence of the priority inheritance boost being cleared.
- The synchronization object ownership is transferred to the unblocked thread.

Tags

primary-only, might-switch

Referenced by rtdm_mutex_unlock().

6.42.2.7 int xnsynch_sleep_on (struct xnsynch * synch, xnticks_t timeout, xntmode_t timeout_mode)

Sleep on an ownerless synchronization object.

Makes the calling thread sleep on the specified synchronization object, waiting for it to be signaled.

This service should be called by upper interfaces wanting the current thread to pend on the given resource. It must not be used with synchronization objects that are supposed to track ownership (XNSY-NCH_OWNER).

Parameters

synch	The descriptor address of the synchronization object to sleep on.	
timeout	The timeout which may be used to limit the time the thread pends on the resource.	
	This value is a wait time given as a count of nanoseconds. It can either be relative,	
	absolute monotonic, or absolute adjustable depending on timeout mode. Passing	
	XN_INFINITE and setting <i>mode</i> to XN_RELATIVE specifies an unbounded wait. All	
	other values are used to initialize a watchdog timer.	
timeout_mode	The mode of the <i>timeout</i> parameter. It can either be set to XN_RELATIVE, XN_A↔	
	BSOLUTE, or XN_REALTIME (see also xntimer_start()).	

Returns

A bitmask which may include zero or one information bit among XNRMID, XNTIMEO and XNB REAK, which should be tested by the caller, for detecting respectively: object deletion, timeout or signal/unblock conditions which might have happened while waiting.

Tags

primary-only, might-switch

References XNBREAK, XNPEND, XNRMID, xnthread_current(), xnthread_suspend(), XNTIMEO, and XNWARN.

Referenced by rtdm_event_timedwait(), rtdm_sem_timeddown(), xnregistry_bind(), xnselect(), and xnthread_join().

6.42.2.8 int xnsynch try acquire (struct xnsynch * synch)

Try acquiring the ownership of a synchronization object.

This service should be called by upper interfaces wanting the current thread to acquire the ownership of the given resource. If the resource is already assigned to another thread, the call returns with an error code.

This service must be used only with synchronization objects that track ownership (XNSYNCH_OWNER set.

The descriptor address of the synchronization object to acquire.	

Returns

Zero is returned if synch has been successfully acquired. Otherwise:

- -EDEADLK is returned if synch is currently held by the calling thread.
- -EBUSY is returned if synch is currently held by another thread.

Tags

primary-only

References xnthread current().

Referenced by rtdm_mutex_timedlock().

6.42.2.9 struct xnthread * xnsynch_wakeup_one_sleeper (struct xnsynch * synch)

Unblock the heading thread from wait.

This service wakes up the thread which is currently leading the synchronization object's pending list. The sleeping thread is unblocked from its pending state, but no reschedule is performed.

This service should be called by upper interfaces wanting to signal the given resource so that a single waiter is resumed. It must not be used with synchronization objects that are supposed to track ownership (XNSYNCH OWNER not set).

Parameters

synch	The descriptor address	of the synchronization	object whose	ownership is changed.

Returns

The descriptor address of the unblocked thread.

Tags

unrestricted

References XNPEND, and xnthread resume().

Referenced by rtdm_sem_up().

6.42.2.10 void xnsynch_wakeup_this_sleeper (struct xnsynch * synch, struct xnthread * sleeper)

Unblock a particular thread from wait.

This service wakes up a specific thread which is currently pending on the given synchronization object. The sleeping thread is unblocked from its pending state, but no reschedule is performed.

This service should be called by upper interfaces wanting to signal the given resource so that a specific waiter is resumed. It must not be used with synchronization objects that are supposed to track ownership (XNSYNCH_OWNER not set).

synch	The descriptor address of the synchronization object whose ownership is changed.	
sleeper	The thread to unblock which MUST be currently linked to the synchronization ob-	
	ject's pending queue (i.e. synch->pendq).	


Tags

unrestricted

References XNPEND, and xnthread_resume().

6.43 Thread services

Collaboration diagram for Thread services:



Modules

Thread state flags

Bits reporting permanent or transient states of threads.

Thread information flags

Bits reporting events notified to threads.

Functions

static struct xnthread * xnthread current (void)

Retrieve the current Cobalt core TCB.

• static struct xnthread * xnthread_from_task (struct task_struct *p)

Retrieve the Cobalt core TCB attached to a Linux task.

static void xnthread test cancel (void)

Introduce a thread cancellation point.

int xnthread_init (struct xnthread *thread, const struct xnthread_init_attr *attr, struct xnsched_class *sched_class, const union xnsched_policy_param *sched_param)

Initialize a new thread.

int xnthread_start (struct xnthread *thread, const struct xnthread_start_attr *attr)

Start a newly created thread.

• int xnthread set mode (int clrmask, int setmask)

Change control mode of the current thread.

void xnthread_suspend (struct xnthread *thread, int mask, xnticks_t timeout, xntmode_t timeout
 _mode, struct xnsynch *wchan)

Suspend a thread.

void xnthread_resume (struct xnthread *thread, int mask)

Resume a thread.

• int xnthread_unblock (struct xnthread *thread)

Unblock a thread.

int xnthread_set_periodic (struct xnthread *thread, xnticks_t idate, xntmode_t timeout_mode, xnticks_t period)

Make a thread periodic.

int xnthread_wait_period (unsigned long *overruns_r)

Wait for the next periodic release point.

int xnthread_set_slice (struct xnthread *thread, xnticks_t quantum)

6.43 Thread services 217

Set thread time-slicing information.

void xnthread_cancel (struct xnthread *thread)

Cancel a thread.

• int xnthread_join (struct xnthread *thread, bool uninterruptible)

Join with a terminated thread.

int xnthread_harden (void)

Migrate a Linux task to the Xenomai domain.

void xnthread relax (int notify, int reason)

Switch a shadow thread back to the Linux domain.

• int xnthread map (struct xnthread *thread, struct completion *done)

Create a shadow thread context over a kernel task.

• int xnthread_migrate (int cpu)

Migrate the current thread.

• int xnthread_set_schedparam (struct xnthread *thread, struct xnsched_class *sched_class, const union xnsched_policy_param *sched_param)

Change the base scheduling parameters of a thread.

6.43.1 Detailed Description

6.43.2 Function Documentation

6.43.2.1 void xnthread_cancel (struct xnthread * thread)

Cancel a thread.

Request cancellation of a thread. This service forces *thread* to exit from any blocking call, then to switch to secondary mode. *thread* will terminate as soon as it reaches a cancellation point. Cancellation points are defined for the following situations:

- thread self-cancels by a call to xnthread_cancel().
- thread invokes a Linux syscall (user-space shadow only).
- thread receives a Linux signal (user-space shadow only).
- thread unblocks from a Xenomai syscall (user-space shadow only).
- thread attempts to block on a Xenomai syscall (user-space shadow only).
- thread explicitly calls xnthread_test_cancel().

Parameters

thread The descriptor address of the thread to terminate.

Tags

task-unrestricted, might-switch

Note

References XNCANCELD, XNDORMANT, XNKICKED, xnsched_run(), xnthread_current(), xnthread_current(), xnthread test cancel(), XNUSER, and XNWEAK.

Referenced by rtdm task init().

218 Module Documentation

```
6.43.2.2 struct xnthread * xnthread_current(void) [static]
```

Retrieve the current Cobalt core TCB.

Returns the address of the current Cobalt core thread descriptor, or NULL if running over a regular Linux task. This call is not affected by the current runtime mode of the core thread.

Note

The returned value may differ from xnsched_current_thread() called from the same context, since the latter returns the root thread descriptor for the current CPU if the caller is running in secondary mode.

Tags

unrestricted

Referenced by rtdm_event_timedwait(), rtdm_mutex_timedlock(), rtdm_sem_timeddown(), xnsynch acquire(), xnsynch_sleep_on(), xnsynch_try_acquire(), xnthread_cancel(), xnthread_harden(), xnthread_join(), xnthread_map(), xnthread_migrate(), xnthread_relax(), xnthread_set_periodic(), xnthread_test_cancel(), and xnthread_wait_period().

```
6.43.2.3 struct xnthread * xnthread from task ( struct task struct * p ) [static]
```

Retrieve the Cobalt core TCB attached to a Linux task.

Returns the address of the Cobalt core thread descriptor attached to the Linux task p, or NULL if p is a regular Linux task. This call is not affected by the current runtime mode of the core thread.

Tags

unrestricted

```
6.43.2.4 int xnthread harden (void)
```

Migrate a Linux task to the Xenomai domain.

This service causes the transition of "current" from the Linux domain to Xenomai. The shadow will resume in the Xenomai domain as returning from schedule().

Tags

```
secondary-only, might-switch
```

References XNRELAX, XNSSTEP, xnthread_current(), xnthread_relax(), and xnthread_test_cancel(). Referenced by xnthread_map().

```
6.43.2.5 int xnthread_init ( struct xnthread * thread, const struct xnthread_init_attr * attr, struct xnsched class * sched class, const union xnsched policy param * sched param )
```

Initialize a new thread.

Initializes a new thread. The thread is left dormant until it is actually started by xnthread start().

6.43 Thread services 219

Parameters

thread	The address of a thread descriptor the nucleus will use to store the thread-specific
	data. This descriptor must always be valid while the thread is active therefore it must
	be allocated in permanent memory.

Warning

Some architectures may require the descriptor to be properly aligned in memory; this is an additional reason for descriptors not to be laid in the program stack where alignement constraints might not always be satisfied.

Parameters

attr	A pointer to an attribute block describing the initial properties of the new thread.
	Members of this structure are defined as follows:

- name: An ASCII string standing for the symbolic name of the thread. This name is copied to a
 safe place into the thread descriptor. This name might be used in various situations by the nucleus
 for issuing human-readable diagnostic messages, so it is usually a good idea to provide a sensible
 value here. NULL is fine though and means "anonymous".
- flags: A set of creation flags affecting the operation. The following flags can be part of this bitmask, each of them affecting the nucleus behaviour regarding the created thread:
 - XNSUSP creates the thread in a suspended state. In such a case, the thread shall be explicitly resumed using the xnthread_resume() service for its execution to actually begin, additionally to issuing xnthread_start() for it. This flag can also be specified when invoking xnthread_ start() as a starting mode.
- XNUSER shall be set if thread will be mapped over an existing user-space task. Otherwise, a new kernel host task is created, then paired with the new Xenomai thread.
- XNFPU (enable FPU) tells the nucleus that the new thread may use the floating-point unit. XNFPU is implicitly assumed for user-space threads even if not set in *flags*.
- affinity: The processor affinity of this thread. Passing CPU_MASK_ALL means "any cpu" from the allowed core affinity mask (cobalt_cpu_affinity). Passing an empty set is invalid.

Parameters

sched_class	The initial scheduling class the new thread should be assigned to.
sched_param	The initial scheduling parameters to set for the new thread; sched_param must be
	valid within the context of sched_class.

Returns

0 is returned on success. Otherwise, the following error code indicates the cause of the failure:

-EINVAL is returned if attr->flags has invalid bits set, or attr->affinity is invalid (e.g. empty).

Tags

secondary-only

References XNFPU, XNSUSP, and XNUSER.

Referenced by rtdm_task_init().

220 Module Documentation

6.43.2.6 int xnthread_join (struct xnthread * thread, bool uninterruptible)

Join with a terminated thread.

This service waits for *thread* to terminate after a call to xnthread_cancel(). If that thread has already terminated or is dormant at the time of the call, then xnthread_join() returns immediately.

xnthread join() adapts to the calling context (primary or secondary).

Parameters

thread	The descriptor address of the thread to join with.
uninterruptible	Boolean telling whether the service should wait for completion uninterruptible if
	called from secondary mode.

Returns

0 is returned on success. Otherwise, the following error codes indicate the cause of the failure:

- -EDEADLK is returned if the current thread attempts to join itself.
- -EINTR is returned if the current thread was unblocked while waiting for thread to terminate.
- -EBUSY indicates that another thread is already waiting for thread to terminate.

Tags

task-unrestricted, might-switch

References XNBREAK, XNDORMANT, XNJOINED, XNRMID, xnsynch_sleep_on(), and xnthread_ current().

Referenced by rtdm_task_join().

6.43.2.7 int xnthread_map (struct xnthread * thread, struct completion * done)

Create a shadow thread context over a kernel task.

This call maps a nucleus thread to the "current" Linux task running in kernel space. The priority and scheduling class of the underlying Linux task are not affected; it is assumed that the caller did set them appropriately before issuing the shadow mapping request.

This call immediately moves the calling kernel thread to the Xenomai domain.

Parameters

thread	The descriptor address of the new shadow thread to be mapped to "current". This
	descriptor must have been previously initialized by a call to xnthread_init().
done	A completion object to be signaled when thread is fully mapped over the current
	Linux context, waiting for xnthread_start().

Returns

0 is returned on success. Otherwise:

- -ERESTARTSYS is returned if the current Linux task has received a signal, thus preventing the final migration to the Xenomai domain (i.e. in order to process the signal in the Linux domain). This error should not be considered as fatal.
- -EPERM is returned if the shadow thread has been killed before the current task had a chance to return to the caller. In such a case, the real-time mapping operation has failed globally, and no Xenomai resource remains attached to it.

6.43 Thread services 221

- -EINVAL is returned if the thread control block bears the XNUSER bit.
- -EBUSY is returned if either the current Linux task or the associated shadow thread is already involved in a shadow mapping.

Tags

secondary-only, might-switch

References XNDORMANT, XNMAPPED, XNRELAX, xnthread_current(), xnthread_harden(), xnthread ← _resume(), xnthread_suspend(), xnthread_test_cancel(), and XNUSER.

6.43.2.8 int xnthread_migrate (int cpu)

Migrate the current thread.

This call makes the current thread migrate to another (real-time) CPU if its affinity allows it. This call is available from primary mode only.

Parameters

сри	The destination CPU.

Return values

	if the thread could migrate;
-EPERM	if the calling context is invalid, or the scheduler is locked.
-EINVAL	if the current thread affinity forbids this migration.

Tags

primary-only, might-switch

References __xntimer_migrate(), XNMOVED, xnsched_run(), and xnthread_current().

6.43.2.9 void xnthread_relax (int notify, int reason)

Switch a shadow thread back to the Linux domain.

This service yields the control of the running shadow back to Linux. This is obtained by suspending the shadow and scheduling a wake up call for the mated user task inside the Linux domain. The Linux task will resume on return from xnthread_suspend() on behalf of the root thread.

Parameters

notify	A boolean flag indicating whether threads monitored from secondary mode switches
	should be sent a SIGDEBUG signal. For instance, some internal operations like task
	exit should not trigger such signal.
reason	The reason to report along with the SIGDEBUG signal.

Tags

primary-only, might-switch

Note

"current" is valid here since the shadow runs with the properties of the Linux task.

References splmax, splnone, XNMOVED, XNRELAX, xnthread_current(), xnthread_suspend(), XNU⇔ SER, and XNWARN.

Referenced by xnthread_harden().

6.43.2.10 void xnthread resume (struct xnthread * thread, int mask)

Resume a thread.

Resumes the execution of a thread previously suspended by one or more calls to xnthread_suspend(). This call removes a suspensive condition affecting the target thread. When all suspensive conditions are gone, the thread is left in a READY state at which point it becomes eligible anew for scheduling.

Parameters

thread	The descriptor address of the resumed thread.
mask	The suspension mask specifying the suspensive condition to remove from the
	thread's wait mask. Possible values usable by the caller are:

- XNSUSP. This flag removes the explicit suspension condition. This condition might be additive to the XNPEND condition.
- XNDELAY. This flag removes the counted delay wait condition.
- XNPEND. This flag removes the resource wait condition. If a watchdog is armed, it is automatically disarmed by this call. Unlike the two previous conditions, only the current thread can set this condition for itself, i.e. no thread can force another one to pend on a resource.

When the thread is eventually resumed by one or more calls to xnthread_resume(), the caller of xnthread_suspend() in the awakened thread that suspended itself should check for the following bits in its own information mask to determine what caused its wake up:

- XNRMID means that the caller must assume that the pended synchronization object has been destroyed (see xnsynch flush()).
- XNTIMEO means that the delay elapsed, or the watchdog went off before the corresponding synchronization object was signaled.
- XNBREAK means that the wait has been forcibly broken by a call to xnthread_unblock().

Tags

unrestricted, might-switch

References XNDELAY, XNHELD, XNPEND, XNREADY, and xntimer stop().

Referenced by xnsynch_flush(), xnsynch_wakeup_one_sleeper(), xnsynch_wakeup_this_sleeper(), xnthread_cancel(), xnthread_map(), xnthread_start(), and xnthread_unblock().

6.43.2.11 int xnthread_set_mode (int clrmask, int setmask)

Change control mode of the current thread.

Change the control mode of the current thread. The control mode affects several behaviours of the Cobalt core regarding this thread.

Parameters

clrmask	Clears the corresponding bits from the control mode before setmask is applied. The
	scheduler lock held by the current thread can be forcibly released by passing the
	XNLOCK bit in this mask. In this case, the lock nesting count is also reset to zero.

6.43 Thread services 223

setmask | The new thread mode. The following flags may be set in this bitmask:

 XNLOCK makes the current thread non-preemptible by other threads. Unless XNTRAPLB is also set for the thread, the latter may still block, dropping the lock temporarily, in which case, the lock will be reacquired automatically when the thread resumes execution.

- XNWARN enables debugging notifications for the current thread. A SIGDEBUG (Linux-originated) signal is sent when the following atypical or abnormal behavior is detected:
 - the current thread switches to secondary mode. Such notification comes in handy for detecting spurious relaxes.
 - CONFIG_XENO_OPT_DEBUG_MUTEX_RELAXED is enabled in the kernel configuration, and the current thread is sleeping on a Cobalt mutex currently owned by a thread running in secondary mode, which reveals a priority inversion.
 - the current thread is about to sleep while holding a Cobalt mutex, and CONFIG_XENO_O

 PT_DEBUG_MUTEX_SLEEP is enabled in the kernel configuration. Blocking for acquiring a mutex does not trigger such a signal though.
 - the current thread has both XNTRAPLB and XNLOCK set, and attempts to block on a Cobalt service, which would cause a lock break.
- XNTRAPLB disallows breaking the scheduler lock. In the default case, a thread which holds the
 scheduler lock is allowed to drop it temporarily for sleeping. If this mode bit is set, such thread
 would return immediately with XNBREAK set from xnthread_suspend(). If XNWARN is set for the
 current thread, SIGDEBUG is sent in addition to raising the break condition.

Tags

primary-only, might-switch

Note

Setting *clrmask* and *setmask* to zero leads to a nop, in which case xnthread_set_mode() returns the current mode.

References XNLBALERT, XNLOCK, and xnsched run().

6.43.2.12 int xnthread_set_periodic (struct xnthread * thread, xnticks_t idate, xntmode_t timeout_mode, xnticks_t period)

Make a thread periodic.

Make a thread periodic by programming its first release point and its period in the processor time line. Subsequent calls to xnthread_wait_period() will delay the thread until the next periodic release point in the processor timeline is reached.

Parameters

thread	The core thread to make periodic. If NULL, the current thread is assumed.
idate	The initial (absolute) date of the first release point, expressed in nanoseconds. The
	affected thread will be delayed by the first call to xnthread_wait_period() until this
	point is reached. If idate is equal to XN_INFINITE, the first release point is set to
	period nanoseconds after the current date. In the latter case, timeout_mode is not
	considered and can have any valid value.

timeout_mode	The mode of the <i>idate</i> parameter. It can either be set to XN_ABSOLUTE or XN_←
	REALTIME with <i>idate</i> different from XN_INFINITE (see also xntimer_start()).
period	The period of the thread, expressed in nanoseconds. As a side-effect, passing XN⊷
	_INFINITE attempts to stop the thread's periodic timer; in the latter case, the routine
	always exits succesfully, regardless of the previous state of this timer.

Returns

0 is returned upon success. Otherwise:

- -ETIMEDOUT is returned idate is different from XN INFINITE and represents a date in the past.
- -EINVAL is returned if period is different from XN_INFINITE but shorter than the scheduling latency
 value for the target system, as available from /proc/xenomai/latency. -EINVAL is also returned if
 timeout_mode is not compatible with idate, such as XN_RELATIVE with idate different from XN
 INFINITE.
- -EPERM is returned if thread is NULL, but the caller is not a Xenomai thread.

Tags

task-unrestricted

References xnsched::cpu, xnthread_current(), xntimer_start(), and xntimer_stop(). Referenced by rtdm task init().

6.43.2.13 int xnthread_set_schedparam (struct xnthread * thread, struct xnsched_class * sched_class, const union xnsched_policy_param * sched_param)

Change the base scheduling parameters of a thread.

Changes the base scheduling policy and paramaters of a thread. If the thread is currently blocked, waiting in priority-pending mode (XNSYNCH_PRIO) for a synchronization object to be signaled, the nucleus will attempt to reorder the object's wait queue so that it reflects the new sleeper's priority, unless the XNSYNCH_DREORD flag has been set for the pended object.

Parameters

thread	The descriptor address of the affected thread. See note.
sched_class	The new scheduling class the thread should be assigned to.
sched_param	The scheduling parameters to set for the thread; sched_param must be valid within
	the context of sched_class.

It is absolutely required to use this service to change a thread priority, in order to have all the needed housekeeping chores correctly performed. i.e. Do *not* call xnsched_set_policy() directly or worse, change the thread.cprio field by hand in any case.

Returns

0 is returned on success. Otherwise, a negative error code indicates the cause of a failure that happened in the scheduling class implementation for *sched_class*. Invalid parameters passed into *sched_param* are common causes of error.

Side effects

• This service does not call the rescheduling procedure but may affect the state of the runnable queue for the previous and new scheduling classes.

6.43 Thread services 225

• Assigning the same scheduling class and parameters to a running or ready thread moves it to the end of the runnable queue, thus causing a manual round-robin.

Tags

task-unregistred

Note

The changes only apply to the Xenomai scheduling parameters for *thread*. There is no propagation/translation of such changes to the Linux scheduler for the task mated to the Xenomai target thread.

6.43.2.14 int xnthread set slice (struct xnthread * thread, xnticks t quantum)

Set thread time-slicing information.

Update the time-slicing information for a given thread. This service enables or disables round-robin scheduling for the thread, depending on the value of *quantum*. By default, times-slicing is disabled for a new thread initialized by a call to xnthread init().

Parameters

thread	The descriptor address of the affected thread.
quantum	The time quantum assigned to the thread expressed in nanoseconds. If quantum
	is different from XN_INFINITE, the time-slice for the thread is set to that value and
	its current time credit is refilled (i.e. the thread is given a full time-slice to run next).
	Otherwise, if <i>quantum</i> equals XN_INFINITE, time-slicing is stopped for that thread.

Returns

0 is returned upon success. Otherwise, -EINVAL is returned if quantum is not XN_INFINITE and:

- the base scheduling class of the target thread does not support time-slicing,
- quantum is smaller than the master clock gravity for a user thread, which denotes a spurious value.

Tags

task-unrestricted

References xnsched::curr, xnsched::rrbtimer, XNRRB, xntimer start(), and xntimer stop().

6.43.2.15 int xnthread_start (struct xnthread * thread, const struct xnthread_start_attr * attr)

Start a newly created thread.

Starts a (newly) created thread, scheduling it for the first time. This call releases the target thread from the XNDORMANT state. This service also sets the initial mode for the new thread.

Parameters

thread	The descriptor address of the started thread which must have been previously ini-
	tialized by a call to xnthread_init().

attr A pointer to an attribute block describing the execution properties of the new thread.

Members of this structure are defined as follows:

- mode: The initial thread mode. The following flags can be part of this bitmask, each of them affecting the nucleus behaviour regarding the started thread:
 - XNLOCK causes the thread to lock the scheduler when it starts. The target thread will have
 to call the xnsched_unlock() service to unlock the scheduler. A non-preemptible thread may
 still block, in which case, the lock is reasserted when the thread is scheduled back in.
 - XNSUSP makes the thread start in a suspended state. In such a case, the thread will have to be explicitly resumed using the xnthread_resume() service for its execution to actually begin.
- entry: The address of the thread's body routine. In other words, it is the thread entry point.
- cookie: A user-defined opaque cookie the nucleus will pass to the emerging thread as the sole argument of its entry point.

Return values

0	if thread could be started;
-EBUSY	if thread was not dormant or stopped;

Tags

task-unrestricted, might-switch

References XNDORMANT, XNLOCK, xnsched_run(), XNSUSP, and xnthread_resume(). Referenced by rtdm_task_init().

6.43.2.16 void xnthread_suspend (struct xnthread * thread, int mask, xnticks_t timeout, xntmode_t timeout mode, struct xnsynch * wchan)

Suspend a thread.

Suspends the execution of a thread according to a given suspensive condition. This thread will not be eligible for scheduling until it all the pending suspensive conditions set by this service are removed by one or more calls to xnthread resume().

Parameters

thread	The descriptor address of the suspended thread.
mask	The suspension mask specifying the suspensive condition to add to the thread's
	wait mask. Possible values usable by the caller are:

- XNSUSP. This flag forcibly suspends a thread, regardless of any resource to wait for. A reverse call
 to xnthread_resume() specifying the XNSUSP bit must be issued to remove this condition, which is
 cumulative with other suspension bits.wchan should be NULL when using this suspending mode.
- XNDELAY. This flags denotes a counted delay wait (in ticks) which duration is defined by the value of the timeout parameter.
- XNPEND. This flag denotes a wait for a synchronization object to be signaled. The wchan argument must points to this object. A timeout value can be passed to bound the wait. This suspending mode should not be used directly by the client interface, but rather through the xnsynch_sleep_on() call.

6.43 Thread services 227

Parameters

timeout	The timeout which may be used to limit the time the thread pends on a resource.
	This value is a wait time given in nanoseconds. It can either be relative, absolute
	monotonic, or absolute adjustable depending on timeout_mode.

Passing XN_INFINITE **and** setting *timeout_mode* to XN_RELATIVE specifies an unbounded wait. All other values are used to initialize a watchdog timer. If the current operation mode of the system timer is oneshot and *timeout* elapses before xnthread_suspend() has completed, then the target thread will not be suspended, and this routine leads to a null effect.

Parameters

timeout_mode	The mode of the timeout parameter. It can either be set to XN_RELATIVE, XN_A
	BSOLUTE, or XN_REALTIME (see also xntimer_start()).
wchan	The address of a pended resource. This parameter is used internally by the syn-
	chronization object implementation code to specify on which object the suspended
	thread pends. NULL is a legitimate value when this parameter does not apply to the
	current suspending mode (e.g. XNSUSP).

Note

If the target thread has received a Linux-originated signal, then this service immediately exits without suspending the thread, but raises the XNBREAK condition in its information mask.

Tags

unrestricted, might-switch

References xnsched::curr, splmax, XNBREAK, XNDELAY, XNHELD, XNKICKED, XNLBALERT, XNR ← EADY, XNRELAX, XNRMID, XNROBBED, XNSUSP, XNTIMEO, xntimer_start(), XNTRAPLB, XNUSER, XNWAKEN, and XNWARN.

Referenced by xnsynch_acquire(), xnsynch_sleep_on(), xnthread_map(), xnthread_relax(), and xnthread wait period().

6.43.2.17 void xnthread_test_cancel (void) [inline], [static]

Introduce a thread cancellation point.

Terminates the current thread if a cancellation request is pending for it, i.e. if xnthread_cancel() was called.

Tags

mode-unrestricted

References XNCANCELD, and xnthread current().

Referenced by xnthread_cancel(), xnthread_harden(), and xnthread_map().

6.43.2.18 int xnthread_unblock (struct xnthread * thread)

Unblock a thread.

Breaks the thread out of any wait it is currently in. This call removes the XNDELAY and XNPEN← D suspensive conditions previously put by xnthread_suspend() on the target thread. If all suspensive conditions are gone, the thread is left in a READY state at which point it becomes eligible anew for scheduling.

Parameters

thread The descriptor address of the unblocked thread.

This call neither releases the thread from the XNSUSP, XNRELAX, XNDORMANT or XNHELD suspensive conditions.

When the thread resumes execution, the XNBREAK bit is set in the unblocked thread's information mask. Unblocking a non-blocked thread is perfectly harmless.

Returns

non-zero is returned if the thread was actually unblocked from a pending wait state, 0 otherwise.

Tags

unrestricted, might-switch

References XNBREAK, XNDELAY, XNPEND, and xnthread resume().

6.43.2.19 int xnthread wait period (unsigned long * overruns r)

Wait for the next periodic release point.

Make the current thread wait for the next periodic release point in the processor time line.

Parameters

overruns_r	If non-NULL, <i>overruns_r</i> must be a pointer to a memory location which will be written
	with the count of pending overruns. This value is copied only when xnthread_wait_←
	period() returns -ETIMEDOUT or success; the memory location remains unmodified
	otherwise. If NULL, this count will never be copied back.

Returns

0 is returned upon success; if *overruns_r* is valid, zero is copied to the pointed memory location. Otherwise:

- -EWOULDBLOCK is returned if xnthread_set_periodic() has not previously been called for the calling thread.
- -EINTR is returned if xnthread_unblock() has been called for the waiting thread before the next periodic release point has been reached. In this case, the overrun counter is reset too.
- -ETIMEDOUT is returned if the timer has overrun, which indicates that one or more previous release points have been missed by the calling thread. If *overruns_r* is valid, the count of pending overruns is copied to the pointed memory location.

Tags

primary-only, might-switch

References XNBREAK, XNDELAY, xnthread_current(), xnthread_suspend(), and xntimer_get_coverruns().

6.44 Timer services 229

6.44 Timer services

The Xenomai timer facility depends on a clock source (xnclock) for scheduling the next activation times. Collaboration diagram for Timer services:



Functions

void xntimer_destroy (struct xntimer *timer)

Release a timer object.

static xnticks t xntimer interval (struct xntimer *timer)

Return the timer interval value.

• int xntimer start (struct xntimer *timer, xnticks t value, xnticks t interval, xntmode t mode)

Arm a timer.

xnticks t xntimer get date (struct xntimer *timer)

Return the absolute expiration date.

xnticks_t xntimer_get_timeout (struct xntimer *timer)

Return the relative expiration date.

• static void xntimer_stop (struct xntimer *timer)

Disarm a timer.

 void xntimer_init (struct xntimer *timer, struct xnclock *clock, void(*handler)(struct xntimer *timer), struct xnsched *sched, int flags)

Initialize a timer object.

void __xntimer_migrate (struct xntimer *timer, struct xnsched *sched)

Migrate a timer.

unsigned long long xntimer_get_overruns (struct xntimer *timer, xnticks_t now)

Get the count of overruns for the last tick.

static int program htick shot (unsigned long delay, struct clock_event_device *cdev)

Program next host tick as a Xenomai timer event.

static void switch_htick_mode (enum clock_event_mode mode, struct clock_event_device *cdev)

Tick mode switch emulation callback.

int xntimer_grab_hardware (void)

Grab the hardware timer on all real-time CPUs.

void xntimer_release_hardware (void)

Release hardware timers.

6.44.1 Detailed Description

The Xenomai timer facility depends on a clock source (xnclock) for scheduling the next activation times.

The core provides and depends on a monotonic clock source (nkclock) with nanosecond resolution, driving the platform timer hardware exposed by the interrupt pipeline.

6.44.2 Function Documentation

6.44.2.1 void __xntimer_migrate (struct xntimer * timer, struct xnsched * sched)

Migrate a timer.

This call migrates a timer to another cpu. In order to avoid pathological cases, it must be called from the CPU to which *timer* is currently attached.

Parameters

timer	The address of the timer object to be migrated.
sched	The address of the destination per-CPU scheduler slot.

Tags

unrestricted, atomic-entry

References xntimer_stop().

Referenced by xnthread_migrate().

6.44.2.2 static int program_htick_shot (unsigned long delay, struct clock_event_device * cdev) [static]

Program next host tick as a Xenomai timer event.

Program the next shot for the host tick on the current CPU. Emulation is done using a nucleus timer attached to the master timebase.

Parameters

delay	The time delta from the current date to the next tick, expressed as a count of
	nanoseconds.
cdev	An pointer to the clock device which notifies us.

Tags

unrestricted

References xnsched::htimer, and xntimer_start().

6.44.2.3 void switch_htick_mode (enum clock_event_mode mode, struct clock_event_device * cdev) [static]

Tick mode switch emulation callback.

Changes the host tick mode for the tick device of the current CPU.

Parameters

mode The new mode to switch to. The possible values are:
--

- CLOCK_EVT_MODE_ONESHOT, for a switch to oneshot mode.
- CLOCK_EVT_MODE_PERIODIC, for a switch to periodic mode. The current implementation for the generic clockevent layer Linux exhibits should never downgrade from a oneshot to a periodic tick mode, so this mode should not be encountered. This said, the associated code is provided, basically for illustration purposes.

6.44 Timer services 231

• CLOCK_EVT_MODE_SHUTDOWN, indicates the removal of the current tick device. Normally, the nucleus only interposes on tick devices which should never be shut down, so this mode should not be encountered.

Parameters

cdev An opaque pointer to the clock device which notifies us.

Tags

unrestricted

Note

GENERIC_CLOCKEVENTS is required from the host kernel.

References xnsched::htimer, xntimer_start(), and xntimer_stop().

6.44.2.4 void xntimer_destroy (struct xntimer * timer)

Release a timer object.

Destroys a timer. After it has been destroyed, all resources associated with the timer have been released. The timer is automatically deactivated before deletion if active on entry.

Parameters

timer	The address of a valid timer descriptor.	

Tags

unrestricted

References xntimer_stop().

Referenced by rtdm_timer_destroy().

6.44.2.5 xnticks_t xntimer_get_date (struct xntimer * timer)

Return the absolute expiration date.

Return the next expiration date of a timer as an absolute count of nanoseconds.

Parameters

timer The address of a valid timer descriptor.

Returns

The expiration date in nanoseconds. The special value XN_INFINITE is returned if *timer* is currently disabled.

Tags

unrestricted, atomic-entry

232 Module Documentation

6.44.2.6 unsigned long long xntimer_get_overruns (struct xntimer * timer, xnticks_t now)

Get the count of overruns for the last tick.

This service returns the count of pending overruns for the last tick of a given timer, as measured by the difference between the expected expiry date of the timer and the date *now* passed as argument.

6.44 Timer services 233

Parameters

timer	The address of a valid timer descriptor.
now	current date (as xnclock_read_raw(xntimer_clock(timer)))

Returns

the number of overruns of timer at date now

Tags

unrestricted, atomic-entry

Referenced by xnthread_wait_period().

6.44.2.7 xnticks_t xntimer_get_timeout (struct xntimer * timer)

Return the relative expiration date.

This call returns the count of nanoseconds remaining until the timer expires.

Parameters

Lina au	The address of a valid timer descriptor
timer	I he address of a valid timer descriptor.
•	The district of the state of th

Returns

The count of nanoseconds until expiry. The special value XN_INFINITE is returned if *timer* is currently disabled. It might happen that the timer expires when this service runs (even if the associated handler has not been fired yet); in such a case, 1 is returned.

Tags

unrestricted, atomic-entry

6.44.2.8 int xntimer_grab_hardware (void)

Grab the hardware timer on all real-time CPUs.

xntimer grab hardware() grabs and tunes the hardware timer for all real-time CPUs.

Host tick emulation is performed for sharing the clock chip between Linux and Xenomai.

Returns

a positive value is returned on success, representing the duration of a Linux periodic tick expressed as a count of nanoseconds; zero should be returned when the Linux kernel does not undergo periodic timing on the given CPU (e.g. oneshot mode). Otherwise:

- -EBUSY is returned if the hardware timer has already been grabbed. xntimer_release_hardware() must be issued before xntimer_grab_hardware() is called again.
- -ENODEV is returned if the hardware timer cannot be used. This situation may occur after the kernel disabled the timer due to invalid calibration results; in such a case, such hardware is unusable for any timing duties.

Tags

secondary-only

References xnsched::cpu, xnsched::htimer, xnintr_init(), xntimer_start(), and xntimer_stop().

234 Module Documentation

6.44.2.9 void xntimer_init (struct xntimer * timer, struct xnclock * clock, void(*)(struct xntimer *timer) handler, struct xnsched * sched, int flags)

Initialize a timer object.

Creates a timer. When created, a timer is left disarmed; it must be started using xntimer_start() in order to be activated.

Parameters

timer	The address of a timer descriptor the nucleus will use to store the object-specific data. This descriptor must always be valid while the object is active therefore it must be allocated in permanent memory.
clock	The clock the timer relates to. Xenomai defines a monotonic system clock, with nanosecond resolution, named nkclock. In addition, external clocks driven by other tick sources may be created dynamically if CONFIG_XENO_OPT_EXTCLOCK is defined.
handler	The routine to call upon expiration of the timer.
sched	An optional pointer to the per-CPU scheduler slot the new timer is affine to. If non-NULL, the timer will fire on the CPU <i>sched</i> is bound to, otherwise it will fire either on the current CPU if real-time, or on the first real-time CPU.
flags	A set of flags describing the timer. The valid flags are:

• XNTIMER_NOBLCK, the timer won't be frozen while GDB takes over control of the application.

A set of clock gravity hints can be passed via the *flags* argument, used for optimizing the built-in heuristics aimed at latency reduction:

- XNTIMER IGRAVITY, the timer activates a leaf timer handler.
- XNTIMER_KGRAVITY, the timer activates a kernel thread.
- XNTIMER_UGRAVITY, the timer activates a user-space thread.

There is no limitation on the number of timers which can be created/active concurrently.

Tags

unrestricted

6.44.2.10 xnticks t xntimer interval (struct xntimer * timer) [inline], [static]

Return the timer interval value.

Return the timer interval value in nanoseconds.

Parameters

timer	The address of a valid timer descriptor.

Returns

The duration of a period in nanoseconds. The special value XN_INFINITE is returned if *timer* is currently disabled or one shot.

Tags

unrestricted, atomic-entry

6.44 Timer services 235

```
6.44.2.11 void xntimer_release_hardware (void)
```

Release hardware timers.

Releases hardware timers previously grabbed by a call to xntimer_grab_hardware().

Tags

secondary-only

References xnsched::cpu, and xnintr destroy().

6.44.2.12 int xntimer_start (struct xntimer * timer, xnticks_t value, xnticks_t interval, xntmode_t mode)

Arm a timer.

Activates a timer so that the associated timeout handler will be fired after each expiration time. A timer can be either periodic or one-shot, depending on the reload value passed to this routine. The given timer must have been previously initialized.

A timer is attached to the clock specified in xntimer init().

Parameters

timer	The address of a valid timer descriptor.
value	The date of the initial timer shot, expressed in nanoseconds.
interval	The reload value of the timer. It is a periodic interval value to be used for repro-
	gramming the next timer shot, expressed in nanoseconds. If interval is equal to
	XN_INFINITE, the timer will not be reloaded after it has expired.
mode	The timer mode. It can be XN_RELATIVE if value shall be interpreted as a relative
	date, XN_ABSOLUTE for an absolute date based on the monotonic clock of the
	related time base (as returned my xnclock_read_monotonic()), or XN_REALTIME
	if the absolute date is based on the adjustable real-time date for the relevant clock
	(obtained from xnclock_read_realtime()).

Returns

0 is returned upon success, or -ETIMEDOUT if an absolute date in the past has been given. In such an event, the timer is nevertheless armed for the next shot in the timeline if *interval* is different from XN_INFINITE.

Tags

unrestricted, atomic-entry

Referenced by program_htick_shot(), rtdm_timer_start(), switch_htick_mode(), xnthread_set_periodic(), xnthread_set_slice(), xnthread_suspend(), and xntimer_grab_hardware().

```
6.44.2.13 int xntimer stop ( struct xntimer * timer ) [inline], [static]
```

Disarm a timer.

This service deactivates a timer previously armed using xntimer_start(). Once disarmed, the timer can be subsequently re-armed using the latter service.

Parameters

timer	The address of a valid timer descriptor.

Tags

unrestricted, atomic-entry


Referenced by __xntimer_migrate(), rtdm_timer_stop(), switch_htick_mode(), xnthread_resume(), xnthread_set_periodic(), xnthread_set_slice(), xntimer_destroy(), and xntimer_grab_hardware().

6.45 Virtual file services 237

6.45 Virtual file services

Virtual files provide a mean to export Xenomai object states to user-space, based on common kernel interfaces.

Collaboration diagram for Virtual file services:



Data Structures

struct xnvfile_lock_ops

Vfile locking operations.

struct xnvfile regular ops

Regular vfile operation descriptor.

struct xnvfile_regular_iterator

Regular vfile iterator.

struct xnvfile_snapshot_ops

Snapshot vfile operation descriptor.

struct xnvfile_rev_tag

Snapshot revision tag.

struct xnvfile_snapshot

Snapshot vfile descriptor.

struct xnvfile_snapshot_iterator

Snapshot-driven vfile iterator.

Functions

• int xnvfile_init_snapshot (const char *name, struct xnvfile_snapshot *vfile, struct xnvfile_directory *parent)

Initialize a snapshot-driven vfile.

int xnvfile_init_regular (const char *name, struct xnvfile_regular *vfile, struct xnvfile_directory *parent)

Initialize a regular vfile.

- int xnvfile_init_dir (const char *name, struct xnvfile_directory *vdir, struct xnvfile_directory *parent)

 Initialize a virtual directory entry.
- int xnvfile_init_link (const char *from, const char *to, struct xnvfile_link *vlink, struct xnvfile_
 directory *parent)

Initialize a virtual link entry.

• void xnvfile_destroy (struct xnvfile *vfile)

Removes a virtual file entry.

ssize t xnvfile get blob (struct xnvfile input *input, void *data, size t size)

Read in a data bulk written to the vfile.

• ssize_t xnvfile_get_string (struct xnvfile_input *input, char *s, size_t maxlen)

Read in a C-string written to the vfile.

ssize_t xnvfile_get_integer (struct xnvfile_input *input, long *valp)

Evaluate the string written to the vfile as a long integer.

Variables

- struct xnvfile_directory cobalt_vfroot
 Xenomai vfile root directory.
- struct xnvfile_directory cobalt_vfroot
 Xenomai vfile root directory.

6.45.1 Detailed Description

Virtual files provide a mean to export Xenomai object states to user-space, based on common kernel interfaces.

This encapsulation is aimed at:

- supporting consistent collection of very large record-based output, without encurring latency peaks for undergoing real-time activities.
- in the future, hiding discrepancies between linux kernel releases, regarding the proper way to export kernel object states to userland, either via the /proc interface or by any other mean.

This virtual file implementation offers record-based read support based on seq_files, single-buffer write support, directory and link handling, all visible from the /proc namespace.

The vfile support exposes four filesystem object types:

• snapshot-driven file (struct xnvfile_snapshot). This is commonly used to export real-time object states via the /proc filesystem. To minimize the latency involved in protecting the vfile routines from changes applied by real-time code on such objects, a snapshot of the data to output is first taken under proper locking, before the collected data is formatted and sent out in a lockless manner.

Because a large number of records may have to be output, the data collection phase is not strictly atomic as a whole, but only protected at record level. The vfile implementation can be notified of updates to the underlying data set, and restart the collection from scratch until the snapshot is fully consistent.

- regular sequential file (struct xnvfile_regular). This is basically an encapsulated sequential file
 object as available from the host kernel (i.e. seq_file), with a few additional features to make it
 more handy in a Xenomai environment, like implicit locking support and shortened declaration for
 simplest, single-record output.
- virtual link (struct xnvfile_link). This is a symbolic link feature integrated with the vfile semantics. The link target is computed dynamically at creation time from a user-given helper routine.
- virtual directory (struct xnvfile_directory). A directory object, which can be used to create a hierarchy for ordering a set of vfile objects.

6.45.2 Function Documentation

6.45.2.1 void xnvfile_destroy (struct xnvfile * vfile)

Removes a virtual file entry.

6.45 Virtual file services 239

Parameters

vfile	A pointer to the virtual file descriptor to remove.
-------	---

Tags

secondary-only

```
6.45.2.2 ssize t xnvfile get blob ( struct xnvfile input * input, void * data, size t size )
```

Read in a data bulk written to the vfile.

When writing to a vfile, the associated store() handler from the snapshot-driven vfile or regular vfile is called, with a single argument describing the input data. xnvfile_get_blob() retrieves this data as an untyped binary blob, and copies it back to the caller's buffer.

Parameters

input	A pointer to the input descriptor passed to the store() handler.
data	The address of the destination buffer to copy the input data to.
size	The maximum number of bytes to copy to the destination buffer. If size is larger than
	the actual data size, the input is truncated to size.

Returns

The number of bytes read and copied to the destination buffer upon success. Otherwise, a negative error code is returned:

· -EFAULT indicates an invalid source buffer address.

Tags

secondary-only

Referenced by xnvfile get integer(), and xnvfile get string().

```
6.45.2.3 ssize_t xnvfile_get_integer ( struct xnvfile_input * input, long * valp )
```

Evaluate the string written to the vfile as a long integer.

When writing to a vfile, the associated store() handler from the snapshot-driven vfile or regular vfile is called, with a single argument describing the input data. xnvfile_get_integer() retrieves and interprets this data as a long integer, and copies the resulting value back to *valp*.

The long integer can be expressed in decimal, octal or hexadecimal bases depending on the prefix found.

Parameters

input	A pointer to the input descriptor passed to the store() handler.
valp	The address of a long integer variable to receive the value.

Returns

The number of characters read while evaluating the input as a long integer upon success. Otherwise, a negative error code is returned:

• -EINVAL indicates a parse error on the input stream; the written text cannot be evaluated as a long integer.

240 Module Documentation

· -EFAULT indicates an invalid source buffer address.

Tags

secondary-only

References xnvfile_get_blob().

```
6.45.2.4 ssize t xnvfile get string ( struct xnvfile input * input, char * s, size t maxlen )
```

Read in a C-string written to the vfile.

When writing to a vfile, the associated store() handler from the snapshot-driven vfile or regular vfile is called, with a single argument describing the input data. xnvfile_get_string() retrieves this data as a null-terminated character string, and copies it back to the caller's buffer.

Parameters

input	A pointer to the input descriptor passed to the store() handler.
S	The address of the destination string buffer to copy the input data to.
maxlen	The maximum number of bytes to copy to the destination buffer, including the ending null character. If <i>maxlen</i> is larger than the actual string length, the input is truncated to <i>maxlen</i> .

Returns

The number of characters read upon success. Otherwise, a negative error code is returned:

· -EFAULT indicates an invalid source buffer address.

Tags

secondary-only

References xnvfile_get_blob().

6.45.2.5 int xnvfile_init_dir (const char * name, struct xnvfile_directory * vdir, struct xnvfile_directory * parent)

Initialize a virtual directory entry.

Parameters

name	The name which should appear in the pseudo-filesystem, identifying the vdir entry.
vdir	A pointer to the virtual directory descriptor to initialize.
parent	A pointer to a virtual directory descriptor standing for the parent directory of the new vdir. If NULL, the /proc root directory will be used. /proc/xenomai is mapped on the globally available <i>cobalt_vfroot</i> vdir.

Returns

0 is returned on success. Otherwise:

• -ENOMEM is returned if the virtual directory entry cannot be created in the /proc hierarchy.

Tags

secondary-only

6.45 Virtual file services 241

6.45.2.6 int xnvfile_init_link (const char * from, const char * to, struct xnvfile_link * vlink, struct xnvfile_directory * parent)

Initialize a virtual link entry.

Parameters

from	The name which should appear in the pseudo-filesystem, identifying the vlink entry.
to	The target file name which should be referred to symbolically by <i>name</i> .
vlink	A pointer to the virtual link descriptor to initialize.
parent	A pointer to a virtual directory descriptor standing for the parent directory of the new
	vlink. If NULL, the /proc root directory will be used. /proc/xenomai is mapped on the
	globally available <i>cobalt_vfroot</i> vdir.

Returns

0 is returned on success. Otherwise:

• -ENOMEM is returned if the virtual link entry cannot be created in the /proc hierarchy.

Tags

secondary-only

6.45.2.7 int xnvfile_init_regular (const char * name, struct xnvfile_regular * vfile, struct xnvfile directory * parent)

Initialize a regular vfile.

Parameters

name	The name which should appear in the pseudo-filesystem, identifying the vfile entry.	
vfile	A pointer to a vfile descriptor to initialize from. The following fields in this structure	
	should be filled in prior to call this routine:	

- .privsz is the size (in bytes) of the private data area to be reserved in the vfile iterator. A NULL value indicates that no private area should be reserved.
- entry.lockops is a pointer to a lockingdescriptor", defining the lock and unlock operations for the vfile. This pointer may be left to NULL, in which case no locking will be applied.
- .ops is a pointer to an operation descriptor.

Parameters

parent	A pointer to a virtual directory descriptor; the vfile entry will be created into this	
·	directory. If NULL, the /proc root directory will be used. /proc/xenomai is mapped	
	on the globally available <i>cobalt_vfroot</i> vdir.	

Returns

0 is returned on success. Otherwise:

• -ENOMEM is returned if the virtual file entry cannot be created in the /proc hierarchy.

Tags

secondary-only

6.45.2.8 int xnvfile_init_snapshot (const char * name, struct **xnvfile_snapshot** * vfile, struct xnvfile directory * parent)

Initialize a snapshot-driven vfile.

6.45 Virtual file services 243

Parameters

name	The name which should appear in the pseudo-filesystem, identifying the vfile entry.	
vfile	A pointer to a vfile descriptor to initialize from. The following fields in this structure	
	should be filled in prior to call this routine:	

- .privsz is the size (in bytes) of the private data area to be reserved in the vfile iterator. A NULL value indicates that no private area should be reserved.
- .datasz is the size (in bytes) of a single record to be collected by the next() handler from the operation descriptor.
- .tag is a pointer to a mandatory vfile revision tag structure (struct xnvfile_rev_tag). This tag will be
 monitored for changes by the vfile core while collecting data to output, so that any update detected
 will cause the current snapshot data to be dropped, and the collection to restart from the beginning.
 To this end, any change to the data which may be part of the collected records, should also invoke
 xnvfile_touch() on the associated tag.
- entry.lockops is a pointer to a lock descriptor, defining the lock and unlock operations for the vfile.
 This pointer may be left to NULL, in which case the operations on the nucleus lock (i.e. nklock) will be used internally around calls to data collection handlers (see operation descriptor).
- .ops is a pointer to an operation descriptor.

Parameters

parent	A pointer to a virtual directory descriptor; the vfile entry will be created into this
	directory. If NULL, the /proc root directory will be used. /proc/xenomai is mapped
	on the globally available <i>cobalt_vfroot</i> vdir.

Returns

0 is returned on success. Otherwise:

• -ENOMEM is returned if the virtual file entry cannot be created in the /proc hierarchy.

Tags

secondary-only

References xnvfile_snapshot_ops::store.

6.45.3 Variable Documentation

6.45.3.1 struct xnvfile directory cobalt vfroot

Xenomai vfile root directory.

This vdir maps the /proc/xenomai directory. It can be used to create a hierarchy of Xenomai-related vfiles under this root.

6.45.3.2 struct xnvfile directory cobalt vfroot

Xenomai vfile root directory.


This vdir maps the /proc/xenomai directory. It can be used to create a hierarchy of Xenomai-related vfiles under this root.

244 Module Documentation

6.46 Analogy framework

A RTDM-based interface for implementing DAQ card drivers.

Collaboration diagram for Analogy framework:



Modules

- Driver API
 Programming interface provided to DAQ card drivers.
- Analogy user API

6.46.1 Detailed Description


A RTDM-based interface for implementing DAQ card drivers.

6.47 Driver API 245

6.47 Driver API

Programming interface provided to DAQ card drivers.

Collaboration diagram for Driver API:



Modules

• Channels and ranges

Channels.

• Driver management services

Analogy driver registration / unregistration.

Subdevice management services

Subdevice declaration in a driver.

Buffer management services

Buffer management services.

- Interrupt management services
- Misc services

6.47.1 Detailed Description

Programming interface provided to DAQ card drivers.

6.48 Driver management services

Analogy driver registration / unregistration.

Collaboration diagram for Driver management services:



Functions

int a4l_register_drv (struct a4l_driver *drv)
 Register an Analogy driver.

• int a4l_unregister_drv (struct a4l_driver *drv)

Unregister an Analogy driver.

6.48.1 Detailed Description

Analogy driver registration / unregistration.

In a common Linux char driver, the developer has to register a fops structure filled with callbacks for read / write / mmap / ioctl operations.

Analogy drivers do not have to implement read / write / mmap / ioctl functions, these procedures are implemented in the Analogy generic layer. Then, the transfers between user-space and kernel-space are already managed. Analogy drivers work with commands and instructions which are some kind of more dedicated read / write operations. And, instead of registering a fops structure, a Analogy driver must register some a4l_driver structure.

6.48.2 Function Documentation

6.48.2.1 int a4l register drv (struct a4l driver * drv)

Register an Analogy driver.

After initialising a driver structure, the driver must be made available so as to be attached.

Parameters

in	drv	Driver descriptor structure

Returns

0 on success, otherwise negative error code.

References a4I_driver::board_name, and a4I_driver::list.

6.48.2.2 int a4l_unregister_drv (struct a4l_driver * drv)

Unregister an Analogy driver.

This function removes the driver descriptor from the Analogy driver list. The driver cannot be attached anymore.

Parameters

in	drv	Driver descriptor structure

Returns

0 on success, otherwise negative error code.

References a4I_driver::board_name, and a4I_driver::list.

248 Module Documentation

6.49 Subdevice management services

Subdevice declaration in a driver.

Collaboration diagram for Subdevice management services:



Functions

- struct a4l_subdevice * a4l_alloc_subd (int sizeof_priv, void(*setup)(struct a4l_subdevice *))
 Allocate a subdevice descriptor.
- int a4l_add_subd (struct a4l_device *dev, struct a4l_subdevice *subd)

 Add a subdevice to the driver descriptor.
- struct a4l_subdevice * a4l_get_subd (struct a4l_device *dev, int idx)
 Get a pointer to the subdevice descriptor referenced by its registration index.

Subdevices types

Flags to define the subdevice type

- #define A4L_SUBD_UNUSED (A4L_SUBD_MASK_SPECIAL|0x1)
 Unused subdevice.
- #define A4L SUBD AI (A4L SUBD MASK READ|0x2)

Analog input subdevice.

• #define A4L_SUBD_AO (A4L_SUBD_MASK_WRITE|0x4)

Analog output subdevice.

#define A4L_SUBD_DI (A4L_SUBD_MASK_READ|0x8)

Digital input subdevice.

• #define A4L_SUBD_DO (A4L_SUBD_MASK_WRITE|0x10)

Digital output subdevice.

• #define A4L_SUBD_DIO (A4L_SUBD_MASK_SPECIAL|0x20)

Digital input/output subdevice.

- #define A4L_SUBD_COUNTER (A4L_SUBD_MASK_SPECIAL|0x40)
 Counter subdevice.
- #define A4L_SUBD_TIMER (A4L_SUBD_MASK_SPECIAL|0x80)
 Timer subdevice.
- #define A4L_SUBD_MEMORY (A4L_SUBD_MASK_SPECIAL|0x100)
 Memory, EEPROM, DPRAM.
- #define A4L_SUBD_CALIB (A4L_SUBD_MASK_SPECIAL|0x200)
 - Calibration subdevice DACs.
- #define A4L_SUBD_PROC (A4L_SUBD_MASK_SPECIAL|0x400)

Processor, DSP.

#define A4L_SUBD_SERIAL (A4L_SUBD_MASK_SPECIAL|0x800)

Serial IO subdevice.

#define A4L SUBD TYPES

Mask which gathers all the types.

Subdevice features

Flags to define the subdevice's capabilities

#define A4L_SUBD_CMD 0x1000

The subdevice can handle command (i.e it can perform asynchronous acquisition)

• #define A4L SUBD MMAP 0x8000

The subdevice support mmap operations (technically, any driver can do it; however, the developer might want that his driver must be accessed through read / write.

Subdevice status

Flags to define the subdevice's status

• #define A4L SUBD BUSY NR 0

The subdevice is busy, a synchronous or an asynchronous acquisition is occuring.

#define A4L_SUBD_BUSY (1 << A4L_SUBD_BUSY_NR)

The subdevice is busy, a synchronous or an asynchronous acquisition is occuring.

#define A4L_SUBD_CLEAN_NR 1

The subdevice is about to be cleaned in the middle of the detach procedure.

#define A4L SUBD CLEAN (1 << A4L SUBD CLEAN NR)

The subdevice is busy, a synchronous or an asynchronous acquisition is occuring.

6.49.1 Detailed Description

Subdevice declaration in a driver.

The subdevice structure is the most complex one in the Analogy driver layer. It contains some description fields to fill and some callbacks to declare.

The description fields are:

- flags: to define the subdevice type and its capabilities;
- chan_desc: to describe the channels which compose the subdevice;
- rng_desc: to declare the usable ranges;

The functions callbakes are:

- do_cmd() and do_cmdtest(): to performe asynchronous acquisitions thanks to commands;
- cancel(): to abort a working asynchronous acquisition;
- munge(): to apply modifications on the data freshly acquired during an asynchronous transfer.
 Warning: using this feature with can significantly reduce the performances (if the munge operation is complex, it will trigger high CPU charge and if the acquisition device is DMA capable, many cache-misses and cache-replaces will occur (the benefits of the DMA controller will vanish);

- trigger(): optionnaly to launch an asynchronous acquisition;
- insn_read(), insn_write(), insn_bits(), insn_config(): to perform synchronous acquisition operations.

Once the subdevice is filled, it must be inserted into the driver structure thanks to a4l add subd().

6.49.2 Function Documentation

```
6.49.2.1 int a4l add subd ( struct a4l device * dev, struct a4l subdevice * subd )
```

Add a subdevice to the driver descriptor.

Once the driver descriptor structure is initialized, the function a4l_add_subd() must be used so to add some subdevices to the driver.

Parameters

in	dev	Device descriptor structure
in	subd	Subdevice descriptor structure

Returns

the index with which the subdevice has been registered, in case of error a negative error code is returned.

References a4l_subdevice::dev, a4l_subdevice::idx, and a4l_subdevice::list.

Allocate a subdevice descriptor.

This is a helper function so as to get a suitable subdevice descriptor

Parameters

in	sizeof_priv	Size of the subdevice's private data
in	setup	Setup function to be called after the allocation

Returns

the index with which the subdevice has been registered, in case of error a negative error code is returned.

References rtdm_malloc().

```
6.49.2.3 struct a4l subdevice* a4l get subd ( struct a4l device * dev, int idx )
```

Get a pointer to the subdevice descriptor referenced by its registration index.

This function is scarcely useful as all the drivers callbacks get the related subdevice descriptor as first argument. This function is not optimized, it goes through a linked list to get the proper pointer. So it must not be used in real-time context but at initialization / cleanup time (attach / detach).

Parameters

in	dev	Device descriptor structure
in	idx	Subdevice index

Returns

0 on success, otherwise negative error code.

6.50 Buffer management services

Buffer management services.

Collaboration diagram for Buffer management services:



Functions

• int a4l buf prepare absput (struct a4l subdevice *subd, unsigned long count)

Update the absolute count of data sent from the device to the buffer since the start of the acquisition and after the next DMA shot.

int a4l_buf_commit_absput (struct a4l_subdevice *subd, unsigned long count)

Set the absolute count of data which was sent from the device to the buffer since the start of the acquisition and until the last DMA shot.

• int a4l_buf_prepare_put (struct a4l_subdevice *subd, unsigned long count)

Set the count of data which is to be sent to the buffer at the next DMA shot.

int a4l_buf_commit_put (struct a4l_subdevice *subd, unsigned long count)

Set the count of data sent to the buffer during the last completed DMA shots.

• int a4l buf put (struct a4l subdevice *subd, void *bufdata, unsigned long count)

Copy some data from the device driver to the buffer.

• int a4l buf prepare absget (struct a4l subdevice *subd, unsigned long count)

Update the absolute count of data sent from the buffer to the device since the start of the acquisition and after the next DMA shot.

int a4l buf commit absget (struct a4l subdevice *subd, unsigned long count)

Set the absolute count of data which was sent from the buffer to the device since the start of the acquisition and until the last DMA shot.

• int a4l_buf_prepare_get (struct a4l_subdevice *subd, unsigned long count)

Set the count of data which is to be sent from the buffer to the device at the next DMA shot.

int a4l_buf_commit_get (struct a4l_subdevice *subd, unsigned long count)

Set the count of data sent from the buffer to the device during the last completed DMA shots.

int a4l buf get (struct a4l subdevice *subd, void *bufdata, unsigned long count)

Copy some data from the buffer to the device driver.

int a4l_buf_evt (struct a4l_subdevice *subd, unsigned long evts)

Signal some event(s) to a user-space program involved in some read / write operation.

unsigned long a4l_buf_count (struct a4l_subdevice *subd)

Get the data amount available in the Analogy buffer.

struct a4l_cmd_desc * a4l_get_cmd (struct a4l_subdevice *subd)

Get the current Analogy command descriptor.

• int a4l get chan (struct a4l subdevice *subd)

Get the channel index according to its type.

6.50.1 Detailed Description

Buffer management services.

The buffer is the key component of the Analogy infrastructure. It manages transfers between the user-space and the Analogy drivers thanks to generic functions which are described hereafter. Thanks to the buffer subsystem, the driver developer does not have to care about the way the user program retrieves or sends data.

To write a classical char driver, the developer has to fill a fops structure so as to provide transfer operations to the user program (read, write, ioctl and mmap if need be).

The Analogy infrastructure manages the whole interface with the userspace; the common read, write, mmap, etc. callbacks are generic Analogy functions. These functions manage (and perform, if need be) transfers between the user-space and an asynchronous buffer thanks to lockless mechanisms.

Consequently, the developer has to use the proper buffer functions in order to write / read acquired data into / from the asynchronous buffer.

Here are listed the functions:

- a4l_buf_prepare_(abs)put() and a4l_buf_commit_(abs)put()
- a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get()
- a4l_buf_put()
- a4l_buf_get()
- a4l_buf_evt().

The functions count might seem high; however, the developer needs a few of them to write a driver. Having so many functions enables to manage any transfer cases:

- If some DMA controller is available, there is no need to make the driver copy the acquired data into the asynchronous buffer, the DMA controller must directly trigger DMA shots into / from the buffer. In that case, a function a4l_buf_prepare_*() must be used so as to set up the DMA transfer and a function a4l buf commit *() has to be called to complete the transfer().
- For DMA controllers which need to work with global counter (the transferred data count since the beginning of the acquisition), the functions a4l_buf_*_abs_*() have been made available.
- If no DMA controller is available, the driver has to perform the copy between the hardware component and the asynchronous buffer. In such cases, the functions a4l_buf_get() and a4l_buf_put() are useful.

6.50.2 Function Documentation

```
6.50.2.1 int a4l_buf_commit_absget ( struct a4l_subdevice * subd, unsigned long count )
```

Set the absolute count of data which was sent from the buffer to the device since the start of the acquisition and until the last DMA shot.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The data count transferred to the device during the last DMA shot plus the data count which have been sent since the beginning of the acqui-
		sition

Returns

0 on success, otherwise negative error code.

References A4L SUBD BUSY NR, a4I subdevice::buf, and a4I subdevice::status.

6.50.2.2 int a4l buf commit absput (struct a4l subdevice * subd, unsigned long count)

Set the absolute count of data which was sent from the device to the buffer since the start of the acquisition and until the last DMA shot.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The data count transferred to the buffer during the last DMA shot plus
		the data count which have been sent / retrieved since the beginning of the acquisition
		the acquisition

Returns

0 on success, otherwise negative error code.

References A4L_SUBD_BUSY_NR, a4l_subdevice::buf, and a4l_subdevice::status.

6.50.2.3 int a4l buf commit get (struct a4l subdevice * subd, unsigned long count)

Set the count of data sent from the buffer to the device during the last completed DMA shots.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The amount of data transferred

Returns

0 on success, otherwise negative error code.

References A4L SUBD BUSY NR, a4I subdevice::buf, and a4I subdevice::status.

6.50.2.4 int a4l_buf_commit_put (struct a4l_subdevice * subd, unsigned long count)

Set the count of data sent to the buffer during the last completed DMA shots.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The amount of data transferred

Returns

0 on success, otherwise negative error code.

References A4L SUBD BUSY NR, a4I subdevice::buf, and a4I subdevice::status.

6.50.2.5 unsigned long a4l_buf_count (struct a4l_subdevice * subd)

Get the data amount available in the Analogy buffer.

Parameters

in	subd	Subdevice descriptor structure

Returns

the amount of data available in the Analogy buffer.

References A4L SUBD BUSY NR, a4I subdevice::buf, and a4I subdevice::status.

6.50.2.6 int a4l_buf_evt (struct a4l_subdevice * subd, unsigned long evts)

Signal some event(s) to a user-space program involved in some read / write operation.

The function a4l_buf_evt() is useful in many cases:

- To wake-up a process waiting for some data to read.
- To wake-up a process waiting for some data to write.
- To notify the user-process an error has occured during the acquistion.

Parameters

in	subd	Subdevice descriptor structure
in	evts	Some specific event to notify:
		 A4L_BUF_ERROR to indicate some error has occured during the transfer
		 A4L_BUF_EOA to indicate the acquisition is complete (this event is automatically set, it should not be used).

Returns

0 on success, otherwise negative error code.

References A4L_SUBD_BUSY_NR, a4l_subdevice::buf, and a4l_subdevice::status.

6.50.2.7 int a4l buf get (struct a4l subdevice * subd, void * bufdata, unsigned long count)

Copy some data from the buffer to the device driver.

The function a4l_buf_get() must copy data coming from the Analogy buffer to some acquisition device. This ring-buffer is an intermediate area between the device driver and the user-space program, which is supposed to provide the data to send to the device.

Parameters

in	subd	Subdevice descriptor structure
in	bufdata	The data buffer to copy into the Analogy buffer
in	count	The amount of data to copy

Returns

0 on success, otherwise negative error code.

References A4L_SUBD_BUSY_NR, a4l_subdevice::buf, and a4l_subdevice::status.

6.50.2.8 int a4l_buf_prepare_absget (struct a4l_subdevice * subd, unsigned long count)

Update the absolute count of data sent from the buffer to the device since the start of the acquisition and after the next DMA shot.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(absg)et() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The data count to be transferred during the next DMA shot plus the
		data count which have been copied since the start of the acquisition

Returns

0 on success, otherwise negative error code.

References A4L SUBD BUSY NR, a4I subdevice::buf, and a4I subdevice::status.

6.50.2.9 int a4l buf prepare absput (struct a4l subdevice * subd, unsigned long count)

Update the absolute count of data sent from the device to the buffer since the start of the acquisition and after the next DMA shot.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(absg)et() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The data count to be transferred during the next DMA shot plus the
		data count which have been copied since the start of the acquisition

Returns

0 on success, otherwise negative error code.

References A4L SUBD BUSY NR, a4I subdevice::buf, and a4I subdevice::status.

6.50.2.10 int a4l_buf_prepare_get (struct a4l_subdevice * subd, unsigned long count)

Set the count of data which is to be sent from the buffer to the device at the next DMA shot.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The data count to be transferred

Returns

0 on success, otherwise negative error code.

References A4L_SUBD_BUSY_NR, a4l_subdevice::buf, and a4l_subdevice::status.

6.50.2.11 int a4l buf prepare put (struct a4l subdevice * subd, unsigned long count)

Set the count of data which is to be sent to the buffer at the next DMA shot.

The functions a4l_buf_prepare_(abs)put(), a4l_buf_commit_(abs)put(), a4l_buf_prepare_(abs)get() and a4l_buf_commit_(abs)get() have been made available for DMA transfers. In such situations, no data copy is needed between the Analogy buffer and the device as some DMA controller is in charge of performing data shots from / to the Analogy buffer. However, some pointers still have to be updated so as to monitor the transfers.

Parameters

in	subd	Subdevice descriptor structure
in	count	The data count to be transferred

Returns

0 on success, otherwise negative error code.

References A4L_SUBD_BUSY_NR, a4l_subdevice::buf, and a4l_subdevice::status.

6.50.2.12 int a4l buf put (struct a4l subdevice * subd, void * bufdata, unsigned long count)

Copy some data from the device driver to the buffer.

The function a4l_buf_put() must copy data coming from some acquisition device to the Analogy buffer. This ring-buffer is an intermediate area between the device driver and the user-space program, which is supposed to recover the acquired data.

Parameters

in	subd	Subdevice descriptor structure
in	bufdata	The data buffer to copy into the Analogy buffer
in	count	The amount of data to copy

Returns

0 on success, otherwise negative error code.

References A4L_SUBD_BUSY_NR, a4l_subdevice::buf, and a4l_subdevice::status.

6.50.2.13 int a4l_get_chan (struct a4l_subdevice * subd)

Get the channel index according to its type.

Parameters

in	subd	Subdevice descriptor structure

Returns

the channel index.

References A4L_CHAN_GLOBAL_CHANDESC, a4l_get_cmd(), a4l_subdevice::buf, a4l_subdevice::chan_desc, a4l_cmd_desc::chan_desc, a4l_channels_desc::chans, a4l_channels_desc::mode, a4l-channel::nb_bits, and a4l_cmd_desc::nb_chan.

6.50.2.14 struct a4l_cmd_desc* a4l_get_cmd (struct a4l_subdevice * subd)

Get the current Analogy command descriptor.

Parameters

in	subd	Subdevice descriptor structure


Returns

the command descriptor.

Referenced by a4l_get_chan().

6.51 Interrupt management services

Collaboration diagram for Interrupt management services:



Functions

260

unsigned int a4l_get_irq (struct a4l_device *dev)

Get the interrupt number in use for a specific device.

• int a4l_request_irq (struct a4l_device *dev, unsigned int irq, a4l_irq_hdlr_t handler, unsigned long flags, void *cookie)

Register an interrupt handler for a specific device.

• int a4l_free_irq (struct a4l_device *dev, unsigned int irq)

Release an interrupt handler for a specific device.

6.51.1 Detailed Description

6.51.2 Function Documentation

6.51.2.1 int a4l_free_irq (struct a4l_device * dev, unsigned int irq)

Release an interrupt handler for a specific device.

Parameters

in	dev	Device descriptor structure
in	irq	Line number of the addressed IRQ

Returns

0 on success, otherwise negative error code.

6.51.2.2 unsigned int a4l_get_irq (struct a4l_device * dev)

Get the interrupt number in use for a specific device.

Parameters

_		
in	dev	Device descriptor structure

Returns

the line number used or A4L_IRQ_UNUSED if no interrupt is registered.

6.51.2.3 int a4l_request_irq (struct a4l_device * dev, unsigned int irq, a4l_irq_hdlr_t handler, unsigned long flags, void * cookie)

Register an interrupt handler for a specific device.

Parameters

262

in	dev	Device descriptor structure
in	irq	Line number of the addressed IRQ
in	handler	Interrupt handler
in	flags	Registration flags: RTDM_IRQTYPE_SHARED: enable IRQ-sharing with other drivers (Warning: real-time drivers and non-real-time drivers cannot share an interrupt line). RTDM_IRQTYPE_EDGE: mark IRQ as edge-triggered (Warning: this flag is meaningless in RTDM-less context). A4L_IRQ_DISABLED: keep IRQ disabled when calling the action handler (Warning: this flag is ignored in RTDM-enabled configuration).
		ianony.
in	cookie	Pointer to be passed to the interrupt handler on invocation


Returns

0 on success, otherwise negative error code.

6.52 Misc services 263

6.52 Misc services

Collaboration diagram for Misc services:



Functions

• unsigned long long a4l_get_time (void)

Get the absolute time in nanoseconds.

6.52.1 Detailed Description

6.52.2 Function Documentation

6.52.2.1 unsigned long long a4l_get_time (void)

Get the absolute time in nanoseconds.

Returns

the absolute time expressed in nanoseconds

References rtdm_clock_read().

6.53 Clocks and timers

Cobalt/POSIX clock and timer services.

Collaboration diagram for Clocks and timers:



Functions

• int clock getres (clockid t clock id, struct timespec *tp)

Get the resolution of the specified clock.

int clock_gettime (clockid_t clock_id, struct timespec *tp)

Read the specified clock.

int clock_settime (clockid_t clock_id, const struct timespec *tp)

Set the specified clock.

- int clock_nanosleep (clockid_t clock_id, int flags, const struct timespec *rqtp, struct timespec *rmtp)

 Sleep some amount of time.
- int nanosleep (const struct timespec *rqtp, struct timespec *rmtp)

Sleep some amount of time.

 int timer_create (clockid_t clockid, const struct sigevent *__restrict__ evp, timer_t *__restrict__ timerid)

Create a timer.

• int timer_delete (timer_t timerid)

Delete a timer object.

int timer_settime (timer_t timerid, int flags, const struct itimerspec *__restrict__ value, struct itimerspec *__restrict__ ovalue)

Start or stop a timer.

• int timer_gettime (timer_t timerid, struct itimerspec *value)

Get timer next expiration date and reload value.

• int timer_getoverrun (timer_t timerid)

Get expiration overruns count since the most recent timer expiration signal delivery.

6.53.1 Detailed Description

Cobalt/POSIX clock and timer services.

Cobalt supports three built-in clocks:

CLOCK_REALTIME maps to the nucleus system clock, keeping time as the amount of time since the Epoch, with a resolution of one nanosecond.

CLOCK_MONOTONIC maps to an architecture-dependent high resolution counter, so is suitable for measuring short time intervals. However, when used for sleeping (with clock_nanosleep()), the CLOC K_MONOTONIC clock has a resolution of one nanosecond, like the CLOCK_REALTIME clock.

6.53 Clocks and timers 265

CLOCK_MONOTONIC_RAW is Linux-specific, and provides monotonic time values from a hardware timer which is not adjusted by NTP. This is strictly equivalent to CLOCK_MONOTONIC with Cobalt, which is not NTP adjusted either.

In addition, external clocks can be dynamically registered using the cobalt_clock_register() service. These clocks are fully managed by Cobalt extension code, which should advertise each incoming tick by calling xnclock_tick() for the relevant clock, from an interrupt context.

Timer objects may be created with the timer_create() service using any of the built-in or external clocks. The resolution of these timers is clock-specific. However, built-in clocks all have nanosecond resolution, as specified for clock nanosleep().

See also

Specification.

6.53.2 Function Documentation

```
6.53.2.1 int clock getres ( clockid t clock id. struct timespec * tp )
```

Get the resolution of the specified clock.

This service returns, at the address res, if it is not NULL, the resolution of the clock clock id.

For both CLOCK_REALTIME and CLOCK_MONOTONIC, this resolution is the duration of one system clock tick. No other clock is supported.

Parameters

	clock identifier, either CLOCK_REALTIME or CLOCK_MONOTONIC;
tp	the address where the resolution of the specified clock will be stored on success.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, <i>clock_id</i> is invalid;

See also

Specification.

Tags

unrestricted

6.53.2.2 int clock gettime (clockid t clock id, struct timespec * tp)

Read the specified clock.

This service returns, at the address tp the current value of the clock clock id. If clock id is:

- CLOCK_REALTIME, the clock value represents the amount of time since the Epoch, with a precision of one system clock tick;
- CLOCK_MONOTONIC or CLOCK_MONOTONIC_RAW, the clock value is given by an architecture-dependent high resolution counter, with a precision independent from the system clock tick duration.

 CLOCK_HOST_REALTIME, the clock value as seen by the host, typically Linux. Resolution and precision depend on the host, but it is guaranteed that both, host and Cobalt, see the same information

Parameters

clock_id	clock identifier, either CLOCK_REALTIME, CLOCK_MONOTONIC, or CLOCK_H↔
	OST_REALTIME;
tp	the address where the value of the specified clock will be stored.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, <i>clock_id</i> is invalid.

See also

Specification.

Tags

unrestricted

Referenced by rt_task_set_periodic().

6.53.2.3 int clock_nanosleep (clockid_t clock_id, int flags, const struct timespec * rqtp, struct timespec * rmtp)

Sleep some amount of time.

This service suspends the calling thread until the wakeup time specified by rqtp, or a signal is delivered to the caller. If the flag TIMER_ABSTIME is set in the flags argument, the wakeup time is specified as an absolute value of the clock $clock_id$. If the flag TIMER_ABSTIME is not set, the wakeup time is specified as a time interval.

If this service is interrupted by a signal, the flag TIMER_ABSTIME is not set, and *rmtp* is not *NULL*, the time remaining until the specified wakeup time is returned at the address *rmtp*.

The resolution of this service is one system clock tick.

Parameters

clock_id clo	lock identifier, either CLOCK_REALTIME or CLOCK_MONOTONIC.
flags on	ne of:
	 0 meaning that the wakeup time rqtp is a time interval; TIMER_ABSTIME, meaning that the wakeup time is an absolute value of the clock clock_id.

6.53 Clocks and timers 267

ro	qtp	address of the wakeup time.
rn	ntp	address where the remaining time before wakeup will be stored if the service is
		interrupted by a signal.

Returns

0 on success;

an error number if:

- EPERM, the caller context is invalid;
- ENOTSUP, the specified clock is unsupported;
- EINVAL, the specified wakeup time is invalid;
- EINTR, this service was interrupted by a signal.

See also

Specification.

Tags

xthread-only, switch-primary

Referenced by nanosleep().

6.53.2.4 int clock_settime (clockid_t clock_id, const struct timespec * tp)

Set the specified clock.

This allow setting the CLOCK_REALTIME clock.

Parameters

clock_id	the id of the clock to be set, only CLOCK_REALTIME is supported.
tp	the address of a struct timespec specifying the new date.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, clock_id is not CLOCK_REALTIME;
	 EINVAL, the date specified by tp is invalid.

See also

Specification.

Tags

unrestricted

6.53.2.5 int nanosleep (const struct timespec * rqtp, struct timespec * rmtp)

Sleep some amount of time.

This service suspends the calling thread until the wakeup time specified by *rqtp*, or a signal is delivered. The wakeup time is specified as a time interval.

If this service is interrupted by a signal and *rmtp* is not *NULL*, the time remaining until the specified wakeup time is returned at the address *rmtp*.

The resolution of this service is one system clock tick.

6.53 Clocks and timers 269

Parameters

rqtp	address of the wakeup time.	
rmtp	address where the remaining time before wakeup will be stored if the service is	
	interrupted by a signal.	

Return values

0	on success;
-1	with errno set if:
	EPERM, the caller context is invalid;
	 EINVAL, the specified wakeup time is invalid;
	 EINTR, this service was interrupted by a signal.

See also

Specification.

Tags

xthread-only, switch-primary

References clock nanosleep().

```
6.53.2.6 int timer_create ( clockid_t clockid, const struct sigevent *__restrict__ evp, timer_t *__restrict__ timerid )
```

Create a timer.

This service creates a timer based on the clock *clockid*.

If *evp* is not *NULL*, it describes the notification mechanism used on timer expiration. Only thread-directed notification is supported (evp->sigev_notify set to *SIGEV_THREAD_ID*).

If evp is NULL, the current Cobalt thread will receive the notifications with signal SIGALRM.

The recipient thread is delivered notifications when it calls any of the sigwait(), sigtimedwait() or sigwait-info() services.

If this service succeeds, an identifier for the created timer is returned at the address *timerid*. The timer is unarmed until started with the timer_settime() service.

Parameters

clockid	clock used as a timing base;
evp	
timerid	address where the identifier of the created timer will be stored on success.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, the clock <i>clockid</i> is invalid;
	 EINVAL, the member sigev_notify of the sigevent structure at the address evp is not SIGEV_THREAD_ID;
	 EINVAL, the member sigev_signo of the sigevent structure is an invalid signal number;
	 EAGAIN, the maximum number of timers was exceeded, recompile with a larger value.

See also

Specification.

Tags

thread-unrestricted

Referenced by pthread_make_periodic_np().

6.53.2.7 int timer_delete (timer_t timerid)

Delete a timer object.

This service deletes the timer timerid.

Parameters

timerid	identifier of the timer to be removed;

Return values

0	on success;
-1	with errno set if:
	• EINVAL, timerid is invalid;
	EPERM, the timer <i>timerid</i> does not belong to the current process.

See also

Specification.

Tags

thread-unrestricted

6.53.2.8 int timer_getoverrun (timer_t timerid)

Get expiration overruns count since the most recent timer expiration signal delivery.

This service returns *timerid* expiration overruns count since the most recent timer expiration signal delivery. If this count is more than *DELAYTIMER_MAX* expirations, *DELAYTIMER_MAX* is returned.

6.53 Clocks and timers 271

Parameters

timerid	Timer identifier.

Returns

the overruns count on success;

- -1 with errno set if:
 - EINVAL, timerid is invalid;
 - EPERM, the timer timerid does not belong to the current process.

See also

Specification.

Tags

unrestricted

6.53.2.9 int timer_gettime (timer_t timerid, struct itimerspec * value)

Get timer next expiration date and reload value.

This service stores, at the address *value*, the expiration date (member *it_value*) and reload value (member *it_interval*) of the timer *timerid*. The values are returned as time intervals, and as multiples of the system clock tick duration (see note in section Clocks and timers services for details on the duration of the system clock tick). If the timer was not started, the returned members *it_value* and *it_interval* of *value* are zero.

Parameters

timerid	timer identifier;
value	address where the timer expiration date and reload value are stored on success.

Return values

0	on success;
-1	with errno set if:
	 EINVAL, timerid is invalid. For timerid to be valid, it must belong to the current process.

See also

Specification.

Tags

unrestricted

6.53.2.10 timer_settime (timer_t timerid, int flags, const struct itimerspec *__restrict__ value, struct itimerspec *__restrict__ ovalue)

Start or stop a timer.

This service sets a timer expiration date and reload value of the timer *timerid*. If *ovalue* is not *NULL*, the current expiration date and reload value are stored at the address *ovalue* as with timer_gettime().

If the member *it_value* of the **itimerspec** structure at *value* is zero, the timer is stopped, otherwise the timer is started. If the member *it_interval* is not zero, the timer is periodic. The current thread must be a Cobalt thread (created with pthread_create()) and will be notified via signal of timer expirations.

When starting the timer, if *flags* is TIMER_ABSTIME, the expiration value is interpreted as an absolute date of the clock passed to the timer_create() service. Otherwise, the expiration value is interpreted as a time interval.

Expiration date and reload value are rounded to an integer count of nanoseconds.

Parameters

timerid	identifier of the timer to be started or stopped;
flags	one of 0 or TIMER_ABSTIME;
value	address where the specified timer expiration date and reload value are read;
ovalue	address where the specified timer previous expiration date and reload value are
	stored if not NULL.

Return values

0	on success;
-1	with errno set if:
	 EINVAL, the specified timer identifier, expiration date or reload value is invalid. For timerid to be valid, it must belong to the cur- rent process.

See also

Specification.

Tags

xcontext, switch-primary

Referenced by pthread_make_periodic_np().

6.54 Condition variables 273

6.54 Condition variables

Cobalt/POSIX condition variable services.

Collaboration diagram for Condition variables:



Functions

• int pthread_cond_init (pthread_cond_t *cond, const pthread_condattr_t *attr)

Initialize a condition variable.

int pthread_cond_destroy (pthread_cond_t *cond)

Destroy a condition variable.

int pthread_cond_wait (pthread_cond_t *cond, pthread_mutex_t *mutex)

Wait on a condition variable.

 int pthread_cond_timedwait (pthread_cond_t *cond, pthread_mutex_t *mutex, const struct timespec *abstime)

Wait a bounded time on a condition variable.

int pthread cond signal (pthread cond t *cond)

Signal a condition variable.

int pthread_cond_broadcast (pthread_cond_t *cond)

Broadcast a condition variable.

int pthread_condattr_init (pthread_condattr_t *attr)

Initialize a condition variable attributes object.

int pthread_condattr_destroy (pthread_condattr_t *attr)

Destroy a condition variable attributes object.

• int pthread_condattr_getclock (const pthread_condattr_t *attr, clockid_t *clk_id)

Get the clock selection attribute from a condition variable attributes object.

• int pthread_condattr_setclock (pthread_condattr_t *attr, clockid_t clk_id)

Set the clock selection attribute of a condition variable attributes object.

int pthread_condattr_getpshared (const pthread_condattr_t *attr, int *pshared)

Get the process-shared attribute from a condition variable attributes object.

int pthread_condattr_setpshared (pthread_condattr_t *attr, int pshared)

Set the process-shared attribute of a condition variable attributes object.

6.54.1 Detailed Description

Cobalt/POSIX condition variable services.

A condition variable is a synchronization object that allows threads to suspend execution until some predicate on shared data is satisfied. The basic operations on conditions are: signal the condition (when the predicate becomes true), and wait for the condition, suspending the thread execution until another thread signals the condition.

A condition variable must always be associated with a mutex, to avoid the race condition where a thread prepares to wait on a condition variable and another thread signals the condition just before the first thread actually waits on it.

Before it can be used, a condition variable has to be initialized with pthread_cond_init(). An attribute object, which reference may be passed to this service, allows to select the features of the created condition variable, namely the *clock* used by the pthread_cond_timedwait() service (*CLOCK_REALTI ME* is used by default), and whether it may be shared between several processes (it may not be shared by default, see pthread_condattr_setpshared()).

Note that only pthread_cond_init() may be used to initialize a condition variable, using the static initializer PTHREAD COND INITIALIZER is not supported.

6.54.2 Function Documentation

```
6.54.2.1 int pthread_cond_broadcast ( pthread_cond_t * cond )
```

Broadcast a condition variable.

This service unblocks all threads blocked on the condition variable *cnd*.

Parameters

cond the condition variable to be signalled.

Returns

0 on succes.

an error number if:

- EINVAL, the condition variable is invalid;
- EPERM, the condition variable is not process-shared and does not belong to the current process.

See also

Specification.

Tags

xthread-only

Referenced by rt cond broadcast().

6.54.2.2 int pthread_cond_destroy (pthread_cond_t * cond)

Destroy a condition variable.

This service destroys the condition variable *cond*, if no thread is currently blocked on it. The condition variable becomes invalid for all condition variable services (they all return the EINVAL error) except pthread_cond_init().

Parameters

cond the condition variable to be destroyed.

6.54 Condition variables 275

Returns

0 on succes,

an error number if:

- EINVAL, the condition variable cond is invalid;
- EPERM, the condition variable is not process-shared and does not belong to the current process;
- EBUSY, some thread is currently using the condition variable.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_cond_create(), and rt_cond_delete().

```
6.54.2.3 int pthread_cond_init ( pthread_cond_t * cond, const pthread_condattr_t * attr )
```

Initialize a condition variable.

This service initializes the condition variable *cond*, using the condition variable attributes object *attr*. If *attr* is *NULL*, default attributes are used (see pthread_condattr_init(")).

Parameters

cond	the condition variable to be initialized;
attr	the condition variable attributes object.

Returns

0 on succes,

an error number if:

- EINVAL, the condition variable attributes object attr is invalid or uninitialized;
- EBUSY, the condition variable cond was already initialized;
- ENOMEM, insufficient memory available from the system heap to initialize the condition variable, increase CONFIG_XENO_OPT_SYS_HEAPSZ.
- EAGAIN, no registry slot available, check/raise CONFIG_XENO_OPT_REGISTRY_NRSL

 OTS.

See also

Specification.

Tags

thread-unrestricted

References pthread_condattr_getclock(), and pthread_condattr_getpshared().

Referenced by rt_cond_create().

6.54.2.4 int pthread_cond_signal (pthread_cond_t * cond)

Signal a condition variable.

This service unblocks one thread blocked on the condition variable *cnd*.

If more than one thread is blocked on the specified condition variable, the highest priority thread is unblocked.

6.54 Condition variables 277

Parameters

cond	the condition variable to be signalled.
------	---

Returns

0 on succes.

an error number if:

- EINVAL, the condition variable is invalid;
- EPERM, the condition variable is not process-shared and does not belong to the current process.

See also

Specification.

Tags

xthread-only

Referenced by rt_cond_signal().

6.54.2.5 int pthread_cond_timedwait (pthread_cond_t * cond, pthread_mutex_t * mutex, const struct timespec * abstime)

Wait a bounded time on a condition variable.

The timeout *abstime* is expressed as an absolute value of the *clock* attribute passed to pthread_cond __init(). By default, *CLOCK_REALTIME* is used.

Parameters

cond	the condition variable to wait for;		
mutex	the mutex associated with <i>cnd</i> ;		
abstime	the timeout, expressed as an absolute value of the clock attribute passed to pthread_cond_init().		

Returns

0 on success,

an error number if:

- EPERM, the caller context is invalid;
- EPERM, the specified condition variable is not process-shared and does not belong to the current process;
- EINVAL, the specified condition variable, mutex or timeout is invalid;
- EINVAL, another thread is currently blocked on *cnd* using another mutex than *mx*;
- EPERM, the specified mutex is not owned by the caller;
- ETIMEDOUT, the specified timeout expired.

See also

Specification.

Tags

xthread-only, switch-primary

Referenced by rt_cond_wait_timed().

```
6.54.2.6 int pthread cond wait ( pthread cond t * cond, pthread mutex t * mutex )
```

Wait on a condition variable.

This service atomically unlocks the mutex mx, and block the calling thread until the condition variable cnd is signalled using $pthread_cond_signal()$ or $pthread_cond_broadcast()$. When the condition is signaled, this service re-acquire the mutex before returning.

Spurious wakeups occur if a signal is delivered to the blocked thread, so, an application should not assume that the condition changed upon successful return from this service.

Even if the mutex mx is recursive and its recursion count is greater than one on entry, it is unlocked before blocking the caller, and the recursion count is restored once the mutex is re-acquired by this service before returning.

Once a thread is blocked on a condition variable, a dynamic binding is formed between the condition vairable cnd and the mutex mx; if another thread calls this service specifying cnd as a condition variable but another mutex than mx, this service returns immediately with the EINVAL status.

This service is a cancellation point for Cobalt threads (created with the pthread_create() service). When such a thread is cancelled while blocked in a call to this service, the mutex mx is re-acquired before the cancellation cleanup handlers are called.

Parameters

cond	the condition variable to wait for;
mutex	the mutex associated with <i>cnd</i> .

Returns

0 on success,

an error number if:

- EPERM, the caller context is invalid;
- EINVAL, the specified condition variable or mutex is invalid;
- EPERM, the specified condition variable is not process-shared and does not belong to the current process;
- EINVAL, another thread is currently blocked on *cnd* using another mutex than *mx*;
- EPERM, the specified mutex is not owned by the caller.

See also

Specification.

Tags

xthread-only, switch-primary

Referenced by rt_cond_wait_timed().

6.54.2.7 int pthread_condattr_destroy (pthread_condattr_t * attr)

Destroy a condition variable attributes object.

This service destroys the condition variable attributes object *attr*. The object becomes invalid for all condition variable services (they all return EINVAL) except pthread_condattr_init().

6.54 Condition variables 279

Parameters

attr | the initialized mutex attributes object to be destroyed.

Returns

0 on success:

an error number if:

• EINVAL, the mutex attributes object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_cond_create().

6.54.2.8 int pthread_condattr_getclock (const pthread_condattr_t * attr, clockid_t * clk_id)

Get the clock selection attribute from a condition variable attributes object.

This service stores, at the address *clk_id*, the value of the *clock* attribute in the condition variable attributes object *attr*.

See pthread_cond_timedwait() for a description of the effect of this attribute on a condition variable. The clock ID returned is CLOCK REALTIME or CLOCK MONOTONIC.

Parameters

attr	an initialized condition variable attributes object,
clk_id	address where the <i>clock</i> attribute value will be stored on success.

Returns

0 on success,

an error number if:

• EINVAL, the attribute object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by pthread_cond_init().

6.54.2.9 int pthread_condattr_getpshared (const pthread_condattr_t * attr, int * pshared)

Get the process-shared attribute from a condition variable attributes object.

This service stores, at the address *pshared*, the value of the *pshared* attribute in the condition variable attributes object *attr*.

The *pshared* attribute may only be one of *PTHREAD_PROCESS_PRIVATE* or *PTHREAD_PROCES S_SHARED*. See <u>pthread_condattr_setpshared()</u> for the meaning of these two constants.

Parameters

attr	an initialized condition variable attributes object.
pshared	address where the value of the <i>pshared</i> attribute will be stored on success.

Returns

0 on success, an error number if:

- EINVAL, the pshared address is invalid;
- EINVAL, the condition variable attributes object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by pthread_cond_init().

6.54.2.10 int pthread_condattr_init (pthread_condattr_t * attr)

Initialize a condition variable attributes object.

This services initializes the condition variable attributes object *attr* with default values for all attributes. Default value are:

- for the clock attribute, CLOCK_REALTIME;
- for the pshared attribute PTHREAD_PROCESS_PRIVATE.

If this service is called specifying a condition variable attributes object that was already initialized, the attributes object is reinitialized.

Parameters

attr	the condition variable attributes object to be initialized.

Returns

0 on success;

an error number if:

• ENOMEM, the condition variable attribute object pointer attr is NULL.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_cond_create().

6.54 Condition variables 281

6.54.2.11 int pthread_condattr_setclock (pthread_condattr_t * attr, clockid_t clk_id)

Set the clock selection attribute of a condition variable attributes object.

This service set the *clock* attribute of the condition variable attributes object *attr*.

See pthread_cond_timedwait() for a description of the effect of this attribute on a condition variable.

Parameters

attr	an initialized condition variable attributes object,
clk_id	value of the <i>clock</i> attribute, may be <i>CLOCK_REALTIME</i> or <i>CLOCK_MONOTONIC</i> .

Returns

0 on success,

an error number if:

- EINVAL, the condition variable attributes object attr is invalid;
- EINVAL, the value of *clk_id* is invalid for the *clock* attribute.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_cond_create().

6.54.2.12 int pthread_condattr_setpshared (pthread_condattr_t * attr, int pshared)

Set the process-shared attribute of a condition variable attributes object.

This service set the *pshared* attribute of the condition variable attributes object attr.

Parameters

attr	an initialized condition variable attributes object.
pshared	value of the <i>pshared</i> attribute, may be one of:
	 PTHREAD_PROCESS_PRIVATE, meaning that a condition variable created with the attributes object attr will only be accessible by threads within the same process as the thread that initialized the condition variable;
	 PTHREAD_PROCESS_SHARED, meaning that a condition variable created with the attributes object attr will be accessible by any thread that has access to the memory where the condition variable is allocated.

Returns

0 on success,

an error status if:

- EINVAL, the condition variable attributes object attr is invalid;
- EINVAL, the value of pshared is invalid.

See also

Specification.

Tags

thread-unrestricted


Referenced by rt_cond_create().

6.55 POSIX interface 283

6.55 POSIX interface

The Cobalt/POSIX interface is an implementation of a subset of the Single Unix specification over the Cobalt core.

Collaboration diagram for POSIX interface:



Modules

· Clocks and timers

Cobalt/POSIX clock and timer services.

Condition variables

Cobalt/POSIX condition variable services.

• Message queues

Cobalt/POSIX message queue services.

Mutual exclusion

Cobalt/POSIX mutual exclusion services.

Process scheduling

Cobalt/POSIX process scheduling.

Semaphores

Cobalt/POSIX semaphore services.

Thread management

Cobalt (POSIX) thread management services.

Scheduling management

Cobalt scheduling management services.

6.55.1 Detailed Description

The Cobalt/POSIX interface is an implementation of a subset of the Single Unix specification over the Cobalt core.

6.56 Message queues 285

6.56 Message queues

Cobalt/POSIX message queue services.

Collaboration diagram for Message queues:



Functions

mqd_t mq_open (const char *name, int oflags,...)

Open a message queue.

int mq_close (mqd_t mqd)

Close a message queue.

• int mq unlink (const char *name)

Unlink a message queue.

int mq_getattr (mqd_t mqd, struct mq_attr *attr)

Get message queue attributes.

int mq_setattr (mqd_t mqd, const struct mq_attr *__restrict__ attr, struct mq_attr *__restrict__
oattr)

Set message queue attributes.

• int mq_send (mqd_t q, const char *buffer, size_t len, unsigned prio)

Send a message to a message queue.

 int mq_timedsend (mqd_t q, const char *buffer, size_t len, unsigned prio, const struct timespec *timeout)

Attempt, during a bounded time, to send a message to a message queue.

• ssize t mq receive (mqd t q, char *buffer, size t len, unsigned *prio)

Receive a message from a message queue.

 ssize_t mq_timedreceive (mqd_t q, char *__restrict__ buffer, size_t len, unsigned *__restrict__ prio, const struct timespec *__restrict__ timeout)

Attempt, during a bounded time, to receive a message from a message queue.

int mq_notify (mqd_t mqd, const struct sigevent *evp)

Enable notification on message arrival.

6.56.1 Detailed Description

Cobalt/POSIX message queue services.

A message queue allow exchanging data between real-time threads. For a POSIX message queue, maximum message length and maximum number of messages are fixed when it is created with mq_open().

6.56.2 Function Documentation

6.56.2.1 int mq_close (mqd_t mqd)

Close a message queue.

This service closes the message queue descriptor *mqd*. The message queue is destroyed only when all open descriptors are closed, and when unlinked with a call to the mq_unlink() service.

Parameters

mqd	message queue descriptor.

Return values

0	on success;
-1	with errno set if:
	EBADF, mqd is an invalid message queue descriptor;
	EPERM, the caller context is invalid.

See also

Specification.

Tags

thread-unrestricted, switch-secondary

6.56.2.2 int mq_getattr (mqd_t mqd, struct mq_attr * attr)

Get message queue attributes.

This service stores, at the address attr, the attributes of the messages queue descriptor mqd.

The following attributes are set:

- mq_flags, flags of the message queue descriptor mqd;
- mq_maxmsg, maximum number of messages in the message queue;
- mq_msgsize, maximum message size;
- mq_curmsgs, number of messages currently in the queue.

Parameters

mqd	message queue descriptor;
attr	address where the message queue attributes will be stored on success.

Return values

0	on success;
-1	with errno set if:
	EBADF, mqd is not a valid descriptor.

See also

Specification.

Tags

thread-unrestricted

6.56.2.3 int mg notify (mgd t mgd, const struct sigevent * evp)

Enable notification on message arrival.

If *evp* is not *NULL* and is the address of a **sigevent** structure with the *sigev_notify* member set to S⇔ IGEV_SIGNAL, the current thread will be notified by a signal when a message is sent to the message queue *mqd*, the queue is empty, and no thread is blocked in call to mq_receive() or mq_timedreceive(). After the notification, the thread is unregistered.

If evp is NULL or the sigev_notify member is SIGEV_NONE, the current thread is unregistered.

Only one thread may be registered at a time.

If the current thread is not a Cobalt thread (created with pthread create()), this service fails.

Parameters

mqd	message queue descriptor;
evp	pointer to an event notification structure.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, <i>evp</i> is invalid;
	 EPERM, the caller context is invalid;
	 EBADF, mqd is not a valid message queue descriptor;
	EBUSY, another thread is already registered.

See also

Specification.

Tags

xthread-only, switch-primary

6.56.2.4 mqd_t mq_open (const char * name, int oflags, ...)

Open a message queue.

This service opens the message queue named *name*.

One of the following values should be set in *oflags:*

- O_RDONLY, meaning that the returned queue descriptor may only be used for receiving messages;
- O_WRONLY, meaning that the returned queue descriptor may only be used for sending messages;

 O_RDWR, meaning that the returned queue descriptor may be used for both sending and receiving messages.

If no message queue named *name* exists, and *oflags* has the *O_CREAT* bit set, the message queue is created by this function, taking two more arguments:

- a mode argument, of type mode t, currently ignored;
- an attr argument, pointer to an **mq_attr** structure, specifying the attributes of the new message queue.

If *oflags* has the two bits *O_CREAT* and *O_EXCL* set and the message queue alread exists, this service fails.

If the O_NONBLOCK bit is set in *oflags*, the mq_send(), mq_receive(), mq_timedsend() and mq_timedreceive() services return -1 with *errno* set to EAGAIN instead of blocking their caller.

The following arguments of the **mq_attr** structure at the address *attr* are used when creating a message queue:

- mq_maxmsg is the maximum number of messages in the queue (128 by default);
- mq_msgsize is the maximum size of each message (128 by default).

name may be any arbitrary string, in which slashes have no particular meaning. However, for portability, using a name which starts with a slash and contains no other slash is recommended.

Parameters

name	name of the message queue to open;
oflags	flags.

Returns

a message queue descriptor on success;

- -1 with errno set if:
 - ENAMETOOLONG, the length of the *name* argument exceeds 64 characters;
 - EEXIST, the bits O_CREAT and O_EXCL were set in oflags and the message queue already exists;
 - ENOENT, the bit O CREAT is not set in oflags and the message queue does not exist;
 - ENOSPC, allocation of system memory failed, or insufficient memory available from the system heap to create the queue, try increasing CONFIG_XENO_OPT_SYS_HEAPSZ;
 - EPERM, attempting to create a message queue from an invalid context;
 - EINVAL, the attr argument is invalid;
 - EMFILE, too many descriptors are currently open.
 - EAGAIN, no registry slot available, check/raise CONFIG_XENO_OPT_REGISTRY_NRSL

 OTS.

See also

Specification.

Tags

thread-unrestricted, switch-secondary

6.56.2.5 ssize_t mq_receive (mqd_t q, char * buffer, size_t len, unsigned * prio)

Receive a message from a message queue.

If the message queue *fd* is not empty and if *len* is greater than the *mq_msgsize* of the message queue, this service copies, at the address *buffer*, the queued message with the highest priority.

If the queue is empty and the flag *O_NONBLOCK* is not set for the descriptor *fd*, the calling thread is suspended until some message is sent to the queue. If the queue is empty and the flag *O_NONBLOCK* is set for the descriptor *fd*, this service returns immediately a value of -1 with *errno* set to EAGAIN.

Parameters

q	the queue descriptor;
buffer	the address where the received message will be stored on success;
len	buffer length;
prio	address where the priority of the received message will be stored on success.

Returns

the message length, and copy a message at the address buffer on success;

- -1 with no message unqueued and errno set if:
 - EBADF, fd is not a valid descriptor open for reading;
 - EMSGSIZE, the length *len* is lesser than the message queue *mq_msgsize* attribute;
 - EAGAIN, the queue is empty, and the flag O_NONBLOCK is set for the descriptor fd;
 - EPERM, the caller context is invalid;
 - EINTR, the service was interrupted by a signal.

See also

Specification.

Tags

xthread-only, switch-primary

6.56.2.6 int mg send (mgd t g, const char * buffer, size t len, unsigned prio)

Send a message to a message queue.

If the message queue *fd* is not full, this service sends the message of length *len* pointed to by the argument *buffer*, with priority *prio*. A message with greater priority is inserted in the queue before a message with lower priority.

If the message queue is full and the flag $O_NONBLOCK$ is not set, the calling thread is suspended until the queue is not full. If the message queue is full and the flag $O_NONBLOCK$ is set, the message is not sent and the service returns immediately a value of -1 with errno set to EAGAIN.

Parameters

q	message queue descriptor;
buffer	pointer to the message to be sent;
len	length of the message;

	and and the and the annual and
nrio	
DITO	I DITUITIV OF LITE THESSAUE.
I	

Returns

0 and send a message on success;

- -1 with no message sent and errno set if:
 - EBADF, fd is not a valid message queue descriptor open for writing;
 - EMSGSIZE, the message length *len* exceeds the *mq_msgsize* attribute of the message queue;
 - EAGAIN, the flag O_NONBLOCK is set for the descriptor fd and the message queue is full;
 - EPERM, the caller context is invalid;
 - EINTR, the service was interrupted by a signal.

See also

Specification.

Tags

xthread-only, switch-primary

```
6.56.2.7 int mq_setattr ( mqd_t mqd, const struct mq_attr *__restrict__ attr, struct mq_attr *__restrict__ oattr )
```

Set message queue attributes.

This service sets the flags of the mqd descriptor to the value of the member mq_flags of the mq_attr structure pointed to by attr.

The previous value of the message queue attributes are stored at the address oattr if it is not NULL.

Only setting or clearing the O_NONBLOCK flag has an effect.

Parameters

mqd	message queue descriptor;
attr	pointer to new attributes (only <i>mq_flags</i> is used);
oattr	if not NULL, address where previous message queue attributes will be stored on
	success.

Return values

0	on success;
-1	with errno set if:
	• EBADF, mqd is not a valid message queue descriptor.

See also

Specification.

Tags

thread-unrestricted

```
6.56.2.8 ssize_t mq_timedreceive ( mqd_t q, char *__restrict__ buffer, size_t len, unsigned *__restrict__ prio, const struct timespec *__restrict__ timeout )
```

Attempt, during a bounded time, to receive a message from a message queue.

This service is equivalent to mq_receive(), except that if the flag *O_NONBLOCK* is not set for the descriptor *fd* and the message queue is empty, the calling thread is only suspended until the timeout *abs_timeout* expires.

Parameters

q	the queue descriptor;
buffer	the address where the received message will be stored on success;
len	buffer length;
prio	address where the priority of the received message will be stored on success.
timeout	the timeout, expressed as an absolute value of the CLOCK_REALTIME clock.

Returns

the message length, and copy a message at the address buffer on success;

- -1 with no message unqueued and errno set if:
 - EBADF, fd is not a valid descriptor open for reading;
 - EMSGSIZE, the length *len* is lesser than the message queue *mq_msgsize* attribute;
 - EAGAIN, the queue is empty, and the flag *O_NONBLOCK* is set for the descriptor *fd*;
 - EPERM, the caller context is invalid;
 - EINTR, the service was interrupted by a signal;
 - ETIMEDOUT, the specified timeout expired.

See also

Specification.

Tags

xthread-only, switch-primary

6.56.2.9 int mq_timedsend (mqd_t q, const char * buffer, size_t len, unsigned prio, const struct timespec * timeout)

Attempt, during a bounded time, to send a message to a message queue.

This service is equivalent to $mq_send()$, except that if the message queue is full and the flag $O_NON \hookrightarrow BLOCK$ is not set for the descriptor fd, the calling thread is only suspended until the timeout specified by $abs\ timeout\ expires$.

Parameters

q	message queue descriptor;
buffer	pointer to the message to be sent;
len	length of the message;
prio	priority of the message;
timeout	the timeout, expressed as an absolute value of the CLOCK_REALTIME clock.

Returns

0 and send a message on success;

- -1 with no message sent and errno set if:
 - EBADF, fd is not a valid message queue descriptor open for writing;
 - EMSGSIZE, the message length exceeds the mq_msgsize attribute of the message queue;
 - EAGAIN, the flag O_NONBLOCK is set for the descriptor fd and the message queue is full;
 - EPERM, the caller context is invalid;
 - ETIMEDOUT, the specified timeout expired;
 - EINTR, the service was interrupted by a signal.

See also

Specification.

Tags

xthread-only, switch-primary

6.56.2.10 int mq_unlink (const char * name)

Unlink a message queue.

This service unlinks the message queue named *name*. The message queue is not destroyed until all queue descriptors obtained with the mq_open() service are closed with the mq_close() service. However, after a call to this service, the unlinked queue may no longer be reached with the mq_open() service.

Parameters

name	name of the message queue to be unlinked.
------	---

Return values

0	on success;
-1	with errno set if:
	• EPERM, the caller context is invalid;
	 ENAMETOOLONG, the length of the name argument exceeds 64 characters;
	ENOENT, the message queue does not exist.

See also

Specification.

Tags

thread-unrestricted, switch-secondary

6.57 Mutual exclusion 293

6.57 Mutual exclusion

Cobalt/POSIX mutual exclusion services.

Collaboration diagram for Mutual exclusion:



Functions

- int pthread_mutex_init (pthread_mutex_t *mutex, const pthread_mutexattr_t *attr)
 Initialize a mutex.
- int pthread_mutex_destroy (pthread_mutex_t *mutex)

Destroy a mutex.

int pthread_mutex_lock (pthread_mutex_t *mutex)

Lock a mutex.

- int pthread_mutex_timedlock (pthread_mutex_t *mutex, const struct timespec *to)
 - Attempt, during a bounded time, to lock a mutex.
- int pthread_mutex_trylock (pthread_mutex_t *mutex)

Attempt to lock a mutex.

• int pthread mutex unlock (pthread mutex t *mutex)

Unlock a mutex.

int pthread_mutexattr_init (pthread_mutexattr_t *attr)

Initialize a mutex attributes object.

• int pthread_mutexattr_destroy (pthread_mutexattr_t *attr)

Destroy a mutex attributes object.

• int pthread_mutexattr_gettype (const pthread_mutexattr_t *attr, int *type)

Get the mutex type attribute from a mutex attributes object.

• int pthread mutexattr settype (pthread mutexattr t *attr, int type)

Set the mutex type attribute of a mutex attributes object.

• int pthread_mutexattr_getprotocol (const pthread_mutexattr_t *attr, int *proto)

Get the protocol attribute from a mutex attributes object.

• int pthread_mutexattr_setprotocol (pthread_mutexattr_t *attr, int proto)

Set the protocol attribute of a mutex attributes object.

int pthread mutexattr getpshared (const pthread mutexattr t *attr, int *pshared)

Get the process-shared attribute of a mutex attributes object.

• int pthread mutexattr setpshared (pthread mutexattr t *attr, int pshared)

Set the process-shared attribute of a mutex attributes object.

6.57.1 Detailed Description

Cobalt/POSIX mutual exclusion services.

A mutex is a MUTual EXclusion device, and is useful for protecting shared data structures from concurrent modifications, and implementing critical sections and monitors.

A mutex has two possible states: unlocked (not owned by any thread), and locked (owned by one thread). A mutex can never be owned by two different threads simultaneously. A thread attempting to lock a mutex that is already locked by another thread is suspended until the owning thread unlocks the mutex first.

Before it can be used, a mutex has to be initialized with pthread_mutex_init(). An attribute object, which reference may be passed to this service, allows to select the features of the created mutex, namely its type (see pthread_mutexattr_settype()), the priority protocol it uses (see pthread_mutexattr_settype()) and whether it may be shared between several processes (see pthread_mutexattr_settype()).

By default, Cobalt mutexes are of the normal type, use no priority protocol and may not be shared between several processes.

Note that only pthread_mutex_init() may be used to initialize a mutex, using the static initializer PTHR← EAD_MUTEX_INITIALIZER is not supported.

6.57.2 Function Documentation

```
6.57.2.1 int pthread_mutex_destroy ( pthread_mutex_t * mutex )
```

Destroy a mutex.

This service destroys the mutex *mx*, if it is unlocked and not referenced by any condition variable. The mutex becomes invalid for all mutex services (they all return the EINVAL error) except pthread_mutex — init().

Parameters

```
mutex the mutex to be destroyed.
```

Returns

0 on success,

an error number if:

- EINVAL, the mutex mx is invalid;
- EPERM, the mutex is not process-shared and does not belong to the current process;
- EBUSY, the mutex is locked, or used by a condition variable.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt mutex delete().

6.57.2.2 int pthread mutex init (pthread mutex t * mutex, const pthread mutexattr t * attr)

Initialize a mutex.

6.57 Mutual exclusion 295



mutex	the mutex to be initialized;
attr	the mutex attributes object.

Returns

0 on success,

an error number if:

- EINVAL, the mutex attributes object attr is invalid or uninitialized;
- EBUSY, the mutex mx was already initialized;
- ENOMEM, insufficient memory available from the system heap to initialize the mutex, increase CONFIG_XENO_OPT_SYS_HEAPSZ.
- EAGAIN, insufficient memory available to initialize the mutex, increase CONFIG_XENO_O
 —
 PT_SHARED_HEAPSZ for a process-shared mutex, or CONFIG_XENO_OPT_PRIVATE_
 —
 HEAPSZ for a process-private mutex.
- EAGAIN, no registry slot available, check/raise CONFIG_XENO_OPT_REGISTRY_NRSL

 OTS.

See also

Specification.

Tags

thread-unrestricted

References pthread_mutexattr_getprotocol(), pthread_mutexattr_getpshared(), and pthread_ \leftarrow mutexattr_gettype().

Referenced by rt_mutex_create().

6.57.2.3 int pthread_mutex_lock (pthread_mutex_t * mutex)

Lock a mutex.

This service attempts to lock the mutex mx. If the mutex is free, it becomes locked. If it was locked by another thread than the current one, the current thread is suspended until the mutex is unlocked. If it was already locked by the current mutex, the behaviour of this service depends on the mutex type:

- for mutexes of the PTHREAD_MUTEX_NORMAL type, this service deadlocks;
- for mutexes of the PTHREAD_MUTEX_ERRORCHECK type, this service returns the EDEADLK error number;
- for mutexes of the *PTHREAD_MUTEX_RECURSIVE* type, this service increments the lock recursion count and returns 0.

Parameters

mutex	the mutex to be locked.

Returns

0 on success

an error number if:

• EPERM, the caller context is invalid;

6.57 Mutual exclusion 297

- EINVAL, the mutex mx is invalid;
- EPERM, the mutex is not process-shared and does not belong to the current process;
- EDEADLK, the mutex is of the PTHREAD_MUTEX_ERRORCHECK type and was already locked by the current thread;
- EAGAIN, the mutex is of the *PTHREAD_MUTEX_RECURSIVE* type and the maximum number of recursive locks has been exceeded.

See also

Specification.

Tags

xthread-only, switch-primary

References XNDEBUG, XNRELAX, and XNWEAK.

Referenced by rt_mutex_acquire_timed().

6.57.2.4 int pthread mutex timedlock (pthread mutex t * mutex, const struct timespec * to)

Attempt, during a bounded time, to lock a mutex.

This service is equivalent to <a href="https://pubm.nih.google-nih

Parameters

mutex	the mutex to be locked;
to	the timeout, expressed as an absolute value of the CLOCK_REALTIME clock.

Returns

0 on success;

an error number if:

- EPERM, the caller context is invalid;
- EINVAL, the mutex *mx* is invalid;
- EPERM, the mutex is not process-shared and does not belong to the current process;
- ETIMEDOUT, the mutex could not be locked and the specified timeout expired;
- EDEADLK, the mutex is of the *PTHREAD_MUTEX_ERRORCHECK* type and the mutex was already locked by the current thread;
- EAGAIN, the mutex is of the PTHREAD_MUTEX_RECURSIVE type and the maximum number of recursive locks has been exceeded.

See also

Specification.

Tags

xthread-only, switch-primary

References XNDEBUG, XNRELAX, and XNWEAK.

Referenced by rt_mutex_acquire_timed().

6.57.2.5 int pthread_mutex_trylock (pthread_mutex_t * mutex)

Attempt to lock a mutex.

This service is equivalent to pthread_mutex_lock(), except that if the mutex mx is locked by another thread than the current one, this service returns immediately.

Parameters

298

mutex the mutex to be locked.

Returns

0 on success;

an error number if:

- EPERM, the caller context is invalid;
- EINVAL, the mutex is invalid;
- EPERM, the mutex is not process-shared and does not belong to the current process;
- EBUSY, the mutex was locked by another thread than the current one;
- EAGAIN, the mutex is recursive, and the maximum number of recursive locks has been exceeded.

See also

Specification.

Tags

xthread-only, switch-primary

References XNDEBUG, XNRELAX, and XNWEAK.

Referenced by rt_mutex_acquire_timed(), and rt_mutex_inquire().

6.57.2.6 int pthread_mutex_unlock (pthread_mutex_t * mutex)

Unlock a mutex.

This service unlocks the mutex mx. If the mutex is of the $PTHREAD_MUTEX_RECURSIVE$ type and the locking recursion count is greater than one, the lock recursion count is decremented and the mutex remains locked.

Attempting to unlock a mutex which is not locked or which is locked by another thread than the current one yields the EPERM error, whatever the mutex *type* attribute.

Parameters

mutex the mutex to be released.

Returns

0 on success:

an error number if:

- EPERM, the caller context is invalid;
- EINVAL, the mutex mx is invalid;
- EPERM, the mutex was not locked by the current thread.

6.57 Mutual exclusion 299

See also

Specification.

Tags

xthread-only, switch-primary

References XNDEBUG, and XNWEAK.

Referenced by rt_mutex_inquire(), and rt_mutex_release().

6.57.2.7 int pthread_mutexattr_destroy (pthread_mutexattr_t * attr)

Destroy a mutex attributes object.

This service destroys the mutex attributes object *attr*. The object becomes invalid for all mutex services (they all return EINVAL) except pthread mutexattr init().

Parameters

attr	the initialized mutex attributes object to be destroyed.

Returns

0 on success;

an error number if:

• EINVAL, the mutex attributes object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_mutex_create().

6.57.2.8 int pthread_mutexattr_getprotocol (const pthread_mutexattr_t * attr, int * proto)

Get the protocol attribute from a mutex attributes object.

This service stores, at the address *proto*, the value of the *protocol* attribute in the mutex attributes object *attr*.

The *protcol* attribute may only be one of *PTHREAD_PRIO_NONE* or *PTHREAD_PRIO_INHERIT*. See pthread_mutexattr_setprotocol() for the meaning of these two constants.

Parameters

attr	an initialized mutex attributes object;	
proto	address where the value of the <i>protocol</i> attribute will be stored on success.	

Returns

0 on success.

an error number if:

- EINVAL, the proto address is invalid;
- EINVAL, the mutex attributes object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by pthread_mutex_init().

6.57.2.9 int pthread mutexattr getpshared (const pthread mutexattr t * attr, int * pshared)

Get the process-shared attribute of a mutex attributes object.

This service stores, at the address *pshared*, the value of the *pshared* attribute in the mutex attributes object *attr*.

The *pashared* attribute may only be one of *PTHREAD_PROCESS_PRIVATE* or *PTHREAD_PROCE SS_SHARED*. See <u>pthread_mutexattr_setpshared()</u> for the meaning of these two constants.

Parameters

attr	an initialized mutex attributes object;	
pshared	address where the value of the <i>pshared</i> attribute will be stored on success.	

Returns

0 on success:

an error number if:

- EINVAL, the pshared address is invalid;
- EINVAL, the mutex attributes object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by pthread_mutex_init().

6.57.2.10 int pthread_mutexattr_gettype (const pthread_mutexattr_t * attr, int * type)

Get the mutex type attribute from a mutex attributes object.

This service stores, at the address type, the value of the type attribute in the mutex attributes object attr.

See pthread_mutex_unlock() for a description of the values of the type attribute and their effect on a mutex.

Parameters

attr	an initialized mutex attributes object,	
type	address where the <i>type</i> attribute value will be stored on success.	

6.57 Mutual exclusion 301

Returns

0 on sucess,

an error number if:

- EINVAL, the type address is invalid;
- EINVAL, the mutex attributes object attr is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by pthread_mutex_init().

```
6.57.2.11 int pthread_mutexattr_init ( pthread_mutexattr_t * attr )
```

Initialize a mutex attributes object.

This services initializes the mutex attributes object *attr* with default values for all attributes. Default value are :

- for the type attribute, PTHREAD_MUTEX_NORMAL;
- for the protocol attribute, PTHREAD_PRIO_NONE;
- for the pshared attribute, PTHREAD_PROCESS_PRIVATE.

If this service is called specifying a mutex attributes object that was already initialized, the attributes object is reinitialized.

Parameters

attr | the mutex attributes object to be initialized.

Returns

0 on success;

an error number if:

• ENOMEM, the mutex attributes object pointer attr is NULL.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_mutex_create().

6.57.2.12 int pthread_mutexattr_setprotocol (pthread_mutexattr_t * attr, int proto)

Set the protocol attribute of a mutex attributes object.

This service set the *type* attribute of the mutex attributes object attr.

Parameters

attr	an initialized mutex attributes object,
proto	value of the <i>protocol</i> attribute, may be one of:
	 PTHREAD_PRIO_NONE, meaning that a mutex created with the attributes object attr will not follow any priority protocol;
	 PTHREAD_PRIO_INHERIT, meaning that a mutex created with the attributes object attr, will follow the priority inheritance protocol.

The value PTHREAD_PRIO_PROTECT (priority ceiling protocol) is unsupported.

Returns

0 on success, an error number if:

- EINVAL, the mutex attributes object attr is invalid;
- ENOTSUP, the value of *proto* is unsupported;
- EINVAL, the value of proto is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_mutex_create().

6.57.2.13 int pthread_mutexattr_setpshared (pthread_mutexattr_t * attr, int pshared)

Set the process-shared attribute of a mutex attributes object.

This service set the *pshared* attribute of the mutex attributes object attr.

Parameters

attr	an initialized mutex attributes object.
pshared	value of the <i>pshared</i> attribute, may be one of:
	 PTHREAD_PROCESS_PRIVATE, meaning that a mutex created with the attributes object attr will only be accessible by threads within the same process as the thread that initialized the mutex;
	 PTHREAD_PROCESS_SHARED, meaning that a mutex created with the attributes object attr will be accessible by any thread that has access to the memory where the mutex is allocated.

Returns

0 on success,

an error status if:

- EINVAL, the mutex attributes object attr is invalid;
- EINVAL, the value of pshared is invalid.

6.57 Mutual exclusion 303

See also

Specification.

Tags

thread-unrestricted

Referenced by rt_mutex_create().

6.57.2.14 int pthread_mutexattr_settype (pthread_mutexattr_t * attr, int type)

Set the mutex type attribute of a mutex attributes object.

This service set the *type* attribute of the mutex attributes object attr.

See pthread_mutex_unlock() for a description of the values of the type attribute and their effect on a mutex.

The PTHREAD_MUTEX_DEFAULT default type is the same as PTHREAD_MUTEX_NORMAL. Note that using a recursive Cobalt mutex with a Cobalt condition variable is safe (see pthread_cond_wait()) documentation).

Parameters

attr	an initialized mutex attributes object,	
type value of the type attribute.		

Returns

0 on success,

an error number if:

- EINVAL, the mutex attributes object attr is invalid;
- EINVAL, the value of *type* is invalid for the *type* attribute.

See also

Specification.

Tags


thread-unrestricted

Referenced by rt_mutex_create().

6.58 Process scheduling

Cobalt/POSIX process scheduling.

Collaboration diagram for Process scheduling:



Functions

• int sched_yield (void)

Yield the processor.

int sched_get_priority_min (int policy)

Get minimum priority of the specified scheduling policy.

int sched_get_priority_min_ex (int policy)

Get extended minimum priority of the specified scheduling policy.

int sched_get_priority_max (int policy)

Get maximum priority of the specified scheduling policy.

int sched_setscheduler (pid_t pid, int policy, const struct sched_param *param)

Set the scheduling policy and parameters of the specified process.

• int sched_setscheduler_ex (pid_t pid, int policy, const struct sched_param_ex *param_ex)

Set extended scheduling policy of a process.

• int sched getscheduler (pid t pid)

Get the scheduling policy of the specified process.

• int sched_getscheduler_ex (pid_t pid, int *policy_r, struct sched_param_ex *param_ex)

Get extended scheduling policy of a process.

int sched_get_priority_max_ex (int policy)

Get extended maximum priority of the specified scheduling policy.

• int sched_setconfig_np (int cpu, int policy, const union sched_config *config, size_t len)

Set CPU-specific scheduler settings for a policy.

• ssize_t sched_getconfig_np (int cpu, int policy, union sched_config *config, size_t *len_r)

*Retrieve CPU-specific scheduler settings for a policy.

6.58.1 Detailed Description

Cobalt/POSIX process scheduling.

See also

Specification.

6.58.2 Function Documentation

6.58.2.1 int sched_get_priority_max (int policy)

Get maximum priority of the specified scheduling policy.

This service returns the maximum priority of the scheduling policy policy.

policy	scheduling policy.	

Return values

0	on success;
-1	with errno set if:
	• EINVAL, <i>policy</i> is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by sched_get_priority_max_ex().

```
6.58.2.2 int sched_get_priority_max_ex ( int policy )
```

Get extended maximum priority of the specified scheduling policy.

This service returns the maximum priority of the scheduling policy *policy*, reflecting any Cobalt extension to standard classes.

Parameters

policy	scheduling policy.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, <i>policy</i> is invalid.

See also

Specification.

Tags

thread-unrestricted

References sched_get_priority_max().

6.58.2.3 int sched_get_priority_min (int policy)

Get minimum priority of the specified scheduling policy.

This service returns the minimum priority of the scheduling policy policy.

policy	scheduling policy.

Return values

0	on success;
-1	with errno set if:
	• EINVAL, <i>policy</i> is invalid.

See also

Specification.

Tags

thread-unrestricted

Referenced by sched_get_priority_min_ex().

```
6.58.2.4 int sched_get_priority_min_ex ( int policy )
```

Get extended minimum priority of the specified scheduling policy.

This service returns the minimum priority of the scheduling policy, reflecting any Cobalt extension to the standard classes.

Parameters

policy	scheduling policy.

Return values

0	on success;
-1	with errno set if:
	EINVAL, <i>policy</i> is invalid.

See also

Specification.

Tags

thread-unrestricted

References sched_get_priority_min().

6.58.2.5 ssize_t sched_getconfig_np (int cpu, int policy, union sched_config * config, size_t * len_r)

Retrieve CPU-specific scheduler settings for a policy.

A configuration is strictly local to the target cpu, and may differ from other processors.

сри	processor to retrieve the configuration of.
policy	scheduling policy to which the configuration data applies. Currently, only SCHED⊷
	_TP and SCHED_QUOTA are valid input.
config	a pointer to a memory area which receives the configuration settings upon success
	of this call.

SCHED_TP specifics

On successful return, config->quota.tp contains the TP schedule active on cpu.

SCHED_QUOTA specifics

On entry, config->quota.get.tgid must contain the thread group identifier to inquire about.

On successful exit, config->quota.info contains the information related to the thread group referenced to by config->quota.get.tgid.

Parameters

in,out	len_r	a pointer to a variable for collecting the overall length of the configura-
		tion data returned (in bytes). This variable must contain the amount of
		space available in <i>config</i> when the request is issued.

Returns

the number of bytes copied to *config* on success; a negative error number if:

- EINVAL, *cpu* is invalid, or *policy* is unsupported by the current kernel configuration, or *len* cannot hold the retrieved configuration data.
- ESRCH, with *policy* equal to SCHED_QUOTA, if the group identifier required to perform the operation is not valid (i.e. config->quota.get.tgid is invalid).
- ENOMEM, lack of memory to perform the operation.
- ENOSPC, len is too short.

Tags

thread-unrestricted, switch-primary

6.58.2.6 int sched_getscheduler (pid_t pid)

Get the scheduling policy of the specified process.

This service retrieves the scheduling policy of the Cobalt process identified by pid.

If *pid* does not identify an existing Cobalt thread/process, this service falls back to the regular sched_ egetscheduler() service.

pid	target process/thread;

Returns

0 on success;

an error number if:

- ESRCH, pid is not found;
- EINVAL, pid is negative
- EFAULT, param_ex is an invalid address;

See also

Specification.

Tags

thread-unrestricted

6.58.2.7 int sched_getscheduler_ex (pid_t pid, int * policy_r, struct sched_param_ex * param_ex)

Get extended scheduling policy of a process.

This service is an extended version of the sched_getscheduler() service, which supports Cobalt-specific and/or additional scheduling policies, not available with the host Linux environment. It retrieves the scheduling policy of the Cobalt process/thread identified by *pid*, and the associated scheduling parameters (e.g. the priority).

Parameters

pid	queried process/thread. If zero, the current thread is assumed.
policy_r	a pointer to a variable receiving the current scheduling policy of <i>pid</i> .
param_ex	a pointer to a structure receiving the current scheduling parameters of <i>pid</i> .

Returns

0 on success;

an error number if:

- ESRCH, pid is not a Cobalt thread;
- EINVAL, pid is negative or param_ex is NULL;
- EFAULT, param_ex is an invalid address;

Tags

thread-unrestricted

6.58.2.8 int sched_setconfig_np (int cpu, int policy, const union sched_config * config, size_t len)

Set CPU-specific scheduler settings for a policy.

A configuration is strictly local to the target cpu, and may differ from other processors.

сри	processor to load the configuration of.
policy	scheduling policy to which the configuration data applies. Currently, SCHED_TP
	and SCHED_QUOTA are valid.
config	a pointer to the configuration data to load on <i>cpu</i> , applicable to <i>policy</i> .

Settings applicable to SCHED_TP

This call controls the temporal partitions for cpu, depending on the operation requested.

- config.tp.op specifies the operation to perform:
- sched_tp_install installs a new TP schedule on cpu, defined by config.tp.windows[]. The global time frame is not activated upon return from this request yet; sched_tp_start must be issued to activate the temporal scheduling on CPU.
- sched_tp_uninstall removes the current TP schedule from cpu, releasing all the attached resources. If no TP schedule exists on CPU, this request has no effect.
- sched_tp_start enables the temporal scheduling on cpu, starting the global time frame. If no TP schedule exists on cpu, this action has no effect.
- sched_tp_stop disables the temporal scheduling on cpu. The current TP schedule is not uninstalled though, and may be re-started later by a sched tp start request.

Attention

As a consequence of this request, threads assigned to the un-scheduled partitions may be starved from CPU time.

- for a *sched_tp_install* operation, config.tp.nr_windows indicates the number of elements present in the config.tp.windows[] array. If config.tp.nr_windows is zero, the action taken is identical to *sched_tp_uninstall*.
- if config.tp.nr_windows is non-zero, config.tp.windows[] is a set scheduling time slots for threads assigned to *cpu*. Each window is specified by its offset from the start of the global time frame (windows[].offset), its duration (windows[].duration), and the partition id it should activate during such period of time (windows[].ptid). This field is not considered for other requests than *sched_* to *install*.

Time slots must be strictly contiguous, i.e. windows[n].offset + windows[n].duration shall equal windows[n + 1].offset. If windows[].ptid is in the range [0..CONFIG_XENO_OPT_SCHED_TP_NRP \hookrightarrow ART-1], SCHED_TP threads which belong to the partition being referred to may be given CPU time on *cpu*, from time windows[].offset to windows[].offset + windows[].duration, provided those threads are in a runnable state.

Time holes between valid time slots may be defined using windows activating the pseudo partition -1. When such window is active in the global time frame, no CPU time is available to SCHED_TP threads on *cpu*.

Note

The sched_tp_confsz(nr_windows) macro returns the length of config.tp depending on the number of time slots to be defined in config.tp.windows[], as specified by config.tp.nr_windows.

Settings applicable to SCHED QUOTA

This call manages thread groups running on *cpu*, defining per-group quota for limiting their CPU consumption.

- config.quota.op should define the operation to be carried out. Valid operations are:
 - sched_quota_add for creating a new thread group on cpu. The new group identifier will be written back to info.tgid upon success. A new group is given no initial runtime budget when created. sched quota set should be issued to enable it.
 - sched_quota_remove for deleting a thread group on cpu. The group identifier should be passed in config.quota.remove.tgid.
 - sched_quota_set for updating the scheduling parameters of a thread group defined on cpu.
 The group identifier should be passed in config.quota.set.tgid, along with the allotted percentage of the quota interval (config.quota.set.quota), and the peak percentage allowed (config.quota.set.quota peak).

All three operations fill in the *config.info* structure with the information reflecting the state of the scheduler on *cpu* with respect to *policy*, after the requested changes have been applied.

Parameters

len overall length of the configuration data (in bytes).

Returns

0 on success; an error number if:

- EINVAL, *cpu* is invalid, or *policy* is unsupported by the current kernel configuration, *len* is invalid, or *config* contains invalid parameters.
- ENOMEM, lack of memory to perform the operation.
- EBUSY, with *policy* equal to SCHED_QUOTA, if an attempt is made to remove a thread group which still manages threads.
- ESRCH, with policy equal to SCHED_QUOTA, if the group identifier required to perform the operation is not valid.

Tags

thread-unrestricted, switch-primary

6.58.2.9 int sched_setscheduler (pid_t pid, int policy, const struct sched_param * param)

Set the scheduling policy and parameters of the specified process.

This service set the scheduling policy of the Cobalt process identified by *pid* to the value *policy*, and its scheduling parameters (i.e. its priority) to the value pointed to by *param*.

If the current Linux thread ID is passed (see gettid(2)), this service turns the current regular POSIX thread into a Cobalt thread. If *pid* is neither the identifier of the current thread nor the identifier of an existing Cobalt thread, this service falls back to the regular sched setscheduler() service.

Parameters

pid	target process/thread;
policy	scheduling policy, one of SCHED_FIFO, SCHED_RR, or SCHED_OTHER;
param	scheduling parameters address.

Returns

0 on success;

an error number if:

- ESRCH, pid is invalid;
- EINVAL, policy or param->sched_priority is invalid;
- EAGAIN, insufficient memory available from the system heap, increase CONFIG_XENO_O

 PT SYS HEAPSZ;
- EFAULT, param is an invalid address;

See also

Specification.

Note

See sched setscheduler ex().

Tags

thread-unrestricted, switch-secondary, switch-primary

References sched_setscheduler_ex().

Referenced by sched setscheduler ex().

6.58.2.10 int sched_setscheduler_ex (pid_t pid, int policy, const struct sched_param_ex * param_ex)

Set extended scheduling policy of a process.

This service is an extended version of the sched_setscheduler() service, which supports Cobalt-specific and/or additional scheduling policies, not available with the host Linux environment. It sets the scheduling policy of the Cobalt process/thread identified by *pid* to the value *policy*, and the scheduling parameters (e.g. its priority) to the value pointed to by *par*.

If the current Linux thread ID or zero is passed (see gettid(2)), this service may turn the current regular POSIX thread into a Cobalt thread.

Parameters

pid	target process/thread. If zero, the current thread is assumed.
policy	scheduling policy, one of SCHED_WEAK, SCHED_FIFO, SCHED_COBALT, SC↔
	HED_RR, SCHED_SPORADIC, SCHED_TP, SCHED_QUOTA or SCHED_NOR⊷
	MAL;

param_ex address of scheduling parameters. As a special exception, a negative sched_← priority value is interpreted as if SCHED_WEAK was given in policy, using the absolute value of this parameter as the weak priority level.

When CONFIG_XENO_OPT_SCHED_WEAK is enabled, SCHED_WEAK exhibits priority levels in the [0..99] range (inclusive). Otherwise, sched_priority must be zero for the SCHED_WEAK policy.

Returns

0 on success;

an error number if:

- ESRCH, pid is not found;
- EINVAL, pid is negative, param_ex is NULL, any of policy or param_ex->sched_priority is invalid;
- EAGAIN, insufficient memory available from the system heap, increase CONFIG_XENO_O
 —
 PT_SYS_HEAPSZ;
- EFAULT, param_ex is an invalid address;

Note

See sched_setscheduler().

Tags

thread-unrestricted, switch-secondary, switch-primary

References sched_setscheduler().

Referenced by sched_setscheduler().

6.58.2.11 int sched_yield (void)

Yield the processor.

This function move the current thread at the end of its priority group.

Return values

0

See also

Specification.

Tags

thread-unrestricted, switch-primary

References XNRELAX, and XNWEAK.

Referenced by pthread_yield().

6.59 Semaphores

Cobalt/POSIX semaphore services.

Collaboration diagram for Semaphores:



Functions

• int sem_init (sem_t *sem, int pshared, unsigned int value)

Initialize an unnamed semaphore.

int sem_destroy (sem_t *sem)

Destroy an unnamed semaphore.

int sem_post (sem_t *sem)

Post a semaphore.

int sem_trywait (sem_t *sem)

Attempt to decrement a semaphore.

int sem_wait (sem_t *sem)

Decrement a semaphore.

• int sem_timedwait (sem_t *sem, const struct timespec *abs_timeout)

Attempt to decrement a semaphore with a time limit.

int sem_close (sem_t *sem)

Close a named semaphore.

• int sem_unlink (const char *name)

Unlink a named semaphore.

6.59.1 Detailed Description

Cobalt/POSIX semaphore services.

Semaphores are counters for resources shared between threads. The basic operations on semaphores are: increment the counter atomically, and wait until the counter is non-null and decrement it atomically.

Semaphores have a maximum value past which they cannot be incremented. The macro $SEM_VALU \leftarrow E_MAX$ is defined to be this maximum value.

6.59.2 Function Documentation

```
6.59.2.1 int sem_close ( sem_t * sem )
```

Close a named semaphore.

This service closes the semaphore *sem*. The semaphore is destroyed only when unlinked with a call to the sem_unlink() service and when each call to sem_open() matches a call to this service.

6.59 Semaphores 315

When a semaphore is destroyed, the memory it used is returned to the system heap, so that further references to this semaphore are not guaranteed to fail, as is the case for unnamed semaphores.

This service fails if *sem* is an unnamed semaphore.

sem	the semaphore to be closed.
-----	-----------------------------

Return values

0	on success;
-1	with errno set if:
	• EINVAL, the semaphore <i>sem</i> is invalid or is an unnamed semaphore.

See also

Specification.

Tags

thread-unrestricted, switch-secondary

6.59.2.2 int sem_destroy (sem_t * sem)

Destroy an unnamed semaphore.

This service destroys the semaphore *sem*. Threads currently blocked on *sem* are unblocked and the service they called return -1 with *errno* set to EINVAL. The semaphore is then considered invalid by all semaphore services (they all fail with *errno* set to EINVAL) except <u>sem_init()</u>.

This service fails if *sem* is a named semaphore.

Parameters

sem the semaphore to be destroyed.

Return values

always	O on success. If SEM_WARNDEL was mentioned in sem_init_np(), the semaphore is deleted as requested and a strictly positive value is returned to warn the caller if threads were pending on it, otherwise zero is returned. If SEM_NOBUSYDEL was mentioned in sem_init_np(), sem_destroy() may succeed only if no thread is waiting on the semaphore to delete, otherwise -EBUSY is returned.
-1	with errno set if:
	 EINVAL, the semaphore sem is invalid or a named semaphore;
	 EPERM, the semaphore sem is not process-shared and does not belong to the current process.
	 EBUSY, a thread is currently waiting on the semaphore sem with SEM_NOBUSYDEL set.

See also

Specification.

Tags

thread-unrestricted

6.59 Semaphores 317

6.59.2.3 int sem_init (sem_t * sem, int pshared, unsigned int value)

Initialize an unnamed semaphore.

This service initializes the semaphore *sm*, with the value *value*.

This service fails if *sm* is already initialized or is a named semaphore.

Parameters

sem	the semaphore to be initialized;
pshared	if zero, means that the new semaphore may only be used by threads in the same process as the thread calling sem_init(); if non zero, means that the new semaphore may be used by any thread that has access to the memory where the semaphore is allocated.
	anouted.
value	the semaphore initial value.

Return values

0	on success,
-1	with errno set if:
	• EBUSY, the semaphore <i>sm</i> was already initialized;
	 EAGAIN, insufficient memory available to initialize the semaphore, increase CONFIG_XENO_OPT_SHARED_HEAPSZ for a process- shared semaphore, or CONFIG_XENO_OPT_PRIVATE_HEAPSZ for a process-private semaphore.
	 EAGAIN, no registry slot available, check/raise CONFIG_XENO_ — OPT_REGISTRY_NRSLOTS.
	• EINVAL, the <i>value</i> argument exceeds <i>SEM_VALUE_MAX</i> .

See also

Specification.

Tags

thread-unrestricted

6.59.2.4 int sem_post (sem_t * sem)

Post a semaphore.

This service posts the semaphore *sem*.

If no thread is currently blocked on this semaphore, its count is incremented unless "pulse" mode is enabled for it (see sem_init_np(), SEM_PULSE). If a thread is blocked on the semaphore, the thread heading the wait queue is unblocked.

Parameters

sem	the semaphore to be signaled.
-----	-------------------------------

Return values

0	on success;
-1	with errno set if:
	EINVAL, the specified semaphore is invalid or uninitialized;
	 EPERM, the semaphore sm is not process-shared and does not belong to the current process;
	• EAGAIN, the semaphore count is SEM_VALUE_MAX.

See also

Specification.

Tags

unrestricted

 $6.59.2.5 \quad int \ sem_timedwait \ (\ sem_t * sem, \ const \ struct \ timespec * abs_timeout \)$

Attempt to decrement a semaphore with a time limit.

This service is equivalent to sem_wait(), except that the caller is only blocked until the timeout abs_
timeout expires.

Parameters

sem	the semaphore to be decremented;
abs_timeout	the timeout, expressed as an absolute value of the relevant clock for the semaphore,
	either CLOCK_MONOTONIC if SEM_RAWCLOCK was mentioned via sem_init_
	np(), or CLOCK_REALTIME otherwise.

Return values

0	on success;
-1	with errno set if:
	 EPERM, the caller context is invalid;
	 EINVAL, the semaphore is invalid or uninitialized;
	 EINVAL, the specified timeout is invalid;
	 EPERM, the semaphore sm is not process-shared and does not belong to the current process;
	 EINTR, the caller was interrupted by a signal while blocked in this service;
	 ETIMEDOUT, the semaphore could not be decremented and the specified timeout expired.

See also

Specification.

Tags

xthread-only, switch-primary

6.59 Semaphores 319

References sem_trywait().

6.59.2.6 int sem_trywait (sem_t * sem)

Attempt to decrement a semaphore.

This service is equivalent to sem_wait(), except that it returns immediately if the semaphore sem is currently depleted, and that it is not a cancellation point.

Parameters

sem	the semaphore to be decremented.
-----	----------------------------------

Return values

0	on success;
-1	with errno set if:
	 EINVAL, the specified semaphore is invalid or uninitialized;
	 EPERM, the semaphore sem is not process-shared and does not belong to the current process;
	 EAGAIN, the specified semaphore is currently fully depleted.
	•

See also

Specification.

Tags

xthread-only

Referenced by sem_timedwait(), and sem_wait().

6.59.2.7 int sem_unlink (const char * name)

Unlink a named semaphore.

This service unlinks the semaphore named *name*. This semaphore is not destroyed until all references obtained with sem_open() are closed by calling sem_close(). However, the unlinked semaphore may no longer be reached with the sem_open() service.

When a semaphore is destroyed, the memory it used is returned to the system heap, so that further references to this semaphore are not guaranteed to fail, as is the case for unnamed semaphores.

Parameters

name	the name of the semaphore to be unlinked.

Return values

0	on success;
-1	with errno set if:
	 ENAMETOOLONG, the length of the name argument exceeds 64 characters;
	ENOENT, the named semaphore does not exist.

See also

Specification.

Tags

thread-unrestricted, switch-secondary

6.59.2.8 int sem_wait (sem_t * sem)

Decrement a semaphore.

This service decrements the semaphore *sem* if it is currently if its value is greater than 0. If the semaphore's value is currently zero, the calling thread is suspended until the semaphore is posted, or a signal is delivered to the calling thread.

This service is a cancellation point for Cobalt threads (created with the pthread_create() service). When such a thread is cancelled while blocked in a call to this service, the semaphore state is left unchanged before the cancellation cleanup handlers are called.

Parameters

sem	the semaphore to be decremented.

Return values

0	on success;
-1	with errno set if:
	 EPERM, the caller context is invalid;
	 EINVAL, the semaphore is invalid or uninitialized;
	 EPERM, the semaphore sem is not process-shared and does not belong to the current process;
	 EINTR, the caller was interrupted by a signal while blocked in this service.

See also

Specification.

Tags

xthread-only, switch-primary

References sem trywait().

6.60 Thread management

Cobalt (POSIX) thread management services.

Collaboration diagram for Thread management:



Functions

- int pthread_create (pthread_t *ptid_r, const pthread_attr_t *attr, void *(*start)(void *), void *arg)

 Create a new thread.
- int pthread_setmode_np (int clrmask, int setmask, int *mode_r)

Set the mode of the current thread.

• int pthread_setname_np (pthread_t thread, const char *name)

Set a thread name.

int pthread_kill (pthread_t thread, int sig)

Send a signal to a thread.

int pthread_join (pthread_t thread, void **retval)

Wait for termination of a specified thread.

6.60.1 Detailed Description

Cobalt (POSIX) thread management services.

See also

Specification.

6.60.2 Function Documentation

6.60.2.1 int pthread_create (pthread_t * ptid_r, const pthread_attr_t * attr, void *(*)(void *) start, void * arg)

Create a new thread.

This service creates a thread managed by the Cobalt core in a dual kernel configuration.

Attributes of the new thread depend on the attr argument. If attr is NULL, default values for these attributes are used.

Returning from the start routine has the same effect as calling pthread exit() with the return value.

ptid_r	address where the identifier of the new thread will be stored on success;
attr	thread attributes;
start	thread start routine;
arg	opaque user-supplied argument passed to start;

Returns

0 on success:

an error number if:

- EINVAL, attr is invalid:
- EAGAIN, insufficient memory available from the system heap to create a new thread, increase CONFIG XENO OPT SYS HEAPSZ;
- EINVAL, thread attribute *inheritsched* is set to PTHREAD_INHERIT_SCHED and the calling thread does not belong to the Cobalt interface;

See also

Specification.

Note

When creating a Cobalt thread for the first time, libcobalt installs an internal handler for the SIGSHAD

OW signal. If you had previously installed a handler for such signal before that point, such handler will be exclusively called for any SIGSHADOW occurrence Xenomai did not send.

If, however, an application-defined handler for SIGSHADOW is installed afterwards, overriding the lib-cobalt handler, the new handler is required to call cobalt_sigshadow_handler() on entry. This routine returns a non-zero value for every occurrence of SIGSHADOW issued by the Cobalt core. If zero instead, the application-defined handler should process the signal.

int cobalt sigshadow handler(int sig, siginfo t *si, void *ctxt);

You should register your handler with sigaction(2), setting the SA SIGINFO flag.

Tags

thread-unrestricted, switch-secondary

6.60.2.2 int pthread_join (pthread_t thread, void ** retval)

Wait for termination of a specified thread.

If *thread* is running and joinable, this service blocks the caller until *thread* terminates or detaches. When *thread* terminates, the caller is unblocked and its return value is stored at the address *value_ptr*.

On the other hand, if *thread* has already finished execution, its return value collected earlier is stored at the address *value_ptr* and this service returns immediately.

This service is a cancelation point for Cobalt threads: if the calling thread is canceled while blocked in a call to this service, the cancelation request is honored and *thread* remains joinable.

Multiple simultaneous calls to pthread_join() specifying the same running target thread block all the callers until the target thread terminates.

thread	identifier of the thread to wait for;
retval	address where the target thread return value will be stored on success.

Returns

0 on success;

an error number if:

- ESRCH, thread is invalid;
- EDEADLK, attempting to join the calling thread;
- EINVAL, thread is detached;
- EPERM, the caller context is invalid.

See also

Specification.

Tags

xthread-only, switch-secondary, switch-primary

Referenced by rt_task_join().

6.60.2.3 int pthread_kill (pthread_t thread, int sig)

Send a signal to a thread.

This service send the signal *sig* to the Cobalt thread *thread* (created with pthread_create()). If *sig* is zero, this service check for existence of the thread *thread*, but no signal is sent.

Parameters

thread	thread identifier;
sig	signal number.

Returns

0 on success;

an error number if:

- EINVAL, sig is an invalid signal number;
- EAGAIN, the maximum number of pending signals has been exceeded;
- ESRCH, thread is an invalid thread identifier.

See also

Specification.

Tags

thread-unrestricted, switch-primary

6.60.2.4 int pthread_setmode_np (int clrmask, int setmask, int * mode_r)

Set the mode of the current thread.

This service sets the mode of the calling thread, which affects its behavior under particular circumstances. *clrmask* and *setmask* are two masks of mode bits which are respectively cleared and set by pthread_setmode_np():

- PTHREAD_LOCK_SCHED, when set, locks the scheduler, which prevents the current thread from being switched out until the scheduler is unlocked. Unless PTHREAD_DISABLE_LOCKBREAK is also set, the thread may still block, dropping the lock temporarily, in which case, the lock will be reacquired automatically when the thread resumes execution. When PTHREAD_LOCK_SCHED is cleared, the current thread drops the scheduler lock, and the rescheduling procedure is initiated.
- When set, PTHREAD_WARNSW enables debugging notifications for the current thread. A S

 IGDEBUG (Linux-originated) signal is sent when the following atypical or abnormal behavior is detected:
 - the current thread switches to secondary mode. Such notification comes in handy for detecting spurious relaxes, with one of the following reason codes:
 - * SIGDEBUG_MIGRATE_SYSCALL, if the thread issued a regular Linux system call.
 - * SIGDEBUG_MIGRATE_SIGNAL, if the thread had to leave real-time mode for handling a Linux signal.
 - * SIGDEBUG_MIGRATE_FAULT, if the thread had to leave real-time mode for handling a processor fault/exception.
 - the current thread is sleeping on a Cobalt mutex currently owned by a thread running in secondary mode, which reveals a priority inversion. In such an event, the reason code passed to the signal handler will be SIGDEBUG MIGRATE PRIOINV.
 - the current thread is about to sleep while holding a Cobalt mutex, and CONFIG_XENO_← OPT_DEBUG_MUTEX_SLEEP is enabled in the kernel configuration. In such an event, the reason code passed to the signal handler will be SIGDEBUG_MUTEX_SLEEP. Blocking for acquiring a mutex does not trigger such signal though.
 - the current thread has enabled PTHREAD_DISABLE_LOCKBREAK and PTHREAD_LOC

 K_SCHED, then attempts to block on a Cobalt service, which would cause a lock break. In such an event, the reason code passed to the signal handler will be SIGDEBUG_LOCK_B
 REAK.
- PTHREAD_DISABLE_LOCKBREAK disallows breaking the scheduler lock. Normally, the scheduler lock is dropped implicitly when the current owner blocks, then reacquired automatically when the owner resumes execution. If PTHREAD_DISABLE_LOCKBREAK is set, the scheduler lock owner would return with EINTR immediately from any blocking call instead (see PTHREAD_WA
 RNSW notifications).
- PTHREAD_CONFORMING can be passed in *setmask* to switch the current Cobalt thread to its preferred runtime mode. The only meaningful use of this switch is to force a real-time thread back to primary mode eagerly. Other usages have no effect.

This service is a non-portable extension of the Cobalt interface.

Parameters

clrmask	set of bits to be cleared.
setmask	set of bits to be set.
mode_r	If non-NULL, <i>mode_r</i> must be a pointer to a memory location which will be written upon success with the previous set of active mode bits. If NULL, the previous set of active mode bits will not be returned.

Returns

0 on success, otherwise:

• EINVAL, some bit in *clrmask* or *setmask* is invalid.

Note

Setting *clrmask* and *setmask* to zero leads to a nop, only returning the previous mode if *mode_r* is a valid address.

Attention

Issuing PTHREAD_CONFORMING is most likely useless or even introduces pure overhead in regular applications, since the Cobalt core performs the necessary mode switches, only when required.

Tags

xthread-only, switch-primary

6.60.2.5 int pthread_setname_np (pthread_t thread, const char * name)

Set a thread name.

This service set to *name*, the name of *thread*. This name is used for displaying information in /proc/xenomai/sched.

This service is a non-portable extension of the Cobalt interface.

Parameters

thread	target thread;	
name	name name of the thread.	

Returns

0 on success;

an error number if:

• ESRCH, thread is invalid.


Tags

xthread-only

6.61 Scheduling management

Cobalt scheduling management services.

Collaboration diagram for Scheduling management:



Functions

- int pthread_setschedparam (pthread_t thread, int policy, const struct sched_param *param)

 Set the scheduling policy and parameters of the specified thread.
- int pthread_setschedparam_ex (pthread_t thread, int policy, const struct sched_param_ex *param_ex)

Set extended scheduling policy of thread.

int pthread_getschedparam (pthread_t thread, int *__restrict__ policy, struct sched_param *__←
restrict__ param)

Get the scheduling policy and parameters of the specified thread.

int pthread_getschedparam_ex (pthread_t thread, int *__restrict__ policy_r, struct sched_param
 _ex *__restrict__ param_ex)

Get extended scheduling policy of thread.

int pthread yield (void)

Yield the processor.

6.61.1 Detailed Description

Cobalt scheduling management services.

6.61.2 Function Documentation

6.61.2.1 int pthread_getschedparam (pthread_t thread, int *__restrict__ policy, struct sched_param
* restrict param)

Get the scheduling policy and parameters of the specified thread.

This service returns, at the addresses *policy* and *par*, the current scheduling policy and scheduling parameters (i.e. priority) of the Cobalt thread *tid*. If *thread* is not the identifier of a Cobalt thread, this service fallback to the regular POSIX pthread_getschedparam() service.

Parameters

thread	target thread;

policy	address where the scheduling policy of tid is stored on success;
param	address where the scheduling parameters of <i>tid</i> is stored on success.

Returns

0 on success; an error number if:

• ESRCH, tid is invalid.

See also

Specification.

Tags

thread-unrestricted

References pthread_getschedparam_ex().

Referenced by pthread_getschedparam_ex().

```
6.61.2.2 int pthread_getschedparam_ex ( pthread_t thread, int *__restrict__ policy_r, struct sched_param_ex *__restrict__ param_ex )
```

Get extended scheduling policy of thread.

This service is an extended version of the regular pthread_getschedparam() service, which also supports Cobalt-specific policies, not available with the host Linux environment.

Parameters

thread	target thread;	
policy_r	address where the scheduling policy of thread is stored on success;	
param_ex	address where the scheduling parameters of thread are stored on success.	

Returns

0 on success; an error number if:

• ESRCH, thread is invalid.

See also

Specification.

Tags

thread-unrestricted

References pthread_getschedparam().

Referenced by pthread getschedparam().

6.61.2.3 int pthread_setschedparam (pthread_t thread, int policy, const struct sched_param * param)

Set the scheduling policy and parameters of the specified thread.

This service set the scheduling policy of the Cobalt thread identified by *pid* to the value *policy*, and its scheduling parameters (i.e. its priority) to the value pointed to by *param*.

If pthread_self() is passed, this service turns the current thread into a Cobalt thread. If *thread* is not the identifier of a Cobalt thread, this service falls back to the regular pthread_setschedparam() service.

Parameters

thread	target Cobalt thread;	
policy	scheduling policy, one of SCHED_FIFO, SCHED_RR, or SCHED_OTHER;	
param	address of scheduling parameters.	

Returns

0 on success;

an error number if:

- ESRCH, pid is invalid;
- EINVAL, policy or param->sched_priority is invalid;
- EAGAIN, insufficient memory available from the system heap, increase CONFIG_XENO_O
 —
 PT_SYS_HEAPSZ;
- EFAULT, param is an invalid address;

See also

Specification.

Note

See pthread_create(), pthread_setschedparam_ex().

Tags

thread-unrestricted, switch-secondary, switch-primary

References pthread_setschedparam_ex().

Referenced by pthread_setschedparam_ex().

6.61.2.4 int pthread_setschedparam_ex (pthread_t thread, int policy, const struct sched_param_ex * param_ex)

Set extended scheduling policy of thread.

This service is an extended version of the regular pthread_setschedparam() service, which supports Cobalt-specific scheduling policies, not available with the host Linux environment.

This service set the scheduling policy of the Cobalt thread to the value *policy*, and its scheduling parameters (e.g. its priority) to the value pointed to by *param_ex*.

If *thread* does not match the identifier of a Cobalt thread, this action falls back to the regular pthread_ setschedparam() service.

Parameters

thread	target Cobalt thread;	
policy	scheduling policy, one of SCHED_WEAK, SCHED_FIFO, SCHED_COBALT, SC⊷	
	HED_RR, SCHED_SPORADIC, SCHED_TP, SCHED_QUOTA or SCHED_NOR⊷	
	MAL;	

param_ex	scheduling parameters address. As a special exception, a negative sched_priority	
	value is interpreted as if SCHED_WEAK was given in <i>policy</i> , using the absolute	
	value of this parameter as the weak priority level.	

When CONFIG_XENO_OPT_SCHED_WEAK is enabled, SCHED_WEAK exhibits priority levels in the [0..99] range (inclusive). Otherwise, sched_priority must be zero for the SCHED_WEAK policy.

Returns

0 on success:

an error number if:

- ESRCH, thread is invalid;
- EINVAL, policy or param_ex->sched_priority is invalid;
- EAGAIN, insufficient memory available from the system heap, increase CONFIG_XENO_O

 PT SYS HEAPSZ;
- EFAULT, param_ex is an invalid address;
- EPERM, the calling process does not have superuser permissions.

See also

Specification.

Note

See pthread_create(), pthread_setschedparam().

Tags

thread-unrestricted, switch-secondary, switch-primary

References pthread_setschedparam().

Referenced by pthread setschedparam().

6.61.2.5 int pthread_yield (void)

Yield the processor.

This function move the current thread at the end of its priority group.

Return values

0

See also

Specification.

Tags

thread-unrestricted, switch-primary

References sched_yield().

6.62 Smokey API 331

6.62 Smokey API

A simple infrastructure for writing and running smoke tests.

A simple infrastructure for writing and running smoke tests.

Smokey is based on the Copperplate API, therefore is available over the single and dual kernel Xenomai configurations indifferently.

The API provides a set of services for declaring any number of test plugins, embodied into a test program. Each plugin usually implements a single smoke test, checking a particular feature of interest. Each plugin present in the running executable is automatically detected by the Smokey init routine. In addition, the Smokey API parses all arguments and options passed on the command line to the executable, running pre-defined actions which are therefore automatically recognized by all programs linked against the Smokey library.

Writing smoke tests with Smokey

A smoke test is composed of a routine which implements the test code, and a set of runtime settings/attributes for running such code. The routine prototype shall be:

```
int run_<test_name>(struct smokey_test *t, int argc, char *const argv[])
```

The test routine should return a zero value for success, or any negated POSIX error code for indicating the failure to the test driver (e.g. -EINVAL if some value is found to be wrong).

With *t* referring to the Smokey test descriptor, and *argc*, *argv* the argument count and vector expunged from all the inner options which may have been previously interpreted by the Smokey API and inner layers (such as Copperplate).

The Smokey API provides the services to declare a complete test (named **foo** in this example) as follows:

```
#include <smokey.h>
smokey_test_plugin(foo, // test name
                    SMOKEY_ARGLIST( // argument list
                          SMOKEY_INT(some_integer),
                          SMOKEY_STRING(some_string),
                          SMOKEY_BOOL(some_boolean),
               ),
                    // description
               "A dummy Smokey-based test plugin\n"
               "\taccepting three optional arguments:\n"
                '\tsome_integer=<value>\n"
                '\tsome_string=<string>\n"
               "\tsome_bool[=0/1]\n'
);
static int run_foo(struct smokey_test *t, int argc, char *const argv[])
     char *s_arg = NULL;
     bool b_arg = false;
int i_arg = 0, ret;
        ret = smokey_parse_args(t, argc, argv);
          return ret;
     if (SMOKEY_ARG_ISSET(foo, some_integer))
         i_arg = SMOKEY_ARG_INT(foo, some_integer);
      if (SMOKEY_ARG_ISSET(foo, some_string))
         s_arg = SMOKEY_ARG_STRING(foo, some_string);
     if (SMOKEY_ARG_ISSET(foo, some_boolean))
b_arg = SMOKEY_ARG_INT(foo, some_boolean);
     return run_some_hypothetical_smoke_test_code(i_arg, s_arg, b_arg);
```

As illustrated, a smoke test is at least composed of a test plugin descriptor (i.e. smokey_test_plugin()), and a run handler named after the test.

Test arguments

Smokey recognizes three argument declarators, namely: SMOKEY_INT(name) for a C (signed) integer, SMOKEY_BOOL(name) for a boolean value and SMOKEY_STRING(name) for a character string.

Each argument can be passed to the test code as a name=value pair, where *name* should match one of the declarators. Before the test-specific arguments can be accessed, a call to smokey_parse_args() must be issued by the test code, passing the parameters received in the run handler.

Once smokey_parse_args() has returned, each argument can be checked individually for presence. If a valid argument was matched on the command line, SMOKEY_ARG_ISSET(test_name, arg_name) returns non-zero. In the latter case, its value can be retrieved by a similar call to SMOKEY_ARG_IN (test_name, arg_name), SMOKEY_ARG_STRING(test_name, arg_name) or SMOKEY_ARG_BOO (test_name, arg_name).

In the above example, passing "some_integer=3" on the command line of any program implementing such Smokey-based test would cause the variable i_arg to receive "3" as a value.

Pre-defined Smokey options

Any program linked against the Smokey API implicitly recognizes the following options:

—list dumps the list of tests implemented in the program to stdout. The information given includes
the description strings provided in the plugin declarators (smokey_test_plugin()). The position and
symbolic name of each test is also issued, which may be used in id specifications with the –run
option (see below).

Note

Test positions may vary depending on changes to the host program like adding or removing other tests, the symbolic name however is stable and identifies each test uniquely.

-run[=<id[,id...]>] selects the tests to be run, determining the active test list among the overall set
of tests detected in the host program. The test driver code (e.g. implementing a test harness
program on top of Smokey) may then iterate over the smokey_test_list for accessing each active
test individually, in the enumeration order specified by the user.

If no argument is passed to -run, Smokey assumes that all tests detected in the current program should be picked, filling *smokey_test_list* with tests by increasing position order.

Otherwise, id may be a test position, a symbolic name, or a range thereof delimited by a dash character. A symbolic name may be matched using a glob(3) type regular expression.

id specification may be:

- 0-9, picks tests #0 to #9
- 3, picks tests #0 to #3
- 5-, picks tests #5 to the highest possible test position
- 2-0, picks tests #2 to #0, in decreasing order
- foo, picks test foo only
- 0,1,foo-picks tests #0, #1, and any test from foo up to the last test defined
- fo* picks any test with a name starting by "fo"
- –keep-going sets the boolean flag smokey_keep_going to a non-zero value, indicating to the test
 driver that receiving a failure code from a smoke test should not abort the test loop. This flag is not
 otherwise interpreted by the Smokey API.

6.62 Smokey API 333

 -verbose[=level] sets the integer smokey_verbose_mode to a non-zero value, which should be interpreted by all parties as the desired verbosity level (defaults to 1).

-vm gives a hint to the test code, about running in a virtual environment, such as KVM. When
passed, the boolean smokey_on_vm is set. Each test may act upon this setting, such as skipping
time-dependent checks that may fail due to any slowdown induced by the virtualization.

Writing a test driver based on the Smokey API

A test driver provides the main() entry point, which should iterate over the test list (*smokey_test_list*) prepared by the Smokey API, for running each test individually. The *for_each_smokey_test()* helper is available for iterating over the active test list.

When this entry point is called, all the initialization chores, including the test detection and the active test selection have been performed by the Smokey API already.

Issuing information notices

The printf-like *smokey_note()* routine is available for issuing notices to the output device (currently std-out), unless –silent was detected on the command line. smokey_note() outputs a terminating newline character. Notes are enabled for any verbosity level greater than zero.

Issuing trace messages

The printf-like *smokey_trace()* routine is available for issuing progress messages to the output device (currently stdout), unless –silent was detected on the command line. smokey_trace() outputs a terminating newline character. Traces are enabled for any verbosity level greater than one.

Therefore, a possible implementation of a test driver could be as basic as:

6.63 Asynchronous acquisition API

Collaboration diagram for Asynchronous acquisition API:



Data Structures

struct a4l_cmd_desc

Structure describing the asynchronous instruction.

Functions

• int a4l_snd_command (a4l_desc_t *dsc, a4l_cmd_t *cmd)

Send a command to an Analoy device.

int a4l_snd_cancel (a4l_desc_t *dsc, unsigned int idx_subd)

Cancel an asynchronous acquisition.

• int a4l_set_bufsize (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long size)

Change the size of the asynchronous buffer.

• int a4l_get_bufsize (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long *size)

Get the size of the asynchronous buffer.

• int a4l_mark_bufrw (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long cur, unsigned long *new)

Update the asynchronous buffer state.

• int a4l_poll (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long ms_timeout)

Get the available data count.

• int a4l_mmap (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long size, void **ptr)

Map the asynchronous ring-buffer into a user-space.

ANALOGY CMD xxx

Common command flags definitions

#define A4L_CMD_SIMUL 0x1

Do not execute the command, just check it.

#define A4L CMD BULK 0x2

Perform data recovery / transmission in bulk mode.

• #define A4L_CMD_WRITE 0x4

Perform a command which will write data to the device.

TRIG xxx

Command triggers flags definitions

#define TRIG NONE 0x00000001

Never trigger.

• #define TRIG_NOW 0x00000002

Trigger now + N ns.

#define TRIG FOLLOW 0x00000004

Trigger on next lower level trig.

• #define TRIG TIME 0x00000008

Trigger at time N ns.

#define TRIG_TIMER 0x00000010

Trigger at rate N ns.

• #define TRIG_COUNT 0x00000020

Trigger when count reaches N.

#define TRIG_EXT 0x00000040

Trigger on external signal N.

#define TRIG_INT 0x00000080

Trigger on analogy-internal signal N.

#define TRIG_OTHER 0x00000100

Driver defined trigger.

#define TRIG_WAKE_EOS 0x0020

Wake up on end-of-scan.

• #define TRIG_ROUND_MASK 0x00030000

Trigger not implemented yet.

#define TRIG_ROUND_NEAREST 0x00000000

Trigger not implemented yet.

• #define TRIG_ROUND_DOWN 0x00010000

Trigger not implemented yet.

#define TRIG_ROUND_UP 0x00020000

Trigger not implemented yet.

#define TRIG_ROUND_UP_NEXT 0x00030000

Trigger not implemented yet.

Channel macros

Specific precompilation macros and constants useful for the channels descriptors tab located in the command structure

• #define CHAN(a) ((a) & 0xffff)

Channel indication macro.

#define RNG(a) (((a) & 0xff) << 16)

Range definition macro.

#define AREF(a) (((a) & 0x03) << 24)

Reference definition macro.

#define FLAGS(a) ((a) & CR_FLAGS_MASK)

Flags definition macro.

#define PACK(a, b, c) (a | RNG(b) | AREF(c))

Channel + range + reference definition macro.

• #define PACK_FLAGS(a, b, c, d) (PACK(a, b, c) | FLAGS(d))

Channel + range + reference + flags definition macro.

• #define AREF GROUND 0x00

Analog reference is analog ground.

#define AREF_COMMON 0x01

Analog reference is analog common.

• #define AREF DIFF 0x02

Analog reference is differential.

#define AREF_OTHER 0x03

Analog reference is undefined.

6.63.1 Detailed Description

6.63.2 Function Documentation

```
6.63.2.1 int a4l_get_bufsize ( a4l_desc_t * dsc, unsigned int idx_subd, unsigned long * size )
```

Get the size of the asynchronous buffer.

During asynchronous acquisition, a ring-buffer enables the transfers from / to user-space. Functions like a4l_read() or a4l_write() recovers / sends data through this intermediate buffer. Please note, there is one ring-buffer per subdevice capable of asynchronous acquisition. By default, each buffer size is set to 64 KB.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
out	size	Buffer size

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong

References a4I descriptor::fd.

```
6.63.2.2 int a4l_mark_bufrw ( a4l_desc_t * dsc, unsigned int idx_subd, unsigned long cur, unsigned long * new )
```

Update the asynchronous buffer state.

When the mapping of the asynchronous ring-buffer (thanks to a4l_mmap() is disabled, common read / write syscalls have to be used. In input case, a4l_read() must be used for:

- the retrieval of the acquired data.
- the notification to the Analogy layer that the acquired data have been consumed, then the area in the ring-buffer which was containing becomes available. In output case, a4l_write() must be called to:
- send some data to the Analogy layer.
- signal the Analogy layer that a chunk of data in the ring-buffer must be used by the driver.

In mmap configuration, these features are provided by unique function named a4l_mark_bufrw(). In input case, a4l_mark_bufrw() can :

- recover the count of data newly available in the ring-buffer.
- notify the Analogy layer how many bytes have been consumed. In output case, a4l_mark_bufrw()
 can:
- · recover the count of data available for writing.
- notify Analogy that some bytes have been written.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	cur	Amount of consumed data
out	new	Amount of available data

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong; the descriptor and the new pointer should be checked; check also the kernel log ("dmesg")
- -EFAULT is returned if a user <-> kernel transfer went wrong

References a4l_descriptor::fd.

6.63.2.3 int a4l_mmap (a4l_desc_t * dsc, unsigned int idx_subd, unsigned long size, void ** ptr)

Map the asynchronous ring-buffer into a user-space.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	size	Size of the buffer to map
out	ptr	Address of the pointer containing the assigned address on return

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong, the descriptor and the pointer should be checked; check also the kernel log
- -EPERM is returned if the function is called in an RT context or if the buffer to resize is mapped in user-space (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- · -EBUSY is returned if the buffer is already mapped in user-space

References a4I descriptor::fd.

6.63.2.4 int a4l poll (a4l desc t * dsc, unsigned int idx subd, unsigned long ms timeout)

Get the available data count.

Parameters

338

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	ms_timeout	The number of miliseconds to wait for some data to be available. Passing A4L_INFINITE causes the caller to block indefinitely until some data is available. Passing A4L_NONBLOCK causes the function to return immediately without waiting for any available data

Returns

the available data count. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- · -EINTR is returned if calling task has been unblocked by a signal

References a4l_descriptor::fd.

Referenced by a4l_async_read(), and a4l_async_write().

6.63.2.5 int a4l set bufsize (a4l desc t * dsc, unsigned int idx subd, unsigned long size)

Change the size of the asynchronous buffer.

During asynchronous acquisition, a ring-buffer enables the transfers from / to user-space. Functions like a4l_read() or a4l_write() recovers / sends data through this intermediate buffer. The function a4l_set_bufsize() can change the size of the ring-buffer. Please note, there is one ring-buffer per subdevice capable of asynchronous acquisition. By default, each buffer size is set to 64 KB.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	size	New buffer size, the maximal tolerated value is 16MB (A4L_BUF_M↔ AXSIZE)

Returns

0 on success. Otherwise:

- -EINVAL is returned if the analogy descriptor is not correct or if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EPERM is returned if the function is called in an RT context or if the buffer to resize is mapped in user-space (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -EBUSY is returned if the selected subdevice is already processing an asynchronous operation
- -ENOMEM is returned if the system is out of memory

References a4l_sys_bufcfg(), and a4l_descriptor::fd.

6.63.2.6 int a4l snd cancel (a4l desc t * dsc, unsigned int idx subd)

Cancel an asynchronous acquisition.

The function a4l_snd_cancel() is devoted to stop an asynchronous acquisition configured thanks to an Analogy command.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Subdevice index

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EIO is returned if the selected subdevice does not support asynchronous operation

References a4l_descriptor::fd.

6.63.2.7 int a4l_snd_command (a4l_desc_t * dsc, a4l_cmd_t * cmd)

Send a command to an Analoy device.

The function a4l_snd_command() triggers asynchronous acquisition.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	cmd	Command structure

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -ENOMEM is returned if the system is out of memory
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -EIO is returned if the selected subdevice cannot handle command
- -EBUSY is returned if the selected subdevice is already processing an asynchronous operation

References a4l_descriptor::fd.

6.64 Asynchronous acquisition API

Collaboration diagram for Asynchronous acquisition API:



Functions

- int a4l_async_read (a4l_desc_t *dsc, void *buf, size_t nbyte, unsigned long ms_timeout)

 Perform asynchronous read operation on the analog input subdevice.
- int a4l_async_write (a4l_desc_t *dsc, void *buf, size_t nbyte, unsigned long ms_timeout)

 Perform asynchronous write operation on the analog input subdevice.

6.64.1 Detailed Description

6.64.2 Function Documentation

6.64.2.1 int a4l_async_read (**a4l_desc_t** * dsc, void * buf, size_t nbyte, unsigned long ms_timeout)

Perform asynchronous read operation on the analog input subdevice.

The function a4l_async_read() is only useful for acquisition configured through an Analogy command.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
out	buf	Input buffer
in	nbyte	Number of bytes to read
in	ms_timeout	The number of miliseconds to wait for some data to be available. Pass-
		ing A4L_INFINITE causes the caller to block indefinitely until some
		data is available. Passing A4L_NONBLOCK causes the function to
		return immediately without waiting for any available data

Returns

Number of bytes read, otherwise negative error code:

- -EINVAL is returned if some argument is missing or wrong, the descriptor should be checked; check also the kernel log
- -ENOENT is returned if the device's reading subdevice is idle (no command was sent)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -EINTR is returned if calling task has been unblocked by a signal

References a4l_poll(), a4l_sys_read(), a4l_descriptor::fd, and a4l_descriptor::idx_read_subd.

6.64.2.2 int a4l_async_write (**a4l_desc_t** * dsc, void * buf, size_t nbyte, unsigned long ms_timeout)

Perform asynchronous write operation on the analog input subdevice.

The function a4l_async_write() is only useful for acquisition configured through an Analogy command.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	buf	Ouput buffer
in	nbyte	Number of bytes to write
in	ms_timeout	The number of miliseconds to wait for some free area to be available. Passing A4L_INFINITE causes the caller to block indefinitely until some data is available. Passing A4L_NONBLOCK causes the function to return immediately without waiting any available space to write data.

Returns

Number of bytes written, otherwise negative error code:

- -EINVAL is returned if some argument is missing or wrong, the descriptor should be checked; check also the kernel log
- -ENOENT is returned if the device's reading subdevice is idle (no command was sent)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- · -EINTR is returned if calling task has been unblocked by a signal

References a4l_poll(), a4l_sys_write(), a4l_descriptor::fd, and a4l_descriptor::idx_write_subd.

6.65 Software calibration API

Collaboration diagram for Software calibration API:



Functions

- int a4l_read_calibration_file (char *name, struct a4l_calibration_data *data)

 Read the analogy generated calibration file.
- int a4l_get_softcal_converter (struct a4l_polynomial *converter, int subd, int chan, int range, struct a4l_calibration_data *data)

Get the polynomial that will be use for the software calibration.

• int a4l_rawtodcal (a4l_chinfo_t *chan, double *dst, void *src, int cnt, struct a4l_polynomial *converter)

Convert raw data (from the driver) to calibrated double units.

• int a4l_dcaltoraw (a4l_chinfo_t *chan, void *dst, double *src, int cnt, struct a4l_polynomial *converter)

Convert double values to raw calibrated data using polynomials.

6.65.1 Detailed Description

6.65.2 Function Documentation

6.65.2.1 int a4l_dcaltoraw (a4l_chinfo_t * chan, void * dst, double * src, int cnt, struct a4l_polynomial * converter)

Convert double values to raw calibrated data using polynomials.

Parameters

in	chan	Channel descriptor
out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of conversion to perform
in	converter	Conversion polynomial

Returns

the count of conversion performed, otherwise a negative error code:

 -EINVAL is returned if some argument is missing or wrong; chan, rng and the pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_dcaltoraw()

References a4I sizeof chan().

6.65.2.2 int a4l_get_softcal_converter (struct a4l_polynomial * converter, int subd, int chan, int range, struct a4l_calibration_data * data)

Get the polynomial that will be use for the software calibration.

Parameters

out	converter	Polynomial to be used on the software calibration
in	subd	Subdevice index
in	chan	Channel
in	range	Range
in	data	Calibration data read from the calibration file

Returns

-1 on error

6.65.2.3 int a4l_rawtodcal (a4l_chinfo_t * chan, double * dst, void * src, int cnt, struct a4l_polynomial * converter)

Convert raw data (from the driver) to calibrated double units.

Parameters

in	chan	Channel descriptor
out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of conversion to perform
in	converter	Conversion polynomial

Returns

the count of conversion performed, otherwise a negative error code:

• -EINVAL is returned if some argument is missing or wrong; chan, rng and the pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_rawtodcal()

References a4l_sizeof_chan().

6.65.2.4 int a4l_read_calibration_file (char * name, struct a4l_calibration_data * data)

Read the analogy generated calibration file.

Parameters

in	name	Name of the calibration file
out	data	Pointer to the calibration file contents

6.66 Descriptor Syscall API

Collaboration diagram for Descriptor Syscall API:



Data Structures

struct a4l_descriptor

Structure containing device-information useful to users.

Functions

int a4l_sys_desc (int fd, a4l_desc_t *dsc, int pass)
 Get a descriptor on an attached device.

ANALOGY_xxx_DESC

Constants used as argument so as to define the description depth to recover

- #define A4L_BSC_DESC 0x0
 BSC stands for basic descriptor (device data)
- #define A4L CPLX DESC 0x1

CPLX stands for complex descriptor (subdevice + channel + range data)

- 6.66.1 Detailed Description
- 6.66.2 Function Documentation
- 6.66.2.1 int a4l_sys_desc (int fd, a4l_desc_t * dsc, int pass)

Get a descriptor on an attached device.

Once the device has been attached, the function a4l_get_desc() retrieves various information on the device (subdevices, channels, ranges, etc.). The function a4l_get_desc() can be called twice:

- The first time, almost all the fields, except sbdata, are set (board_name, nb_subd, idx_read_subd, idx_write_subd, magic, sbsize); the last field, sbdata, is supposed to be a pointer on a buffer, which size is defined by the field sbsize.
- The second time, the buffer pointed by sbdata is filled with data about the subdevices, the channels and the ranges.

Between the two calls, an allocation must be performed in order to recover a buffer large enough to contain all the data. These data are set up according a root-leaf organization (device -> subdevice -> channel -> range). They cannot be accessed directly; specific functions are available so as to retrieve them:

- a4l_get_subdinfo() to get some subdevice's characteristics.
- a4l get chaninfo() to get some channel's characteristics.
- a4l_get_rnginfo() to get some range's characteristics.

Parameters

in	fd	Driver file descriptor
out	dsc	Device descriptor
in	pass	Description level to retrieve:
		 A4L_BSC_DESC to get the basic descriptor (notably the size of the data buffer to allocate).
		 A4L_CPLX_DESC to get the complex descriptor, the data buffer is filled with characteristics about the subdevices, the channels and the ranges.

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong; the pass argument should be checked; check also the kernel log ("dmesg")
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -ENODEV is returned if the descriptor is incoherent (the device may be unattached)


References A4L_BSC_DESC, a4l_descriptor::magic, a4l_descriptor::sbdata, and a4l_descriptor ⇒ ::sbsize.

Referenced by a4l_fill_desc(), and a4l_open().

6.67 Descriptor API 347

6.67 Descriptor API

Collaboration diagram for Descriptor API:



Functions

- int a4l_open (a4l_desc_t *dsc, const char *fname)
 - Open an Analogy device and basically fill the descriptor.
- int a4l_close (a4l_desc_t *dsc)
 - Close the Analogy device related with the descriptor.
- int a4l_fill_desc (a4l_desc_t *dsc)
 - Fill the descriptor with subdevices, channels and ranges data.
- int a4l_get_subdinfo (a4l_desc_t *dsc, unsigned int subd, a4l_sbinfo_t **info)
 - Get an information structure on a specified subdevice.
- int a4l_get_chinfo (a4l_desc_t *dsc, unsigned int subd, unsigned int chan, a4l_chinfo_t **info)

 Get an information structure on a specified channel.
- int a4l_get_rnginfo (a4l_desc_t *dsc, unsigned int subd, unsigned int chan, unsigned int rng, a4l
 rnginfo t **info)

Get an information structure on a specified range.

6.67.1 Detailed Description

This is the API interface used to fill and use Analogy device descriptor structure

6.67.2 Function Documentation

Close the Analogy device related with the descriptor.

The file descriptor is associated with a context. The context is one of the enabler of asynchronous transfers. So, by closing the file descriptor, the programer must keep in mind that the currently occuring asynchronous transfer will cancelled.

Parameters

in	dsc	Device descriptor

Returns

0 on success. Otherwise:

 -EINVAL is returned if some argument is missing or wrong; the the dsc pointer should be checked; check also the kernel log ("dmesg")

References a4l_sys_close(), and a4l_descriptor::fd.

```
6.67.2.2 int a4l_fill_desc ( a4l_desc_t * dsc )
```

Fill the descriptor with subdevices, channels and ranges data.

Parameters

in	dsc	Device descriptor partly filled by a4l_open().
	400	Bovios descriptor partly fined by a fi_opon().

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong; the the dsc pointer should be checked; check also the kernel log ("dmesg")
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -ENODEV is returned if the descriptor is incoherent (the device may be unattached)

References A4L_CPLX_DESC, a4l_sys_desc(), a4l_descriptor::fd, and a4l_descriptor::magic.

6.67.2.3 int a4l_get_chinfo (**a4l_desc_t** * dsc, unsigned int subd, unsigned int chan, a4l_chinfo_t ** info)

Get an information structure on a specified channel.

Parameters

in	dsc	Device descriptor filled by a4l_open() and a4l_fill_desc()
in	subd	Subdevice index
in	chan	Channel index
out	info	Channel information structure

Returns

0 on success. Otherwise:

 -EINVAL is returned if some argument is missing or wrong; subd, chan and the dsc pointer should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_get_chinfo()

References a4l_descriptor::magic, a4l_descriptor::nb_subd, and a4l_descriptor::sbdata.

Referenced by a4l_find_range().

6.67.2.4 int a4l_get_rnginfo (**a4l_desc_t** * dsc, unsigned int subd, unsigned int chan, unsigned int rng, a4l rnginfo t ** info)

Get an information structure on a specified range.

6.67 Descriptor API 349

Parameters

in	dsc	Device descriptor filled by a4l_open() and a4l_fill_desc()
in	subd	Subdevice index
in	chan	Channel index
in	rng	Range index
out	info	Range information structure

Returns

0 on success. Otherwise:

 -EINVAL is returned if some argument is missing or wrong; subd, chan, rng and the dsc pointer should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_get_rnginfo()

References a4I descriptor::magic, a4I descriptor::nb subd, and a4I descriptor::sbdata.

Referenced by a4l_find_range().

6.67.2.5 int a4l_get_subdinfo (a4l_desc_t * dsc, unsigned int subd, a4l_sbinfo_t ** info)

Get an information structure on a specified subdevice.

Parameters

in	dsc	Device descriptor filled by a4l_open() and a4l_fill_desc()
in	subd	Subdevice index
out	info	Subdevice information structure

Returns

0 on success. Otherwise:

• -EINVAL is returned if some argument is missing or wrong; subd and the dsc pointer should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_get_subdinfo().

References a4I descriptor::magic, a4I descriptor::nb subd, and a4I descriptor::sbdata.

Referenced by a4l_sync_dio().

6.67.2.6 int a4l_open (a4l_desc_t * dsc, const char * fname)

Open an Analogy device and basically fill the descriptor.

Parameters

out	dsc	Device descriptor
in	fname	Device name

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong; the fname and the dsc pointer should be checked; check also the kernel log ("dmesg")
- -EFAULT is returned if a user <-> kernel transfer went wrong

References A4L_BSC_DESC, a4l_sys_close(), a4l_sys_desc(), a4l_sys_open(), and a4l_descriptor::fd.

6.68 Math API

Collaboration diagram for Math API:



Functions

int a4l_math_polyfit (unsigned r_dim, double *r, double orig, const unsigned dim, double *x, double *y)

Calculate the polynomial fit.

- void a4l_math_mean (double *pmean, double *val, unsigned nr)

 Calculate the aritmetic mean of an array of values.
- void a4l_math_stddev (double *pstddev, double mean, double *val, unsigned nr)
- Calculate the standard deviation of an array of values.

 void a4l_math_stddev_of_mean (double *pstddevm, double mean, double *val, unsigned nr)
- void a4l_math_stddev_of_mean (double *pstddevm, double mean, double *val, unsigned nr)
 Calculate the standard deviation of the mean.

6.68.1 Detailed Description

6.68.2 Function Documentation

6.68.2.1 void a4l_math_mean (double * pmean, double * val, unsigned nr)

Calculate the aritmetic mean of an array of values.

Parameters

out	pmean	Pointer to the resulting value
in	val	Array of input values
in	nr	Number of array elements

6.68.2.2 int a4l_math_polyfit (unsigned r_dim, double * r, double orig, const unsigned dim, double * x, double * y)

Calculate the polynomial fit.

Parameters

in	r_dim	Number of elements of the resulting polynomial
out	r	Polynomial

6.68 Math API 351

in	orig	
in	dim	Number of elements in the polynomials
in	X	Polynomial
in	У	Polynomial

Operation:

We are looking for Res such that A.Res = Y, with A the Vandermonde matrix made from the X vector.

Using the least square method, this means finding Res such that: $A^{t}A.Res = A^{t}Y$

If we write A = Q.R with $Q^{\hat{}}t.Q = 1$, and R non singular, this can be reduced to: R.Res = $Q^{\hat{}}t.Y$ mat_qr() gives us R and $Q^{\hat{}}t.Y$ from A and Y

We can then obtain Res by back substitution using mat_upper_triangular_backsub() with R upper triangular.

6.68.2.3 void a4l_math_stddev (double * pstddev, double mean, double * val, unsigned nr)

Calculate the standard deviation of an array of values.

Parameters

out	pstddev	Pointer to the resulting value
in	mean	Mean value
in	val	Array of input values
in	nr	Number of array elements

Referenced by a4l_math_stddev_of_mean().

6.68.2.4 void a4l_math_stddev_of_mean (double * pstddevm, double mean, double * val, unsigned nr)

Calculate the standard deviation of the mean.

Parameters

out	pstddevm	Pointer to the resulting value
in	mean	Mean value
in	val	Array of input values
in	nr	Number of array elements

References a4l_math_stddev().

6.69 Range / conversion API

Collaboration diagram for Range / conversion API:



Functions

• int a4l_sizeof_chan (a4l_chinfo_t *chan)

Get the size in memory of an acquired element.

int a4l_sizeof_subd (a4l_sbinfo_t *subd)

Get the size in memory of a digital acquired element.

• int a4l_find_range (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int idx_chan, unsigned long unit, double min, double max, a4l_rnginfo_t **rng)

Find the must suitable range.

• int a4l_rawtoul (a4l_chinfo_t *chan, unsigned long *dst, void *src, int cnt)

Unpack raw data (from the driver) into unsigned long values.

• int a4l_rawtof (a4l_chinfo_t *chan, a4l_rnginfo_t *rng, float *dst, void *src, int cnt)

Convert raw data (from the driver) to float-typed samples.

int a4l_rawtod (a4l_chinfo_t *chan, a4l_rnginfo_t *rng, double *dst, void *src, int cnt)

Convert raw data (from the driver) to double-typed samples.

int a4l_ultoraw (a4l_chinfo_t *chan, void *dst, unsigned long *src, int cnt)

Pack unsigned long values into raw data (for the driver)

• int a4l_ftoraw (a4l_chinfo_t *chan, a4l_rnginfo_t *rng, void *dst, float *src, int cnt)

Convert float-typed samples to raw data (for the driver)

• int a4l_dtoraw (a4l_chinfo_t *chan, a4l_rnginfo_t *rng, void *dst, double *src, int cnt)

Convert double-typed samples to raw data (for the driver)

6.69.1 Detailed Description

6.69.2 Function Documentation

6.69.2.1 int a4l dtoraw (a4l chinfo t*chan, a4l rnginfo t*rng, void*dst, double*src, int cnt)

Convert double-typed samples to raw data (for the driver)

Parameters

in	chan	Channel descriptor
in	rng	Range descriptor

out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of conversion to perform

Returns

the count of conversion performed, otherwise a negative error code:

 -EINVAL is returned if some argument is missing or wrong; chan, rng and the pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_dtoraw()

References A4L RNG FACTOR, and a4l sizeof chan().

6.69.2.2 int a4l_find_range (a4l_desc_t * dsc, unsigned int idx_subd, unsigned int idx_chan, unsigned long unit, double min, double max, a4l_rnginfo_t ** rng)

Find the must suitable range.

Parameters

in	dsc	Device descriptor filled by a4l_open() and a4l_fill_desc()
in	idx_subd	Index of the concerned subdevice
in	idx_chan	Index of the concerned channel
in	unit	Unit type used in the range
in	min	Minimal limit value
in	max	Maximal limit value
out	rng	Found range

Returns

The index of the most suitable range on success. Otherwise:

- -ENOENT is returned if a suitable range is not found.
- -EINVAL is returned if some argument is missing or wrong; idx_subd, idx_chan and the dsc pointer should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_find_range()

References a4l_get_chinfo(), a4l_get_rnginfo(), A4L_RNG_FACTOR, A4L_RNG_UNIT, and a4l_ \leftarrow descriptor::magic.

6.69.2.3 int a4l_ftoraw (a4l_chinfo_t * chan, a4l_rnginfo_t * rng, void * dst, float * src, int cnt)

Convert float-typed samples to raw data (for the driver)

Parameters

in	chan	Channel descriptor
in	rng	Range descriptor
out	dst	Ouput buffer
in	src	Input buffer

in	cnt	Count of conversion to perform
111	Ont	Count of conversion to perform

Returns

the count of conversion performed, otherwise a negative error code:

• -EINVAL is returned if some argument is missing or wrong; chan, rng and the pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_ftoraw()

References A4L_RNG_FACTOR, and a4l_sizeof_chan().

Convert raw data (from the driver) to double-typed samples.

Parameters

in	chan	Channel descriptor
in	rng	Range descriptor
out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of conversion to perform

Returns

the count of conversion performed, otherwise a negative error code:

 -EINVAL is returned if some argument is missing or wrong; chan, rng and the pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_rawtod()

References A4L_RNG_FACTOR, and a4l_sizeof_chan().

Convert raw data (from the driver) to float-typed samples.

Parameters

in	chan	Channel descriptor
in	rng	Range descriptor
out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of conversion to perform

Returns

the count of conversion performed, otherwise a negative error code:

• -EINVAL is returned if some argument is missing or wrong; chan, rng and the pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_rawtod()

References A4L RNG FACTOR, and a4l sizeof chan().

6.69.2.6 int a4l_rawtoul (a4l_chinfo_t * chan, unsigned long * dst, void * src, int cnt)

Unpack raw data (from the driver) into unsigned long values.

This function takes as input driver-specific data and scatters each element into an entry of an unsigned long table. It is a convenience routine which performs no conversion, just copy.

Parameters

in	chan	Channel descriptor
out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of transfer to copy

Returns

the count of copy performed, otherwise a negative error code:

 -EINVAL is returned if some argument is missing or wrong; chan, dst and src pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_ultoraw()

References a4l_sizeof_chan().

Get the size in memory of an acquired element.

According to the board, the channels have various acquisition widths. With values like 8, 16 or 32, there is no problem finding out the size in memory (1, 2, 4); however with widths like 12 or 24, this function might be helpful to guess the size needed in RAM for a single acquired element.

Parameters

in	chan	Channel descriptor

Returns

the size in memory of an acquired element, otherwise a negative error code:

-EINVAL is returned if the argument chan is NULL

Referenced by a4l_dcaltoraw(), a4l_ftoraw(), a4l_rawtod(), a4l_rawtod(),

```
6.69.2.8 int a4l sizeof subd (a4l sbinfo t*subd)
```

Get the size in memory of a digital acquired element.

This function is only useful for DIO subdevices. Digital subdevices are a specific kind of subdevice on which channels are regarded as bits composing the subdevice's bitfield. During a DIO acquisition, all bits are sampled. Therefore, a4l_sizeof_chan() is useless in this case and we have to use a4l_sizeof_cban(). With bitfields which sizes are 8, 16 or 32, there is no problem finding out the size in memory (1, 2, 4); however with widths like 12 or 24, this function might be helpful to guess the size needed in RAM for a single acquired element.

Parameters

in	subd	Subdevice descriptor
----	------	----------------------

Returns

the size in memory of an acquired element, otherwise a negative error code:

• -EINVAL is returned if the argument chan is NULL or if the subdevice is not a digital subdevice

References A4L_SUBD_DI, A4L_SUBD_DIO, A4L_SUBD_DO, and A4L_SUBD_TYPES. Referenced by a4l_sync_dio().

6.69.2.9 int a4l_ultoraw (a4l_chinfo_t * chan, void * dst, unsigned long * src, int cnt)

Pack unsigned long values into raw data (for the driver)

This function takes as input a table of unsigned long values and gather them according to the channel width. It is a convenience routine which performs no conversion, just formatting.

Parameters

in	chan	Channel descriptor
out	dst	Ouput buffer
in	src	Input buffer
in	cnt	Count of transfer to copy

Returns

the count of copy performed, otherwise a negative error code:


 -EINVAL is returned if some argument is missing or wrong; chan, dst and src pointers should be checked; check also the kernel log ("dmesg"); WARNING: a4l_fill_desc() should be called before using a4l_ultoraw()

References a4I sizeof chan().

6.70 Level 1 API 357

6.70 Level 1 API

Collaboration diagram for Level 1 API:



Modules

- Asynchronous acquisition API
- Descriptor API
- Synchronous acquisition API

6.70.1 Detailed Description

6.71 Synchronous acquisition API

Collaboration diagram for Synchronous acquisition API:



Data Structures

• struct a4l instruction

Structure describing the synchronous instruction.

struct a4l_instruction_list

Structure describing the list of synchronous instructions.

Macros

#define A4L_INSN_WAIT_MAX 100000
 Maximal wait duration.

Functions

- int a4l_snd_insnlist (a4l_desc_t *dsc, a4l_insnlst_t *arg)

 Perform a list of synchronous acquisition misc operations.
- int a4l_snd_insn (a4l_desc_t *dsc, a4l_insn_t *arg)

Perform a synchronous acquisition misc operation.

Instruction type

Flags to define the type of instruction

- #define A4L_INSN_READ (0 | A4L_INSN_MASK_READ)
 Read instruction.
- #define A4L_INSN_WRITE (1 | A4L_INSN_MASK_WRITE)

Write instruction.

#define A4L_INSN_BITS

"Bits" instruction

• #define A4L_INSN_CONFIG

Configuration instruction.

• #define A4L_INSN_GTOD

Get time instruction.

#define A4L INSN WAIT

Wait instruction.

#define A4L_INSN_INTTRIG

Trigger instruction (to start asynchronous acquisition)

Configuration instruction type

Values to define the type of configuration instruction

- #define A4L_INSN_CONFIG_DIO_INPUT 0
- #define A4L INSN CONFIG DIO OUTPUT 1
- #define A4L_INSN_CONFIG_DIO_OPENDRAIN 2
- #define A4L_INSN_CONFIG_ANALOG_TRIG 16
- #define A4L INSN CONFIG ALT SOURCE 20
- #define A4L_INSN_CONFIG_DIGITAL TRIG 21
- #define A4L INSN CONFIG BLOCK SIZE 22
- #define A4L_INSN_CONFIG_TIMER_1 23
- #define A4L INSN CONFIG FILTER 24
- #define A4L_INSN_CONFIG_CHANGE_NOTIFY 25
- #define A4L INSN CONFIG SERIAL CLOCK 26
- #define A4L INSN CONFIG BIDIRECTIONAL DATA 27
- #define A4L INSN CONFIG DIO QUERY 28
- #define A4L INSN CONFIG PWM OUTPUT 29
- #define A4L_INSN_CONFIG_GET_PWM_OUTPUT 30
- #define A4L INSN CONFIG ARM 31
- #define A4L_INSN_CONFIG_DISARM 32
- #define A4L_INSN_CONFIG_GET_COUNTER_STATUS 33
- #define A4L INSN CONFIG RESET 34
- #define A4L_INSN_CONFIG_GPCT_SINGLE_PULSE_GENERATOR 1001 /* Use CTR as single pulsegenerator */
- #define A4L_INSN_CONFIG_GPCT_PULSE_TRAIN_GENERATOR 1002 /* Use CTR as pulse-traingenerator */
- #define A4L_INSN_CONFIG_GPCT_QUADRATURE_ENCODER 1003 /* Use the counter as encoder */
- #define A4L INSN CONFIG SET GATE SRC 2001 /* Set gate source */
- #define A4L_INSN_CONFIG_GET_GATE_SRC 2002 /* Get gate source */
- #define A4L INSN CONFIG SET CLOCK SRC 2003 /* Set master clock source */
- #define A4L_INSN_CONFIG_GET_CLOCK_SRC 2004 /* Get master clock source */
- #define A4L INSN CONFIG SET OTHER SRC 2005 /* Set other source */
- #define A4L_INSN_CONFIG_SET_COUNTER_MODE 4097
- #define A4L_INSN_CONFIG_SET_ROUTING 4099
- #define A4L_INSN_CONFIG_GET_ROUTING 4109

Counter status bits

Status bits for INSN_CONFIG_GET_COUNTER_STATUS

- #define A4L_COUNTER_ARMED 0x1
- #define A4L COUNTER COUNTING 0x2
- #define A4L COUNTER TERMINAL COUNT 0x4

IO direction

Values to define the IO polarity

- #define A4L_INPUT 0
- #define A4L OUTPUT 1
- #define A4L OPENDRAIN 2

Events types

Values to define the Analogy events. They might used to send some specific events through the instruction interface.

- #define A4L EV START 0x00040000
- #define A4L EV SCAN BEGIN 0x00080000
- #define A4L EV CONVERT 0x00100000
- #define **A4L_EV_SCAN_END** 0x00200000
- #define **A4L_EV_STOP** 0x00400000

6.71.1 Detailed Description

6.71.2 Function Documentation

```
6.71.2.1 int a4l snd insn ( a4l desc t * dsc, a4l insn t * arg )
```

Perform a synchronous acquisition misc operation.

The function a4l snd insn() triggers a synchronous acquisition.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	arg	Instruction structure

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -ENOMEM is returned if the system is out of memory

References a4I descriptor::fd.

Referenced by a4l_config_subd(), a4l_sync_dio(), a4l_sync_read(), and a4l_sync_write().

Perform a list of synchronous acquisition misc operations.

The function a4l_snd_insnlist() is able to send many synchronous instructions on a various set of sub-devices, channels, etc.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	arg	Instructions list structure

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong


• -ENOMEM is returned if the system is out of memory

References a4I_descriptor::fd.

Referenced by a4l_sync_read(), and a4l_sync_write().

6.72 Level 2 API

Collaboration diagram for Level 2 API:



Modules

- Asynchronous acquisition API
- Software calibration API
- Math API
- Range / conversion API
- Synchronous acquisition API

6.72.1 Detailed Description

6.73 Synchronous acquisition API

Collaboration diagram for Synchronous acquisition API:



Functions

• int a4l_sync_write (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void *buf, size_t nbyte)

Perform a synchronous acquisition write operation.

• int a4l_sync_read (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void *buf, size_t nbyte)

Perform a synchronous acquisition read operation.

- int a4l_sync_dio (a4l_desc_t *dsc, unsigned int idx_subd, void *mask, void *buf)
 - Perform a synchronous acquisition digital acquisition.
- int a4l_config_subd (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int type,...)

 Configure a subdevice.

6.73.1 Detailed Description

6.73.2 Function Documentation

6.73.2.1 int a4I config subd (a4I desc t * dsc, unsigned int idx subd, unsigned int type, ...)

Configure a subdevice.

a4l_config_subd() takes a variable count of arguments. According to the configuration type, some additional argument is necessary:

- A4L_INSN_CONFIG_DIO_INPUT: the channel index (unsigned int)
- A4L_INSN_CONFIG_DIO_OUTPUT: the channel index (unsigned int)
- A4L INSN CONFIG DIO QUERY: the returned DIO polarity (unsigned int *)

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	type	Configuration parameter

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -ENOSYS is returned if the configuration parameter is not supported

6.73.2.2 int a4l_sync_dio (a4l_desc_t * dsc, unsigned int idx_subd, void * mask, void * buf)

Perform a synchronous acquisition digital acquisition.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	mask	Write mask which indicates which bit(s) must be modified
in,out	buf	Input / output buffer

Returns

Number of bytes read, otherwise negative error code:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -ENOMEM is returned if the system is out of memory
- -ENOSYS is returned if the driver does not provide any handler "instruction bits"

References a4l_get_subdinfo(), A4L_INSN_BITS, a4l_sizeof_subd(), a4l_snd_insn(), a4l_instruction :: data_size, and a4l_instruction::type.

6.73.2.3 int a4l_sync_read (**a4l_desc_t** * dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void * buf, size_t nbyte)

Perform a synchronous acquisition read operation.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	chan_desc	Channel descriptor (channel, range and reference)
in	ns_delay	Optional delay (in nanoseconds) to wait between the setting of the in-
		put channel and sample(s) acquisition(s).
in	buf	Input buffer
in	nbyte	Number of bytes to read

Returns

Number of bytes read, otherwise negative error code:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong

· -ENOMEM is returned if the system is out of memory

References A4L_INSN_READ, A4L_INSN_WAIT, a4l_snd_insn(), a4l_snd_insnlist(), a4l_instruction_\circ list::count, a4l_instruction::data, a4l_instruction::data_size, and a4l_instruction::type.

6.73.2.4 int a4l_sync_write (**a4l_desc_t** * dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void * buf, size_t nbyte)

Perform a synchronous acquisition write operation.

Parameters

in	dsc	Device descriptor filled by a4l_open() (and optionally a4l_fill_desc())
in	idx_subd	Index of the concerned subdevice
in	chan_desc	Channel descriptor (channel, range and reference)
in	ns_delay	Optional delay (in nanoseconds) to wait between the setting of the in-
		put channel and sample(s) acquisition(s).
in	buf	Output buffer
in	nbyte	Number of bytes to write

Returns


Number of bytes written, otherwise negative error code:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -ENOMEM is returned if the system is out of memory

References A4L_INSN_WAIT, A4L_INSN_WRITE, a4l_snd_insn(), a4l_snd_insnlist(), a4l_instruction list::count, a4l_instruction::data, a4l_instruction::data size, and a4l_instruction::type.

6.74 Analogy user API

Collaboration diagram for Analogy user API:



Modules

- Level 1 API
- Level 2 API
- Level 0 API


6.74.1 Detailed Description

This is the API interface of Analogy library

6.75 Level 0 API 367

6.75 Level 0 API

Collaboration diagram for Level 0 API:



Modules

- Descriptor Syscall API
- Basic Syscall API
- Attach / detach Syscall API

6.75.1 Detailed Description

System call interface to core Analogy services

This interface should not be used directly by applications.

6.76 Basic Syscall API

Collaboration diagram for Basic Syscall API:



Functions

• int a4l_sys_open (const char *fname)

Open an Analogy device.

• int a4l_sys_close (int fd)

Close an Analogy device.

int a4l_sys_read (int fd, void *buf, size_t nbyte)

Read from an Analogy device.

int a4l_sys_write (int fd, void *buf, size_t nbyte)

Write to an Analogy device.

6.76.1 Detailed Description

6.76.2 Function Documentation

6.76.2.1 int a4l_sys_close (int fd)

Close an Analogy device.

Parameters

in fd File descriptor as returned by a4I_sys_open()

Returns

0 on success, otherwise a negative error code.

Referenced by a4l_close(), and a4l_open().

6.76.2.2 int a4l_sys_open (const char * fname)

Open an Analogy device.

Parameters

in	fname	Device name

Returns

Positive file descriptor value on success, otherwise a negative error code.

Referenced by a4l_open().

6.76.2.3 int a4l_sys_read (int fd, void * buf, size_t nbyte)

Read from an Analogy device.

The function a4l_read() is only useful for acquisition configured through an Analogy command.

Parameters

in	fd	File descriptor as returned by a4l_sys_open()
out	buf	Input buffer
in	nbyte	Number of bytes to read

Returns

Number of bytes read. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -ENOENT is returned if the device's reading subdevice is idle (no command was sent)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- · -EINTR is returned if calling task has been unblocked by a signal

Referenced by a4I async read().

6.76.2.4 int a4l_sys_write (int fd, void * buf, size_t nbyte)

Write to an Analogy device.

The function a4l_write() is only useful for acquisition configured through an Analogy command.

Parameters

in	fd	File descriptor as returned by a4l_sys_open()
in	buf	Output buffer
in	nbyte	Number of bytes to write

Returns

Number of bytes written. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -ENOENT is returned if the device's writing subdevice is idle (no command was sent)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -EINTR is returned if calling task has been unblocked by a signal

Referenced by a4l async write().

6.77 Attach / detach Syscall API

Collaboration diagram for Attach / detach Syscall API:



Functions

- int a4l_sys_attach (int fd, a4l_lnkdesc_t *arg)
 Attach an Analogy device to a driver.
- int a4l_sys_detach (int fd)

Detach an Analogy device from a driver.

• int a4l_sys_bufcfg (int fd, unsigned int idx_subd, unsigned long size)

Configure the buffer size.

6.77.1 Detailed Description

6.77.2 Function Documentation

6.77.2.1 int a4l_sys_attach (int fd, a4l_lnkdesc_t * arg)

Attach an Analogy device to a driver.

Parameters

in	fd	File descriptor as returned by a4l_sys_open()
in	arg	Link descriptor argument

Returns

0 on success. Otherwise:

- -ENOMEM is returned if the system is out of memory
- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -ENODEV is returned in case of internal error (Please, type "dmesg" for more info)
- -ENXIO is returned in case of internal error (Please, type "dmesg" for more info)

6.77.2.2 int a4l_sys_bufcfg (int fd, unsigned int idx_subd, unsigned long size)

Configure the buffer size.

This function can configure the buffer size of the file descriptor currently in use. If the subdevice index is set to A4L_BUF_DEFMAGIC, it can also define the default buffser size at open time.

Parameters

in	fd	File descriptor as returned by a4l_sys_open()
in	idx_subd	Index of the concerned subdevice
in	size	Buffer size to be set

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EPERM is returned if the function is called in an RT context or if the buffer to resize is mapped in user-space (Please, type "dmesg" for more info)
- -EFAULT is returned if a user <-> kernel transfer went wrong
- -EBUSY is returned if the selected subdevice is already processing an asynchronous operation
- · -ENOMEM is returned if the system is out of memory

Referenced by a4l_set_bufsize().

6.77.2.3 int a4l_sys_detach (int fd)

Detach an Analogy device from a driver.

Parameters

in	fd File descriptor as returned by a4l_sys_open()	
----	--	--

Returns

0 on success. Otherwise:

- -EINVAL is returned if some argument is missing or wrong (Please, type "dmesg" for more info)
- -EBUSY is returned if the device to be detached is in use
- -EPERM is returned if the devive to be detached still has some buffer mapped in user-space
- -ENODEV is returned in case of internal error (Please, type "dmesg" for more info)
- -ENXIO is returned in case of internal error (Please, type "dmesg" for more info)

6.78 Alarm services

General-purpose watchdog timers.

Collaboration diagram for Alarm services:



Data Structures

struct RT_ALARM_INFO
 Alarm status descriptor.

Functions

- int rt_alarm_start (RT_ALARM *alarm, RTIME value, RTIME interval)
 Start an alarm.
- int rt_alarm_stop (RT_ALARM *alarm) Stop an alarm.

otop arraiarri.

- int rt_alarm_inquire (RT_ALARM *alarm, RT_ALARM_INFO *info)
 Query alarm status.
- int rt_alarm_create (RT_ALARM *alarm, const char *name, void(*handler)(void *arg), void *arg)

 Create an alarm object.
- int rt_alarm_delete (RT_ALARM *alarm)

 Delete an alarm.

6.78.1 Detailed Description

General-purpose watchdog timers.

Alarms are general-purpose watchdog timers. Alchemy tasks may create any number of alarms and use them to run a user-defined handler, after a specified initial delay has elapsed. Alarms can be either one shot or periodic; in the latter case, the real-time system automatically reprograms the alarm for the next shot according to a user-defined interval value.

6.78.2 Function Documentation

6.78.2.1 int rt_alarm_create (RT_ALARM * alarm, const char * name, void(*)(void *arg) handler, void * arg)

Create an alarm object.

This routine creates an object triggering an alarm routine at a specified time in the future. Alarms can be periodic or oneshot, depending on the reload interval value passed to rt_alarm_start().

6.78 Alarm services 373

Parameters

alarm	The address of an alarm descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the alarm. When non-NULL and non-empty, a copy of this string is used for indexing the created alarm into the object registry.
handler	The address of the routine to call when the alarm expires. This routine is passed the <i>arg</i> value.
arg	A user-defined opaque argument passed to the handler.

Returns

Zero is returned upon success. Otherwise:

- -ENOMEM is returned if the system fails to get memory from the local pool in order to create the alarm.
- -EEXIST is returned if the *name* is conflicting with an already registered alarm.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Alarms are process-private objects and thus cannot be shared by multiple processes, even if they belong to the same Xenomai session.

```
6.78.2.2 int rt_alarm_delete ( RT_ALARM * alarm )
```

Delete an alarm.

This routine deletes an alarm object previously created by a call to rt_alarm_create().

Parameters

alarm	The alarm descriptor.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *alarm* is not a valid alarm descriptor.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

```
6.78.2.3 int rt_alarm_inquire ( RT_ALARM * alarm, RT_ALARM_INFO * info )
```

Query alarm status.

This routine returns the status information about the specified *alarm*.

Parameters

alarm	The alarm descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if alarm is not a valid alarm descriptor.

Tags

unrestricted, switch-primary

References RT_ALARM_INFO::active, RT_ALARM_INFO::expiries, and RT_ALARM_INFO::name.

6.78.2.4 int rt_alarm_start (RT_ALARM * alarm, RTIME value, RTIME interval)

Start an alarm.

This routine programs the trigger date of an alarm object. An alarm can be either periodic or oneshot, depending on the *interval* value.

Alarm handlers are always called on behalf of Xenomai's internal timer event routine. Therefore, Xenomai routines which can be called from such handlers are restricted to the set of services available on behalf of an asynchronous context.

This service overrides any previous setup of the expiry date and reload interval for the alarm.

Parameters

alarm	The alarm descriptor.
value	The relative date of the first expiry, expressed in clock ticks (see note).
interval	The reload value of the alarm. It is a periodic interval value to be used for repro-
	gramming the next alarm shot, expressed in clock ticks (see note). If interval is
	equal to TM_INFINITE, the alarm will not be reloaded after it has expired.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if alarm is not a valid alarm descriptor.
- · -EPERM is returned if this service was called from an invalid context.

Tags

xthread-only, switch-primary

Note

Each of the initial *value* and *interval* is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.78.2.5 int rt_alarm_stop (RT_ALARM * alarm)

Stop an alarm.

This routine disables an alarm object, preventing any further expiry until it is re-enabled via rt_alarm_← start().

6.78 Alarm services 375

Parameters

alarm Th	he alarm descriptor.
----------	----------------------

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if *alarm* is not a valid alarm descriptor.

Tags

unrestricted, switch-primary

6.79 Buffer services

Lightweight FIFO IPC mechanism.

Collaboration diagram for Buffer services:



Data Structures

struct RT_BUFFER_INFO
 Buffer status descriptor.

Macros

#define B_PRIO 0x1 /* Pend by task priority order. */
 Creation flags.

Functions

- int rt_buffer_create (RT_BUFFER *bf, const char *name, size_t bufsz, int mode)

 Create an IPC buffer.
- int rt_buffer_delete (RT_BUFFER *bf)

Delete an IPC buffer.

 ssize_t rt_buffer_write_timed (RT_BUFFER *bf, const void *ptr, size_t size, const struct timespec *abs_timeout)

Write to an IPC buffer.

- static ssize_t rt_buffer_write_until (RT_BUFFER *bf, const void *ptr, size_t size, RTIME timeout)

 Write to an IPC buffer (with absolute scalar timeout).
- static ssize_t rt_buffer_write (RT_BUFFER *bf, const void *ptr, size_t size, RTIME timeout)

 Write to an IPC buffer (with relative scalar timeout).
- ssize_t rt_buffer_read_timed (RT_BUFFER *bf, void *ptr, size_t size, const struct timespec *abs
 _timeout)

Read from an IPC buffer.

- static ssize_t rt_buffer_read_until (RT_BUFFER *bf, void *ptr, size_t size, RTIME timeout)

 Read from an IPC buffer (with absolute scalar timeout).
- static ssize_t rt_buffer_read (RT_BUFFER *bf, void *ptr, size_t size, RTIME timeout)

Read from an IPC buffer (with relative scalar timeout).

• int rt_buffer_clear (RT_BUFFER *bf)

Clear an IPC buffer.

• int rt_buffer_inquire (RT_BUFFER *bf, RT_BUFFER_INFO *info)

Query buffer status.

int rt_buffer_bind (RT_BUFFER *bf, const char *name, RTIME timeout)

6.79 Buffer services 377

Bind to an IPC buffer.

• int rt buffer unbind (RT BUFFER *bf)

Unbind from an IPC buffer.

6.79.1 Detailed Description

Lightweight FIFO IPC mechanism.

A buffer is a lightweight IPC mechanism, implementing a fast, one-way producer-consumer data path. All messages written are buffered in a single memory area in strict FIFO order, until read either in blocking or non-blocking mode.

Message are always atomically handled on the write side (i.e. no interleave, no short writes), whilst only complete messages are normally returned to the read side. However, short reads may happen under a well-defined situation (see note in rt_buffer_read()), albeit they can be fully avoided by proper use of the buffer.

6.79.2 Macro Definition Documentation

6.79.2.1 #define B PRIO 0x1 /* Pend by task priority order. */

Creation flags.

Referenced by rt buffer create().

6.79.3 Function Documentation

6.79.3.1 int rt_buffer_bind (RT_BUFFER * bf, const char * name, RTIME timeout)

Bind to an IPC buffer.

This routine creates a new descriptor to refer to an existing IPC buffer identified by its symbolic name. If the object does not exist on entry, the caller may block until a buffer of the given name is created.

Parameters

bf	The address of a buffer descriptor filled in by the operation. Contents of this memory
	is undefined upon failure.
name	A valid NULL-terminated name which identifies the buffer to bind to. This string
	should match the object name argument passed to rt_buffer_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.79.3.2 int rt buffer clear (RT BUFFER * bf)

Clear an IPC buffer.

This routine empties a buffer from any data.

Parameters

bf The buffer descriptor.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if *bf* is not a valid buffer descriptor.

Tags

unrestricted, switch-primary

6.79.3.3 int rt buffer create (RT BUFFER * bf, const char * name, size t bufsz, int mode)

Create an IPC buffer.

This routine creates an IPC object that allows tasks to send and receive data asynchronously via a memory buffer. Data may be of an arbitrary length, albeit this IPC is best suited for small to medium-sized messages, since data always have to be copied to the buffer during transit. Large messages may be more efficiently handled by message queues (RT_QUEUE).

Parameters

bf	The address of a buffer descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the buffer. When non-NULL and non-empty, a copy of this string is used for indexing the created buffer into the object registry.
bufsz	The size of the buffer space available to hold data. The required memory is obtained from the main heap.
mode	The buffer creation mode. The following flags can be OR'ed into this bitmask, each of them affecting the new buffer:

- B_FIFO makes tasks pend in FIFO order for reading data from the buffer.
- B_PRIO makes tasks pend in priority order for reading data from the buffer.

This parameter also applies to tasks blocked on the buffer's write side (see rt_buffer_write()).

6.79 Buffer services 379

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if mode is invalid or bufsz is zero.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the buffer.
- -EEXIST is returned if the *name* is conflicting with an already registered buffer.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Buffers can be shared by multiple processes which belong to the same Xenomai session.

References B_PRIO.

```
6.79.3.4 int rt buffer delete ( RT BUFFER * bf )
```

Delete an IPC buffer.

This routine deletes a buffer object previously created by a call to rt buffer create().

Parameters

bf	The buffer descriptor.
----	------------------------

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if bf is not a valid buffer descriptor.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

```
6.79.3.5 int rt_buffer_inquire ( RT_BUFFER * bf, RT_BUFFER_INFO * info )
```

Query buffer status.

This routine returns the status information about the specified buffer.

Parameters

bf	The buffer descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if bf is not a valid buffer descriptor.

Tags

unrestricted, switch-primary

References RT_BUFFER_INFO::availmem, RT_BUFFER_INFO::iwaiters, RT_BUFFER_INFO::name, RT_BUFFER_INFO::owaiters, and RT_BUFFER_INFO::totalmem.

```
6.79.3.6 ssize_t rt_buffer_read ( RT_BUFFER * bf, void * ptr, size_t len, RTIME timeout ) [inline], [static]
```

Read from an IPC buffer (with relative scalar timeout).

This routine is a variant of rt_buffer_read_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

bf	The buffer descriptor.
ptr	A pointer to a memory area which will be written upon success with the received
	data.
len	The length in bytes of the memory area pointed to by ptr.
timeout	A delay expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_buffer_read_timed().

```
6.79.3.7 ssize_t rt_buffer_read_timed ( RT_BUFFER * bf, void * ptr, size_t len, const struct timespec * abs_timeout )
```

Read from an IPC buffer.

This routine reads the next message from the specified buffer. If no message is available on entry, the caller is allowed to block until enough data is written to the buffer, or a timeout elapses.

Parameters

bf	The buffer descriptor.
ptr	A pointer to a memory area which will be written upon success with the received
	data.
len	The length in bytes of the memory area pointed to by ptr. Under normal circum-
	stances, rt_buffer_read_timed() only returns entire messages as specified by the
	len argument, or an error value. However, short reads are allowed when a potential
	deadlock situation is detected (see note below).

6.79 Buffer services 381

abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for a mes-
	sage to be available from the buffer (see note). Passing NULL causes the caller to
	block indefinitely until enough data is available. Passing { .tv_sec = 0, .tv_nsec = 0 }
	causes the service to return immediately without blocking in case not enough data
	is available.

Returns

The number of bytes read from the buffer is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs_timeout is reached before a complete message arrives.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and not enough data is immediately available on entry to form a complete message.
- -EINTR is returned if rt_task_unblock() was called for the current task before enough data became available to form a complete message.
- -EINVAL is returned if *bf* is not a valid buffer descriptor, or *len* is greater than the actual buffer length.
- -EIDRM is returned if *bf* is deleted while the caller was waiting for data. In such event, *bf* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Note

A short read (i.e. fewer bytes returned than requested by *len*) may happen whenever a pathological use of the buffer is encountered. This condition only arises when the system detects that one or more writers are waiting for sending data, while a reader would have to wait for receiving a complete message at the same time. For instance, consider the following sequence, involving a 1024-byte buffer (bf) and two threads:

writer thread > rt_write_buffer(&bf, ptr, 1, TM_INFINITE); (one byte to read, 1023 bytes available for sending) writer thread > rt_write_buffer(&bf, ptr, 1024, TM_INFINITE); (writer blocks - no space for another 1024-byte message) reader thread > rt_read_buffer(&bf, ptr, 1024, TM_INFINITE); (short read - a truncated (1-byte) message is returned)

In order to prevent both threads to wait for each other indefinitely, a short read is allowed, which may be completed by a subsequent call to rt_buffer_read() or rt_buffer_read_until(). If that case arises, thread priorities, buffer and/or message lengths should likely be fixed, in order to eliminate such condition.

Tags

xthread-nowait, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_buffer_read(), and rt_buffer_read_until().

```
6.79.3.8 ssize_t rt_buffer_read_until ( RT_BUFFER * bf, void * ptr, size_t len, RTIME abs_timeout ) [inline], [static]
```

Read from an IPC buffer (with absolute scalar timeout).

This routine is a variant of rt_buffer_read_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

bf	The buffer descriptor.
ptr	A pointer to a memory area which will be written upon success with the received
	data.
len	The length in bytes of the memory area pointed to by ptr.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_buffer_read_timed().

6.79.3.9 int rt buffer unbind (RT BUFFER * bf)

Unbind from an IPC buffer.

Parameters

bf	The buffer descriptor.

This routine releases a previous binding to an IPC buffer. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

```
6.79.3.10 ssize_t rt_buffer_write ( RT_BUFFER * bf, const void * ptr, size_t len, RTIME timeout ) [inline], [static]
```

Write to an IPC buffer (with relative scalar timeout).

This routine is a variant of rt_buffer_write_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

bf	The buffer descriptor.
ptr	The address of the message data to be written to the buffer.
len	The length in bytes of the message data.
timeout	A delay expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_buffer_write_timed().

6.79.3.11 ssize_t rt_buffer_write_timed (RT_BUFFER * bf, const void * ptr, size_t len, const struct timespec * abs_timeout)

Write to an IPC buffer.

This routine writes a message to the specified buffer. If not enough buffer space is available on entry to hold the message, the caller is allowed to block until enough room is freed, or a timeout elapses, whichever comes first.

6.79 Buffer services 383

Parameters

bf	The buffer descriptor.
ptr	The address of the message data to be written to the buffer.
len	The length in bytes of the message data. Zero is a valid value, in which case the
	buffer is left untouched, and zero is returned to the caller.
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for enough
	buffer space to be available to hold the message (see note). Passing NULL causes
	the caller to block indefinitely until enough buffer space is available. Passing { .tv_~
	sec = 0, .tv_nsec = 0 } causes the service to return immediately without blocking in
	case of buffer space shortage.

Returns

The number of bytes written to the buffer is returned upon success. Otherwise:

- -ETIMEDOUT is returned if the absolute *abs_timeout* date is reached before enough buffer space is available to hold the message.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and no buffer space is immediately available on entry to hold the message.
- -EINTR is returned if rt_task_unblock() was called for the current task before enough buffer space became available to hold the message.
- -EINVAL is returned if *bf* is not a valid buffer descriptor, or *len* is greater than the actual buffer length.
- -EIDRM is returned if *bf* is deleted while the caller was waiting for buffer space. In such event, *bf* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_buffer_write(), and rt_buffer_write_until().

6.79.3.12 ssize_t rt_buffer_write_until (RT_BUFFER * bf, const void * ptr, size_t len, RTIME abs timeout) [inline], [static]

Write to an IPC buffer (with absolute scalar timeout).

This routine is a variant of rt_buffer_write_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

bf The buffer descriptor.	
---------------------------	--

ptr	The address of the message data to be written to the buffer.
len	The length in bytes of the message data.
abs_timeout	An absolute date expressed in clock ticks.

Tags


xthread-nowait, switch-primary

References rt_buffer_write_timed().

6.80 Condition variable services

POSIXish condition variable mechanism.

Collaboration diagram for Condition variable services:



Data Structures

struct RT_COND_INFO

Condition variable status descriptor.

Functions

• int rt_cond_create (RT_COND *cond, const char *name)

Create a condition variable.

• int rt_cond_delete (RT_COND *cond)

Delete a condition variable.

• int rt_cond_signal (RT_COND *cond)

Signal a condition variable.

int rt_cond_broadcast (RT_COND *cond)

Broadcast a condition variable.

int rt_cond_wait_timed (RT_COND *cond, RT_MUTEX *mutex, const struct timespec *abs_
 timeout)

Wait on a condition variable.

static int rt_cond_wait_until (RT_COND *cond, RT_MUTEX *mutex, RTIME timeout)

Wait on a condition variable (with absolute scalar timeout).

• static int rt_cond_wait (RT_COND *cond, RT_MUTEX *mutex, RTIME timeout)

Wait on a condition variable (with relative scalar timeout).

int rt_cond_inquire (RT_COND *cond, RT_COND_INFO *info)

Query condition variable status.

• int rt_cond_bind (RT_COND *cond, const char *name, RTIME timeout)

Bind to a condition variable.

• int rt_cond_unbind (RT_COND *cond)

Unbind from a condition variable.

6.80.1 Detailed Description

POSIXish condition variable mechanism.

A condition variable is a synchronization mechanism which allows tasks to suspend execution until some predicate on some arbitrary shared data is satisfied.

The basic operations on conditions are: signal the condition (when the predicate becomes true), and wait for the condition, blocking the task execution until another task signals the condition. A condition variable must always be associated with a mutex, to avoid a well-known race condition where a task prepares to wait on a condition variable and another task signals the condition just before the first task actually waits on it.

6.80.2 Function Documentation

```
6.80.2.1 int rt cond bind ( RT COND * cond, const char * name, RTIME timeout )
```

Bind to a condition variable.

This routine creates a new descriptor to refer to an existing condition variable identified by its symbolic name. If the object not exist on entry, the caller may block until a condition variable of the given name is created.

Parameters

cond	The address of a condition variable descriptor filled in by the operation. Contents of
	this memory is undefined upon failure.
name	A valid NULL-terminated name which identifies the condition variable to bind to. This
	string should match the object name argument passed to rt_cond_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if timeout is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.80.2.2 int rt_cond_broadcast (RT_COND * cond)

Broadcast a condition variable.

All tasks currently waiting on the condition variable are immediately unblocked.

Parameters

cond	The condition variable descriptor.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if cond is not a valid condition variable descriptor.

Tags

unrestricted, switch-primary

References pthread_cond_broadcast().

6.80.2.3 int rt cond create (RT COND * cond, const char * name)

Create a condition variable.

Create a synchronization object which allows tasks to suspend execution until some predicate on shared data is satisfied.

Parameters

cond	The address of a condition variable descriptor which can be later used to identify
	uniquely the created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the condition variable. When non-
	NULL and non-empty, a copy of this string is used for indexing the created condition
	variable into the object registry.

Returns

Zero is returned upon success. Otherwise:

- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the condition variable.
- -EEXIST is returned if the *name* is conflicting with an already registered condition variable.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Condition variables can be shared by multiple processes which belong to the same Xenomai session.

Attention

If the underlying threading library does not support pthread_condattr_setclock(), timings with Alchemy condition variables will be based on CLOCK_REALTIME, and may therefore be affected by updates to the system date (e.g. NTP). This typically concerns legacy setups based on the linuxthreads library. In the normal case, timings are based on CLOCK_MONOTONIC.

References pthread_cond_destroy(), pthread_cond_init(), pthread_condattr_destroy(), pthread_ \leftarrow condattr_init(), pthread_condattr_setclock(), and pthread_condattr_setpshared().

```
6.80.2.4 int rt_cond_delete ( RT_COND * cond )
```

Delete a condition variable.

This routine deletes a condition variable object previously created by a call to rt_cond_create().

Parameters

```
cond The condition variable descriptor.
```

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if alarm is not a valid condition variable descriptor.
- -EPERM is returned if this service was called from an asynchronous context.
- -EBUSY is returned upon an attempt to destroy the object referenced by *cond* while it is referenced (for example, while being used in a rt_cond_wait(), rt_cond_wait_timed() or rt_cond_wait_until() by another task).

Tags

thread-unrestricted, switch-secondary

References pthread_cond_destroy().

```
6.80.2.5 int rt_cond_inquire ( RT_COND * cond, RT_COND_INFO * info )
```

Query condition variable status.

This routine returns the status information about the specified condition variable.

Parameters

cond	The condition variable descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if cond is not a valid condition variable descriptor.

Tags

unrestricted, switch-primary

References RT COND INFO::name.

```
6.80.2.6 int rt_cond_signal ( RT_COND * cond )
```

Signal a condition variable.

If the condition variable *cond* is pended, this routine immediately unblocks the first waiting task (by queuing priority order).

Parameters

cond	The condition variable descriptor.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if cond is not a valid condition variable descriptor.

Tags

unrestricted, switch-primary

References pthread_cond_signal().

```
6.80.2.7 int rt_cond_unbind ( RT_COND * cond )
```

Unbind from a condition variable.

Parameters

cond	The condition variable descriptor.
------	------------------------------------

This routine releases a previous binding to a condition variable. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

```
6.80.2.8 int rt_cond_wait ( RT_COND * cond, RT_MUTEX * mutex, RTIME timeout ) [inline], [static]
```

Wait on a condition variable (with relative scalar timeout).

This routine is a variant of rt_cond_wait_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

cond	The condition variable descriptor.
mutex	The address of the mutex serializing the access to the shared data.
timeout	A delay expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_cond_wait_timed().

```
6.80.2.9 int rt_cond_wait_timed ( RT_COND * cond, RT_MUTEX * mutex, const struct timespec * abs_timeout )
```

Wait on a condition variable.

This service atomically releases the mutex and blocks the calling task, until the condition variable *cond* is signaled or a timeout occurs, whichever comes first. The mutex is re-acquired before returning from this service.

Parameters

cond	The condition variable descriptor.
mutex	The address of the mutex serializing the access to the shared data.
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for the condition variable to be signaled (see note). Passing NULL causes the caller to block indefinitely.

Returns

Zero is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs timeout is reached before the condition variable is signaled.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } .
- -EINTR is returned if rt_task_unblock() was called for the current task.
- -EINVAL is returned if cond is not a valid condition variable descriptor.
- -EIDRM is returned if *cond* is deleted while the caller was waiting on the condition variable. In such event, *cond* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-only, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

References pthread_cond_timedwait(), and pthread_cond_wait().

Referenced by rt_cond_wait(), and rt_cond_wait_until().

Wait on a condition variable (with absolute scalar timeout).

This routine is a variant of rt_cond_wait_timed() accepting an abs_timeout specification expressed as a scalar value.

Parameters

cond	The condition variable descriptor.
mutex	The address of the mutex serializing the access to the shared data.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_cond_wait_timed().

6.81 Event flag group services

Inter-task notification mechanism based on discrete flags.

Collaboration diagram for Event flag group services:



Data Structures

• struct RT EVENT INFO

Event status descriptor.

Macros

#define EV_PRIO 0x1 /* Pend by task priority order. */

Creation flags.

#define EV_ANY 0x1 /* Disjunctive wait. */

Operation flags.

Functions

int rt event delete (RT EVENT *event)

Delete an event flag group.

 int rt_event_wait_timed (RT_EVENT *event, unsigned int mask, unsigned int *mask_r, int mode, const struct timespec *abs_timeout)

Wait for an arbitrary set of events.

• static int rt_event_wait_until (RT_EVENT *event, unsigned int mask, unsigned int *mask_r, int mode, RTIME timeout)

Wait for an arbitrary set of events (with absolute scalar timeout).

 static int rt_event_wait (RT_EVENT *event, unsigned int mask, unsigned int *mask_r, int mode, RTIME timeout)

Wait for an arbitrary set of events (with relative scalar timeout).

• int rt event inquire (RT EVENT *event, RT EVENT INFO *info)

Query event flag group status.

int rt event bind (RT EVENT *event, const char *name, RTIME timeout)

Bind to an event flag group.

Create an event flag group.

int rt_event_unbind (RT_EVENT *event)

Unbind from an event flag group.

• int rt_event_create (RT_EVENT *event, const char *name, unsigned int ivalue, int mode)

int rt_event_signal (RT_EVENT *event, unsigned int mask)

Signal an event.

• int rt_event_clear (RT_EVENT *event, unsigned int mask, unsigned int *mask_r)

Clear event flags.

6.81.1 Detailed Description

Inter-task notification mechanism based on discrete flags.

An event flag group is a synchronization object represented by a long-word structure; every available bit in this word represents a user-defined event flag.

When a bit is set, the associated event is said to have occurred. Xenomai tasks can use this mechanism to signal the occurrence of particular events to other tasks.

Tasks can either wait for events to occur in a conjunctive manner (all awaited events must have occurred to satisfy the wait request), or in a disjunctive way (at least one of the awaited events must have occurred to satisfy the wait request).

6.81.2 Macro Definition Documentation

6.81.2.1 #define EV ANY 0x1 /* Disjunctive wait. */

Operation flags.

Referenced by rt_event_wait_timed().

6.81.2.2 #define EV_PRIO 0x1 /* Pend by task priority order. */

Creation flags.

Referenced by rt_event_create().

6.81.3 Function Documentation

6.81.3.1 int rt_event_bind (RT_EVENT * event, const char * name, RTIME timeout)

Bind to an event flag group.

This routine creates a new descriptor to refer to an existing event flag group identified by its symbolic name. If the object does not exist on entry, the caller may block until an event flag group of the given name is created.

Parameters

event	The address of an event flag group descriptor filled in by the operation. Contents of
	this memory is undefined upon failure.
name	A valid NULL-terminated name which identifies the event flag group to bind to. This
	string should match the object name argument passed to rt_event_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.

- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.81.3.2 int rt_event_clear (RT_EVENT * event, unsigned int mask, unsigned int * mask_r)

Clear event flags.

This routine clears a set of flags from event.

Parameters

event	The event descriptor.
mask	The set of event flags to be cleared.
mask_r	If non-NULL, mask_r is the address of a memory location which will receive the
	previous value of the event flag group before the flags are cleared.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if event is not a valid event flag group descriptor.

Tags

unrestricted, switch-primary

6.81.3.3 int rt_event_create (RT_EVENT * event, const char * name, unsigned int ivalue, int mode)

Create an event flag group.

Event groups provide for task synchronization by allowing a set of flags (or "events") to be waited for and posted atomically. An event group contains a mask of received events; an arbitrary set of event flags can be pended or posted in a single operation.

Parameters

event	The address of an event descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the event. When non-NULL and non-empty, a copy of this string is used for indexing the created event into the object registry.

ivalue	The initial value of the group's event mask.
mode	The event group creation mode. The following flags can be OR'ed into this bitmask:

- EV_FIFO makes tasks pend in FIFO order on the event flag group.
- EV_PRIO makes tasks pend in priority order on the event flag group.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if mode is invalid.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the event flag group.
- -EEXIST is returned if the name is conflicting with an already registered event flag group.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Event flag groups can be shared by multiple processes which belong to the same Xenomai session.

References EV PRIO.

```
6.81.3.4 int rt event delete ( RT EVENT * event )
```

Delete an event flag group.

This routine deletes a event flag group previously created by a call to rt_event_create().

Parameters

event	The event descriptor.
-------	-----------------------

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if event is not a valid event flag group descriptor.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

```
6.81.3.5 int rt_event_inquire ( RT_EVENT * event, RT_EVENT_INFO * info )
```

Query event flag group status.

This routine returns the status information about event.

Parameters

event	The event descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if event is not a valid event flag group descriptor.

Tags

unrestricted, switch-primary

References RT_EVENT_INFO::name, RT_EVENT_INFO::nwaiters, and RT_EVENT_INFO::value.

```
6.81.3.6 int rt_event_signal ( RT_EVENT * event, unsigned int mask )
```

Signal an event.

Post a set of flags to *event*. All tasks having their wait request satisfied as a result of this operation are immediately readied.

Parameters

event	The event descriptor.
mask	The set of events to be posted.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if event is not an event flag group descriptor.

Tags

unrestricted, switch-primary

```
6.81.3.7 int rt_event_unbind ( RT_EVENT * event )
```

Unbind from an event flag group.

Parameters

event	The event descriptor.

This routine releases a previous binding to an event flag group. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

6.81.3.8 int rt_event_wait (RT_EVENT * event, unsigned int mask, unsigned int * mask_r, int mode, RTIME timeout) [inline], [static]

Wait for an arbitrary set of events (with relative scalar timeout).

This routine is a variant of rt_event_wait_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

event	The event descriptor.
mask	The set of bits to wait for.
mask_r	The value of the event mask at the time the task was readied.
mode	The pend mode.
timeout	A delay expressed in clock ticks,

Tags

xthread-nowait, switch-primary

References rt_event_wait_timed().

6.81.3.9 int rt_event_wait_timed (RT_EVENT * event, unsigned int mask, unsigned int * mask_r, int mode, const struct timespec * abs timeout)

Wait for an arbitrary set of events.

Waits for one or more events to be signaled in event, or until a timeout elapses.

Parameters

event	The event descriptor.
mask	The set of bits to wait for. Passing zero causes this service to return immediately
	with a success value; the current value of the event mask is also copied to mask_r.
mask_r	The value of the event mask at the time the task was readied.
mode	The pend mode. The following flags can be OR'ed into this bitmask, each of them
	affecting the operation:

- EV_ANY makes the task pend in disjunctive mode (i.e. OR); this means that the request is fulfilled when at least one bit set into *mask* is set in the current event mask.
- EV_ALL makes the task pend in conjunctive mode (i.e. AND); this means that the request is fulfilled when at all bits set into *mask* are set in the current event mask.

Parameters

abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for the re-
	quest to be satisfied (see note). Passing NULL causes the caller to block indefinitely
	until the request is satisfied. Passing { .tv_sec = 0, .tv_nsec = 0 } causes the service
	to return without blocking in case the request cannot be satisfied immediately.

Returns

Zero is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs_timeout is reached before the request is satisfied.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and the requested flags are not set on entry to the call.
- -EINTR is returned if rt_task_unblock() was called for the current task before the request is satisfied.
- -EINVAL is returned if *mode* is invalid, or *event* is not a valid event flag group descriptor.
- -EIDRM is returned if *event* is deleted while the caller was sleeping on it. In such a case, *event* is no more valid upon return of this service.

• -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

abs_timeout value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

References EV ANY.

Referenced by rt_event_wait(), and rt_event_wait_until().

6.81.3.10 int rt_event_wait_until (RT_EVENT * event, unsigned int mask, unsigned int * mask_r, int mode, RTIME abs_timeout) [inline], [static]

Wait for an arbitrary set of events (with absolute scalar timeout).

This routine is a variant of rt_event_wait_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

event	The event descriptor.
mask	The set of bits to wait for.
mask_r	The value of the event mask at the time the task was readied.
mode	The pend mode.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_event_wait_timed().

6.82 Heap management services

Region of memory dedicated to real-time allocation.

Collaboration diagram for Heap management services:



Data Structures

struct RT_HEAP_INFO

Heap status descriptor.

Macros

#define H_PRIO 0x1 /* Pend by task priority order. */
 Creation flags.

Functions

- int rt_heap_create (RT_HEAP *heap, const char *name, size_t heapsize, int mode)

 Create a heap.
- int rt_heap_delete (RT_HEAP *heap)

Delete a heap.

 int rt_heap_alloc_timed (RT_HEAP *heap, size_t size, const struct timespec *abs_timeout, void **blockp)

Allocate a block from a heap.

• static int rt_heap_alloc_until (RT_HEAP *heap, size_t size, RTIME timeout, void **blockp)

Allocate a block from a heap (with absolute scalar timeout).

• static int rt_heap_alloc (RT_HEAP *heap, size_t size, RTIME timeout, void **blockp)

Allocate a block from a heap (with relative scalar timeout).

int rt_heap_free (RT_HEAP *heap, void *block)

Release a block to a heap.

• int rt_heap_inquire (RT_HEAP *heap, RT_HEAP_INFO *info)

Query heap status.

• int rt_heap_bind (RT_HEAP *heap, const char *name, RTIME timeout)

Bind to a heap.

• int rt_heap_unbind (RT_HEAP *heap)

Unbind from a heap.

6.82.1 Detailed Description

Region of memory dedicated to real-time allocation.

Heaps are regions of memory used for dynamic memory allocation in a time-bounded fashion. Blocks of memory are allocated and freed in an arbitrary order and the pattern of allocation and size of blocks is not known until run time.

6.82.2 Macro Definition Documentation

6.82.2.1 #define H_PRIO 0x1 /* Pend by task priority order. */

Creation flags.

Referenced by rt heap create().

6.82.3 Function Documentation

```
6.82.3.1 int rt_heap_alloc ( RT_HEAP * heap, size_t size, RTIME timeout, void ** blockp ) [inline], [static]
```

Allocate a block from a heap (with relative scalar timeout).

This routine is a variant of rt_heap_alloc_timed() accepting a relative timeout specification expressed as a scalar value.

Tags

xthread-nowait, switch-primary

References rt_heap_alloc_timed().

```
6.82.3.2 int rt_heap_alloc_timed ( RT_HEAP * heap, size_t size, const struct timespec * abs_timeout, void ** blockp )
```

Allocate a block from a heap.

This service allocates a block from a given heap, or returns the address of the single memory segment if H_SINGLE was mentioned in the creation mode to rt_heap_create(). When not enough memory is available on entry to this service, tasks may be blocked until their allocation request can be fulfilled.

Parameters

heap	The heap descriptor.
size	The requested size (in bytes) of the block. If the heap is managed as a single-
	block area (H_SINGLE), this value can be either zero, or the same value given to
	rt_heap_create(). In that case, the same block covering the entire heap space is
	returned to all callers of this service.
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for a block of
	the requested size to be available from the heap (see note). Passing NULL causes
	the caller to block indefinitely until a block is available. Passing { .tv_sec = 0, .tv↔
	_nsec = 0 } causes the service to return immediately without blocking in case not
	block is available.

blockp	A pointer to a memory location which will be written upon success with the address
-	of the allocated block, or the start address of the single memory segment. In the
	former case, the block can be freed using rt_heap_free().

Returns

Zero is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs timeout is reached before a block is available.
- -EWOULDBLOCK is returned if abs_timeout is equal to { .tv_sec = 0, .tv_nsec = 0 } and no block is immediately available on entry to fulfill the allocation request.
- -EINTR is returned if rt_task_unblock() was called for the current task before a block became available.
- -EINVAL is returned if *heap* is not a valid heap descriptor, or *heap* is managed as a single-block area (i.e. H_SINGLE mode) and *size* is non-zero but does not match the original heap size passed to rt_heap_create().
- -EIDRM is returned if *heap* is deleted while the caller was waiting for a block. In such event, *heap* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

If shared multi-processing is enabled (i.e. —enable-pshared was passed to the configure script), requests for a block size larger than twice the allocation page size are rounded up to the next page size. The allocation page size is currently 512 bytes long (HOBJ_PAGE_SIZE), which means that any request larger than 1k will be rounded up to the next 512 byte boundary. abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see —alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_heap_alloc(), and rt_heap_alloc_until().

```
6.82.3.3 int rt_heap_alloc_until ( RT_HEAP * heap, size_t size, RTIME abs_timeout, void ** blockp ) [inline], [static]
```

Allocate a block from a heap (with absolute scalar timeout).

This routine is a variant of rt_heap_alloc_timed() accepting an absolute timeout specification expressed as a scalar value.

Tags

xthread-nowait, switch-primary

References rt_heap_alloc_timed().

```
6.82.3.4 int rt_heap_bind ( RT_HEAP * heap, const char * name, RTIME timeout )
```

Bind to a heap.

This routine creates a new descriptor to refer to an existing heap identified by its symbolic name. If the object does not exist on entry, the caller may block until a heap of the given name is created.

Parameters

heap	The address of a heap descriptor filled in by the operation. Contents of this memory
	is undefined upon failure.
name	A valid NULL-terminated name which identifies the heap to bind to. This string
	should match the object name argument passed to rt_heap_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.82.3.5 int rt_heap_create (RT_HEAP * heap, const char * name, size_t heapsz, int mode)

Create a heap.

This routine creates a memory heap suitable for time-bounded allocation requests of RAM chunks. When not enough memory is available, tasks may be blocked until their allocation request can be fulfilled.

By default, heaps support allocation of multiple blocks of memory in an arbitrary order. However, it is possible to ask for single-block management by passing the H_SINGLE flag into the *mode* parameter, in which case the entire memory space managed by the heap is made available as a unique block. In this mode, all allocation requests made through rt_heap_alloc() will return the same block address, pointing at the beginning of the heap memory.

Parameters

heap	The address of a heap descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the heap. When non-NULL and non-empty, a copy of this string is used for indexing the created heap into the object registry.

heapsz	The size (in bytes) of the memory pool, blocks will be claimed and released to. This
	area is not extensible, so this value must be compatible with the highest memory
	pressure that could be expected. The valid range is between 1 byte and 2Gb.
mode	The heap creation mode. The following flags can be OR'ed into this bitmask, each
	of them affecting the new heap:

- H FIFO makes tasks pend in FIFO order on the heap when waiting for available blocks.
- H_PRIO makes tasks pend in priority order on the heap when waiting for available blocks.
- H_SINGLE causes the entire heap space to be managed as a single memory block.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if mode is invalid, or heapsz is zero or larger than 2Gb.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the heap.
- -EEXIST is returned if the *name* is conflicting with an already registered heap.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Heaps can be shared by multiple processes which belong to the same Xenomai session.

References H_PRIO.

```
6.82.3.6 int rt_heap_delete ( RT_HEAP * heap )
```

Delete a heap.

This routine deletes a heap object previously created by a call to rt_heap_create(), releasing all tasks currently blocked on it.

Parameters

heap	The heap descriptor.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if heap is not a valid heap descriptor.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

6.82.3.7 int rt_heap_free (RT_HEAP * heap, void * block)

Release a block to a heap.

This service should be used to release a block to the heap it belongs to. An attempt to fulfill the request of every task blocked on rt_heap_alloc() is made once *block* is returned to the memory pool.

Parameters

heap	The heap descriptor.
block	The address of the block to free.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if *heap* is not a valid heap descriptor, or *block* is not a valid block previously allocated by the rt_heap_alloc() service from *heap*.

Tags

unrestricted, switch-primary

```
6.82.3.8 int rt_heap_inquire ( RT_HEAP * heap, RT_HEAP_INFO * info )
```

Query heap status.

This routine returns the status information about heap.

Parameters

heap	The heap descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if heap is not a valid heap descriptor.

Tags

unrestricted, switch-primary

References RT_HEAP_INFO::heapsize, RT_HEAP_INFO::name, RT_HEAP_INFO::nwaiters, RT_HE⇔ AP INFO::usablemem, and RT HEAP INFO::usedmem.

```
6.82.3.9 int rt_heap_unbind ( RT_HEAP * heap )
```

Unbind from a heap.

Parameters

heap	The heap descriptor.
------	----------------------

This routine releases a previous binding to a heap. After this call has returned, the descriptor is no more valid for referencing this object.


Tags

thread-unrestricted

6.83 Alchemy API

A programming interface reminiscent from traditional RTOS APIs.

Collaboration diagram for Alchemy API:



Modules

Alarm services

General-purpose watchdog timers.

• Buffer services

Lightweight FIFO IPC mechanism.

• Condition variable services

POSIXish condition variable mechanism.

6.83 Alchemy API 407

• Event flag group services

Inter-task notification mechanism based on discrete flags.

• Heap management services

Region of memory dedicated to real-time allocation.

Mutex services

POSIXish mutual exclusion servicesl.

Message pipe services

Two-way communication channel between Xenomai & Linux domains.

Message queue services

real-time IPC mechanism for sending messages of arbitrary size

• Semaphore services

Counting semaphore IPC mechanism.

Task management services

Services dealing with preemptive multi-tasking.

Timer management services

Services for reading and spinning on the hardware timer.

6.83.1 Detailed Description

A programming interface reminiscent from traditional RTOS APIs.

This interface is an evolution of the former *native* API available with the Xenomai 2.x series.

6.84 Mutex services

POSIXish mutual exclusion servicesl.

Collaboration diagram for Mutex services:



Data Structures

struct RT MUTEX INFO

Mutex status descriptor.

Functions

• int rt_mutex_create (RT_MUTEX *mutex, const char *name)

Create a mutex.

• int rt mutex delete (RT MUTEX *mutex)

Delete a mutex.

int rt_mutex_acquire_timed (RT_MUTEX *mutex, const struct timespec *abs_timeout)

Acquire/lock a mutex (with absolute timeout date).

static int rt_mutex_acquire_until (RT_MUTEX *mutex, RTIME timeout)

Acquire/lock a mutex (with absolute scalar timeout).

• static int rt_mutex_acquire (RT_MUTEX *mutex, RTIME timeout)

Acquire/lock a mutex (with relative scalar timeout).

• int rt mutex release (RT MUTEX *mutex)

Release/unlock a mutex.

int rt_mutex_inquire (RT_MUTEX *mutex, RT_MUTEX_INFO *info)

Query mutex status.

int rt_mutex_bind (RT_MUTEX *mutex, const char *name, RTIME timeout)

Bind to a mutex.

int rt_mutex_unbind (RT_MUTEX *mutex)

Unbind from a mutex.

6.84.1 Detailed Description

POSIXish mutual exclusion servicesl.

A mutex is a MUTual EXclusion object, and is useful for protecting shared data structures from concurrent modifications, and implementing critical sections and monitors.

A mutex has two possible states: unlocked (not owned by any task), and locked (owned by one task). A mutex can never be owned by two different tasks simultaneously. A task attempting to lock a mutex that is already locked by another task is blocked until the latter unlocks the mutex first.

Xenomai mutex services enforce a priority inheritance protocol in order to solve priority inversions.

6.84 Mutex services 409

6.84.2 Function Documentation

6.84.2.1 int rt_mutex_acquire (RT_MUTEX * mutex, RTIME timeout) [inline], [static]

Acquire/lock a mutex (with relative scalar timeout).

This routine is a variant of rt_mutex_acquire_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

mutex	The mutex descriptor.
timeout	A delay expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_mutex_acquire_timed().

6.84.2.2 int rt_mutex_acquire_timed (RT_MUTEX * mutex, const struct timespec * abs_timeout)

Acquire/lock a mutex (with absolute timeout date).

Attempt to lock a mutex. The calling task is blocked until the mutex is available, in which case it is locked again before this service returns. Xenomai mutexes are implicitely recursive and implement the priority inheritance protocol.

Parameters

mutex	The mutex descriptor.
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for the mutex to be available (see note). Passing NULL the caller to block indefinitely. Passing { .tv_sec = 0, .tv_nsec = 0 } causes the service to return immediately without blocking
	in case <i>mutex</i> is already locked by another task.

Returns

Zero is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs_timeout is reached before the mutex is available.
- -EWOULDBLOCK is returned if *timeout* is { .tv_sec = 0, .tv_nsec = 0 } and the mutex is not immediately available.
- -EINTR is returned if rt task unblock() was called for the current task.
- -EINVAL is returned if *mutex* is not a valid mutex descriptor.
- -EIDRM is returned if *mutex* is deleted while the caller was waiting on it. In such event, *mutex* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-only, switch-primary

Side effects

Over the Cobalt core, an Alchemy task with priority zero keeps running in primary mode until it releases the mutex, at which point it is switched back to secondary mode automatically.

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

 $References\ pthread_mutex_lock(),\ pthread_mutex_timedlock(),\ and\ pthread_mutex_trylock().$

Referenced by rt mutex acquire(), and rt mutex acquire until().

6.84.2.3 int rt_mutex_acquire_until (RT_MUTEX * mutex, RTIME abs_timeout) [inline], [static]

Acquire/lock a mutex (with absolute scalar timeout).

This routine is a variant of rt_mutex_acquire_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

mutex	The mutex descriptor.
abs_timeout An absolute date expressed in clock ticks.	

Tags

xthread-only, switch-primary

References rt_mutex_acquire_timed().

6.84.2.4 int rt_mutex_bind (RT_MUTEX * mutex, const char * name, RTIME timeout)

Bind to a mutex.

This routine creates a new descriptor to refer to an existing mutex identified by its symbolic name. If the object not exist on entry, the caller may block until a mutex of the given name is created.

Parameters

mutex	The address of a mutex descriptor filled in by the operation. Contents of this memory
	is undefined upon failure.
name	A valid NULL-terminated name which identifies the mutex to bind to. This string
	should match the object name argument passed to rt_mutex_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

6.84 Mutex services 411

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.84.2.5 int rt mutex create (RT MUTEX * mutex, const char * name)

Create a mutex.

Create a mutual exclusion object that allows multiple tasks to synchronize access to a shared resource. A mutex is left in an unlocked state after creation.

Parameters

mutex	The address of a mutex descriptor which can be later used to identify uniquely the created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the mutex. When non-NULL and
	non-empty, a copy of this string is used for indexing the created mutex into the object
	registry.

Returns

Zero is returned upon success. Otherwise:

- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the mutex.
- -EEXIST is returned if the *name* is conflicting with an already registered mutex.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Mutexes can be shared by multiple processes which belong to the same Xenomai session.

References pthread_mutex_init(), pthread_mutexattr_destroy(), pthread_mutexattr_init(), pthread_computexattr_setprotocol(), pthread_mutexattr_setpshared(), and pthread_mutexattr_settype().

6.84.2.6 int rt_mutex_delete (RT_MUTEX * mutex)

Delete a mutex.

This routine deletes a mutex object previously created by a call to rt_mutex_create().

Parameters

mutex	The mutex descriptor.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *alarm* is not a valid mutex descriptor.
- -EPERM is returned if this service was called from an asynchronous context.
- -EBUSY is returned upon an attempt to destroy the object referenced by mutex while it is referenced (for example, while being used in a rt_mutex_acquite(), rt_mutex_acquire_timed() or rt_
 mutex_acquire_until() by another task).

Tags

thread-unrestricted, switch-secondary

References pthread_mutex_destroy().

```
6.84.2.7 int rt mutex inquire ( RT MUTEX * mutex, RT MUTEX INFO * info )
```

Query mutex status.

This routine returns the status information about the specified mutex.

Parameters

mutex	The mutex descriptor.	
info	A pointer to the returnbuffer" to copy the information to.	

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

- -EINVAL is returned if *mutex* is not a valid mutex descriptor.
- -EPERM is returned if this service is called from an interrupt context.

Tags

xthread-only, switch-primary

References RT_MUTEX_INFO::name, RT_MUTEX_INFO::owner, pthread_mutex_trylock(), and pthread_mutex_unlock().

```
6.84.2.8 int rt_mutex_release ( RT_MUTEX * mutex )
```

Release/unlock a mutex.

This routine releases a mutex object previously locked by a call to rt_mutex_acquire() or rt_mutex_acquire() or rt_mutex_acquire_until(). If the mutex is pended, the first waiting task (by priority order) is immediately unblocked and transferred the ownership of the mutex; otherwise, the mutex is left in an unlocked state.

6.84 Mutex services 413

Parameters

mutex	The mutex descriptor	

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if alarm is not a valid mutex descriptor.
- -EPERM is returned if *mutex* is not owned by the current task, or more generally if this service was called from a context which cannot own any mutex (e.g. interrupt context).

Tags

xthread-only, switch-primary

References pthread_mutex_unlock().

6.84.2.9 int rt mutex unbind (RT MUTEX * mutex)

Unbind from a mutex.

Parameters

mutex The mutex descriptor.

This routine releases a previous binding to a mutex. After this call has returned, the descriptor is no more valid for referencing this object.

6.85 Message pipe services

Two-way communication channel between Xenomai & Linux domains.

Collaboration diagram for Message pipe services:



Macros

#define P_MINOR_AUTO XNPIPE_MINOR_AUTO

Creation flags.

• #define P URGENT XNPIPE URGENT

Operation flags.

Functions

• int rt pipe delete (RT PIPE *pipe)

Delete a message pipe.

ssize_t rt_pipe_read_timed (RT_PIPE *pipe, void *buf, size_t size, const struct timespec *abs_
 timeout)

Read a message from a pipe.

• static ssize_t rt_pipe_read_until (RT_PIPE *pipe, void *buf, size_t size, RTIME timeout)

Read from a pipe (with absolute scalar timeout).

• static ssize_t rt_pipe_read (RT_PIPE *pipe, void *buf, size_t size, RTIME timeout)

Read from a pipe (with relative scalar timeout).

• ssize_t rt_pipe_write (RT_PIPE *pipe, const void *buf, size_t size, int mode)

Write a message to a pipe.

• ssize_t rt_pipe_stream (RT_PIPE *pipe, const void *buf, size_t size)

Stream bytes through a pipe.

• int rt_pipe_bind (RT_PIPE *pipe, const char *name, RTIME timeout)

Bind to a message pipe.

int rt_pipe_unbind (RT_PIPE *pipe)

Unbind from a message pipe.

• int rt_pipe_create (RT_PIPE *pipe, const char *name, int minor, size_t poolsize)

Create a message pipe.

6.85.1 Detailed Description

Two-way communication channel between Xenomai & Linux domains.

A message pipe is a two-way communication channel between Xenomai threads and normal Linux threads using regular file I/O operations on a pseudo-device. Pipes can be operated in a message-oriented fashion so that message boundaries are preserved, and also in byte-oriented streaming mode from real-time to normal Linux threads for optimal throughput.

Xenomai threads open their side of the pipe using the rt_pipe_create() service; regular Linux threads do the same by opening one of the /dev/rtpN special devices, where N is the minor number agreed upon between both ends of each pipe.

In addition, named pipes are available through the registry support, which automatically creates a symbolic link from entries under /proc/xenomai/registry/rtipc/xddp/ to the corresponding special device file.

Note

Alchemy's message pipes are fully based on the XDDP protocol available from the RTDM/ipc driver

6.85.2 Macro Definition Documentation

6.85.2.1 #define P MINOR AUTO XNPIPE MINOR AUTO

Creation flags.

Referenced by rt_pipe_create().

6.85.2.2 #define P_URGENT XNPIPE_URGENT

Operation flags.

Referenced by rt_pipe_write().

6.85.3 Function Documentation

6.85.3.1 int rt_pipe_bind (RT_PIPE * pipe, const char * name, RTIME timeout)

Bind to a message pipe.

This routine creates a new descriptor to refer to an existing message pipe identified by its symbolic name. If the object does not exist on entry, the caller may block until a pipe of the given name is created.

Parameters

pipe	The address of a pipe descriptor filled in by the operation. Contents of this memory
	is undefined upon failure.
name	A valid NULL-terminated name which identifies the pipe to bind to. This string should
	match the object name argument passed to rt_pipe_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.85.3.2 int rt_pipe_create (RT_PIPE * pipe, const char * name, int minor, size_t poolsize)

Create a message pipe.

This service opens a bi-directional communication channel for exchanging messages between Xenomai threads and regular Linux threads. Pipes natively preserve message boundaries, but can also be used in byte-oriented streaming mode from Xenomai to Linux.

rt_pipe_create() always returns immediately, even if no thread has opened the associated special device file yet. On the contrary, the non real-time side could block upon attempt to open the special device file until rt_pipe_create() is issued on the same pipe from a Xenomai thread, unless O_NONBLOCK was given to the open(2) system call.

Parameters

pipe	The address of a pipe descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the pipe. When non-NULL and non-empty, a copy of this string is used for indexing the created pipe into the object registry.

Named pipes are supported through the use of the registry. Passing a valid *name* parameter when creating a message pipe causes a symbolic link to be created from /proc/xenomai/registry/rtipc/xddp/*name* to the associated special device (i.e. /dev/rtp*), so that the specific *minor* information does not need to be known from those processes for opening the proper device file. In such a case, both sides of the pipe only need to agree upon a symbolic name to refer to the same data path, which is especially useful whenever the *minor* number is picked up dynamically using an adaptive algorithm, such as passing P MINOR AUTO as *minor* value.

Parameters

minor	The minor number of the device associated with the pipe. Passing P_MINOR_←
	AUTO causes the minor number to be auto-allocated. In such a case, a symbolic
	link will be automatically created from /proc/xenomai/registry/rtipc/xddp/name to the
	allocated pipe device entry. Valid minor numbers range from 0 to CONFIG_XEN←
	O_OPT_PIPE_NRDEV-1.
poolsize	Specifies the size of a dedicated buffer pool for the pipe. Passing 0 means that all
	message allocations for this pipe are performed on the Cobalt core heap.

Returns

The minor number assigned to the connection is returned upon success. Otherwise:

- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the pipe.
- -ENODEV is returned if *minor* is different from P_MINOR_AUTO and is not a valid minor number.
- -EEXIST is returned if the *name* is conflicting with an already registered pipe.
- -EBUSY is returned if *minor* is already open.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

References IPCPROTO_XDDP, rtipc_port_label::label, P_MINOR_AUTO, sockaddr_ipc::sipc_family, sockaddr_ipc::sipc_port, XDDP_BUFSZ, XDDP_LABEL, and XDDP_POOLSZ.

```
6.85.3.3 int rt_pipe_delete ( RT_PIPE * pipe )
```

Delete a message pipe.

This routine deletes a pipe object previously created by a call to rt_pipe_create(). All resources attached to that pipe are automatically released, all pending data is flushed.

Parameters

pipe	The pipe descriptor.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *pipe* is not a valid pipe descriptor.
- -EIDRM is returned if pipe is a closed pipe descriptor.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

```
6.85.3.4 ssize_t rt_pipe_read ( RT_PIPE * pipe, void * buf, size_t size, RTIME timeout ) [inline], [static]
```

Read from a pipe (with relative scalar timeout).

This routine is a variant of rt_queue_read_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

pipe	The pipe descriptor.
buf	
	received.
size	The count of bytes from the received message to read up into <i>buf</i> . If <i>size</i> is lower
	than the actual message size, -ENOBUFS is returned since the incompletely received message would be lost. If <i>size</i> is zero, this call returns immediately with no
	other action.
timeout	A delay expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_pipe_read_timed().

6.85.3.5 ssize_t rt_pipe_read_timed (RT_PIPE * pipe, void * buf, size_t size, const struct timespec * abs_timeout)

Read a message from a pipe.

This service reads the next available message from a given pipe.

Parameters

pipe	The pipe descriptor.
buf	A pointer to a memory area which will be written upon success with the message received.
size	The count of bytes from the received message to read up into <i>buf</i> . If <i>size</i> is lower than the actual message size, -ENOBUFS is returned since the incompletely received message would be lost. If <i>size</i> is zero, this call returns immediately with no other action.
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for a message to be available from the pipe (see note). Passing NULL causes the caller to block indefinitely until a message is available. Passing { .tv_sec = 0, .tv_nsec = 0 } causes the service to return immediately without blocking in case no message is available.

Returns

The number of bytes available from the received message is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs timeout is reached before a message arrives.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and no message is immediately available on entry to the call.
- -EINTR is returned if rt_task_unblock() was called for the current task before a message was available.
- -EINVAL is returned if pipe is not a valid pipe descriptor.
- -EIDRM is returned if *pipe* is deleted while the caller was waiting for a message. In such event, *pipe* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

References SO RCVTIMEO.

Referenced by rt_pipe_read(), and rt_pipe_read_until().

6.85.3.6 ssize_t rt_pipe_read_until (RT_PIPE * pipe, void * buf, size_t size, RTIME abs_timeout) [inline], [static]

Read from a pipe (with absolute scalar timeout).

This routine is a variant of rt_queue_read_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

pipe	The pipe descriptor.
buf	A pointer to a memory area which will be written upon success with the message
	received.
size	The count of bytes from the received message to read up into buf. If size is lower
	than the actual message size, -ENOBUFS is returned since the incompletely re-
	ceived message would be lost. If size is zero, this call returns immediately with no
	other action.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_pipe_read_timed().

```
6.85.3.7 ssize_t rt_pipe_stream ( RT_PIPE * pipe, const void * buf, size_t size )
```

Stream bytes through a pipe.

This service writes a sequence of bytes to be received from the associated special device. Unlike rt_← pipe_send(), this service does not preserve message boundaries. Instead, an internal buffer is filled on the fly with the data, which will be consumed as soon as the receiver wakes up.

Data buffers sent by the rt_pipe_stream() service are always transmitted in FIFO order (i.e. P_NORMAL mode).

Parameters

pipe	The pipe descriptor.
buf	The address of the first data byte to send. The data will be copied to an internal
	buffer before transmission.
size	The size in bytes of the buffer. Zero is a valid value, in which case the service
	returns immediately without sending any data.

Returns

The number of bytes sent upon success; this value may be lower than *size*, depending on the available space in the internal buffer. Otherwise:

- -EINVAL is returned if *mode* is invalid or *pipe* is not a pipe descriptor.
- -ENOMEM is returned if not enough buffer space is available to complete the operation.
- -EIDRM is returned if pipe is a closed pipe descriptor.

Note

Writing data to a pipe before any peer has opened the associated special device is allowed. The output will be buffered until then, only restricted by the available memory in the associated buffer pool (see rt_pipe_create()).

Tags

xcontext, switch-primary

```
6.85.3.8 int rt pipe unbind ( RT PIPE * pipe )
```

Unbind from a message pipe.

Parameters

pipe	The pipe descriptor.
, ,	

This routine releases a previous binding to a message pipe. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

6.85.3.9 ssize_t rt_pipe_write (RT_PIPE * pipe, const void * buf, size_t size, int mode)

Write a message to a pipe.

This service writes a complete message to be received from the associated special device. rt_pipe_\(\cdot\) write() always preserves message boundaries, which means that all data sent through a single call of this service will be gathered in a single read(2) operation from the special device.

This service differs from rt_pipe_send() in that it accepts a pointer to the raw data to be sent, instead of a canned message buffer.

Parameters

pipe	The pipe descriptor.
buf	The address of the first data byte to send. The data will be copied to an internal
	buffer before transmission.
size	The size in bytes of the message (payload data only). Zero is a valid value, in which
	case the service returns immediately without sending any message.
mode	A set of flags affecting the operation:

- P_URGENT causes the message to be prepended to the output queue, ensuring a LIFO ordering.
- P_NORMAL causes the message to be appended to the output queue, ensuring a FIFO ordering.

Returns

Upon success, this service returns *size*. Upon error, one of the following error codes is returned:

- -EINVAL is returned if *mode* is invalid or *pipe* is not a pipe descriptor.
- -ENOMEM is returned if not enough buffer space is available to complete the operation.
- -EIDRM is returned if *pipe* is a closed pipe descriptor.

Note

Writing data to a pipe before any peer has opened the associated special device is allowed. The output will be buffered until then, only restricted by the available memory in the associated buffer pool (see rt_pipe_create()).

Tags

xcontext, switch-primary

References P_URGENT.

6.86 Message queue services

real-time IPC mechanism for sending messages of arbitrary size Collaboration diagram for Message queue services:



Data Structures

struct RT_QUEUE_INFO
 Queue status descriptor.

Macros

#define Q_PRIO 0x1 /* Pend by task priority order. */
 Creation flags.

Functions

• int rt_queue_create (RT_QUEUE *queue, const char *name, size_t poolsize, size_t qlimit, int mode)

Create a message queue.

• int rt_queue_delete (RT_QUEUE *queue)

Delete a message queue.

void * rt_queue_alloc (RT_QUEUE *queue, size_t size)

Allocate a message buffer.

• int rt_queue_free (RT_QUEUE *queue, void *buf)

Free a message buffer.

- int rt_queue_send (RT_QUEUE *queue, const void *buf, size_t size, int mode)
 - Send a message to a queue.
- ssize_t rt_queue_receive_timed (RT_QUEUE *queue, void **bufp, const struct timespec *abs_
 timeout)

Receive a message from a queue (with absolute timeout date).

static ssize_t rt_queue_receive_until (RT_QUEUE *queue, void **bufp, RTIME timeout)

Receive from a queue (with absolute scalar timeout).

• static ssize_t rt_queue_receive (RT_QUEUE *queue, void **bufp, RTIME timeout)

Receive from a queue (with relative scalar timeout).

 ssize_t rt_queue_read_timed (RT_QUEUE *queue, void *buf, size_t size, const struct timespec *abs_timeout)

Read from a queue.

• static ssize_t rt_queue_read_until (RT_QUEUE *queue, void *buf, size_t size, RTIME timeout)

Read from a queue (with absolute scalar timeout).

• static ssize_t rt_queue_read (RT_QUEUE *queue, void *buf, size_t size, RTIME timeout)

Read from a queue (with relative scalar timeout).

• int rt_queue_flush (RT_QUEUE *queue)

Flush pending messages from a queue.

• int rt_queue_inquire (RT_QUEUE *queue, RT_QUEUE_INFO *info)

Query queue status.

• int rt_queue_bind (RT_QUEUE *queue, const char *name, RTIME timeout)

Bind to a message queue.

int rt_queue_unbind (RT_QUEUE *queue)

Unbind from a message queue.

6.86.1 Detailed Description

real-time IPC mechanism for sending messages of arbitrary size

Message queueing is a method by which real-time tasks can exchange or pass data through a Xenomai-managed queue of messages. Messages can vary in length and be assigned different types or usages. A message queue can be created by one task and used by multiple tasks that send and/or receive messages to the queue.

6.86.2 Macro Definition Documentation

6.86.2.1 #define Q PRIO 0x1 /* Pend by task priority order. */

Creation flags.

Referenced by rt queue create().

6.86.3 Function Documentation

Allocate a message buffer.

This service allocates a message buffer from the queue's internal pool. This buffer can be filled in with payload information, prior enqueuing it by a call to rt_queue_send(). When used in pair, these services provide a zero-copy interface for sending messages.

Parameters

q	The queue descriptor.
size	The requested size in bytes of the buffer. Zero is an acceptable value, which means
	that the message conveys no payload; in this case, the receiver will get a zero-sized message.

Returns

The address of the allocated buffer upon success, or NULL if the call fails.

Tags

unrestricted, switch-primary

6.86.3.2 int rt_queue_bind (RT_QUEUE * q, const char * name, RTIME timeout)

Bind to a message queue.

This routine creates a new descriptor to refer to an existing message queue identified by its symbolic name. If the object does not exist on entry, the caller may block until a queue of the given name is created.

Parameters

q	The address of a queue descriptor filled in by the operation. Contents of this mem-
	ory is undefined upon failure.
name	A valid NULL-terminated name which identifies the queue to bind to. This string
	should match the object name argument passed to rt_queue_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if timeout is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.86.3.3 int rt_queue_create (RT_QUEUE * q, const char * name, size_t poolsize, size_t qlimit, int mode)

Create a message queue.

Create a message queue object which allows multiple tasks to exchange data through the use of variable-sized messages. A message queue is created empty.

Parameters

q	The address of a queue descriptor which can be later used to identify uniquely the
	created object, upon success of this call.

name	An ASCII string standing for the symbolic name of the queue. When non-NULL
Harric	
	and non-empty, a copy of this string is used for indexing the created queue into the
	object registry.
poolsize	The size (in bytes) of the message buffer pool to be pre-allocated for holding mes-
	sages. Message buffers will be claimed and released to this pool. The buffer pool
	memory cannot be extended. See note.
qlimit	This parameter allows to limit the maximum number of messages which can be
	queued at any point in time, sending to a full queue begets an error. The special
	value Q_UNLIMITED can be passed to disable the limit check.
mode	The queue creation mode. The following flags can be OR'ed into this bitmask, each
	of them affecting the new queue:

- Q_FIFO makes tasks pend in FIFO order on the queue for consuming messages.
- Q_PRIO makes tasks pend in priority order on the queue.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if mode is invalid or poolsize is zero.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the queue.
- -EEXIST is returned if the name is conflicting with an already registered queue.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Queues can be shared by multiple processes which belong to the same Xenomai session. Each message pending into the queue consumes four long words plus the actual payload size, aligned to the next long word boundary. e.g. a 6 byte message on a 32 bit platform would require 24 bytes of storage into the pool.

When *qlimit* is given (i.e. different from Q_UNLIMITED), this overhead is accounted for automatically, so that *qlimit* messages of *poolsize* / *qlimit* bytes can be stored into the pool concurrently. Otherwise, *poolsize* is increased by 5% internally to cope with such overhead.

References Q PRIO.

6.86.3.4 int rt_queue_delete (RT_QUEUE * q)

Delete a message queue.

This routine deletes a queue object previously created by a call to rt_queue_create(). All resources attached to that queue are automatically released, including all pending messages.

Parameters

q The queue descriptor.

Returns

426

Zero is returned upon success. Otherwise:

- -EINVAL is returned if q is not a valid queue descriptor.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

```
6.86.3.5 int rt_queue_flush ( RT_QUEUE * q )
```

Flush pending messages from a queue.

This routine flushes all messages currently pending in a queue, releasing all message buffers appropriately.

Parameters

q The queue descriptor.

Returns

Zero is returned upon success. Otherwise:

-EINVAL is returned if q is not a valid queue descriptor.

Tags

unrestricted, switch-primary

```
6.86.3.6 int rt_queue_free ( RT_QUEUE * q, void * buf )
```

Free a message buffer.

This service releases a message buffer to the queue's internal pool.

Parameters

q	The queue descriptor.
buf	The address of the message buffer to free. Even zero-sized messages carrying no
	payload data must be freed, since they are assigned a valid memory space to store
	internal information.

Returns

Zero is returned upon success, or -EINVAL if *buf* is not a valid message buffer previously allocated by the rt_queue_alloc() service, or the caller did not get ownership of the message through a successful return from rt_queue_receive().

Tags

unrestricted, switch-primary

```
6.86.3.7 int rt_queue_inquire ( RT_QUEUE * q, RT_QUEUE_INFO * info )
```

Query queue status.

This routine returns the status information about the specified queue.

Parameters

q	The queue descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if q is not a valid queue descriptor.

Tags

unrestricted, switch-primary

References RT_QUEUE_INFO::mode, RT_QUEUE_INFO::name, RT_QUEUE_INFO::nmessages, R \leftarrow T_QUEUE_INFO::nwaiters, RT_QUEUE_INFO::poolsize, RT_QUEUE_INFO::qlimit, and RT_QUEU \leftarrow E_INFO::usedmem.

Read from a queue (with relative scalar timeout).

This routine is a variant of rt_queue_read_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

q	The queue descriptor.
buf	A pointer to a memory area which will be written upon success with the received
	message payload.
size	The length in bytes of the memory area pointed to by buf.
timeout	A delay expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_queue_read_timed().

```
6.86.3.9 ssize_t rt_queue_read_timed ( RT_QUEUE * q, void * buf, size_t size, const struct timespec * abs timeout )
```

Read from a queue.

This service reads the next available message from a given queue.

Parameters

q	The queue descriptor.
buf	A pointer to a memory area which will be written upon success with the received
	message payload. The internal message buffer conveying the data is automatically
	freed by this call. If –enable-pshared is enabled in the configuration, buf must have
	been obtained from the Xenomai memory allocator via xnmalloc() or any service
	based on it, such as rt_heap_alloc().
size	The length in bytes of the memory area pointed to by buf. Messages larger than
	size are truncated appropriately.
abs_timeout	, , , , , , , , , , , , , , , , , , , ,
	sage to be available from the queue (see note). Passing NULL causes the caller to
	block indefinitely until a message is available. Passing { .tv_sec = 0, .tv_nsec = 0
	} causes the service to return immediately without blocking in case no message is
	available.

Returns

The number of bytes copied to *buf* is returned upon success. Zero is a possible value corresponding to a zero-sized message passed to rt_queue_send() or rt_queue_write(). Otherwise:

- -ETIMEDOUT is returned if abs timeout is reached before a message arrives.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and no message is immediately available on entry to the call.
- -EINTR is returned if rt_task_unblock() was called for the current task before a message was available.
- -EINVAL is returned if q is not a valid queue descriptor.
- ullet -EIDRM is returned if q is deleted while the caller was waiting for a message. In such event, q is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_queue_read(), and rt_queue_read_until().

6.86.3.10 ssize_t rt_queue_read_until (RT_QUEUE * q, void * buf, size_t size, RTIME abs_timeout) [inline], [static]

Read from a queue (with absolute scalar timeout).

This routine is a variant of rt_queue_read_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

q	The queue descriptor.
buf	A pointer to a memory area which will be written upon success with the received
	message payload.
size	The length in bytes of the memory area pointed to by buf.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_queue_read_timed().

Receive from a queue (with relative scalar timeout).

This routine is a variant of rt_queue_receive_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

q	The queue descriptor.
bufp	A pointer to a memory location which will be written with the address of the received
	message.
timeout	A delay expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_queue_receive_timed().

Receive a message from a queue (with absolute timeout date).

This service receives the next available message from a given queue.

Parameters

q	The queue descriptor.
bufp	A pointer to a memory location which will be written with the address of the received message, upon success. Once consumed, the message space should be freed
	using rt_queue_free().
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for a message to be available from the queue (see note). Passing NULL causes the caller to block indefinitely until a message is available. Passing { .tv_sec = 0, .tv_nsec = 0 } causes the service to return immediately without blocking in case no message is available.

Returns

The number of bytes available from the received message is returned upon success. Zero is a possible value corresponding to a zero-sized message passed to rt_queue_send() or rt_queue_ write(). Otherwise:

- -ETIMEDOUT is returned if abs_timeout is reached before a message arrives.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and no message is immediately available on entry to the call.
- -EINTR is returned if rt_task_unblock() was called for the current task before a message was available.
- -EINVAL is returned if *q* is not a valid queue descriptor.
- -EIDRM is returned if *q* is deleted while the caller was waiting for a message. In such event, *q* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_queue_receive(), and rt_queue_receive_until().

```
6.86.3.13 ssize_t rt_queue_receive_until ( RT_QUEUE * q, void ** bufp, RTIME abs_timeout ) [inline], [static]
```

Receive from a queue (with absolute scalar timeout).

This routine is a variant of rt_queue_receive_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

q	The queue descriptor.
bufp	A pointer to a memory location which will be written with the address of the received
	message.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_queue_receive_timed().

```
6.86.3.14 int rt_queue_send ( RT_QUEUE * q, const void * buf, size_t size, int mode )
```

Send a message to a queue.

This service sends a complete message to a given queue. The message must have been allocated by a previous call to rt_queue_alloc().

Parameters

q	The queue descriptor.
buf	The address of the message buffer to be sent. The message buffer must have been allocated using the rt_queue_alloc() service. Once passed to rt_queue_send(), the memory pointed to by buf is no more under the control of the sender and thus should not be referenced by it anymore; deallocation of this memory must be handled on the receiving side.
size	The actual size in bytes of the message, which may be lower than the allocated size for the buffer obtained from rt_queue_alloc(). Zero is a valid value, in which case an empty message will be sent.
mode	A set of flags affecting the operation:

- Q_URGENT causes the message to be prepended to the message queue, ensuring a LIFO ordering.
- Q_NORMAL causes the message to be appended to the message queue, ensuring a FIFO ordering.
- Q_BROADCAST causes the message to be sent to all tasks currently waiting for messages. The
 message is not copied; a reference count is maintained instead so that the message will remain
 valid until the last receiver releases its own reference using rt_queue_free(), after which the message space will be returned to the queue's internal pool.

Returns

Upon success, this service returns the number of receivers which got awaken as a result of the operation. If zero is returned, no task was waiting on the receiving side of the queue, and the message has been enqueued. Upon error, one of the following error codes is returned:

- -EINVAL is returned if q is not a message queue descriptor, mode is invalid, or buf is NULL.
- -ENOMEM is returned if queuing the message would exceed the limit defined for the queue at creation.

Tags

unrestricted, switch-primary

6.86.3.15 int rt_queue_unbind (RT_QUEUE * q)

Unbind from a message queue.

Parameters

q | The queue descriptor.

This routine releases a previous binding to a message queue. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

6.87 Semaphore services

Counting semaphore IPC mechanism.

Collaboration diagram for Semaphore services:



Data Structures

struct RT_SEM_INFO

Semaphore status descriptor.

Macros

#define S_PRIO 0x1 /* Pend by task priority order. */
 Creation flags.

Functions

- int rt_sem_create (RT_SEM *sem, const char *name, unsigned long icount, int mode)
- Create a counting semaphore.int rt_sem_delete (RT_SEM *sem)

Delete a semaphore.

int rt_sem_p_timed (RT_SEM *sem, const struct timespec *abs_timeout)

Pend on a semaphore.

• static int rt_sem_p_until (RT_SEM *sem, RTIME timeout)

Pend on a semaphore (with absolute scalar timeout).

• static int rt_sem_p (RT_SEM *sem, RTIME timeout)

Pend on a semaphore (with relative scalar timeout).

• int rt sem v (RT SEM *sem)

Signal a semaphore.

• int rt_sem_broadcast (RT_SEM *sem)

Broadcast a semaphore.

int rt_sem_inquire (RT_SEM *sem, RT_SEM_INFO *info)

Query semaphore status.

• int rt_sem_bind (RT_SEM *sem, const char *name, RTIME timeout)

Bind to a semaphore.

• int rt_sem_unbind (RT_SEM *sem)

Unbind from a semaphore.

6.87.1 Detailed Description

Counting semaphore IPC mechanism.

A counting semaphore is a synchronization object for controlling the concurrency level allowed in accessing a resource from multiple real-time tasks, based on the value of a count variable accessed atomically. The semaphore is used through the P ("Proberen", from the Dutch "test and decrement") and V ("Verhogen", increment) operations. The P operation decrements the semaphore count by one if non-zero, or waits until a V operation is issued by another task. Conversely, the V operation releases a resource by incrementing the count by one, unblocking the heading task waiting on the P operation if any. Waiting on a semaphore may cause a priority inversion.

If no more than a single resource is made available at any point in time, the semaphore enforces mutual exclusion and thus can be used to serialize access to a critical section. However, mutexes should be used instead in order to prevent priority inversions, based on the priority inheritance protocol.

6.87.2 Macro Definition Documentation

6.87.2.1 #define S PRIO 0x1 /* Pend by task priority order. */

Creation flags.

Referenced by rt sem create().

6.87.3 Function Documentation

6.87.3.1 int rt_sem_bind (RT_SEM * sem, const char * name, RTIME timeout)

Bind to a semaphore.

This routine creates a new descriptor to refer to an existing semaphore identified by its symbolic name. If the object does not exist on entry, the caller may block until a semaphore of the given name is created.

Parameters

sem	The address of a semaphore descriptor filled in by the operation. Contents of this
	memory is undefined upon failure.
name	A valid NULL-terminated name which identifies the semaphore to bind to. This string
	should match the object name argument passed to rt_sem_create().
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing
	TM_INFINITE causes the caller to block indefinitely until the object is registered.
	Passing TM_NONBLOCK causes the service to return immediately without waiting
	if the object is not registered on entry.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.87.3.2 int rt sem broadcast (RT SEM * sem)

Broadcast a semaphore.

All tasks currently waiting on the semaphore are immediately unblocked. The semaphore count is set to zero.

Parameters

sem	The semaphore descriptor.
-----	---------------------------

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if sem is not a valid semaphore descriptor.

Tags

unrestricted

6.87.3.3 int rt sem create (RT SEM * sem, const char * name, unsigned long icount, int mode)

Create a counting semaphore.

Parameters

sem	The address of a semaphore descriptor which can be later used to identify unique	
	the created object, upon success of this call.	
name	An ASCII string standing for the symbolic name of the semaphore. When non-NULL	
	and non-empty, a copy of this string is used for indexing the created semaphore into	
	the object registry.	
icount	The initial value of the counting semaphore.	
mode	The semaphore creation mode. The following flags can be OR'ed into this bitmask:	

- S_FIFO makes tasks pend in FIFO order on the semaphore.
- S_PRIO makes tasks pend in priority order on the semaphore.
- S_PULSE causes the semaphore to behave in "pulse" mode. In this mode, the V (signal) operation attempts to release a single waiter each time it is called, without incrementing the semaphore count, even if no waiter is pending. For this reason, the semaphore count in pulse mode remains zero.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if icount is non-zero and S_PULSE is set in mode, or mode is otherwise invalid.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the semaphore.

- -EEXIST is returned if the name is conflicting with an already registered semaphore.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Semaphores can be shared by multiple processes which belong to the same Xenomai session.

References S_PRIO.

```
6.87.3.4 int rt_sem_delete ( RT_SEM * sem )
```

Delete a semaphore.

This routine deletes a semaphore previously created by a call to rt_sem_create().

Parameters

sem	The semaphore descriptor.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if sem is not a valid semaphore descriptor.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

```
6.87.3.5 int rt_sem_inquire ( RT_SEM * sem, RT_SEM_INFO * info )
```

Query semaphore status.

This routine returns the status information about the specified semaphore.

Parameters

sem	The semaphore descriptor.
info	A pointer to the returnbuffer" to copy the information to.

Returns

Zero is returned and status information is written to the structure pointed at by *info* upon success. Otherwise:

• -EINVAL is returned if sem is not a valid semaphore descriptor.

Tags

unrestricted

References RT_SEM_INFO::count, RT_SEM_INFO::name, and RT_SEM_INFO::nwaiters.

```
6.87.3.6 intrt_sem_p ( RT_SEM * sem, RTIME timeout ) [inline], [static]
```

Pend on a semaphore (with relative scalar timeout).

This routine is a variant of rt_sem_p_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

sem	The semaphore descriptor.
timeout	A delay expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_sem_p_timed().

```
6.87.3.7 int rt_sem_p_timed ( RT_SEM * sem, const struct timespec * abs_timeout )
```

Pend on a semaphore.

Test and decrement the semaphore count. If the semaphore value is greater than zero, it is decremented by one and the service immediately returns to the caller. Otherwise, the caller is blocked until the semaphore is either signaled or destroyed, unless a non-blocking operation was required.

Parameters

sem	The semaphore descriptor.
abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for the request to be satisfied (see note). Passing NULL causes the caller to block indefinitely until the request is satisfied. Passing { .tv_sec = 0, .tv_nsec = 0 } causes the service
	to return without blocking in case the request cannot be satisfied immediately.

Returns

Zero is returned upon success. Otherwise:

- -ETIMEDOUT is returned if abs timeout is reached before the request is satisfied.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and the semaphore count is zero on entry.
- -EINTR is returned if rt_task_unblock() was called for the current task before the request is satisfied.
- -EINVAL is returned if sem is not a valid semaphore descriptor.
- -EIDRM is returned if *sem* is deleted while the caller was sleeping on it. In such a case, *sem* is no more valid upon return of this service.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_sem_p(), and rt_sem_p_until().

6.87.3.8 int rt_sem_p_until (RT_SEM * sem, RTIME abs_timeout) [inline], [static]

Pend on a semaphore (with absolute scalar timeout).

This routine is a variant of rt_sem_p_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

sem	The semaphore descriptor.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-nowait, switch-primary

References rt_sem_p_timed().

```
6.87.3.9 int rt sem unbind ( RT SEM * sem )
```

Unbind from a semaphore.

Parameters

```
sem | The semaphore descriptor.
```

This routine releases a previous binding to a semaphore. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

```
6.87.3.10 int rt_sem_v ( RT_SEM * sem )
```

Signal a semaphore.

If the semaphore is pended, the task heading the wait queue is immediately unblocked. Otherwise, the semaphore count is incremented by one, unless the semaphore is used in "pulse" mode (see rt_sem
__create()).

Parameters

sem	The semaphore descriptor.

Returns

Zero is returned upon success. Otherwise:

-EINVAL is returned if sem is not a valid semaphore descriptor.

Tags

unrestricted

6.88 Task management services

Services dealing with preemptive multi-tasking.

Collaboration diagram for Task management services:



Data Structures

struct RT_TASK_INFO

Task status descriptor.

Macros

#define T_LOPRIO 0

Task priorities.

#define T_LOCK __THREAD_M_LOCK

Task mode bits.

#define T_WARNSW __THREAD_M_WARNSW

Cobalt only, nop over Mercury.

Functions

int rt_task_delete (RT_TASK *task)

Delete a real-time task.

int rt_task_set_affinity (RT_TASK *task, const cpu_set_t *cpus)

Set CPU affinity of real-time task.

int rt_task_start (RT_TASK *task, void(*entry)(void *arg), void *arg)

Start a real-time task.

• int rt_task_shadow (RT_TASK *task, const char *name, int prio, int mode)

Turn caller into a real-time task.

int rt_task_join (RT_TASK *task)

Wait on the termination of a real-time task.

• int rt_task_wait_period (unsigned long *overruns_r)

Wait for the next periodic release point.

int rt task sleep (RTIME delay)

Delay the current real-time task (with relative delay).

• int rt_task_sleep_until (RTIME date)

Delay the current real-time task (with absolute wakeup date).

• int rt_task_same (RT_TASK *task1, RT_TASK *task2)

Compare real-time task descriptors.

• int rt_task_suspend (RT_TASK *task)

Suspend a real-time task.

int rt_task_resume (RT_TASK *task)

Resume a real-time task.

RT TASK * rt task self (void)

Retrieve the current task descriptor.

• int rt task set priority (RT TASK *task, int prio)

Change the base priority of a real-time task.

• int rt_task_set_mode (int clrmask, int setmask, int *mode_r)

Change the current task mode.

int rt_task_yield (void)

Manual round-robin.

• int rt task unblock (RT TASK *task)

Unblock a real-time task.

• int rt_task_slice (RT_TASK *task, RTIME quantum)

Set a task's round-robin quantum.

• int rt_task_inquire (RT_TASK *task, RT_TASK_INFO *info)

Retrieve information about a real-time task.

ssize_t rt_task_send_timed (RT_TASK *task, RT_TASK_MCB *mcb_s, RT_TASK_MCB *mcb_r, const struct timespec *abs_timeout)

Send a message to a real-time task.

static ssize_t rt_task_send_until (RT_TASK *task, RT_TASK_MCB *mcb_s, RT_TASK_MC
 B *mcb r, RTIME timeout)

Send a message to a real-time task (with absolute scalar timeout).

static ssize_t rt_task_send (RT_TASK *task, RT_TASK_MCB *mcb_s, RT_TASK_MCB *mcb_r, RTIME timeout)

Send a message to a real-time task (with relative scalar timeout).

• int rt_task_receive_timed (RT_TASK_MCB *mcb_r, const struct timespec *abs_timeout)

Receive a message from a real-time task.

static int rt_task_receive_until (RT_TASK_MCB *mcb_r, RTIME timeout)

Receive a message from a real-time task (with absolute scalar timeout).

• static int rt_task_receive (RT_TASK_MCB *mcb_r, RTIME timeout)

Receive a message from a real-time task (with relative scalar timeout).

int rt_task_reply (int flowid, RT_TASK_MCB *mcb_s)

Reply to a remote task message.

int rt_task_bind (RT_TASK *task, const char *name, RTIME timeout)

Bind to a task.

• int rt task unbind (RT TASK *task)

Unbind from a task.

int rt_task_create (RT_TASK *task, const char *name, int stksize, int prio, int mode)

Create a real-time task.

• int rt_task_set_periodic (RT_TASK *task, RTIME idate, RTIME period)

Make a real-time task periodic.

• int rt_task_spawn (RT_TASK *task, const char *name, int stksize, int prio, int mode, void(*entry)(void *arg), void *arg)

Create and start a real-time task.

6.88.1 Detailed Description

Services dealing with preemptive multi-tasking.

Each Alchemy task is an independent portion of the overall application code embodied in a C procedure, which executes on its own stack context.

6.88.2 Macro Definition Documentation

6.88.2.1 #define T_LOCK __THREAD_M_LOCK

Task mode bits.

Referenced by rt_task_create(), rt_task_set_mode(), and rt_task_shadow().

6.88.2.2 #define T LOPRIO 0

Task priorities.

6.88.2.3 #define T WARNSW THREAD M WARNSW

Cobalt only, nop over Mercury.

Referenced by rt_task_create(), rt_task_set_mode(), and rt_task_shadow().

6.88.3 Function Documentation

6.88.3.1 int rt task bind (RT TASK * task, const char * name, RTIME timeout)

Bind to a task.

This routine creates a new descriptor to refer to an existing Alchemy task identified by its symbolic name. If the object does not exist on entry, the caller may block until a task of the given name is created.

Parameters

task	The address of a task descriptor filled in by the operation. Contents of this memory	
	is undefined upon failure.	
name	A valid NULL-terminated name which identifies the task to bind to. This string should	
	match the object name argument passed to rt_task_create(), or rt_task_shadow().	
timeout	The number of clock ticks to wait for the registration to occur (see note). Passing	
	TM_INFINITE causes the caller to block indefinitely until the object is registered.	
	Passing TM_NONBLOCK causes the service to return immediately without waiting	
	if the object is not registered on entry.	

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task before the retrieval has completed.
- -EWOULDBLOCK is returned if *timeout* is equal to TM_NONBLOCK and the searched object is not registered on entry.
- -ETIMEDOUT is returned if the object cannot be retrieved within the specified amount of time.
- -EPERM is returned if this service should block, but was not called from a Xenomai thread.

Tags

xthread-nowait, switch-primary

Note

The *timeout* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.88.3.2 int rt_task_create (RT_TASK * task, const char * name, int stksize, int prio, int mode)

Create a real-time task.

This service creates a task with access to the full set of Xenomai real-time services. If *prio* is non-zero, the new task belongs to Xenomai's real-time FIFO scheduling class, aka SCHED_FIFO. If *prio* is zero, the task belongs to the regular SCHED_OTHER class.

Creating tasks with zero priority is useful for running non real-time processes which may invoke blocking real-time services, such as pending on a semaphore, reading from a message queue or a buffer, and so on.

Once created, the task is left dormant until it is actually started by rt_task_start().

Parameters

task	The address of a task descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the task. When non-NULL and
	non-empty, a copy of this string is used for indexing the created task into the object
	registry.
stksize	The size of the stack (in bytes) for the new task. If zero is passed, a system-
	dependent default size will be substituted.
prio	The base priority of the new task. This value must be in the [0 99] range, where 0
	is the lowest effective priority.
mode	The task creation mode. The following flags can be OR'ed into this bitmask:

- T_JOINABLE allows another task to wait on the termination of the new task. rt_task_join() shall be called for this task to clean up any resources after its termination.
- T_LOCK causes the new task to lock the scheduler prior to entering the user routine specified by rt_task_start(). A call to rt_task_set_mode() from the new task is required to drop this lock.
- When running over the Cobalt core, T_WARNSW causes the SIGDEBUG signal to be sent to the current task whenever it switches to the secondary mode. This feature is useful to detect unwanted migrations to the Linux domain. This flag has no effect over the Mercury core.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if either prio, mode or stksize are invalid.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the task.
- -EEXIST is returned if the *name* is conflicting with an already registered task.

Tags

thread-unrestricted, switch-secondary

Side effects

- When running over the Cobalt core:
 - calling rt_task_create() causes SCHED_FIFO tasks to switch to secondary mode.
 - members of Xenomai's SCHED_FIFO class running in the primary domain have utmost priority over all Linux activities in the system, including Linux interrupt handlers.
- When running over the Mercury core, the new task belongs to the regular POSIX SCHED_F

 IFO class.

Note

Tasks can be referred to from multiple processes which all belong to the same Xenomai session.

Examples:

cross-link.c.

References T_LOCK, and T_WARNSW.

Referenced by rt task spawn().

```
6.88.3.3 int rt_task_delete ( RT_TASK * task )
```

Delete a real-time task.

This call terminates a task previously created by rt task create().

Tasks created with the T_JOINABLE flag shall be joined by a subsequent call to rt_task_join() once successfully deleted, to reclaim all resources.

Parameters

$task \mid l$ ne task descriptor.	task	The task descriptor.		
-----------------------------------	------	----------------------	--	--

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if task is not a valid task descriptor.
- -EPERM is returned if *task* is NULL and this service was called from an invalid context. In addition, this error is always raised when this service is called from asynchronous context, such as a timer/alarm handler.

Tags

thread-unrestricted, switch-secondary

Note

The caller must be an Alchemy task if *task* is NULL.

Examples:

cross-link.c.

```
6.88.3.4 int rt_task_inquire ( RT_TASK * task, RT_TASK_INFO * info )
```

Retrieve information about a real-time task.

Return various information about an Alchemy task. This service may also be used to probe for task existence.

Parameters

task	The task descriptor. If <i>task</i> is NULL, the information about the current task is returned.
info	The address of a structure the task information will be written to. Passing NULL is valid, in which case the system is only probed for existence of the specified task.

Returns

Zero is returned if the task exists. In addition, if *info* is non-NULL, it is filled in with task information.

- -EINVAL is returned if task is not a valid task descriptor, or if prio is invalid.
- -EPERM is returned if task is NULL and this service was called from an invalid context.

Tags

thread-unrestricted, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

References RT_TASK_INFO::name, RT_TASK_INFO::pid, RT_TASK_INFO::prio, and RT_TASK_IN→ FO::stat.

Wait on the termination of a real-time task.

This service blocks the caller in non-real-time context until *task* has terminated. All resources are released after successful completion of this service.

The specified task must have been created by the same process that wants to join it, and the T_JOIN ← ABLE mode flag must have been set on creation to rt_task_create().

Tasks created with the T_JOINABLE flag shall be joined by a subsequent call to rt_task_join() once successfully deleted, to reclaim all resources.

Parameters

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if task is not a valid task descriptor.
- -EINVAL is returned if the task was not created with T_JOINABLE set or some other task is already waiting on the termination.
- -EDEADLK is returned if task refers to the caller.
- -ESRCH is returned if task no longer exists or refers to task created by a different process.

Tags

thread-unrestricted, switch-primary

Note

After successful completion of this service, it is neither required nor valid to additionally invoke rt_task_delete() on the same task.

References pthread_join().

6.88.3.6 ssize_t rt_task_receive (RT_TASK_MCB * mcb_r, RTIME timeout) [inline], [static]

Receive a message from a real-time task (with relative scalar timeout).

This routine is a variant of rt_task_receive_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

mcb_r	The address of a message control block referring to the receive message area.
timeout	A delay expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_task_receive_timed().

```
6.88.3.7 int rt_task_receive_timed ( RT_TASK_MCB * mcb_r, const struct timespec * abs_timeout )
```

Receive a message from a real-time task.

This service is part of the synchronous message passing support available to Alchemy tasks. The caller receives a variable-sized message from another task. The sender is blocked until the caller invokes rt_task_reply() to finish the transaction.

A basic message control block is used to store the location and size of the data area to receive from the client, in addition to a user-defined operation code.

Parameters

mcb_r	The address of a message control block referring to the receive message area. The
	fields from this control block should be set as follows:

- mcb_r->data should contain the address of a buffer large enough to collect the data sent by the remote task;
- mcb_r->size should contain the size in bytes of the buffer space pointed at by mcb_r->data. If mcb_r->size is lower than the actual size of the received message, no data copy takes place and -ENOBUFS is returned to the caller. See note.

Upon return, mcb_r->opcode will contain the operation code sent from the remote task using rt_task_← send().

Parameters

abs_timeout	The number of clock ticks to wait for receiving a message (see note). Passing NULL
	causes the caller to block indefinitely until a remote task eventually sends a mes-
	sage. Passing { .tv_sec = 0, .tv_nsec = 0 } causes the service to return immediately
	without waiting if no remote task is currently waiting for sending a message.

Returns

A strictly positive value is returned upon success, representing a flow identifier for the opening transaction; this token should be passed to rt_task_reply(), in order to send back a reply to and unblock the remote task appropriately. Otherwise:

- -EPERM is returned if this service was called from an invalid context.
- -EINTR is returned if rt_task_unblock() was called for the current task before a message was received.

- -ENOBUFS is returned if *mcb_r* does not point at a message area large enough to collect the remote task's message.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and no remote task is currently waiting for sending a message to the caller.
- -ETIMEDOUT is returned if no message was received within the timeout.

Tags

xthread-only, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_task_receive(), and rt_task_receive_until().

```
6.88.3.8 ssize_t rt_task_receive_until ( RT_TASK_MCB * mcb_r, RTIME abs_timeout ) [inline], [static]
```

Receive a message from a real-time task (with absolute scalar timeout).

This routine is a variant of rt_task_receive_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

mcb_r	The address of a message control block referring to the receive message area.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_task_receive_timed().

```
6.88.3.9 int rt_task_reply (int flowid, RT_TASK_MCB * mcb_s)
```

Reply to a remote task message.

This service is part of the synchronous message passing support available to Alchemy tasks. The caller sends a variable-sized message back to a remote task, in response to this task's initial message received by a call to rt_task_receive(). As a consequence of calling rt_task_reply(), the remote task will be unblocked from the rt_task_send() service.

A basic message control block is used to store the location and size of the data area to send back, in addition to a user-defined status code.

Parameters

flowid	The flow identifier returned by a previous call to rt_task_receive() which uniquely
	identifies the current transaction.

mcb_s The address of an optional message control block referring to the message to be sent back. If mcb_s is NULL, the remote will be unblocked without getting any reply data. When mcb_s is valid, the fields from this control block should be set as follows:

- mcb_s->data should contain the address of the payload data to send to the remote task.
- mcb_s->size should contain the size in bytes of the payload data pointed at by mcb_s->data. Zero is a legitimate value, and indicates that no payload data will be transferred. In the latter case, mcb s->data will be ignored.
- mcb_s->opcode is an opaque status code carried during the message transfer the caller can fill
 with any appropriate value. It will be made available "as is" to the remote task into the status code
 field by the rt_task_send() service. If mcb_s is NULL, Zero will be returned to the remote task into
 the status code field.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if flowid is invalid.
- -ENXIO is returned if *flowid* does not match the expected identifier returned from the latest call of the current task to rt_task_receive(), or if the remote task stopped waiting for the reply in the meantime (e.g. the remote could have been deleted or forcibly unblocked).
- -ENOBUFS is returned if the reply data referred to by *mcb_s* is larger than the reply area mentioned by the remote task when calling rt_task_send(). In such a case, the remote task also receives -← ENOBUFS on return from rt_task_send().
- -EPERM is returned if this service was called from an invalid context.

Tags

xthread-only, switch-primary

```
6.88.3.10 int rt task resume ( RT TASK * task )
```

Resume a real-time task.

Forcibly resume the execution of a task which was previously suspended by a call to rt_task_suspend(), if the suspend nesting count decrements to zero.

Parameters

·	task	The task descriptor.	
---	------	----------------------	--

Returns

Zero is returned upon success. Otherwise:

-EINVAL is returned if task is not a valid task descriptor.

Tags

unrestricted, switch-primary

Note

Blocked and suspended task states are cumulative. Therefore, resuming a task currently waiting on a synchronization object (e.g. semaphore, queue) does not make it eligible for scheduling until the awaited resource is eventually acquired, or a timeout elapses.

```
6.88.3.11 int rt_task_same ( RT_TASK * task1, RT_TASK * task2 )
```

Compare real-time task descriptors.

This predicate returns true if task1 and task2 refer to the same task.

Parameters

task1	First task descriptor to compare.
task2	Second task descriptor to compare.

Returns

A non-zero value is returned if both descriptors refer to the same task, zero otherwise.

Tags

unrestricted

```
6.88.3.12 RT_TASK * rt_task_self (void)
```

Retrieve the current task descriptor.

Return the address of the current Alchemy task descriptor.

Returns

The address of the task descriptor referring to the current Alchemy task is returned upon success, or NULL if not called from a valid Alchemy task context.

Tags

xthread-only

```
6.88.3.13 ssize_t rt_task_send ( RT_TASK * task, RT_TASK_MCB * mcb_r, RTIME timeout ) [inline], [static]
```

Send a message to a real-time task (with relative scalar timeout).

This routine is a variant of rt_task_send_timed() accepting a relative timeout specification expressed as a scalar value.

Parameters

task	The task descriptor.
mcb_s	The address of the message control block referring to the message to be sent.
mcb_r	The address of an optional message control block referring to the reply message
	area.
timeout	A delay expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_task_send_timed().

6.88.3.14 ssize_t rt_task_send_timed (RT_TASK * task, RT_TASK_MCB * mcb_r, const struct timespec * abs_timeout)

Send a message to a real-time task.

This service is part of the synchronous message passing support available to Alchemy tasks. The caller sends a variable-sized message to another task, waiting for the remote to receive the initial message by a call to rt_task_receive(), then reply to it using rt_task_reply().

A basic message control block is used to store the location and size of the data area to send or retrieve upon reply, in addition to a user-defined operation code.

Parameters

task	The task descriptor.
mcb_s	The address of the message control block referring to the message to be sent. The
	fields from this control block should be set as follows:

- mcb s->data should contain the address of the payload data to send to the remote task.
- mcb_s->size should contain the size in bytes of the payload data pointed at by mcb_s->data. Zero
 is a legitimate value, and indicates that no payload data will be transferred. In the latter case,
 mcb_s->data will be ignored.
- mcb_s->opcode is an opaque operation code carried during the message transfer, the caller can
 fill with any appropriate value. It will be made available "as is" to the remote task into the operation
 code field by the rt_task_receive() service.

Parameters

mcb_r	The address of an optional message control block referring to the reply message
	area. If mcb_r is NULL and a reply is sent back by the remote task, the reply
	message will be discarded, and -ENOBUFS will be returned to the caller. When
	mcb_r is valid, the fields from this control block should be set as follows:

- mcb_r->data should contain the address of a buffer large enough to collect the reply data from the remote task.
- mcb_r->size should contain the size in bytes of the buffer space pointed at by mcb_r->data. If mcb_r->size is lower than the actual size of the reply message, no data copy takes place and -ENOBUFS is returned to the caller.

Upon return, mcb_r->opcode will contain the status code sent back from the remote task using rt_task
_reply(), or zero if unspecified.

Parameters

abs_timeout	An absolute date expressed in clock ticks, specifying a time limit to wait for the
	recipient task to reply to the initial message (see note). Passing NULL causes the
	caller to block indefinitely until a reply is received. Passing { .tv_sec = 0, .tv_nsec
	= 0 } causes the service to return without blocking in case the recipient task is not
	waiting for messages at the time of the call.

Returns

A positive value is returned upon success, representing the length (in bytes) of the reply message returned by the remote task. Zero is a success status, meaning either that mcb_r was NULL on entry, or that no actual message was passed to the remote call to rt task reply(). Otherwise:

-EINVAL is returned if task is not a valid task descriptor.

- · -EPERM is returned if this service was called from an invalid context.
- -ENOBUFS is returned if mcb_r does not point at a message area large enough to collect the remote task's reply. This includes the case where mcb_r is NULL on entry, despite the remote task attempts to send a reply message.
- -EWOULDBLOCK is returned if abs_timeout is { .tv_sec = 0, .tv_nsec = 0 } and the recipient task is not currently waiting for a message on the rt_task_receive() service.
- -EIDRM is returned if task has been deleted while waiting for a reply.
- -EINTR is returned if rt_task_unblock() was called for the current task before any reply was received from the recipient task.

Tags

xthread-only, switch-primary

Note

abs_timeout is interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_task_send(), and rt_task_send_until().

```
6.88.3.15 ssize_t rt_task_send_until ( RT_TASK * task, RT_TASK_MCB * mcb_r, RTIME abs_timeout ) [inline], [static]
```

Send a message to a real-time task (with absolute scalar timeout).

This routine is a variant of rt_task_send_timed() accepting an absolute timeout specification expressed as a scalar value.

Parameters

task	The task descriptor.
mcb_s	The address of the message control block referring to the message to be sent.
mcb_r	The address of an optional message control block referring to the reply message
	area.
abs_timeout	An absolute date expressed in clock ticks.

Tags

xthread-only, switch-primary

References rt_task_send_timed().

```
6.88.3.16 int rt_task_set_affinity ( RT_TASK * task, const cpu_set_t * cpus )
```

Set CPU affinity of real-time task.

This calls makes task affine to the set of CPUs defined by cpus.

Parameters

task	The task descriptor. If <i>task</i> is NULL, the CPU affinity of the current task is changed.
cpus	The set of CPUs <i>task</i> should be affine to.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *task* is NULL but the caller is not a Xenomai task, or if *task* is non-NULL but not a valid task descriptor.
- -EINVAL is returned if *cpus* contains no processors that are currently physically on the system and permitted to the process according to any restrictions that may be imposed by the "cpuset" mechanism described in cpuset(7).

Tags

thread-unrestricted, switch-secondary

Note

The caller must be an Alchemy task if task is NULL.

6.88.3.17 int rt task set mode (int clrmask, int setmask, int * mode r)

Change the current task mode.

Each Alchemy task has a set of internal flags determining several operating conditions. rt_task_set—mode() takes a bitmask of mode bits to clear for disabling the corresponding modes for the current task, and another one to set for enabling them. The mode bits which were previously in effect before the change can be returned upon request.

The following bits can be part of the bitmask:

- T_LOCK causes the current task to lock the scheduler on the current CPU, preventing all further involuntary task switches on this CPU. Clearing this bit unlocks the scheduler.
- Only when running over the Cobalt core:
 - T_WARNSW causes the SIGDEBUG signal to be sent to the current task whenever it switches to the secondary mode. This feature is useful to detect unwanted migrations to the Linux domain.
 - T_CONFORMING can be passed in *setmask* to switch the current Alchemy task to its preferred runtime mode. The only meaningful use of this switch is to force a real-time task back to primary mode (see note). Any other use leads to a nop.

These two last flags have no effect over the Mercury core, and are simply ignored.

Parameters

clrmask	A bitmask of mode bits to clear for the current task, before setmask is applied. Zero
	is an acceptable value which leads to a no-op.
setmask	A bitmask of mode bits to set for the current task. Zero is an acceptable value which
	leads to a no-op.
mode_r	If non-NULL, mode_r must be a pointer to a memory location which will be written
	upon success with the previous set of active mode bits. If NULL, the previous set of
	active mode bits will not be returned.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if task is not a valid task descriptor, or if any bit from clrmask or setmask is invalid.
- -EPERM is returned if this service was called from an invalid context.

Tags

xthread-only, switch-primary

Note

The caller must be an Alchemy task.

Forcing the task mode using the T_CONFORMING bit from user code is almost always wrong, since the Xenomai/cobalt core handles mode switches internally when/if required. Most often, manual mode switching from applications introduces useless overhead. This mode bit is part of the API only to cover rare use cases in middleware code based on the Alchemy interface.

References T LOCK, and T WARNSW.

6.88.3.18 int rt task set periodic (RT TASK * task, RTIME idate, RTIME period)

Make a real-time task periodic.

Make a task periodic by programing its first release point and its period in the processor time line. *task* should then call rt_task_wait_period() to sleep until the next periodic release point in the processor timeline is reached.

Parameters

task	The task descriptor. If <i>task</i> is NULL, the current task is made periodic. <i>task</i> must
	belong the current process.
idate	The initial (absolute) date of the first release point, expressed in clock ticks (see
	note). If <i>idate</i> is equal to TM_NOW, the current system date is used.
period	The period of the task, expressed in clock ticks (see note). Passing TM_INFINITE
	stops the task's periodic timer if enabled, then returns successfully.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *task* is NULL but the caller is not a Xenomai task, or if *task* is non-NULL but not a valid task descriptor.
- -ETIMEDOUT is returned if idate is different from TM_INFINITE and represents a date in the past.

Tags

thread-unrestricted, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

Over Cobalt, -EINVAL is returned if *period* is different from TM_INFINITE but shorter than the user scheduling latency value for the target system, as displayed by /proc/xenomai/latency.

The *idate* and *period* values are interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

Attention

Unlike its Xenomai 2.x counterpart, rt_task_set_periodic() will **NOT** block *task* until *idate* is reached. The first beat in the periodic timeline should be awaited for by a call to rt_task_wait←_period().

Examples:

cross-link.c.

References clock gettime().

```
6.88.3.19 int rt task set priority ( RT TASK * task, int prio )
```

Change the base priority of a real-time task.

The base priority of a task defines the relative importance of the work being done by each task, which gains conrol of the CPU accordingly.

Changing the base priority of a task does not affect the priority boost the target task might have obtained as a consequence of a priority inheritance undergoing.

Parameters

task	The task descriptor. If <i>task</i> is NULL, the priority of the current task is changed.
prio	The new priority. This value must range from [T_LOPRIO T_HIPRIO] (inclusive)
	where T_LOPRIO is the lowest effective priority.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *task* is not a valid task descriptor, or if *prio* is invalid.
- -EPERM is returned if task is NULL and this service was called from an invalid context.

Tags

thread-unrestricted, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

Assigning the same priority to a running or ready task moves it to the end of its priority group, thus causing a manual round-robin.

```
6.88.3.20 int rt task shadow ( RT TASK * task, const char * name, int prio, int mode )
```

Turn caller into a real-time task.

Extends the calling Linux task with Xenomai capabilities, with access to the full set of Xenomai real-time services. This service is typically used for turning the main() thread of an application process into a Xenomai-enabled task.

If *prio* is non-zero, the new task moves to Xenomai's real-time FIFO scheduling class, aka SCHED_FIFO. If *prio* is zero, the task moves to the regular SCHED_OTHER class.

Running Xenomai tasks with zero priority is useful for running non real-time processes which may invoke blocking real-time services, such as pending on a semaphore, reading from a message queue or a buffer, and so on.

Once shadowed with the Xenomai extension, the calling task returns and resumes execution normally from the call site.

Parameters

task	If non-NULL, the address of a task descriptor which can be later used to identify
	uniquely the task, upon success of this call. If NULL, no descriptor is returned.
name	An ASCII string standing for the symbolic name of the task. When non-NULL and
	non-empty, a copy of this string is used for indexing the task into the object registry.
prio	The base priority of the task. This value must be in the [0 99] range, where 0 is
	the lowest effective priority.
mode	The task shadowing mode. The following flags can be OR'ed into this bitmask:

- T_LOCK causes the current task to lock the scheduler before returning to the caller, preventing all
 further involuntary task switches on the current CPU. A call to rt_task_set_mode() from the current
 task is required to drop this lock.
- When running over the Cobalt core, T_WARNSW causes the SIGDEBUG signal to be sent to the current task whenever it switches to the secondary mode. This feature is useful to detect unwanted migrations to the Linux domain. This flag has no effect over the Mercury core.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if prio is invalid.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the task extension.
- -EEXIST is returned if the *name* is conflicting with an already registered task.
- -EBUSY is returned if the caller is already mapped to a Xenomai task context.
- -EPERM is returned if this service was called from an invalid context.

Tags

pthread-only, switch-secondary

Side effects

Over the Cobalt core, the caller always returns from this service in primary mode.

Note

Tasks can be referred to from multiple processes which all belong to the same Xenomai session.

Examples:

rtcanrecv.c, and rtcansend.c.

References T_LOCK, and T_WARNSW.

6.88.3.21 int rt_task_sleep (RTIME delay)

Delay the current real-time task (with relative delay).

This routine is a variant of rt_task_sleep_until() accepting a relative timeout specification.

Parameters

delay	A relative delay expressed in clock ticks (see note). A zero delay causes this service
	to return immediately to the caller with a success status.

Returns

See rt task sleep until().

Tags

xthread-only, switch-primary

Note

The *delay* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

Examples:

cross-link.c, and rtcansend.c.

```
6.88.3.22 int rt_task_sleep_until ( RTIME date )
```

Delay the current real-time task (with absolute wakeup date).

Delay the execution of the calling task until a given date is reached. The caller is put to sleep, and does not consume any CPU time in such a state.

Parameters

date	An absolute date expressed in clock ticks, specifying a wakeup date (see note). As
	a special case, TM_INFINITE is an acceptable value that causes the caller to block
	indefinitely, until rt_task_unblock() is called against it. Otherwise, any wake up date
	in the past causes the task to return immediately.

Returns

Zero is returned upon success. Otherwise:

- -EINTR is returned if rt_task_unblock() was called for the current task.
- -ETIMEDOUT is returned if date has already elapsed.
- -EPERM is returned if this service was called from an invalid context.

Tags

xthread-only, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

The *date* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.88.3.23 int rt_task_slice (RT_TASK * task, RTIME quantum)

Set a task's round-robin quantum.

Set the time credit allotted to a task undergoing the round-robin scheduling. If *quantum* is non-zero, rt_task_slice() also refills the current quantum for the target task, otherwise, time-slicing is stopped for that task.

In other words, rt_task_slice() should be used to toggle round-robin scheduling for an Alchemy task.

Parameters

task	The task descriptor. If <i>task</i> is NULL, the time credit of the current task is changed.
	task must belong to the current process.
quantum	The round-robin quantum for the task expressed in clock ticks (see note).

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if task is not a valid task descriptor, or if prio is invalid.
- -EPERM is returned if task is NULL and this service was called from an invalid context.

Tags

thread-unrestricted, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

The *quantum* value is interpreted as a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

6.88.3.24 int rt_task_spawn (RT_TASK * task, const char * name, int stksize, int prio, int mode, void(*)(void *arg) entry, void * arg)

Create and start a real-time task.

This service spawns a task by combining calls to rt_task_create() and rt_task_start() for the new task.

Parameters

task	The address of a task descriptor which can be later used to identify uniquely the created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the task. When non-NULL and non-empty, a copy of this string is used for indexing the created task into the object registry.
stksize	The size of the stack (in bytes) for the new task. If zero is passed, a system-dependent default size will be substituted.
prio	The base priority of the new task. This value must be in the [0 99] range, where 0 is the lowest effective priority.
mode	The task creation mode. See rt_task_create().
entry	The address of the task entry point.

arg	A user-defined opaque argument <i>entry</i> will receive.

Returns

456

See rt_task_create().

Tags

thread-unrestricted, switch-secondary

Side effects

```
see rt_task_create().
```

References rt_task_create(), and rt_task_start().

```
6.88.3.25 int rt_task_start ( RT_TASK * task, void(*)(void *arg) entry, void * arg )
```

Start a real-time task.

This call starts execution of a task previously created by rt_task_create(). This service causes the started task to leave the initial dormant state.

Parameters

task	The task descriptor.
entry	The address of the task entry point.
arg	A user-defined opaque argument <i>entry</i> will receive.

Returns

Zero is returned upon success. Otherwise:

-EINVAL is returned if task is not a valid task descriptor.

Tags

thread-unrestricted, switch-primary

Note

Starting an already started task leads to a nop, returning a success status.

Examples:

cross-link.c.

Referenced by rt_task_spawn().

```
6.88.3.26 int rt_task_suspend ( RT_TASK * task )
```

Suspend a real-time task.

Forcibly suspend the execution of a task. This task will not be eligible for scheduling until it is explicitly resumed by a call to rt_task_resume(). In other words, the suspended state caused by a call to rt_task_suspend() is cumulative with respect to the delayed and blocked states caused by other services, and is managed separately from them.

A nesting count is maintained so that rt_task_suspend() and rt_task_resume() must be used in pairs.

Receiving a Linux signal causes the suspended task to resume immediately.

Parameters

task The task descriptor. If task is NULL, the current task is suspended.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *task* is NULL but the caller is not a Xenomai task, or if *task* is non-NULL but not a valid task descriptor.
- -EINTR is returned if a Linux signal has been received by the caller if suspended.
- -EPERM is returned if task is NULL and this service was called from an invalid context.

Tags

thread-unrestricted, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

Blocked and suspended task states are cumulative. Therefore, suspending a task currently waiting on a synchronization object (e.g. semaphore, queue) holds its execution until it is resumed, despite the awaited resource may have been acquired, or a timeout has elapsed in the meantime.

```
6.88.3.27 int rt task unbind (RT TASK * task )
```

Unbind from a task.

Parameters

```
task The task descriptor.
```

This routine releases a previous binding to an Alchemy task. After this call has returned, the descriptor is no more valid for referencing this object.

Tags

thread-unrestricted

```
6.88.3.28 int rt_task_unblock ( RT_TASK * task )
```

Unblock a real-time task.

Break the task out of any wait it is currently in. This call clears all delay and/or resource wait condition for the target task.

However, rt_task_unblock() does not resume a task which has been forcibly suspended by a previous call to rt_task_suspend(). If all suspensive conditions are gone, the task becomes eligible anew for scheduling.

Parameters

task	The task descriptor.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if task is not a valid task descriptor.

Tags

unrestricted, switch-primary

```
6.88.3.29 int rt task wait period (unsigned long * overruns r)
```

Wait for the next periodic release point.

Delay the current task until the next periodic release point is reached. The periodic timer should have been previously started for *task* by a call to rt_task_set_periodic().

Parameters

overruns_r	If non-NULL, overruns_r shall be a pointer to a memory location which will be written
	with the count of pending overruns. This value is written to only when rt_task←
	_wait_period() returns -ETIMEDOUT or success. The memory location remains
	unmodified otherwise. If NULL, this count will not be returned.

Returns

Zero is returned upon success. If *overruns_r* is non-NULL, zero is written to the pointed memory location. Otherwise:

- -EWOULDBLOCK is returned if rt_task_set_periodic() was not called for the current task.
- -EINTR is returned if rt_task_unblock() was called for the waiting task before the next periodic release point was reached. In this case, the overrun counter is also cleared.
- -ETIMEDOUT is returned if a timer overrun occurred, which indicates that a previous release point was missed by the calling task. If *overruns_r* is non-NULL, the count of pending overruns is written to the pointed memory location.
- -EPERM is returned if this service was called from an invalid context.

Tags

xthread-only, switch-primary

Note

If the current release point has already been reached at the time of the call, the current task immediately returns from this service with no delay.

Examples:

cross-link.c.

```
6.88.3.30 int rt_task_yield ( void )
```

Manual round-robin.

Move the current task to the end of its priority group, so that the next equal-priority task in ready state is switched in.

Returns

Zero is returned upon success. Otherwise:

• -EPERM is returned if this service was called from an invalid context.

Tags

xthread-only, switch-primary

6.89 Timer management services

Services for reading and spinning on the hardware timer.

Collaboration diagram for Timer management services:



Data Structures

• struct rt_timer_info

Timer status descriptor.

Typedefs

typedef struct rt_timer_info RT_TIMER_INFO
 Timer status descriptor.

Functions

static RTIME rt_timer_read (void)

Return the current system time.

SRTIME rt_timer_ns2ticks (SRTIME ns)

Convert nanoseconds to Alchemy clock ticks.

SRTIME rt_timer_ticks2ns (SRTIME ticks)

Convert Alchemy clock ticks to nanoseconds.

• void rt_timer_inquire (RT_TIMER_INFO *info)

Inquire about the Alchemy clock.

void rt_timer_spin (RTIME ns)

Busy wait burning CPU cycles.

6.89.1 Detailed Description

Services for reading and spinning on the hardware timer.

6.89.2 Typedef Documentation

6.89.2.1 typedef struct rt_timer_info RT_TIMER_INFO

Timer status descriptor.

This structure reports information about the Alchemy clock, returned by a call to rt_timer_inquire().

6.89.3 Function Documentation

```
6.89.3.1 void rt_timer_inquire ( RT_TIMER_INFO * info )
```

Inquire about the Alchemy clock.

Return status information about the Alchemy clock.

Parameters

info The address of a structure to fill with the clock information.

Tags

unrestricted

References rt timer info::date, and rt timer info::period.

```
6.89.3.2 SRTIME rt_timer_ns2ticks ( SRTIME ns )
```

Convert nanoseconds to Alchemy clock ticks.

Convert a count of nanoseconds to Alchemy clock ticks. This routine operates on signed nanosecond values. This is the converse call to rt_timer_ticks2ns().

Parameters

ns The count of nanoseconds to convert.

Returns

The corresponding value expressed in clock ticks of the Alchemy clock. The resolution of the Alchemy clock can be set using the –alchemy-clock-resolution option when starting the application process (defaults to 1 nanosecond).

Tags

unrestricted

Examples:

cross-link.c, and rtcansend.c.

```
6.89.3.3 RTIME rt_timer_read ( void ) [inline], [static]
```

Return the current system time.

Return the current time maintained by the Xenomai core clock.

Returns

The current time expressed in clock ticks (see note).

Tags

unrestricted

Note

462

The *time* value is a multiple of the Alchemy clock resolution (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

Examples:

cross-link.c.

6.89.3.4 void rt_timer_spin (RTIME ns)

Busy wait burning CPU cycles.

Enter a busy waiting loop for a count of nanoseconds.

Since this service is always called with interrupts enabled, the caller might be preempted by other real-time activities, therefore the actual delay might be longer than specified.

Parameters

ns The time to wait expressed in nanoseconds.

Tags

unrestricted

6.89.3.5 SRTIME rt_timer_ticks2ns (SRTIME ns)

Convert Alchemy clock ticks to nanoseconds.

Convert a count of Alchemy clock ticks to nanoseconds. This routine operates on signed nanosecond values. This is the converse call to rt_timer_ns2ticks().

Parameters

ns The count of nanoseconds to convert.

Returns

The corresponding value expressed in nanoseconds. The resolution of the Alchemy clock can be set using the –alchemy-clock-resolution option when starting the application process (defaults to 1 nanosecond).

Tags

unrestricted

6.90 VxWorks® emulator

A VxWorks® emulation library on top of Xenomai.

A VxWorks® emulation library on top of Xenomai.

The emulator mimicks the behavior described in the public documentation of the WIND 5.x API for the following class of services:

- taskLib, taskInfoLib, taskHookLib,
- semLib, msgQLib, wdLib, memPartLib
- intLib, tickLib, sysLib (partial)
- errnoLib, lstLib, kernelLib (partial)

6.91 pSOS® emulator

A pSOS® emulation library on top of Xenomai.

A pSOS® emulation library on top of Xenomai.

The emulator mimicks the behavior described in the public documentation of the pSOS 2.x API for the following class of services:

- Tasks, Events, Queues, Semaphores
- Partitions, Regions, Timers

6.92 Transition Kit 465

6.92 Transition Kit

A set of wrappers and services easing the transition from Xenomai 2.x to 3.x.

• int COMPAT__rt_task_create (RT_TASK *task, const char *name, int stksize, int prio, int mode)

Create a real-time task (compatibility service).

int COMPAT__rt_task_set_periodic (RT_TASK *task, RTIME idate, RTIME period)

Make a real-time task periodic (compatibility service).

• int COMPAT__rt_alarm_create (RT_ALARM *alarm, const char *name)

Create an alarm object (compatibility service).

int rt alarm wait (RT ALARM *alarm)

Wait for the next alarm shot (compatibility service).

 int COMPAT__rt_event_create (RT_EVENT *event, const char *name, unsigned long ivalue, int mode)

Create an event flag group.

int COMPAT__rt_event_signal (RT_EVENT *event, unsigned long mask)
 Signal an event.

- int COMPAT__rt_event_clear (RT_EVENT *event, unsigned long mask, unsigned long *mask_r)
 Clear event flags.
- int COMPAT__rt_pipe_create (RT_PIPE *pipe, const char *name, int minor, size_t poolsize)

 Create a message pipe.
- int pthread_make_periodic_np (pthread_t thread, struct timespec *starttp, struct timespec *periodtp)

Make a thread periodic (compatibility service).

int pthread_wait_np (unsigned long *overruns_r)

Wait for the next periodic release point (compatibility service)

6.92.1 Detailed Description

A set of wrappers and services easing the transition from Xenomai 2.x to 3.x.

This interface provides a source compatibility layer for building applications based on the Xenomai 2.x *posix* and *native* APIs over Xenomai 3.x.

6.92.2 Function Documentation

```
6.92.2.1 int COMPAT__rt_alarm_create ( RT_ALARM * alarm, const char * name )
```

Create an alarm object (compatibility service).

This routine creates an object triggering an alarm routine at a specified time in the future. Alarms can be periodic or oneshot, depending on the reload interval value passed to rt_alarm_start(). A task can wait for timeouts using the rt_alarm_wait() service.

Parameters

alarm	The address of an alarm descriptor which can be later used to identify uniquely the
	created object, upon success of this call.

name	An ASCII string standing for the symbolic name of the alarm. When non-NULL and
	non-empty, a copy of this string is used for indexing the created alarm into the object
	registry.

Returns

Zero is returned upon success. Otherwise:

- -ENOMEM is returned if the system fails to get memory from the local pool in order to create the alarm.
- -EEXIST is returned if the *name* is conflicting with an already registered alarm.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Alarms are process-private objects and thus cannot be shared by multiple processes, even if they belong to the same Xenomai session.

Deprecated This is a compatibility service from the Transition Kit.

Clear event flags.

This call is the legacy form of the rt_event_clear() service, using a long event mask. The new form uses a regular integer to hold the event mask instead.

Parameters

event	The event descriptor.
mask	The set of event flags to be cleared.
mask_r	If non-NULL, mask_r is the address of a memory location which will receive the
	previous value of the event flag group before the flags are cleared.

Returns

Zero is returned upon success. Otherwise:

• -EINVAL is returned if event is not a valid event flag group descriptor.

Tags

unrestricted, switch-primary

Deprecated This is a compatibility service from the Transition Kit.

```
6.92.2.3 int COMPAT__rt_event_create ( RT_EVENT * event, const char * name, unsigned long ivalue, int mode )
```

Create an event flag group.

This call is the legacy form of the rt_event_create() service, using a long event mask. The new form uses a regular integer to hold the event mask instead.

6.92 Transition Kit 467

Parameters

event	The address of an event descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the event. When non-NULL and non-empty, a copy of this string is used for indexing the created event into the object registry.
ivalue	The initial value of the group's event mask.
mode	The event group creation mode. The following flags can be OR'ed into this bitmask:

- EV_FIFO makes tasks pend in FIFO order on the event flag group.
- EV PRIO makes tasks pend in priority order on the event flag group.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if mode is invalid.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the event flag group.
- -EEXIST is returned if the name is conflicting with an already registered event flag group.
- · -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

Note

Event flag groups can be shared by multiple processes which belong to the same Xenomai session.

Deprecated This is a compatibility service from the Transition Kit.

```
6.92.2.4 int COMPAT__rt_event_signal ( RT_EVENT * event, unsigned long mask )
```

Signal an event.

This call is the legacy form of the rt_event_signal() service, using a long event mask. The new form uses a regular integer to hold the event mask instead.

Parameters

event	The event descriptor.
mask	The set of events to be posted.

Returns

Zero is returned upon success. Otherwise:

-EINVAL is returned if event is not an event flag group descriptor.

Tags

unrestricted, switch-primary

Deprecated This is a compatibility service from the Transition Kit.

6.92.2.5 int COMPAT__rt_pipe_create (RT_PIPE * pipe, const char * name, int minor, size_t poolsize)

Create a message pipe.

This call is the legacy form of the rt_pipe_create() service, which returns a zero status upon success. The new form returns the *minor* number assigned to the connection instead, which is useful when P_\iff MINOR AUTO is specified in the call (see the discussion about the *minor* parameter).

This service opens a bi-directional communication channel for exchanging messages between Xenomai threads and regular Linux threads. Pipes natively preserve message boundaries, but can also be used in byte-oriented streaming mode from Xenomai to Linux.

rt_pipe_create() always returns immediately, even if no thread has opened the associated special device file yet. On the contrary, the non real-time side could block upon attempt to open the special device file until rt_pipe_create() is issued on the same pipe from a Xenomai thread, unless O_NONBLOCK was given to the open(2) system call.

Parameters

pipe	The address of a pipe descriptor which can be later used to identify uniquely the
	created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the pipe. When non-NULL and
	non-empty, a copy of this string is used for indexing the created pipe into the object
	registry.

Named pipes are supported through the use of the registry. Passing a valid *name* parameter when creating a message pipe causes a symbolic link to be created from /proc/xenomai/registry/rtipc/xddp/*name* to the associated special device (i.e. /dev/rtp*), so that the specific *minor* information does not need to be known from those processes for opening the proper device file. In such a case, both sides of the pipe only need to agree upon a symbolic name to refer to the same data path, which is especially useful whenever the *minor* number is picked up dynamically using an adaptive algorithm, such as passing P_MINOR_AUTO as *minor* value.

Parameters

minor	The minor number of the device associated with the pipe. Passing P_MINOR_
	AUTO causes the minor number to be auto-allocated. In such a case, a symbolic
	link will be automatically created from /proc/xenomai/registry/rtipc/xddp/name to the
	allocated pipe device entry. Valid minor numbers range from 0 to CONFIG_XEN←
	O_OPT_PIPE_NRDEV-1.
poolsize	Specifies the size of a dedicated buffer pool for the pipe. Passing 0 means that all
	message allocations for this pipe are performed on the Cobalt core heap.

Returns

This compatibility call returns zero upon success. Otherwise:

- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the pipe.
- -ENODEV is returned if minor is different from P MINOR AUTO and is not a valid minor number.
- -EEXIST is returned if the *name* is conflicting with an already registered pipe.
- -EBUSY is returned if *minor* is already open.
- -EPERM is returned if this service was called from an asynchronous context.

Tags

thread-unrestricted, switch-secondary

6.92 Transition Kit 469

6.92.2.6 int COMPAT__rt_task_create (RT_TASK * task, const char * name, int stksize, int prio, int mode)

Create a real-time task (compatibility service).

This service creates a task with access to the full set of Xenomai real-time services.

This service creates a task with access to the full set of Xenomai real-time services. If *prio* is non-zero, the new task belongs to Xenomai's real-time FIFO scheduling class, aka SCHED_FIFO. If *prio* is zero, the task belongs to the regular SCHED_OTHER class.

Creating tasks with zero priority is useful for running non real-time processes which may invoke blocking real-time services, such as pending on a semaphore, reading from a message queue or a buffer, and so on.

Once created, the task is left dormant until it is actually started by rt_task_start().

Parameters

task	The address of a task descriptor which can be later used to identify uniquely the created object, upon success of this call.
name	An ASCII string standing for the symbolic name of the task. When non-NULL and non-empty, a copy of this string is used for indexing the created task into the object registry.
stksize	The size of the stack (in bytes) for the new task. If zero is passed, a system-dependent default size will be substituted.
prio	The base priority of the new task. This value must be in the [0 99] range, where 0 is the lowest effective priority.
mode	The task creation mode. The following flags can be OR'ed into this bitmask:

- T_FPU allows the task to use the FPU whenever available on the platform. This flag may be omitted, as it is automatically set when a FPU is present on the platform, cleared otherwise.
- T_SUSP causes the task to start in suspended mode. In such a case, the thread will have to be explicitly resumed using the rt_task_resume() service for its execution to actually begin.
- T_CPU(cpuid) makes the new task affine to CPU # cpuid. CPU identifiers range from 0 to 7 (inclusive).
- T_JOINABLE allows another task to wait on the termination of the new task. rt_task_join() shall be called for this task to clean up any resources after its termination.

Passing T_FPU|T_CPU(1) in the *mode* parameter thus creates a task with FPU support enabled and which will be affine to CPU #1.

• When running over the Cobalt core, T_WARNSW causes the SIGDEBUG signal to be sent to the current task whenever it switches to the secondary mode. This feature is useful to detect unwanted migrations to the Linux domain. This flag has no effect over the Mercury core.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if either prio, mode or stksize are invalid.
- -ENOMEM is returned if the system fails to get memory from the main heap in order to create the task.
- -EEXIST is returned if the name is conflicting with an already registered task.

Tags

thread-unrestricted, switch-secondary

Side effects

470

- calling rt_task_create() causes SCHED_FIFO tasks to switch to secondary mode.
- members of Xenomai's SCHED_FIFO class running in the primary domain have utmost priority over all Linux activities in the system, including Linux interrupt handlers.

Note

Tasks can be referred to from multiple processes which all belong to the same Xenomai session.

Deprecated This is a compatibility service from the Transition Kit.

```
6.92.2.7 int COMPAT rt task set periodic ( RT TASK * task, RTIME idate, RTIME period )
```

Make a real-time task periodic (compatibility service).

Make a task periodic by programing its first release point and its period in the processor time line. *task* should then call rt_task_wait_period() to sleep until the next periodic release point in the processor timeline is reached.

Parameters

task	The task descriptor. If task is NULL, the current task is made periodic. task must
	belong the current process.
idate	The initial (absolute) date of the first release point, expressed in clock ticks (see
	note). If <i>idate</i> is equal to TM_NOW, the current system date is used. Otherwise, if
	task is NULL or equal to rt_task_self(), the caller is delayed until idate has elapsed.
period	The period of the task, expressed in clock ticks (see note). Passing TM_INFINITE
	stops the task's periodic timer if enabled, then returns successfully.

Returns

Zero is returned upon success. Otherwise:

- -EINVAL is returned if *task* is NULL but the caller is not a Xenomai task, or if *task* is non-NULL but not a valid task descriptor.
- -ETIMEDOUT is returned if idate is different from TM INFINITE and represents a date in the past.

Tags

thread-unrestricted, switch-primary

Note

The caller must be an Alchemy task if task is NULL.

Unlike the original Xenomai 2.x call, this emulation delays the caller until *idate* has elapsed only if *task* is NULL or equal to rt_task_self().

Side effects

Over Cobalt, -EINVAL is returned if *period* is different from TM_INFINITE but shorter than the user scheduling latency value for the target system, as displayed by /proc/xenomai/latency.

6.92 Transition Kit 471

Note

The idate and period values are interpreted as a multiple of the Alchemy clock resolution (see -alchemy-clock-resolution option, defaults to 1 nanosecond).

Deprecated This is a compatibility service from the Transition Kit.

6.92.2.8 int pthread make periodic np (pthread t thread, struct timespec * starttp, struct timespec * periodtp)

Make a thread periodic (compatibility service).

This service makes the POSIX thread periodic.

Parameters

thread	thread to arm a periodic timer for.
starttp	start time, expressed as an absolute value of the CLOCK_REALTIME clock.
periodtp	period, expressed as a time interval.

Returns

0 on success;

an error number if:

- ESRCH, thread is invalid.
- ETIMEDOUT, the start time has already passed.
- EPERM, the caller is not a Xenomai thread.
- EINVAL, thread does not refer to the current thread.

Note

Unlike the original Xenomai 2.x call, this emulation does not delay the caller waiting for the first periodic release point. In addition, thread must be equal to pthread self().

Deprecated This service is a non-portable extension of the Xenomai 2.x POSIX interface, not available with Xenomai 3.x. Instead, Cobalt-based applications should set up a periodic timer using the timer create(), timer settime() call pair, then wait for release points via sigwaitinfo(). Overruns can be detected by looking at the siginfo.si overrun field. Alternatively, applications may obtain a file descriptor referring to a Cobalt timer via the timerfd() call, and read() from it to wait for timeouts.

References timer create(), and timer settime().

6.92.2.9 int pthread wait np (unsigned long * overruns r)

Wait for the next periodic release point (compatibility service)

Delay the current thread until the next periodic release point is reached. The periodic timer should have been previously started for thread by a call to pthread_make_periodic_np().

Parameters

472 Module Documentation

overruns_r	If non-NULL, <i>overruns_r</i> shall be a pointer to a memory location which will be written
_	with the count of pending overruns. This value is written to only when pthread_wait←
	np() returns ETIMEDOUT or success. The memory location remains unmodified
	otherwise. If NULL, this count will not be returned.

Returns

Zero is returned upon success. If *overruns_r* is non-NULL, zero is written to the pointed memory location. Otherwise:

- EWOULDBLOCK is returned if pthread_make_periodic_np() was not called for the current thread.
- EINTR is returned if thread was interrupted by a signal before the next periodic release point was reached.
- ETIMEDOUT is returned if a timer overrun occurred, which indicates that a previous release point was missed by the calling thread. If *overruns_r* is non-NULL, the count of pending overruns is written to the pointed memory location.
- EPERM is returned if this service was called from an invalid context.

Note

If the current release point has already been reached at the time of the call, the current thread immediately returns from this service with no delay.

Deprecated This service is a non-portable extension of the Xenomai 2.x POSIX interface, not available with Xenomai 3.x. Instead, Cobalt-based applications should set up a periodic timer using the timer_create(), timer_settime() call pair, then wait for release points via sigwaitinfo(). Overruns can be detected by looking at the siginfo.si_overrun field. Alternatively, applications may obtain a file descriptor referring to a Cobalt timer via the timerfd() call, and read() from it to wait for timeouts.

```
6.92.2.10 int rt alarm wait (RT ALARM * alarm )
```

Wait for the next alarm shot (compatibility service).

This service allows the current task to suspend execution until the specified alarm triggers. The priority of the current task is raised above all other tasks - except those also undergoing an alarm wait.

Returns

Zero is returned upon success, after the alarm timed out. Otherwise:

- -EINVAL is returned if alarm is not a valid alarm descriptor.
- · -EPERM is returned if this service was called from an invalid context.
- -EINTR is returned if rt_task_unblock() was called for the current task before the request is satisfied.
- -EIDRM is returned if *alarm* is deleted while the caller was sleeping on it. In such a case, *alarm* is no more valid upon return of this service.

Tags

xthread-only, switch-primary

Deprecated This is a compatibility service from the Transition Kit.

Chapter 7

Data Structure Documentation

7.1 a4l_channel Struct Reference

Structure describing some channel's characteristics.

Data Fields

- unsigned long flags
- unsigned long nb_bits

7.1.1 Detailed Description

Structure describing some channel's characteristics.

7.1.2 Field Documentation

7.1.2.1 unsigned long a4l_channel::flags

Channel flags to define the reference.

7.1.2.2 unsigned long a4l_channel::nb_bits

Channel resolution.

Referenced by a4l_get_chan().


The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/analogy/channel_range.h

7.2 a4l_channels_desc Struct Reference

Structure describing a channels set.

Collaboration diagram for a4l_channels_desc:



Data Fields

- unsigned long mode
- unsigned long length
- struct a4l_channel chans []

7.2.1 Detailed Description

Structure describing a channels set.

7.2.2 Field Documentation

7.2.2.1 struct a4l_channel a4l_channels_desc::chans[]

Channels tab

Referenced by a4l_get_chan().

7.2.2.2 unsigned long a4l channels desc::length

Channels count

7.2.2.3 unsigned long a4l_channels_desc::mode

Declaration mode (global or per channel)

Referenced by a4l_get_chan().

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/analogy/channel_range.h

7.3 a4l cmd desc Struct Reference

Structure describing the asynchronous instruction.

unsigned char idx_subd

Subdevice to which the command will be applied.

unsigned long flags

Command flags.

• unsigned int start_src

Start trigger type.

unsigned int start_arg

Start trigger argument.

• unsigned int scan_begin_src

Scan begin trigger type.

• unsigned int scan_begin_arg

Scan begin trigger argument.

unsigned int convert_src

Convert trigger type.

unsigned int convert_arg

Convert trigger argument.

• unsigned int scan_end_src

Scan end trigger type.

unsigned int scan_end_arg

Scan end trigger argument.

• unsigned int stop_src

Stop trigger type.

unsigned int stop_arg

Stop trigger argument.

unsigned char nb_chan

Count of channels related with the command.

• unsigned int * chan_descs

Tab containing channels descriptors.

• unsigned int data_len

< cmd simulation valid stages (driver dependent)

• sampl_t * data

Driver specific buffer pointer.

7.3.1 Detailed Description

Structure describing the asynchronous instruction.

See also

a4l_snd_command()

7.3.2 Field Documentation

7.3.2.1 unsigned int a4l_cmd_desc::data_len

< cmd simulation valid stages (driver dependent)

Driver specific buffer size

7.3.2.2 unsigned char a4l_cmd_desc::idx_subd

Subdevice to which the command will be applied.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/analogy.h

7.4 a4l_descriptor Struct Reference

Structure containing device-information useful to users.

Data Fields

char board_name [A4L_NAMELEN]

Board name.

• char driver name [A4L NAMELEN]

Driver name.

• int nb_subd

Subdevices count.

int idx_read_subd

Input subdevice index.

int idx_write_subd

Output subdevice index.

int fd

File descriptor.

• unsigned int magic

Opaque field.

• int sbsize

Data buffer size.

• void * sbdata

Data buffer pointer.

7.4.1 Detailed Description

Structure containing device-information useful to users.

See also

```
a4l_get_desc()
```

7.4.2 Field Documentation

7.4.2.1 char a4l_descriptor::board_name[A4L_NAMELEN]

Board name.

7.4.2.2 char a4l_descriptor::driver_name[A4L_NAMELEN]

Driver name.

7.4.2.3 int a4l_descriptor::fd

File descriptor.

Referenced by a4l_async_read(), a4l_async_write(), a4l_close(), a4l_fill_desc(), a4l_get_bufsize(), a4l_mark_bufrw(), a4l_mmap(), a4l_open(), a4l_poll(), a4l_set_bufsize(), a4l_snd_cancel(), a4l_snd_cancel(), a4l_snd_insn(), a4l_snd_insn(

7.4.2.4 int a4l_descriptor::idx_read_subd

Input subdevice index.

Referenced by a4l_async_read().

7.4.2.5 int a4l_descriptor::idx_write_subd

Output subdevice index.

Referenced by a4l_async_write().

7.4.2.6 unsigned int a4l_descriptor::magic

Opaque field.

Referenced by a4l_fill_desc(), a4l_find_range(), a4l_get_chinfo(), a4l_get_rnginfo(), a4l_get_subdinfo(), a4l_sys_desc().

7.4.2.7 int a4l_descriptor::nb_subd

Subdevices count.

Referenced by a4l_get_chinfo(), a4l_get_rnginfo(), and a4l_get_subdinfo().

7.4.2.8 void* a4l_descriptor::sbdata

Data buffer pointer.

Referenced by a4l_get_chinfo(), a4l_get_rnginfo(), a4l_get_subdinfo(), and a4l_sys_desc().

7.4.2.9 int a4l_descriptor::sbsize

Data buffer size.

Referenced by a4l_sys_desc().

The documentation for this struct was generated from the following file:

• include/rtdm/analogy.h

7.5 a4l_driver Struct Reference

Structure containing driver declaration data.

• struct list_head list

List stuff.

• struct module * owner

Pointer to module containing the code.

unsigned int flags

Type / status driver's flags.

• char * board name

Board name.

char * driver_name

driver name

• int privdata_size

Size of the driver's private data.

• int(* attach)(struct a4l_device *, struct a4l_link_desc *)

Attach procedure.

int(* detach)(struct a4l_device *)

Detach procedure.

7.5.1 Detailed Description

Structure containing driver declaration data.

See also

```
rt_task_inquire()
```

The documentation for this struct was generated from the following file:

include/cobalt/kernel/rtdm/analogy/driver.h

7.6 a4l_instruction Struct Reference

Structure describing the synchronous instruction.

Data Fields

unsigned int type

Instruction type.

• unsigned int idx_subd

Subdevice to which the instruction will be applied.

• unsigned int chan_desc

Channel descriptor.

unsigned int data_size

Size of the intruction data.

• void * data

Instruction data.

7.6.1 Detailed Description

Structure describing the synchronous instruction.

See also

a4l_snd_insn()

7.6.2 Field Documentation

7.6.2.1 unsigned int a4l_instruction::idx_subd

Subdevice to which the instruction will be applied.


The documentation for this struct was generated from the following file:

• include/rtdm/uapi/analogy.h

7.7 a4l_instruction_list Struct Reference

Structure describing the list of synchronous instructions.

Collaboration diagram for a4l_instruction_list:



Data Fields

· unsigned int count

Instructions count.

• a4l_insn_t * insns

Tab containing the instructions pointers.

7.7.1 Detailed Description

Structure describing the list of synchronous instructions.

See also

a4l_snd_insnlist()

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/analogy.h

7.8 a4l_range Struct Reference

Structure describing a (unique) range.

Data Fields

- long min
- long max
- unsigned long flags

7.8.1 Detailed Description

Structure describing a (unique) range.

7.8.2 Field Documentation

7.8.2.1 unsigned long a4l_range::flags

Range flags (unit, etc.)

7.8.2.2 long a4l_range::max

Maximal falue

7.8.2.3 long a4l_range::min

Minimal value


The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/analogy/channel_range.h

7.9 a4I_subdevice Struct Reference

Structure describing the subdevice.

Collaboration diagram for a4l_subdevice:



Data Fields

struct list_head list

List stuff.

• struct a4l device * dev

Containing device.

unsigned int idx

Subdevice index.

struct a4l_buffer * buf

Linked buffer.

• unsigned long status

Subdevice's status.

unsigned long flags

Type flags.

struct a4l_channels_desc * chan_desc

Tab of channels descriptors pointers.

struct a4l_rngdesc * rng_desc

Tab of ranges descriptors pointers.

struct a4l_cmd_desc * cmd_mask

Command capabilities mask.

int(* insn_read)(struct a4l_subdevice *, struct a4l_kernel_instruction *)

Callback for the instruction "read".

• int(* insn_write)(struct a4l_subdevice *, struct a4l_kernel_instruction *)

Callback for the instruction "write".

int(* insn_bits)(struct a4l_subdevice *, struct a4l_kernel_instruction *)

Callback for the instruction "bits".

int(* insn_config)(struct a4l_subdevice *, struct a4l_kernel_instruction *)

Callback for the configuration instruction.

int(* do_cmd)(struct a4l_subdevice *, struct a4l_cmd_desc *)

Callback for command handling.

• int(* do_cmdtest)(struct a4l_subdevice *, struct a4l_cmd_desc *)

Callback for command checking.

void(* cancel)(struct a4l_subdevice *)

Callback for asynchronous transfer cancellation.

void(* munge)(struct a4l_subdevice *, void *, unsigned long)

Callback for munge operation.

• int(* trigger)(struct a4l_subdevice *, lsampl_t)

Callback for trigger operation.

• char priv [0]

Private data.

7.9.1 Detailed Description

Structure describing the subdevice.

See also

a4l add subd()

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/analogy/subdevice.h

7.10 atomic_t Struct Reference

Copyright © 2011 Gilles Chanteperdrix gilles.chanteperdrix@xenomai.org.

7.10.1 Detailed Description

Copyright © 2011 Gilles Chanteperdrix gilles.chanteperdrix@xenomai.org.

Copyright © 2013 Philippe Gerum rpm@xenomai.org.

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.


The documentation for this struct was generated from the following file:

• include/boilerplate/atomic.h

7.11 can_bittime Struct Reference

Custom CAN bit-time definition.

Collaboration diagram for can_bittime:



Data Fields

• can_bittime_type_t type

Type of bit-time definition.

• struct can_bittime_std std

Standard bit-time.

struct can_bittime_btr btr

Hardware-spcific BTR bit-time.

7.11.1 Detailed Description

Custom CAN bit-time definition.

Examples:

rtcanconfig.c.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.12 can_bittime_btr Struct Reference

Hardware-specific BTR bit-times.

Data Fields

• uint8_t btr0

Bus timing register 0.

• uint8_t btr1

Bus timing register 1.

7.12.1 Detailed Description

Hardware-specific BTR bit-times.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.13 can bittime std Struct Reference

Standard bit-time parameters according to Bosch.

Data Fields

```
uint32_t brp
```

Baud rate prescaler.

uint8_t prop_seg

from 1 to 8

uint8_t phase_seg1

from 1 to 8

uint8_t phase_seg2

from 1 to 8

• uint8_t sjw:7

from 1 to 4

• uint8_t sam:1

1 - enable triple sampling

7.13.1 Detailed Description

Standard bit-time parameters according to Bosch.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.14 can_filter Struct Reference

Filter for reception of CAN messages.

Data Fields

• uint32_t can_id

CAN ID which must match with incoming IDs after passing the mask.

• uint32 t can mask

Mask which is applied to incoming IDs.

7.14.1 Detailed Description

Filter for reception of CAN messages.

This filter works as follows: A received CAN ID is AND'ed bitwise with can_mask and then compared to can_id. This also includes the CAN_EFF_FLAG and CAN_RTR_FLAG of CAN_xxx_FLAG. If this comparison is true, the message will be received by the socket. The logic can be inverted with the can_id flag CAN_INV_FILTER:

```
if (can_id & CAN_INV_FILTER) {
   if ((received_can_id & can_mask) != (can_id & ~CAN_INV_FILTER))
       accept-message;
} else {
   if ((received_can_id & can_mask) == can_id)
       accept-message;
}
```

Multiple filters can be arranged in a filter list and set with Sockopts. If one of these filters matches a CAN ID upon reception of a CAN frame, this frame is accepted.

Examples:

```
can-rtt.c, and rtcanrecv.c.
```

7.14.2 Field Documentation

```
7.14.2.1 uint32_t can_filter::can_id
```

CAN ID which must match with incoming IDs after passing the mask.

The filter logic can be inverted with the flag CAN_INV_FILTER.

Examples:

rtcanrecv.c.

```
7.14.2.2 uint32_t can_filter::can_mask
```

Mask which is applied to incoming IDs.

See CAN ID masks if exactly one CAN ID should come through.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.15 can_frame Struct Reference

Raw CAN frame.

Public Member Functions

uint8_t data[8] __attribute__ ((aligned(8)))
 Payload data bytes.

• can_id_t can_id

CAN ID of the frame.

• uint8_t can_dlc

Size of the payload in bytes.

7.15.1 Detailed Description

Raw CAN frame.

Central structure for receiving and sending CAN frames.

Examples:

can-rtt.c, rtcanrecv.c, and rtcansend.c.

7.15.2 Field Documentation

7.15.2.1 can_id_t can_frame::can_id

CAN ID of the frame.

See CAN ID flags for special bits.

Examples:

can-rtt.c.


The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.16 can_ifreq Struct Reference

CAN interface request descriptor.

Collaboration diagram for can_ifreq:



7.16.1 Detailed Description

CAN interface request descriptor.

Parameter block for submitting CAN control requests.

Examples:

can-rtt.c, rtcanconfig.c, rtcanrecv.c, and rtcansend.c.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.17 macb_dma_desc Struct Reference

Hardware DMA descriptor.

Data Fields

• u32 addr

DMA address of data buffer.

• u32 ctrl

Control and status bits.

7.17.1 Detailed Description

Hardware DMA descriptor.

The documentation for this struct was generated from the following file:

• kernel/drivers/net/drivers/rt_macb.h

7.18 macb_tx_skb Struct Reference

Data about an skb which is being transmitted.

Data Fields

struct rtskb * skb

skb currently being transmitted

• dma_addr_t mapping

DMA address of the skb's data buffer.

7.18.1 Detailed Description

Data about an skb which is being transmitted.

The documentation for this struct was generated from the following file:

kernel/drivers/net/drivers/rt_macb.h

7.19 RT_ALARM_INFO Struct Reference

Alarm status descriptor.

Data Fields

unsigned long expiries

Number of past expiries.

char name [XNOBJECT_NAME_LEN]

Name of alarm object.

int active

Active flag.

7.19.1 Detailed Description

Alarm status descriptor.

This structure reports various static and runtime information about a real-time alarm, returned by a call to rt_alarm_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/alarm.h

7.20 RT_BUFFER_INFO Struct Reference

Buffer status descriptor.

• int iwaiters

Number of tasks waiting on the read side of the buffer for input data.

int owaiters

Number of tasks waiting on the write side of the buffer for sending out data.

size_t totalmem

Overall size of buffer (in bytes).

size_t availmem

Amount of memory currently available for holding more data.

char name [XNOBJECT_NAME_LEN]

Name of the buffer.

7.20.1 Detailed Description

Buffer status descriptor.

This structure reports various static and runtime information about a real-time buffer, returned by a call to rt_buffer_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/buffer.h

7.21 RT COND INFO Struct Reference

Condition variable status descriptor.

Data Fields

char name [XNOBJECT_NAME_LEN]

Name of condition variable.

7.21.1 Detailed Description

Condition variable status descriptor.

This structure reports various static and runtime information about a condition variable, returned by a call to rt_cond_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/cond.h

7.22 RT_EVENT_INFO Struct Reference

Event status descriptor.

• unsigned int value

Current value of the event flag group.

int nwaiters

Number of tasks currently waiting for events.

• char name [XNOBJECT_NAME_LEN]

Name of event flag group.

7.22.1 Detailed Description

Event status descriptor.

This structure reports various static and runtime information about an event flag group, returned by a call to rt_event_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/event.h

7.23 RT_HEAP_INFO Struct Reference

Heap status descriptor.

Data Fields

• int nwaiters

Number of tasks waiting for available memory in rt_heap_alloc().

• int mode

Creation mode flags as given to rt_heap_create().

size_t heapsize

Size of heap (in bytes) as given to rt_heap_create().

• size_t usablemem

Maximum amount of memory available from the heap.

• size_t usedmem

Amount of heap memory currently consumed.

• char name [XNOBJECT_NAME_LEN]

Name of heap.

7.23.1 Detailed Description

Heap status descriptor.

This structure reports various static and runtime information about a real-time heap, returned by a call to rt_heap_inquire().

7.23.2 Field Documentation

Size of heap (in bytes) as given to rt_heap_create().

The maximum amount of memory available from this heap may be larger, due to internal padding. Referenced by rt_heap_inquire().

Maximum amount of memory available from the heap.

This value accounts for the overhead of internal data structures required to maintain the heap. Referenced by rt_heap_inquire().

Amount of heap memory currently consumed.

info.usablemem - info.usedmem computes the current amount of free memory in the relevant heap. Referenced by rt_heap_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/heap.h

7.24 RT_MUTEX_INFO Struct Reference

Mutex status descriptor.

Data Fields

RT_TASK owner

Current mutex owner, or NO ALCHEMY TASK if unlocked.

char name [XNOBJECT_NAME_LEN]

Name of mutex.

7.24.1 Detailed Description

Mutex status descriptor.

This structure reports various static and runtime information about a mutex, returned by a call to rt_\(\to\) mutex_inquire().

7.24.2 Field Documentation

Current mutex owner, or NO_ALCHEMY_TASK if unlocked.

This information is in essence transient, and may not be valid anymore once used by the caller.

Referenced by rt_mutex_inquire().

The documentation for this struct was generated from the following file:

include/alchemy/mutex.h

7.25 RT_QUEUE_INFO Struct Reference

Queue status descriptor.

Data Fields

int nwaiters

Number of tasks currently waiting on the queue for messages.

int nmessages

Number of messages pending in queue.

• int mode

Queue mode bits, as given to rt_queue_create().

• size t qlimit

Maximum number of messages in queue, zero if unlimited.

size_t poolsize

Size of memory pool for holding message buffers (in bytes).

• size t usedmem

Amount of memory consumed from the buffer pool.

char name [XNOBJECT_NAME_LEN]

Name of message queue.

7.25.1 Detailed Description

Queue status descriptor.

This structure reports various static and runtime information about a real-time queue, returned by a call to rt_queue_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/queue.h

7.26 RT_SEM_INFO Struct Reference

Semaphore status descriptor.

Data Fields

· unsigned long count

Current semaphore value.

• int nwaiters

Number of tasks waiting on the semaphore.

• char name [XNOBJECT_NAME_LEN]

Name of semaphore.

7.26.1 Detailed Description

Semaphore status descriptor.

This structure reports various static and runtime information about a semaphore, returned by a call to rt_sem_inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/sem.h

7.27 RT TASK INFO Struct Reference

Task status descriptor.

Data Fields

• int prio

Task priority.

struct threadobj_stat stat

Task status.

char name [XNOBJECT_NAME_LEN]

Name of task.

• pid_t pid

Host pid.

7.27.1 Detailed Description

Task status descriptor.

This structure reports various static and runtime information about a real-time task, returned by a call to rt task inquire().

The documentation for this struct was generated from the following file:

• include/alchemy/task.h

7.28 rt_timer_info Struct Reference

Timer status descriptor.

Data Fields

RTIME period

Clock resolution in nanoseconds.

• RTIME date

Current monotonic date expressed in clock ticks.

7.28.1 Detailed Description

Timer status descriptor.

This structure reports information about the Alchemy clock, returned by a call to rt_timer_inquire().

7.28.2 Field Documentation

7.28.2.1 RTIME rt timer info::date

Current monotonic date expressed in clock ticks.

The duration of a tick depends on the Alchemy clock resolution for the process (see –alchemy-clock-resolution option, defaults to 1 nanosecond).

Referenced by rt_timer_inquire().


The documentation for this struct was generated from the following file:

• include/alchemy/timer.h

7.29 rtdm dev context Struct Reference

Device context.

Collaboration diagram for rtdm_dev_context:



Data Fields

• struct rtdm_device * device

Set of active device operation handlers.

• char dev_private [0]

Begin of driver defined context data structure.

7.29.1 Detailed Description

Device context.

A device context structure is associated with every open device instance. RTDM takes care of its creation and destruction and passes it to the operation handlers when being invoked.

Drivers can attach arbitrary data immediately after the official structure. The size of this data is provided via rtdm driver.context size during device registration.

7.29.2 Field Documentation

7.29.2.1 struct rtdm device* rtdm dev context::device

Set of active device operation handlers.

Reference to owning device

Referenced by rtdm fd device().


The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/driver.h

7.30 rtdm device Struct Reference

RTDM device.

Collaboration diagram for rtdm_device:



struct rtdm_driver * driver

Device driver.

void * device data

Driver definable device data.

const char * label

Device label template for composing the device name.

int minor

Minor number of the device.

```
struct {
```

Reserved area.

7.30.1 Detailed Description

RTDM device.

This descriptor describes a RTDM device instance. The structure holds runtime data, therefore it must reside in writable memory.

7.30.2 Field Documentation

```
7.30.2.1 struct { ... }
```

Reserved area.

```
7.30.2.2 struct rtdm_driver* rtdm_device::driver
```

Device driver.

Referenced by rtdm_dev_register(), rtdm_dev_unregister(), udd_get_device(), and udd_register_device().

```
7.30.2.3 const char* rtdm_device::label
```

Device label template for composing the device name.

A limited printf-like format string is assumed, with a provision for replacing the first d/i placeholder found in the string by the device minor number. It is up to the driver to actually mention this placeholder or not, depending on the naming convention for its devices. For named devices, the corresponding device node will automatically appear in the /dev/rtdm hierarchy with hotplug-enabled device filesystems (DEVTMP FS).

Referenced by rtdm_dev_register(), and udd_register_device().

```
7.30.2.4 int rtdm device::minor
```

Minor number of the device.

If RTDM_FIXED_MINOR is present in the driver flags, the value stored in this field is used verbatim by rtdm_dev_register(). Otherwise, the RTDM core automatically assigns minor numbers to all devices

managed by the driver referred to by driver, in order of registration, storing the resulting values into this field

Device nodes created for named devices in the Linux /dev hierarchy are assigned this minor number.

The minor number of the current device handling an I/O request can be retreived by a call to rtdm_fd_← minor().

Referenced by rtdm_dev_register(), and rtdm_dev_unregister().

The documentation for this struct was generated from the following file:

include/cobalt/kernel/rtdm/driver.h

7.31 rtdm device info Struct Reference

Device information.

Data Fields

int device_flags

Device flags, see Device Flags for details.

int device_class

Device class ID, see RTDM CLASS xxx.

• int device sub class

Device sub-class, either RTDM_SUBCLASS_GENERIC or a RTDM_SUBCLASS_xxx definition of the related Device Profile.

int profile_version

Supported device profile version.

7.31.1 Detailed Description

Device information.


The documentation for this struct was generated from the following file:

• include/rtdm/uapi/rtdm.h

7.32 rtdm_driver Struct Reference

RTDM driver.

Collaboration diagram for rtdm_driver:



Data Fields

• struct rtdm_profile_info profile_info

Class profile information.

int device_flags

Device flags, see Device Flags for details.

size_t context_size

Size of driver defined appendix to struct rtdm_dev_context.

int protocol_family

Protocol device identification: protocol family (PF_xxx)

int socket_type

Protocol device identification: socket type (SOCK xxx)

struct rtdm_fd_ops ops

I/O operation handlers.

struct rtdm_sm_ops smops

State management handlers.

int device_count

Count of devices this driver manages.

```
struct {};
```

Reserved area.

7.32.1 Detailed Description

RTDM driver.

This descriptor describes a RTDM device driver. The structure holds runtime data, therefore it must reside in writable memory.

7.32.2 Field Documentation

7.32.2.1 int rtdm_driver::device_count

Count of devices this driver manages.

This value is used to allocate a chrdev region for named devices.

Referenced by rtdm dev register(), and udd register device().

7.32.2.2 int rtdm driver::device flags

Device flags, see Device Flags for details.

Referenced by rtdm_dev_register(), rtdm_dev_unregister(), and udd_register_device().

7.32.2.3 struct rtdm profile info rtdm driver::profile info

Class profile information.

The RTDM PROFILE INFO() macro **must** be used for filling up this field.

Referenced by udd_get_device(), and udd_register_device().

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/driver.h

7.33 rtdm_fd_ops Struct Reference

RTDM file operation descriptor.

Data Fields

- int(* open)(struct rtdm_fd *fd, int oflags)
 - See rtdm_open_handler().
- int(* socket)(struct rtdm_fd *fd, int protocol)

See rtdm_socket_handler().

void(* close)(struct rtdm_fd *fd)

See rtdm_close_handler().

- int(* ioctl_rt)(struct rtdm_fd *fd, unsigned int request, void __user *arg)
 See rtdm_ioctl_handler().
- int(* ioctl_nrt)(struct rtdm_fd *fd, unsigned int request, void __user *arg)
 See rtdm_ioctl_handler().
- ssize_t(* read_rt)(struct rtdm_fd *fd, void __user *buf, size_t size)
 See rtdm_read_handler().
- ssize_t(* read_nrt)(struct rtdm_fd *fd, void __user *buf, size_t size)

 See rtdm read handler().
- ssize_t(* write_rt)(struct rtdm_fd *fd, const void __user *buf, size_t size)

 See rtdm_write_handler().
- ssize_t(* write_nrt)(struct rtdm_fd *fd, const void __user *buf, size_t size)

 See rtdm_write_handler().
- ssize_t(* recvmsg_rt)(struct rtdm_fd *fd, struct user_msghdr *msg, int flags)

 See rtdm_recvmsg_handler().
- ssize_t(* recvmsg_nrt)(struct rtdm_fd *fd, struct user_msghdr *msg, int flags)

 See rtdm recvmsg handler().
- ssize_t(* sendmsg_rt)(struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)
 See rtdm_sendmsg_handler().

- ssize_t(* sendmsg_nrt)(struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)
 See rtdm_sendmsg_handler().
- int(* select)(struct rtdm_fd *fd, struct xnselector *selector, unsigned int type, unsigned int index)

 See rtdm select handler().
- int(* mmap)(struct rtdm_fd *fd, struct vm_area_struct *vma)
 See rtdm mmap handler().
- unsigned long(* get_unmapped_area)(struct rtdm_fd *fd, unsigned long len, unsigned long pgoff, unsigned long flags)

See rtdm get unmapped area handler().

7.33.1 Detailed Description

RTDM file operation descriptor.

This structure describes the operations available with a RTDM device, defining handlers for submitting I/O requests. Those handlers are implemented by RTDM device drivers.

7.33.2 Field Documentation

7.33.2.1 void(* rtdm_fd_ops::close) (struct rtdm_fd *fd)

See rtdm_close_handler().

Referenced by rtdm_dev_register().

7.33.2.2 unsigned long(* rtdm_fd_ops::get_unmapped_area) (struct rtdm_fd *fd, unsigned long len, unsigned long pgoff, unsigned long flags)

See rtdm_get_unmapped_area_handler().

7.33.2.3 int(* rtdm_fd_ops::ioctl_nrt) (struct rtdm_fd *fd, unsigned int request, void __user *arg)

See rtdm ioctl handler().

7.33.2.4 int(* rtdm fd ops::ioctl rt) (struct rtdm fd *fd, unsigned int request, void user *arg)

See rtdm_ioctl_handler().

7.33.2.5 int(* rtdm_fd_ops::mmap) (struct rtdm_fd *fd, struct vm_area_struct *vma)

See rtdm_mmap_handler().

7.33.2.6 int(* rtdm fd ops::open) (struct rtdm fd *fd, int oflags)

See rtdm open handler().

Referenced by rtdm_dev_register(), and udd_register_device().

7.33.2.7 ssize_t(* rtdm_fd_ops::read_nrt) (struct rtdm_fd *fd, void __user *buf, size_t size)

See rtdm read handler().

7.33.2.8 ssize_t(* rtdm_fd_ops::read_rt) (struct rtdm_fd *fd, void __user *buf, size_t size)

See rtdm_read_handler().

7.33.2.9 ssize_t(* rtdm_fd_ops::recvmsg_nrt) (struct rtdm_fd *fd, struct user_msghdr *msg, int flags)

See rtdm recvmsg handler().

7.33.2.10 ssize_t(* rtdm_fd_ops::recvmsg_rt) (struct rtdm_fd *fd, struct user_msghdr *msg, int flags)

See rtdm_recvmsg_handler().

7.33.2.11 int(* rtdm_fd_ops::select) (struct rtdm_fd *fd, struct xnselector *selector, unsigned int type, unsigned int index)

See rtdm_select_handler().

7.33.2.12 ssize_t(* rtdm_fd_ops::sendmsg_nrt) (struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)

See rtdm_sendmsg_handler().

7.33.2.13 ssize_t(* rtdm_fd_ops::sendmsg_rt) (struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)

See rtdm_sendmsg_handler().

7.33.2.14 int(* rtdm_fd_ops::socket) (struct rtdm_fd *fd, int protocol)

See rtdm socket handler().

Referenced by rtdm_dev_register().

7.33.2.15 ssize_t(* rtdm_fd_ops::write_nrt) (struct rtdm_fd *fd, const void __user *buf, size_t size)

See rtdm write handler().

7.33.2.16 ssize_t(* rtdm_fd_ops::write_rt) (struct rtdm_fd *fd, const void __user *buf, size_t size)

See rtdm_write_handler().

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/fd.h

7.34 rtdm_sm_ops Struct Reference

RTDM state management handlers.

• int(* start)(struct rtdm_driver *drv)

Handler called upon transition to COBALT_STATE_WARMUP.

• int(* stop)(struct rtdm_driver *drv)

Handler called upon transition to COBALT STATE TEARDOWN.

7.34.1 Detailed Description

RTDM state management handlers.

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/driver.h

7.35 rtipc_port_label Struct Reference

Port label information structure.

Data Fields

char label [XNOBJECT_NAME_LEN]

Port label string, null-terminated.

7.35.1 Detailed Description

Port label information structure.

Examples:

bufp-label.c, iddp-label.c, and xddp-label.c.

7.35.2 Field Documentation

7.35.2.1 char rtipc_port_label::label[XNOBJECT_NAME_LEN]

Port label string, null-terminated.

Referenced by rt_pipe_create().

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/ipc.h

7.36 rtser_config Struct Reference

Serial device configuration.

int config_mask

mask specifying valid fields, see RTSER_SET_xxx

int baud_rate

baud rate, default RTSER_DEF_BAUD

int parity

number of parity bits, see RTSER_xxx_PARITY

• int data bits

number of data bits, see RTSER_xxx_BITS

• int stop_bits

number of stop bits, see RTSER_xxx_STOPB

int handshake

handshake mechanisms, see RTSER_xxx_HAND

• int fifo_depth

reception FIFO interrupt threshold, see RTSER_FIFO_xxx

nanosecs_rel_t rx_timeout

reception timeout, see RTSER_TIMEOUT_xxx for special values

• nanosecs_rel_t tx_timeout

transmission timeout, see RTSER_TIMEOUT_xxx for special values

nanosecs_rel_t event_timeout

event timeout, see RTSER_TIMEOUT_xxx for special values

int timestamp_history

enable timestamp history, see RTSER_xxx_TIMESTAMP_HISTORY

int event_mask

event mask to be used with RTSER_RTIOC_WAIT_EVENT, see RTSER_EVENT_xxx

• int rs485

enable RS485 mode, see RTSER_RS485_xxx

7.36.1 Detailed Description

Serial device configuration.

Examples:

cross-link.c.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/serial.h

7.37 rtser_event Struct Reference

Additional information about serial device events.

• int events

signalled events, see RTSER_EVENT_xxx

int rx_pending

number of pending input characters

• nanosecs_abs_t last_timestamp

last interrupt timestamp

nanosecs_abs_t rxpend_timestamp

reception timestamp of oldest character in input queue

7.37.1 Detailed Description

Additional information about serial device events.

Examples:

cross-link.c.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/serial.h

7.38 rtser_status Struct Reference

Serial device status.

Data Fields

• int line_status

line status register, see RTSER_LSR_xxx

• int modem_status

modem status register, see RTSER_MSR_xxx

7.38.1 Detailed Description

Serial device status.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/serial.h

7.39 sockaddr_can Struct Reference

Socket address structure for the CAN address family.

Data Fields

sa_family_t can_family
 CAN address family, must be AF_CAN.

int can_ifindex

Interface index of CAN controller.

7.39.1 Detailed Description

Socket address structure for the CAN address family.

Examples:

can-rtt.c, rtcanrecv.c, and rtcansend.c.

7.39.2 Field Documentation

7.39.2.1 int sockaddr_can::can_ifindex

Interface index of CAN controller.

See SIOCGIFINDEX.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/can.h

7.40 sockaddr_ipc Struct Reference

Socket address structure for the RTIPC address family.

Data Fields

sa_family_t sipc_family
 RTIPC address family, must be AF_RTIPC.

rtipc_port_t sipc_port

Port number.

7.40.1 Detailed Description

Socket address structure for the RTIPC address family.

Examples:

bufp-label.c, bufp-readwrite.c, iddp-label.c, iddp-sendrecv.c, xddp-echo.c, xddp-label.c, and xddp-stream.c.

7.40.2 Field Documentation

7.40.2.1 rtipc_port_t sockaddr_ipc::sipc_port

Port number.


Referenced by rt_pipe_create().

The documentation for this struct was generated from the following file:

include/rtdm/uapi/ipc.h

7.41 udd_device Struct Reference

Collaboration diagram for udd_device:



Data Structures

struct udd_reserved

Reserved to the UDD core.

Data Fields

• const char * device_name

Name of the device managed by the mini-driver, appears automatically in the /dev/rtdm namespace upon creation.

• int device_flags

Additional device flags (e.g.

• int device_subclass

Subclass code of the device managed by the mini-driver (see RTDM_SUBCLASS_xxx definition in the Device Profiles).

int irq

IRQ number.

struct udd memregion mem regions [UDD NR MAPS]

Array of memory regions defined by the device.

int(* open)(struct rtdm_fd *fd, int oflags)

Ancillary open() handler, optional.

void(* close)(struct rtdm_fd *fd)

Ancillary close() handler, optional.

int(* ioctl)(struct rtdm_fd *fd, unsigned int request, void *arg)

Ancillary ioctl() handler, optional.

int(* mmap)(struct rtdm_fd *fd, struct vm_area_struct *vma)

Ancillary mmap() handler for the mapper device, optional.

int(* interrupt)(struct udd_device *udd)

7.41.1 Detailed Description

UDD device descriptor.

This descriptor defines the characteristics of a UDD-based mini-driver when registering via a call to udd_register_device().

7.41.2 Field Documentation

7.41.2.1 void(* udd device::close) (struct rtdm fd *fd)

Ancillary close() handler, optional.

See rtdm_close_handler().

Note

This handler is called from secondary mode only.

7.41.2.2 int udd_device::device_flags

Additional device flags (e.g.

RTDM EXCLUSIVE) RTDM NAMED DEVICE may be omitted).

Referenced by udd_register_device().

7.41.2.3 int udd_device::device_subclass

Subclass code of the device managed by the mini-driver (see RTDM_SUBCLASS_xxx definition in the Device Profiles).

The main class code is pre-set to RTDM CLASS UDD.

7.41.2.4 int(* udd_device::interrupt) (struct udd_device *udd)

Ancillary handler for receiving interrupts. This handler must be provided if the mini-driver hands over I ← RQ handling to the UDD core, by setting the *irq* field to a valid value, different from UDD_IRQ_CUSTOM and UDD_IRQ_NONE.

The ->interrupt() handler shall return one of the following status codes:

- RTDM_IRQ_HANDLED, if the mini-driver successfully handled the IRQ. This flag can be combined with RTDM_IRQ_DISABLE to prevent the Cobalt kernel from re-enabling the interrupt line upon return, otherwise it is re-enabled automatically.
- RTDM_IRQ_NONE, if the interrupt does not match any IRQ the mini-driver can handle.

Once the ->interrupt() handler has returned, the UDD core notifies user-space Cobalt threads waiting for IRQ events (if any).

Note

This handler is called from primary mode only.

Referenced by udd_register_device().

7.41.2.5 int(* udd device::ioctl) (struct rtdm fd *fd, unsigned int request, void *arg)

Ancillary ioctl() handler, optional.

See rtdm ioctl handler().

If this routine returns -ENOSYS, the default action implemented by the UDD core for the corresponding request will be applied, as if no ioctl handler had been defined.

Note

This handler is called from primary mode only.

7.41.2.6 int udd device::irg

IRQ number.

If valid, the UDD core manages the corresponding interrupt line, installing a base handler. Otherwise, a special value can be passed for declaring unmanaged IRQs.

Referenced by $udd_disable_irq()$, $udd_enable_irq()$, $udd_register_device()$, and $udd_unregister_device()$.

7.41.2.7 struct **udd_memregion** udd_device::mem_regions[UDD_NR_MAPS]

Array of memory regions defined by the device.

The array can be sparse, with some entries bearing the UDD_MEM_NONE type interleaved with valid ones. See the discussion about UDD memory regions.

Referenced by udd register device(), and udd unregister device().

7.41.2.8 int(* udd_device::mmap) (struct rtdm_fd *fd, struct vm_area_struct *vma)

Ancillary mmap() handler for the mapper device, optional.

See rtdm_mmap_handler(). The mapper device operates on a valid region defined in the mem_regions[] array. A pointer to the region can be obtained by a call to udd_get_region().

If this handler is NULL, the UDD core establishes the mapping automatically, depending on the memory type defined for the region.

Note

This handler is called from secondary mode only.

7.41.2.9 int(* udd device::open) (struct rtdm fd *fd, int oflags)

Ancillary open() handler, optional.

See rtdm open handler().

Note

This handler is called from secondary mode only.

The documentation for this struct was generated from the following file:

include/cobalt/kernel/rtdm/udd.h

7.42 udd_memregion Struct Reference

Data Fields

• const char * name

Name of the region (informational but required)

unsigned long addr

Start address of the region.

• size t len

Length (in bytes) of the region.

int type

Type of the region.

7.42.1 Detailed Description

UDD memory region descriptor.

This descriptor defines the characteristics of a memory region declared to the UDD core by the minidriver. All valid regions should be declared in the udd_device.mem_regions[] array, invalid/unassigned ones should bear the UDD_MEM_NONE type.

The UDD core exposes each region via the mmap(2) interface to the application. To this end, a companion mapper device is created automatically when registering the mini-driver.

The mapper device creates special files in the RTDM namespace for reaching the individual regions, which the application can open then map to its address space via the mmap(2) system call.

For instance, declaring a region of physical memory at index #2 of the memory region array could be done as follows:

```
static struct udd_device udd;

static int foocard_pci_probe(struct pci_dev *dev, const struct pci_device_id *id)
{
    udd.device_name = "foocard";
    ...
    udd.mem_regions[2].name = "ADC";
    udd.mem_regions[2].addr = pci_resource_start(dev, 1);
    udd.mem_regions[2].len = pci_resource_len(dev, 1);
    udd.mem_regions[2].type = UDD_MEM_PHYS;
    ...
    return udd_register_device(&udd);
}
```

This will make such region accessible via the mapper device using the following sequence of code, via the default ->mmap() handler from the UDD core:

```
int fd, fdm;
void *p;

fd = open("/dev/foocard", O_RDWR);
fdm = open("/dev/foocard,mapper@2", O_RDWR);
p = mmap(NULL, 4096, PROT_READ|PROT_WRITE, 0, fdm, 0);
```

Note

No mapper device is created unless a valid region has been declared in the udd_device.mem_← regions[] array.

7.42.2 Field Documentation

7.42.2.1 unsigned long udd_memregion::addr

Start address of the region.

This may be a physical or virtual address, depending on the memory type.

```
7.42.2.2 size_t udd_memregion::len
```

Length (in bytes) of the region.

This value must be PAGE_SIZE aligned.

```
7.42.2.3 int udd_memregion::type
```

Type of the region.

See the discussion about UDD memory types for possible values.

Referenced by udd_register_device(), and udd_unregister_device().


The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/udd.h

7.43 udd device::udd reserved Struct Reference

Reserved to the UDD core.

Collaboration diagram for udd_device::udd_reserved:



7.43.1 Detailed Description

Reserved to the UDD core.

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/rtdm/udd.h

7.44 udd_signotify Struct Reference

UDD event notification descriptor.

Data Fields

- pid t pid
 - PID of the Cobalt thread to notify upon interrupt receipt.
- int sig

Signal number to send to PID for notifying, which must be in the range [SIGRTMIN .

7.44.1 Detailed Description

UDD event notification descriptor.

This structure shall be used to pass the information required to enable/disable the notification by signal upon interrupt receipt.

If PID is zero or negative, the notification is disabled. Otherwise, the Cobalt thread whose PID is given will receive the Cobalt signal also mentioned, along with the count of interrupts at the time of the receipt stored in siginfo.si_int. A Cobalt thread must explicitly wait for notifications using the sigwaitinfo() or sigtimedwait() services (no asynchronous mode available).

7.44.2 Field Documentation

7.44.2.1 pid_t udd_signotify::pid

PID of the Cobalt thread to notify upon interrupt receipt.

If pid is zero or negative, the notification is disabled.

7.44.2.2 int udd_signotify::sig

Signal number to send to PID for notifying, which must be in the range [SIGRTMIN .

. SIGRTMAX] inclusive. This value is not considered if *pid* is zero or negative.

The documentation for this struct was generated from the following file:

• include/rtdm/uapi/udd.h

7.45 xnheap::xnbucket Struct Reference

log2 bucket list

7.45.1 Detailed Description

log2 bucket list

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/heap.h

7.46 xnsched Struct Reference

Scheduling information structure.

Data Fields

- unsigned long status
- unsigned long Iflags
- struct xnthread * curr
- int cpu
- cpumask_t resched
- struct xnsched_rt rt
- volatile unsigned inesting
- struct xntimer htimer
- struct xntimer rrbtimer

7.46.1 Detailed Description

Scheduling information structure.

7.46.2 Field Documentation

7.46.2.1 int xnsched::cpu

Mask of CPUs needing rescheduling.

Referenced by xnthread_set_periodic(), xntimer_grab_hardware(), and xntimer_release_hardware().

7.46.2.2 struct xnthread* xnsched::curr

Owner CPU id.

Referenced by xnsched_run(), xnthread_set_slice(), and xnthread_suspend().

7.46.2.3 struct xntimer xnsched::htimer

Round-robin timer.

Referenced by program_htick_shot(), switch_htick_mode(), xnclock_tick(), and xntimer_grab_ ← hardware().

7.46.2.4 volatile unsigned xnsched::inesting

Host timer.

7.46.2.5 unsigned long xnsched::lflags

Current thread.

Referenced by xnclock_tick().

7.46.2.6 cpumask_t xnsched::resched

Context of built-in real-time class.

7.46.2.7 struct xntimer xnsched::rrbtimer

Root thread control block.

Referenced by xnthread_set_slice().

7.46.2.8 struct xnsched_rt xnsched::rt

Interrupt nesting level.

7.46.2.9 unsigned long xnsched::status

< Scheduler specific status bitmask. Scheduler specific local flags bitmask.

Referenced by xnclock_tick().

The documentation for this struct was generated from the following file:

include/cobalt/kernel/sched.h

7.47 xnvfile lock ops Struct Reference

Vfile locking operations.

Data Fields

- int(* get)(struct xnvfile *vfile)
- void(* put)(struct xnvfile *vfile)

7.47.1 Detailed Description

Vfile locking operations.

This structure describes the operations to be provided for implementing locking support on vfiles. They apply to both snapshot-driven and regular vfiles.

7.47.2 Field Documentation

7.47.2.1 int(* xnvfile_lock_ops::get) (struct xnvfile *vfile)

This handler should grab the desired lock.

Parameters

vfile | A pointer to the virtual file which needs locking.

Returns

zero should be returned if the call succeeds. Otherwise, a negative error code can be returned; upon error, the current vfile operation is aborted, and the user-space caller is passed back the error value.

7.47.2.2 void(* xnvfile_lock_ops::put) (struct xnvfile *vfile)

This handler should release the lock previously grabbed by the get() handler.

Parameters

vfile A pointer to the virtual file which currently holds the lock to release.

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/vfile.h

7.48 xnvfile_regular_iterator Struct Reference

Regular vfile iterator.

Data Fields

• loff_t pos

Current record position while iterating.

• struct seq_file * seq

Backlink to the host sequential file supporting the vfile.

struct xnvfile regular * vfile

Backlink to the vfile being read.

• char private [0]

Start of private area.

7.48.1 Detailed Description

Regular vfile iterator.

This structure defines an iterator over a regular vfile.

7.48.2 Field Documentation

7.48.2.1 loff t xnvfile regular iterator::pos

Current record position while iterating.

7.48.2.2 char xnvfile_regular_iterator::private[0]

Start of private area.

Use xnvfile_iterator_priv() to address it.

7.48.2.3 struct seq_file* xnvfile_regular_iterator::seq

Backlink to the host sequential file supporting the vfile.

7.48.2.4 struct xnvfile_regular* xnvfile_regular_iterator::vfile

Backlink to the vfile being read.

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/vfile.h

7.49 xnvfile_regular_ops Struct Reference

Regular vfile operation descriptor.

Data Fields

- int(* rewind)(struct xnvfile_regular_iterator *it)
- void *(* begin)(struct xnvfile_regular_iterator *it)
- void *(* next)(struct xnvfile_regular_iterator *it)
- void(* end)(struct xnvfile_regular_iterator *it)
- int(* show)(struct xnvfile regular iterator *it, void *data)
- ssize_t(* store)(struct xnvfile_input *input)

7.49.1 Detailed Description

Regular vfile operation descriptor.

This structure describes the operations available with a regular vfile. It defines handlers for sending back formatted kernel data upon a user-space read request, and for obtaining user data upon a user-space write request.

7.49.2 Field Documentation

7.49.2.1 void*(* xnvfile regular ops::begin) (struct xnvfile regular iterator *it)

This handler should prepare for iterating over the records upon a read request, starting from the specified position.

Parameters

it	A pointer to the current vfile iterator. On entry, it->pos is set to the (0-based) position
	of the first record to output. This handler may be called multiple times with different
	position requests.

Returns

A pointer to the first record to format and output, to be passed to the show() handler as its data parameter, if the call succeeds. Otherwise:

- NULL in case no record is available, in which case the read operation will terminate immediately with no output.
- VFILE_SEQ_START, a special value indicating that the show() handler should receive a NULL data pointer first, in order to output a header.
- ERR_PTR(errno), where errno is a negative error code; upon error, the current operation will be aborted immediately.

Note

This handler is optional; if none is given in the operation descriptor (i.e. NULL value), the show() handler() will be called only once for a read operation, with a NULL *data* parameter. This particular setting is convenient for simple regular viiles having a single, fixed record to output.

7.49.2.2 void(* xnvfile regular ops::end) (struct xnvfile regular iterator *it)

This handler is called after all records have been output.

Parameters

it	A pointer to the current vfile iterator.

Note

This handler is optional and the pointer may be NULL.

7.49.2.3 void*(* xnvfile regular ops::next) (struct xnvfile regular iterator *it)

This handler should return the address of the next record to format and output by the show()handler".

Parameters

it	A pointer to the current vfile iterator. On entry, it->pos is set to the (0-based) position
	of the next record to output.

Returns

A pointer to the next record to format and output, to be passed to the show() handler as its data parameter, if the call succeeds. Otherwise:

- NULL in case no record is available, in which case the read operation will terminate immediately with no output.
- ERR_PTR(errno), where errno is a negative error code; upon error, the current operation will be aborted immediately.

Note

This handler is optional; if none is given in the operation descriptor (i.e. NULL value), the read operation will stop after the first invocation of the show() handler.

7.49.2.4 int(* xnvfile regular ops::rewind) (struct xnvfile regular iterator *it)

This handler is called only once, when the virtual file is opened, before the begin() handler is invoked.

Parameters

it A pointer to the vfile iterator which will be used to read the file contents.

Returns

Zero should be returned upon success. Otherwise, a negative error code aborts the operation, and is passed back to the reader.

Note

This handler is optional. It should not be used to allocate resources but rather to perform consistency checks, since no closure call is issued in case the open sequence eventually fails.

7.49.2.5 int(* xnvfile regular ops::show) (struct xnvfile regular iterator *it, void *data)

This handler should format and output a record.

xnvfile_printf(), xnvfile_write(), xnvfile_puts() and xnvfile_putc() are available to format and/or emit the output. All routines take the iterator argument *it* as their first parameter.

Parameters

it	A pointer to the current vfile iterator.
data	A pointer to the record to format then output. The first call to the handler may
	receive a NULL data pointer, depending on the presence and/or return of a hander;
	the show handler should test this special value to output any header that fits, prior
	to receiving more calls with actual records.

Returns

zero if the call succeeds, also indicating that the handler should be called for the next record if any. Otherwise:

- A negative error code. This will abort the output phase, and return this status to the reader.
- VFILE_SEQ_SKIP, a special value indicating that the current record should be skipped and will not be output.

7.49.2.6 ssize_t(* xnvfile_regular_ops::store) (struct xnvfile_input *input)

This handler receives data written to the vfile, likely for updating some kernel setting, or triggering any other action which fits. This is the only handler which deals with the write-side of a vfile. It is called when writing to the /proc entry of the vfile from a user-space process.

The input data is described by a descriptor passed to the handler, which may be subsequently passed to parsing helper routines. For instance, xnvfile_get_string() will accept the input descriptor for returning the written data as a null-terminated character string. On the other hand, xnvfile_get_integer() will attempt to return a long integer from the input data.

Parameters

input	A pointer to an input descriptor. It refers to an opaque data from the handler's
	standpoint.

Returns

the number of bytes read from the input descriptor if the call succeeds. Otherwise, a negative error code. Return values from parsing helper routines are commonly passed back to the caller by the store() handler.

Note

This handler is optional, and may be omitted for read-only vfiles.

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/vfile.h

7.50 xnvfile_rev_tag Struct Reference

Snapshot revision tag.

Data Fields

int rev

Current revision number.

7.50.1 Detailed Description

Snapshot revision tag.

This structure defines a revision tag to be used with snapshot-driven vfiles.

7.50.2 Field Documentation

7.50.2.1 int xnvfile_rev_tag::rev

Current revision number.


The documentation for this struct was generated from the following file:

• include/cobalt/kernel/vfile.h

7.51 xnvfile_snapshot Struct Reference

Snapshot vfile descriptor.

Collaboration diagram for xnvfile_snapshot:



7.51.1 Detailed Description

Snapshot vfile descriptor.

This structure describes a snapshot-driven vfile. Reading from such a vfile involves a preliminary data collection phase under lock protection, and a subsequent formatting and output phase of the collected data records. Locking is done in a way that does not increase worst-case latency, regardless of the number of records to be collected for output.


The documentation for this struct was generated from the following file:

include/cobalt/kernel/vfile.h

7.52 xnvfile_snapshot_iterator Struct Reference

Snapshot-driven vfile iterator.

Collaboration diagram for xnvfile_snapshot_iterator:



Data Fields

• int nrdata

Number of collected records.

caddr_t databuf

Address of record buffer.

struct seq_file * seq

Backlink to the host sequential file supporting the vfile.

struct xnvfile_snapshot * vfile

Backlink to the vfile being read.

• void(* endfn)(struct xnvfile_snapshot_iterator *it, void *buf)

Buffer release handler.

• char private [0]

Start of private area.

7.52.1 Detailed Description

Snapshot-driven vfile iterator.

This structure defines an iterator over a snapshot-driven vfile.

7.52.2 Field Documentation

7.52.2.1 caddr_t xnvfile_snapshot_iterator::databuf

Address of record buffer.

7.52.2.2 void(* xnvfile_snapshot_iterator::endfn) (struct xnvfile_snapshot_iterator *it, void *buf)

Buffer release handler.

7.52.2.3 int xnvfile_snapshot_iterator::nrdata

Number of collected records.

7.52.2.4 char xnvfile snapshot iterator::private[0]

Start of private area.

Use xnvfile iterator priv() to address it.

7.52.2.5 struct seq file* xnvfile snapshot iterator::seq

Backlink to the host sequential file supporting the vfile.

7.52.2.6 struct xnvfile snapshot* xnvfile snapshot iterator::vfile

Backlink to the vfile being read.

The documentation for this struct was generated from the following file:

• include/cobalt/kernel/vfile.h

7.53 xnvfile snapshot ops Struct Reference

Snapshot vfile operation descriptor.

Data Fields

- int(* rewind)(struct xnvfile_snapshot_iterator *it)
- void *(* begin)(struct xnvfile snapshot iterator *it)
- void(* end)(struct xnvfile_snapshot_iterator *it, void *buf)
- int(* next)(struct xnvfile_snapshot_iterator *it, void *data)
- int(* show)(struct xnvfile_snapshot_iterator *it, void *data)
- ssize_t(* store)(struct xnvfile_input *input)

7.53.1 Detailed Description

Snapshot vfile operation descriptor.

This structure describes the operations available with a snapshot-driven vfile. It defines handlers for returning a printable snapshot of some Xenomai object contents upon a user-space read request, and for updating this object upon a user-space write request.

7.53.2 Field Documentation

7.53.2.1 void*(* xnvfile snapshot ops::begin) (struct xnvfile snapshot iterator *it)

This handler should allocate the snapshot buffer to hold records during the data collection phase. When specified, all records collected via the next()handler" will be written to a cell from the memory area returned by begin().

Parameters

it	A pointer to the current snapshot iterator.
----	---

Returns

A pointer to the record buffer, if the call succeeds. Otherwise:

- NULL in case of allocation error. This will abort the data collection, and return -ENOMEM to the reader.
- VFILE_SEQ_EMPTY, a special value indicating that no record will be output. In such a case, the
 next() handler will not be called, and the data collection will stop immediately. However, the show()
 handler will still be called once, with a NULL data pointer (i.e. header display request).

Note

This handler is optional; if none is given, an internal allocation depending on the value returned by the rewind() handler can be obtained.

7.53.2.2 void(* xnvfile snapshot ops::end) (struct xnvfile snapshot iterator *it, void *buf)

This handler releases the memory buffer previously obtained from begin(). It is usually called after the snapshot data has been output by show(), but it may also be called before rewinding the vfile after a revision change, to release the dropped buffer.

Parameters

it	A pointer to the current snapshot iterator.
buf	A pointer to the buffer to release.

Note

This routine is optional and the pointer may be NULL. It is not needed upon internal buffer allocation; see the description of the rewind()handler".

7.53.2.3 int(* xnvfile snapshot ops::next) (struct xnvfile snapshot iterator *it, void *data)

This handler fetches the next record, as part of the snapshot data to be sent back to the reader via the show().

Parameters

it	A pointer to the current snapshot iterator.
data	A pointer to the record to fill in.

Returns

a strictly positive value, if the call succeeds and leaves a valid record into *data*, which should be passed to the show() handler() during the formatting and output phase. Otherwise:

- A negative error code. This will abort the data collection, and return this status to the reader.
- VFILE_SEQ_SKIP, a special value indicating that the current record should be skipped. In such a
 case, the data pointer is not advanced to the next position before the next() handler is called anew.

Note

This handler is called with the vfile lock held. Before each invocation of this handler, the vfile core checks whether the revision tag has been touched, in which case the data collection is restarted from scratch. A data collection phase succeeds whenever all records can be fetched via the next() handler, while the revision tag remains unchanged, which indicates that a consistent snapshot of the object state was taken.

7.53.2.4 int(* xnvfile snapshot ops::rewind) (struct xnvfile snapshot iterator *it)

This handler (re-)initializes the data collection, moving the seek pointer at the first record. When the file revision tag is touched while collecting data, the current reading is aborted, all collected data dropped, and the vfile is eventually rewound.

Parameters

- it A pointer to the current snapshot iterator. Two useful information can be retrieved from this iterator in this context:
 - it->vfile is a pointer to the descriptor of the virtual file being rewound.
 - xnvfile_iterator_priv(it) returns a pointer to the private data area, available from the descriptor, which size is vfile->privsz. If the latter size is zero, the returned pointer is meaningless and should not be used.

Returns

A negative error code aborts the data collection, and is passed back to the reader. Otherwise:

- a strictly positive value is interpreted as the total number of records which will be returned by the next() handler during the data collection phase. If no begin() handler is provided in the operation descriptor, this value is used to allocate the snapshot buffer internally. The size of this buffer would then be vfile->datasz * value.
- zero leaves the allocation to the begin() handler if present, or indicates that no record is to be output in case such handler is not given.

Note

This handler is optional; a NULL value indicates that nothing needs to be done for rewinding the vfile. It is called with the vfile lock held.

7.53.2.5 int(* xnvfile_snapshot_ops::show) (struct xnvfile_snapshot_iterator *it, void *data)

This handler should format and output a record from the collected data.

xnvfile_printf(), xnvfile_write(), xnvfile_puts() and xnvfile_putc() are available to format and/or emit the output. All routines take the iterator argument *it* as their first parameter.

Parameters

it A pointer to the current snapshot iterator.

-1-1-	A resistant to the ground to formed these extent. The first cell to the boundless is absented
aata	A pointer to the record to format then output. The first call to the handler is always
	passed a NULL data pointer; the show handler should test this special value to
	output any header that fits, prior to receiving more calls with actual records.

Returns

zero if the call succeeds, also indicating that the handler should be called for the next record if any. Otherwise:

- A negative error code. This will abort the output phase, and return this status to the reader.
- VFILE_SEQ_SKIP, a special value indicating that the current record should be skipped and will not be output.

7.53.2.6 ssize t(* xnvfile snapshot ops::store) (struct xnvfile input *input)

This handler receives data written to the vfile, likely for updating the associated Xenomai object's state, or triggering any other action which fits. This is the only handler which deals with the write-side of a vfile. It is called when writing to the /proc entry of the vfile from a user-space process.

The input data is described by a descriptor passed to the handler, which may be subsequently passed to parsing helper routines. For instance, xnvfile_get_string() will accept the input descriptor for returning the written data as a null-terminated character string. On the other hand, xnvfile_get_integer() will attempt to return a long integer from the input data.

Parameters

input	A pointer to an input descriptor. It refers to an opaque data from the handler's
-	standpoint.

Returns

the number of bytes read from the input descriptor if the call succeeds. Otherwise, a negative error code. Return values from parsing helper routines are commonly passed back to the caller by the store() handler.

Note

This handler is optional, and may be omitted for read-only vfiles.

Referenced by xnvfile init snapshot().

The documentation for this struct was generated from the following file:


• include/cobalt/kernel/vfile.h

Chapter 8


File Documentation

8.1 include/cobalt/kernel/rtdm/analogy/channel_range.h File Reference

Analogy for Linux, channel, range related features. Include dependency graph for channel_range.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct a4l_channel
 - Structure describing some channel's characteristics.
- struct a4l_channels_desc
 - Structure describing a channels set.
- struct a4l_range
 - Structure describing a (unique) range.

Macros

- #define A4L_CHAN_GLOBAL 0x10
 - Internal use flag (must not be used by driver developer)
- #define A4L RNG GLOBAL 0x8
 - Internal use flag (must not be used by driver developer)
- #define RANGE(x, y)

Macro to declare a (unique) range with no unit defined.

#define RANGE_V(x, y)

Macro to declare a (unique) range in Volt.

#define RANGE_mA(x, y)

Macro to declare a (unique) range in milliAmpere.

#define RANGE_ext(x, y)

Macro to declare a (unique) range in some external reference.

#define A4L RNG GLOBAL RNGDESC 0

Constant to define a ranges descriptor as global (inter-channel)

• #define A4L_RNG_PERCHAN_RNGDESC 1

Constant to define a ranges descriptor as specific for a channel.

• #define RNG GLOBAL(x)

Macro to declare a ranges global descriptor in one line.

Channel reference

Flags to define the channel's reference

- #define A4L_CHAN_AREF_GROUND 0x1
 - Ground reference.
- #define A4L CHAN AREF COMMON 0x2

Common reference.

- #define A4L CHAN AREF DIFF 0x4
 - Differential reference.
- #define A4L CHAN AREF OTHER 0x8

Misc reference.

Channels declaration mode

Constant to define whether the channels in a descriptor are identical

- #define A4L CHAN GLOBAL CHANDESC 0
 - Global declaration, the set contains channels with similar characteristics.
- #define A4L CHAN PERCHAN CHANDESC 1

Per channel declaration, the decriptor gathers differents channels.

8.1.1 Detailed Description

Analogy for Linux, channel, range related features.

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.


8.2 include/cobalt/kernel/rtdm/analogy/driver.h File Reference

Analogy for Linux, driver facilities.

Include dependency graph for driver.h:



This graph shows which files directly or indirectly include this file:



Data Structures

• struct a4l_driver

Structure containing driver declaration data.

8.2.1 Detailed Description

Analogy for Linux, driver facilities.

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.


8.3 include/cobalt/kernel/rtdm/driver.h File Reference

Real-Time Driver Model for Xenomai, driver API header.

Include dependency graph for driver.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct rtdm_dev_context
 - Device context.
- struct rtdm_sm_ops

RTDM state management handlers.

- struct rtdm_driver
 - RTDM driver.
- struct rtdm_device

RTDM device.

Macros

• #define RTDM_MAX_MINOR 256

Maximum number of named devices per driver.

#define cobalt_atomic_enter(__context)

Enter atomic section (dual kernel only)

#define cobalt atomic leave(context)

Leave atomic section (dual kernel only)

#define RTDM_EXECUTE_ATOMICALLY(code_block)

Execute code block atomically (DEPRECATED)

• #define RTDM LOCK UNLOCKED(name) IPIPE SPIN LOCK UNLOCKED

Static lock initialisation.

#define rtdm_lock_get_irqsave(__lock, __context) ((__context) = __rtdm_lock_get_irqsave(__ ← lock))

Acquire lock and disable preemption, by stalling the head domain.

#define rtdm lock irgsave(context) splhigh(context)

Disable preemption locally.

#define rtdm_lock_irgrestore(__context) splexit(__context)

Restore preemption state.

#define rtdm_irq_get_arg(irq_handle, type) ((type *)irq_handle->cookie)

Retrieve IRQ handler argument.

Device Flags

Static flags describing a RTDM device

#define RTDM EXCLUSIVE 0x0001

If set, only a single instance of the device can be requested by an application.

#define RTDM FIXED MINOR 0x0002

Use fixed minor provided in the rtdm device description for registering.

#define RTDM_NAMED_DEVICE 0x0010

If set, the device is addressed via a clear-text name.

#define RTDM PROTOCOL DEVICE 0x0020

If set, the device is addressed via a combination of protocol ID and socket type.

#define RTDM_DEVICE_TYPE_MASK 0x00F0

Mask selecting the device type.

#define RTDM SECURE DEVICE 0x80000000

Flag indicating a secure variant of RTDM (not supported here)

RTDM profile information descriptor

RTDM profile information

This descriptor details the profile information associated to a RTDM class of device managed by a driver.

#define RTDM CLASS MAGIC 0x8284636c

Initializer for class profile information.

#define RTDM_PROFILE_INFO(__name, __id, __subid, __version)

Initializer for class profile information.

RTDM_IRQTYPE_xxx

Interrupt registrations flags

#define RTDM IRQTYPE SHARED XN IRQTYPE SHARED

Enable IRQ-sharing with other real-time drivers.

#define RTDM_IRQTYPE_EDGE XN_IRQTYPE_EDGE

Mark IRQ as edge-triggered, relevant for correct handling of shared edge-triggered IRQs.

RTDM IRQ xxx

Return flags of interrupt handlers

- #define RTDM_IRQ_NONE XN_IRQ_NONE Unhandled interrupt.
- #define RTDM_IRQ_HANDLED XN_IRQ_HANDLED

Denote handled interrupt.

#define RTDM IRQ DISABLE XN IRQ DISABLE

Request interrupt disabling on exit.

Task Priority Range

Maximum and minimum task priorities

- #define RTDM_TASK_LOWEST_PRIORITY 0
- #define RTDM TASK HIGHEST PRIORITY 99

Task Priority Modification

Raise or lower task priorities by one level

- #define RTDM TASK RAISE PRIORITY (+1)
- #define RTDM_TASK_LOWER_PRIORITY (-1)

Typedefs

- typedef ipipe_spinlock_t rtdm_lock_t
 - Lock variable.
- typedef unsigned long rtdm_lockctx_t

Variable to save the context while holding a lock.

- typedef int(* rtdm_irq_handler_t) (rtdm_irq_t *irq_handle)
 - Interrupt handler.
- typedef void(* rtdm_nrtsig_handler_t) (rtdm_nrtsig_t *nrt_sig, void *arg)

Non-real-time signal handler.

• typedef void(* rtdm_timer_handler_t) (rtdm_timer_t *timer)

Timer handler.

typedef void(* rtdm_task_proc_t) (void *arg)

Real-time task procedure.

Enumerations

RTDM_SELECTTYPE_xxx

Event types select can bind to

enum rtdm_selecttype { RTDM_SELECTTYPE_READ = XNSELECT_READ, RTDM_SELEC
 TTYPE_WRITE = XNSELECT_WRITE, RTDM_SELECTTYPE_EXCEPT = XNSELECT_EX
 CEPT }

RTDM_TIMERMODE_xxx

Timer operation modes

enum rtdm_timer_mode { RTDM_TIMERMODE_RELATIVE = XN_RELATIVE, RTDM_TIME ← RMODE_ABSOLUTE = XN_ABSOLUTE, RTDM_TIMERMODE_REALTIME = XN_REALTIME }

Functions

static void * rtdm fd to private (struct rtdm fd *fd)

Locate the driver private area associated to a device context structure.

static struct rtdm_fd * rtdm_private_to_fd (void *dev_private)

Locate a device file descriptor structure from its driver private area.

• static bool rtdm_fd_is_user (struct rtdm_fd *fd)

Tell whether the passed file descriptor belongs to an application.

• static struct rtdm device * rtdm fd device (struct rtdm fd *fd)

Locate a device structure from a file descriptor.

• int rtdm dev register (struct rtdm device *device)

Register a RTDM device.

void rtdm_dev_unregister (struct rtdm_device *device)

Unregister a RTDM device.

• void rtdm toseg init (rtdm toseg t *timeout seg, nanosecs rel t timeout)

Initialise a timeout sequence.

static void rtdm_lock_init (rtdm_lock_t *lock)

Dynamic lock initialisation.

static void rtdm lock get (rtdm lock t *lock)

Acquire lock from non-preemptible contexts.

static void rtdm_lock_put (rtdm_lock_t *lock)

Release lock without preemption restoration.

static void rtdm_lock_put_irqrestore (rtdm_lock_t *lock, rtdm_lockctx_t context)

Release lock and restore preemption state.

• int rtdm_irq_request (rtdm_irq_t *irq_handle, unsigned int irq_no, rtdm_irq_handler_t handler, unsigned long flags, const char *device name, void *arg)

Register an interrupt handler.

void rtdm schedule nrt work (struct work struct *lostage work)

Put a work task in Linux non real-time global workqueue from primary mode.

void rtdm_timer_destroy (rtdm_timer_t *timer)

Destroy a timer.

• int rtdm_timer_start (rtdm_timer_t *timer, nanosecs_abs_t expiry, nanosecs_rel_t interval, enum rtdm_timer_mode mode)

Start a timer.

• void rtdm timer stop (rtdm timer t *timer)

Stop a timer.

int rtdm_task_init (rtdm_task_t *task, const char *name, rtdm_task_proc_t task_proc, void *arg, int priority, nanosecs_rel_t period)

Initialise and start a real-time task.

void rtdm_task_busy_sleep (nanosecs_rel_t delay)

Busy-wait a specified amount of time.

void rtdm_event_init (rtdm_event_t *event, unsigned long pending)

Initialise an event.

int rtdm_event_wait (rtdm_event_t *event)

Wait on event occurrence.

int rtdm_event_timedwait (rtdm_event_t *event, nanosecs_rel_t timeout, rtdm_toseq_t *timeout
seq)

Wait on event occurrence with timeout.

void rtdm_event_signal (rtdm_event_t *event)

Signal an event occurrence.

void rtdm_event_clear (rtdm_event_t *event)

Clear event state.

void rtdm event pulse (rtdm event t *event)

Signal an event occurrence to currently listening waiters.

void rtdm_event_destroy (rtdm_event_t *event)

Destroy an event.

void rtdm sem init (rtdm sem t *sem, unsigned long value)

Initialise a semaphore.

• int rtdm_sem_down (rtdm_sem_t *sem)

Decrement a semaphore.

Decrement a semaphore with timeout.

void rtdm_sem_up (rtdm_sem_t *sem)

Increment a semaphore.

• void rtdm sem destroy (rtdm sem t *sem)

Destroy a semaphore.

void rtdm_mutex_init (rtdm_mutex_t *mutex)

Initialise a mutex.

• int rtdm mutex lock (rtdm mutex t *mutex)

Request a mutex.

int rtdm_mutex_timedlock (rtdm_mutex_t *mutex, nanosecs_rel_t timeout, rtdm_toseq_
 t *timeout_seq)

Request a mutex with timeout.

void rtdm mutex unlock (rtdm mutex t *mutex)

Release a mutex.

void rtdm_mutex_destroy (rtdm_mutex_t *mutex)

Destroy a mutex.

• int rtdm_ratelimit (struct rtdm_ratelimit_state *rs, const char *func)

Enforces a rate limit.

8.3.1 Detailed Description

Real-Time Driver Model for Xenomai, driver API header.

Copyright (C) 2005-2007 Jan Kiszka jan.kiszka@web.de Copyright (C) 2005 Joerg Langenberg joerg.langenberg@gmx.net Copyright (C) 2008 Gilles Chanteperdrix gilles.chanteperdrix@xenomai.

org Copyright (C) 2014 Philippe Gerum rpm@xenomai.org

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.3.2 Macro Definition Documentation

8.3.2.1 #define RTDM_CLASS_MAGIC 0x8284636c

Initializer for class profile information.

This macro must be used to fill in the class profile information field from a RTDM driver.

Parameters

name	Class name (unquoted).
id	Class major identification number (profile_version.class_id).
subid	Class minor identification number (profile_version.subclass_id).
version	Profile version number.

Note

See Device Profiles.

```
8.3.2.2 #define RTDM_PROFILE_INFO( __name, __id, __subid, __version )
```

Value:

```
{
    .name = ( # __name ),
    .class_id = (__id),
    .subclass_id = (__subid),
    .version = (__version),
    .magic = ~RTDM_CLASS_MAGIC,
    .owner = THIS_MODULE,
}
```

Initializer for class profile information.

This macro must be used to fill in the class profile information field from a RTDM driver.

Parameters

name	Class name (unquoted).
id	Class major identification number (profile_version.class_id).
subid	Class minor identification number (profile_version.subclass_id).
version	Profile version number.

Note

See Device Profiles.

8.3.3 Function Documentation

8.3.3.1 static struct **rtdm device*** rtdm fd device (struct rtdm fd * fd) [static]

Locate a device structure from a file descriptor.

Parameters

in	fd	File descriptor

Returns

The address of the device structure to which this file descriptor is attached.

References rtdm_dev_context::device.

Referenced by udd_get_device().

8.3.3.2 static bool rtdm_fd_is_user (struct rtdm_fd * fd) [inline], [static]

Tell whether the passed file descriptor belongs to an application.

Parameters

in	fd	File descriptor

Returns

true if passed file descriptor belongs to an application, false otherwise.

8.3.3.3 static void* rtdm_fd_to_private (struct rtdm_fd * fd) [inline], [static]

Locate the driver private area associated to a device context structure.

Parameters

in	fd	File descriptor structure associated with opened device instance

Returns

The address of the private driver area associated to *file* descriptor.

References rtdm_dev_context::dev_private.

8.3.3.4 static struct rtdm_fd* rtdm_private_to_fd (void * dev_private) [static]

Locate a device file descriptor structure from its driver private area.

Parameters

in	dev_private	Address of a private context area


Returns

The address of the file descriptor structure defining dev private.


8.4 include/cobalt/kernel/rtdm/analogy/subdevice.h File Reference

Analogy for Linux, subdevice related features.

Include dependency graph for subdevice.h:



This graph shows which files directly or indirectly include this file:



Data Structures

• struct a4l subdevice

Structure describing the subdevice.

8.4.1 Detailed Description

Analogy for Linux, subdevice related features.

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr


Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.


You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.5 include/rtdm/can.h File Reference

Include dependency graph for can.h:



This graph shows which files directly or indirectly include this file:



8.5.1 Detailed Description

Note

Copyright (C) 2006 Wolfgang Grandegger wg@grandegger.com Copyright (C) 2005, 2006 Sebastian Smolorz Sebastian.Smolorz@stud.uni-hannover.de

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU


General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.6 include/rtdm/uapi/can.h File Reference

Real-Time Driver Model for RT-Socket-CAN, CAN device profile header.

This graph shows which files directly or indirectly include this file:



Data Structures

struct can_bittime_std

Standard bit-time parameters according to Bosch.

struct can_bittime_btr

Hardware-specific BTR bit-times.

• struct can_bittime

Custom CAN bit-time definition.

• struct can_filter

Filter for reception of CAN messages.

• struct sockaddr can

Socket address structure for the CAN address family.

• struct can_frame

Raw CAN frame.

struct can_ifreq

CAN interface request descriptor.

Macros

• #define AF_CAN 29

CAN address family.

• #define PF_CAN AF_CAN

CAN protocol family.

• #define SOL_CAN_RAW 103

CAN socket levels.

CAN ID masks

Bit masks for masking CAN IDs

• #define CAN_EFF_MASK 0x1FFFFFFF

Bit mask for extended CAN IDs.

• #define CAN_SFF_MASK 0x000007FF

Bit mask for standard CAN IDs.

CAN ID flags

Flags within a CAN ID indicating special CAN frame attributes

#define CAN_EFF_FLAG 0x80000000

Extended frame.

#define CAN RTR FLAG 0x40000000

Remote transmission frame.

#define CAN ERR FLAG 0x20000000

Error frame (see Errors), not valid in struct can_filter.

#define CAN INV FILTER CAN ERR FLAG

Invert CAN filter definition, only valid in struct can filter.

Particular CAN protocols

Possible protocols for the PF_CAN protocol family

Currently only the RAW protocol is supported.

• #define CAN RAW 1

Raw protocol of PF_CAN, applicable to socket type SOCK_RAW.

CAN controller modes

Special CAN controllers modes, which can be or'ed together.

Note

These modes are hardware-dependent. Please consult the hardware manual of the CAN controller for more detailed information.

- #define CAN CTRLMODE LISTENONLY 0x1
- #define CAN CTRLMODE LOOPBACK 0x2
- #define CAN_CTRLMODE_3_SAMPLES 0x4

Timestamp switches

Arguments to pass to RTCAN_RTIOC_TAKE_TIMESTAMP

#define RTCAN_TAKE_NO_TIMESTAMPS 0

Switch off taking timestamps.

#define RTCAN_TAKE_TIMESTAMPS 1

Do take timestamps.

RAW socket options

Setting and getting CAN RAW socket options.

• #define CAN RAW FILTER 0x1

CAN filter definition.

• #define CAN_RAW_ERR_FILTER 0x2

CAN error mask.

#define CAN RAW LOOPBACK 0x3

CAN TX loopback.

#define CAN_RAW_RECV_OWN_MSGS 0x4

CAN receive own messages.

IOCTLs

CAN device IOCTLs

Deprecated Passing struct ifreqas a request descriptor for CAN IOCTLs is still accepted for backward compatibility, however it is recommended to switch to struct can_ifreqat the first opportunity.

#define SIOCGIFINDEX defined_by_kernel_header_file
 Get CAN interface index by name.

#define SIOCSCANBAUDRATE _IOW(RTIOC_TYPE_CAN, 0x01, struct can_ifreq)
 Set baud rate.

#define SIOCGCANBAUDRATE _IOWR(RTIOC_TYPE_CAN, 0x02, struct can_ifreq)
 Get baud rate.

• #define SIOCSCANCUSTOMBITTIME _IOW(RTIOC_TYPE_CAN, 0x03, struct can_ifreq) Set custom bit time parameter.

• #define SIOCGCANCUSTOMBITTIME _IOWR(RTIOC_TYPE_CAN, 0x04, struct can_ifreq)

Get custom bit-time parameters.

#define SIOCSCANMODE _IOW(RTIOC_TYPE_CAN, 0x05, struct can_ifreq)
 Set operation mode of CAN controller.

#define SIOCGCANSTATE _IOWR(RTIOC_TYPE_CAN, 0x06, struct can_ifreq)
 Get current state of CAN controller.

#define SIOCSCANCTRLMODE _IOW(RTIOC_TYPE_CAN, 0x07, struct can_ifreq)
 Set special controller modes.

#define SIOCGCANCTRLMODE _IOWR(RTIOC_TYPE_CAN, 0x08, struct can_ifreq)
 Get special controller modes.

#define RTCAN_RTIOC_TAKE_TIMESTAMP_IOW(RTIOC_TYPE_CAN, 0x09, int)
 Enable or disable storing a high precision timestamp upon reception of a CAN frame.

• #define RTCAN_RTIOC_RCV_TIMEOUT_IOW(RTIOC_TYPE_CAN, 0x0A, nanosecs_rel_t) Specify a reception timeout for a socket.

• #define RTCAN_RTIOC_SND_TIMEOUT_IOW(RTIOC_TYPE_CAN, 0x0B, nanosecs_rel_t) Specify a transmission timeout for a socket.

Error mask

Error class (mask) in can_id field of struct can frame to be used with CAN RAW ERR FILTER.

Note: Error reporting is hardware dependent and most CAN controllers report less detailed error conditions than the SJA1000.

Note: In case of a bus-off error condition (CAN_ERR_BUSOFF), the CAN controller is **not** restarted automatically. It is the application's responsibility to react appropriately, e.g. calling CAN_MODE_

START.

Note: Bus error interrupts (CAN_ERR_BUSERROR) are enabled when an application is calling a Recv function on a socket listening on bus errors (using CAN_RAW_ERR_FILTER). After one bus error has occured, the interrupt will be disabled to allow the application time for error processing and to efficiently avoid bus error interrupt flooding.

• #define CAN_ERR_TX_TIMEOUT 0x00000001U

TX timeout (netdevice driver)

• #define CAN ERR LOSTARB 0x00000002U

Lost arbitration (see data[0])

• #define CAN ERR CRTL 0x00000004U

Controller problems (see data[1])

• #define CAN ERR PROT 0x00000008U

Protocol violations (see data[2], data[3])

#define CAN_ERR_TRX 0x00000010U

Transceiver status (see data[4])

#define CAN ERR ACK 0x00000020U

Received no ACK on transmission.

- #define CAN_ERR_BUSOFF 0x00000040U

 Bus off.
- #define CAN_ERR_BUSERROR 0x00000080U
 Bus error (may flood!)
- #define CAN_ERR_RESTARTED 0x00000100U

Controller restarted.

#define CAN_ERR_MASK 0x1FFFFFFFU
 Omit EFF, RTR, ERR flags.

Arbitration lost error

Error in the data[0] field of struct can_frame.

 #define CAN_ERR_LOSTARB_UNSPEC 0x00 unspecified

Controller problems

Error in the data[1] field of struct can frame.

- #define CAN_ERR_CRTL_UNSPEC 0x00 unspecified
- #define CAN_ERR_CRTL_RX_OVERFLOW 0x01 RX buffer overflow.
- #define CAN_ERR_CRTL_TX_OVERFLOW 0x02
 TX buffer overflow.
- #define CAN_ERR_CRTL_RX_WARNING 0x04 reached warning level for RX errors
- #define CAN_ERR_CRTL_TX_WARNING 0x08
 reached warning level for TX errors
- #define CAN_ERR_CRTL_RX_PASSIVE 0x10
 reached passive level for RX errors
- #define CAN_ERR_CRTL_TX_PASSIVE 0x20
 reached passive level for TX errors

Protocol error type

Error in the data[2] field of struct can frame.

- #define CAN_ERR_PROT_UNSPEC 0x00
 unspecified
- #define CAN_ERR_PROT_BIT 0x01 single bit error
- #define CAN_ERR_PROT_FORM 0x02

frame format error

- #define CAN_ERR_PROT_STUFF 0x04 bit stuffing error
- #define CAN ERR PROT BIT0 0x08

unable to send dominant bit

• #define CAN ERR PROT BIT1 0x10

unable to send recessive bit

#define CAN_ERR_PROT_OVERLOAD 0x20

bus overload

• #define CAN ERR PROT ACTIVE 0x40

active error announcement

#define CAN_ERR_PROT_TX 0x80

error occured on transmission

Protocol error location

Error in the data[4] field of struct can frame.

- #define CAN_ERR_PROT_LOC_UNSPEC 0x00
 unspecified
- #define CAN_ERR_PROT_LOC_SOF 0x03 start of frame
- #define CAN_ERR_PROT_LOC_ID28_21 0x02
 ID bits 28 21 (SFF: 10 3)
- #define CAN_ERR_PROT_LOC_ID20_18 0x06
 ID bits 20 18 (SFF: 2 0)
- #define CAN_ERR_PROT_LOC_SRTR 0x04 substitute RTR (SFF: RTR)
- #define CAN_ERR_PROT_LOC_IDE 0x05

identifier extension

- #define CAN_ERR_PROT_LOC_ID17_13 0x07
 ID bits 17-13.
- #define CAN_ERR_PROT_LOC_ID12_05 0x0F
 ID bits 12-5.
- #define CAN_ERR_PROT_LOC_ID04_00 0x0E
 ID bits 4-0.
- #define CAN_ERR_PROT_LOC_RTR 0x0C RTR.
- #define CAN_ERR_PROT_LOC_RES1 0x0D
 reserved bit 1
- #define CAN_ERR_PROT_LOC_RES0 0x09
 reserved bit 0
- #define CAN_ERR_PROT_LOC_DLC 0x0B data length code
- #define CAN_ERR_PROT_LOC_DATA 0x0A data section
- #define CAN_ERR_PROT_LOC_CRC_SEQ 0x08 CRC sequence.
- #define CAN_ERR_PROT_LOC_CRC_DEL 0x18

 CRC delimiter.
- #define CAN_ERR_PROT_LOC_ACK 0x19
- #define CAN_ERR_PROT_LOC_ACK_DEL 0x1B ACK delimiter.
- #define CAN_ERR_PROT_LOC_EOF 0x1A
 end of frame
- #define CAN_ERR_PROT_LOC_INTERM 0x12 intermission
- #define CAN_ERR_TRX_UNSPEC 0x00 0000 0000
- #define CAN_ERR_TRX_CANH_NO_WIRE 0x04 0000 0100
- #define CAN_ERR_TRX_CANH_SHORT_TO_BAT 0x05 0000 0101

```
    #define CAN_ERR_TRX_CANH_SHORT_TO_VCC 0x06
0000 0110
```

- #define CAN_ERR_TRX_CANH_SHORT_TO_GND 0x07 0000 0111
- #define CAN_ERR_TRX_CANL_NO_WIRE 0x40 0100 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_BAT 0x50 0101 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_VCC 0x60 0110 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_GND 0x70 0111 0000
- #define CAN_ERR_TRX_CANL_SHORT_TO_CANH 0x80 1000 0000

Typedefs

typedef uint32_t can_id_t

Type of CAN id (see CAN_xxx_MASK and CAN_xxx_FLAG)

typedef can_id_t can_err_mask_t

Type of CAN error mask.

typedef uint32_t can_baudrate_t

Baudrate definition in bits per second.

typedef enum CAN_BITTIME_TYPE can_bittime_type_t

See CAN BITTIME TYPE.

typedef enum CAN_MODE can_mode_t

See CAN MODE.

typedef int can_ctrlmode_t

See CAN_CTRLMODE.

typedef enum CAN_STATE can_state_t

See CAN STATE.

typedef struct can_filter can_filter_t

Filter for reception of CAN messages.

typedef struct can_frame can_frame_t

Raw CAN frame.

Enumerations

• enum CAN_BITTIME_TYPE { CAN_BITTIME_STD, CAN_BITTIME_BTR } Supported CAN bit-time types.

CAN operation modes

Modes into which CAN controllers can be set

enum CAN_MODE { CAN_MODE_STOP = 0, CAN_MODE_START, CAN_MODE_SLEEP }

CAN controller states

States a CAN controller can be in.

enum CAN_STATE {
 CAN_STATE_ERROR_ACTIVE = 0, CAN_STATE_ACTIVE = 0, CAN_STATE_ERROR_WA
 RNING = 1, CAN_STATE_BUS_WARNING = 1,
 CAN_STATE_ERROR_PASSIVE = 2, CAN_STATE_BUS_PASSIVE = 2, CAN_STATE_BU
 S_OFF, CAN_STATE_SCANNING_BAUDRATE,
 CAN_STATE_STOPPED, CAN_STATE_SLEEPING }

8.6.1 Detailed Description

Real-Time Driver Model for RT-Socket-CAN, CAN device profile header.

Note

Copyright (C) 2006 Wolfgang Grandegger wg@grandegger.com

Copyright (C) 2005, 2006 Sebastian Smolorz Sebastian. Smolorz@stud.uni-hannover.de

This RTDM CAN device profile header is based on:

include/linux/can.h, include/linux/socket.h, net/can/pf_can.h in linux-can.patch, a CAN socket framework for Linux

Copyright (C) 2004, 2005, Robert Schwebel, Benedikt Spranger, Marc Kleine-Budde, Pengutronix

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU

General Public License for more details.


You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.7 include/cobalt/kernel/rtdm/fd.h File Reference

Include dependency graph for fd.h:



This graph shows which files directly or indirectly include this file:



Data Structures

struct rtdm_fd_ops

RTDM file operation descriptor.

Functions

• int rtdm_open_handler (struct rtdm_fd *fd, int oflags)

Open handler for named devices.

• int rtdm socket handler (struct rtdm fd *fd, int protocol)

Socket creation handler for protocol devices.

void rtdm_close_handler (struct rtdm_fd *fd)

Close handler.

• int rtdm_ioctl_handler (struct rtdm_fd *fd, unsigned int request, void __user *arg)

IOCTL handler.

• ssize_t rtdm_read_handler (struct rtdm_fd *fd, void __user *buf, size_t size)

Read handler.

• ssize_t rtdm_write_handler (struct rtdm_fd *fd, const void __user *buf, size_t size)

Write handler.

ssize t rtdm recvmsg handler (struct rtdm fd *fd, struct user msghdr *msg, int flags)

Receive message handler.

• ssize_t rtdm_sendmsg_handler (struct rtdm_fd *fd, const struct user_msghdr *msg, int flags)

**Transmit message handler.*

• int rtdm_select_handler (struct rtdm_fd *fd, struct xnselector *selector, unsigned int type, unsigned int index)

Select handler.

• int rtdm_mmap_handler (struct rtdm_fd *fd, struct vm_area_struct *vma)

Memory mapping handler.

• unsigned long rtdm_get_unmapped_area_handler (struct rtdm_fd *fd, unsigned long len, unsigned long pgoff, unsigned long flags)

Allocate mapping region in address space.

• struct rtdm_fd * rtdm_fd_get (int ufd, unsigned int magic)

Retrieve and lock a RTDM file descriptor.

int rtdm_fd_lock (struct rtdm_fd *fd)

Hold a reference on a RTDM file descriptor.

void rtdm_fd_put (struct rtdm_fd *fd)

Release a RTDM file descriptor obtained via rtdm_fd_get()

void rtdm_fd_unlock (struct rtdm_fd *fd)

Drop a reference on a RTDM file descriptor.

• int rtdm fd select (int ufd, struct xnselector *selector, unsigned int type)

Bind a selector to specified event types of a given file descriptor.

8.7.1 Detailed Description

operation handlers

8.7.2 Function Documentation

8.7.2.1 struct rtdm fd* rtdm fd get (int ufd, unsigned int magic)

Retrieve and lock a RTDM file descriptor.

Parameters

in	ufd	User-side file descriptor
in	magic	Magic word for lookup validation

Returns

Pointer to the RTDM file descriptor matching ufd, or ERR PTR(-EBADF).

Note

The file descriptor returned must be later released by a call to rtdm fd put().

Tags

unrestricted

Referenced by rtdm_fd_select().

8.7.2.2 int rtdm_fd_lock (struct rtdm_fd * fd)

Hold a reference on a RTDM file descriptor.

Parameters

in	fd	Target file descriptor
----	----	------------------------

Note

rtdm_fd_lock() increments the reference counter of fd. You only need to call this function in special scenarios, e.g. when keeping additional references to the file descriptor that have different lifetimes. Only use rtdm_fd_lock() on descriptors that are currently locked via an earlier rtdm_fd← __get()/rtdm_fd_lock() or while running a device operation handler.

Tags

unrestricted

8.7.2.3 void rtdm fd put (struct rtdm fd * fd)

Release a RTDM file descriptor obtained via rtdm_fd_get()

Parameters

in	fd	RTDM file descriptor to release
----	----	---------------------------------

Note

Every call to rtdm_fd_get() must be matched by a call to rtdm_fd_put().

Tags

unrestricted

Referenced by rtdm_fd_select().

8.7.2.4 int rtdm_fd_select (int ufd, struct xnselector * selector, unsigned int type)

Bind a selector to specified event types of a given file descriptor.

This function is invoked by higher RTOS layers implementing select-like services. It shall not be called directly by RTDM drivers.

Parameters

in	ufd	User-side file descriptor to bind to
in,out	selector	Selector object that shall be bound to the given event
in	type	Event type the caller is interested in

Returns

0 on success, otherwise:

- -EBADF is returned if the file descriptor ufd cannot be resolved.
- -EINVAL is returned if type is invalid.

Tags

task-unrestricted

References rtdm_fd_get(), rtdm_fd_put(), splnone, and spltest.

8.7.2.5 void rtdm_fd_unlock (struct rtdm_fd * fd)

Drop a reference on a RTDM file descriptor.

Parameters

in	fd	Target file descriptor

Note

Every call to rtdm_fd_lock() must be matched by a call to rtdm_fd_unlock().


Tags

unrestricted


8.8 include/rtdm/uapi/ipc.h File Reference

This file is part of the Xenomai project.

Include dependency graph for ipc.h:



This graph shows which files directly or indirectly include this file:



Data Structures

struct rtipc_port_label

Port label information structure.

struct sockaddr_ipc

Socket address structure for the RTIPC address family.

Macros

XDDP socket options

Setting and getting XDDP socket options.

- #define XDDP_LABEL 1
 - XDDP label assignment.
- #define XDDP_POOLSZ 2

XDDP local pool size configuration.

- #define XDDP_BUFSZ 3
 - XDDP streaming buffer size configuration.
- #define XDDP_MONITOR 4

XDDP monitoring callback.

XDDP events

Specific events occurring on XDDP channels, which can be monitored via the XDDP_MONITOR socket option.

- #define XDDP EVTIN 1
 - Monitor writes to the non real-time endpoint.
- #define XDDP_EVTOUT 2
 - Monitor reads from the non real-time endpoint.
- #define XDDP EVTDOWN 3
 - Monitor close from the non real-time endpoint.
- #define XDDP_EVTNOBUF 4

Monitor memory shortage for non real-time datagrams.

IDDP socket options

Setting and getting IDDP socket options.

```
    #define IDDP_LABEL 1
    IDDP label assignment.
```

#define IDDP_POOLSZ 2

IDDP local pool size configuration.

BUFP socket options

Setting and getting BUFP socket options.

#define BUFP_LABEL 1
 BUFP label assignment.

#define BUFP_BUFSZ 2

BUFP buffer size configuration.

Socket level options

Setting and getting supported standard socket level options.

- #define SO_SNDTIMEO defined_by_kernel_header_file
 IPCPROTO_IDDP and IPCPROTO_BUFP protocols support the standard SO_SNDTIMEO socket option, from the SOL_SOCKET level.
- #define SO_RCVTIMEO defined_by_kernel_header_file

 All RTIPC protocols support the standard SO_RCVTIMEO socket option, from the SOL_SOCKET level.

Typedefs

typedef int16_t rtipc_port_t
 Port number type for the RTIPC address family.

Enumerations

RTIPC protocol list

protocols for the PF_RTIPC protocol family

enum { IPCPROTO_IPC = 0, IPCPROTO_XDDP = 1, IPCPROTO_IDDP = 2, IPCPROTO_B
 UFP = 3 }

Functions

Supported operations

Standard socket operations supported by the RTIPC protocols.

- int socket__AF_RTIPC (int domain=AF_RTIPC, int type=SOCK_DGRAM, int protocol)

 Create an endpoint for communication in the AF_RTIPC domain.
- int close__AF_RTIPC (int sockfd)
 - Close a RTIPC socket descriptor.
- int bind__AF_RTIPC (int sockfd, const struct sockaddr_ipc *addr, socklen_t addrlen)

 Bind a RTIPC socket to a port.
- int connect__AF_RTIPC (int sockfd, const struct sockaddr_ipc *addr, socklen_t addrlen)

 Initiate a connection on a RTIPC socket.
- int setsockopt__AF_RTIPC (int sockfd, int level, int optname, const void *optval, socklen_

 t optlen)

Set options on RTIPC sockets.

- int getsockopt__AF_RTIPC (int sockfd, int level, int optname, void *optval, socklen_t *optlen)

 Get options on RTIPC sockets.
- ssize_t sendmsg__AF_RTIPC (int sockfd, const struct msghdr *msg, int flags)
 Send a message on a RTIPC socket.
- ssize_t recvmsg__AF_RTIPC (int sockfd, struct msghdr *msg, int flags)
 Receive a message from a RTIPC socket.
- int getsockname__AF_RTIPC (int sockfd, struct sockaddr_ipc *addr, socklen_t *addrlen)

 Get socket name.
- int getpeername__AF_RTIPC (int sockfd, struct sockaddr_ipc *addr, socklen_t *addrlen)

 Get socket peer.

8.8.1 Detailed Description

This file is part of the Xenomai project.

Note

Copyright (C) 2009 Philippe Gerum rpm@xenomai.org


This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.


You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.9 include/rtdm/rtdm.h File Reference

Include dependency graph for rtdm.h:



This graph shows which files directly or indirectly include this file:



8.9.1 Detailed Description

Note

Copyright (C) 2005, 2006 Jan Kiszka jan.kiszka@web.de
Copyright (C) 2005 Joerg Langenberg joerg.langenberg@gmx.net

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.10 include/rtdm/uapi/rtdm.h File Reference

Real-Time Driver Model for Xenomai, user API header.

This graph shows which files directly or indirectly include this file:



Data Structures

struct rtdm_device_info
 Device information.

Macros

API Versioning

• #define RTDM_API_VER 9

Common user and driver API version.

#define RTDM_API_MIN_COMPAT_VER 9

Minimum API revision compatible with the current release.

RTDM_TIMEOUT_xxx

Special timeout values

• #define RTDM_TIMEOUT_INFINITE 0

Block forever.

#define RTDM_TIMEOUT_NONE (-1)

Any negative timeout means non-blocking.

RTDM CLASS xxx

Device classes

- #define RTDM CLASS PARPORT 1
- #define RTDM CLASS SERIAL 2
- #define RTDM_CLASS_CAN 3
- #define RTDM_CLASS_NETWORK 4
- #define RTDM_CLASS_RTMAC 5
- #define RTDM CLASS TESTING 6
- #define RTDM CLASS RTIPC 7
- #define RTDM CLASS COBALT 8
- #define RTDM_CLASS UDD 9
- #define RTDM CLASS MEMORY 10
- #define RTDM_CLASS_MISC 223
- #define RTDM_CLASS_EXPERIMENTAL 224
- #define RTDM_CLASS_MAX 255

Device Naming

Maximum length of device names (excluding the final null character)

• #define RTDM MAX DEVNAME LEN 31

RTDM_PURGE_xxx_BUFFER

Flags selecting buffers to be purged

- #define RTDM_PURGE_RX_BUFFER 0x0001
- #define RTDM_PURGE_TX_BUFFER 0x0002

Common IOCTLs

The following IOCTLs are common to all device rtdm profiles.

#define RTIOC_DEVICE_INFO _IOR(RTIOC_TYPE_COMMON, 0x00, struct rtdm_device_
 info)

Retrieve information about a device or socket.

• #define RTIOC PURGE IOW(RTIOC TYPE COMMON, 0x10, int)

Purge internal device or socket buffers.

Typedefs

• typedef uint64_t nanosecs_abs_t

RTDM type for representing absolute dates.

typedef int64_t nanosecs_rel_t

RTDM type for representing relative intervals.

typedef struct rtdm_device_info rtdm_device_info_t

Device information.

8.10.1 Detailed Description

Real-Time Driver Model for Xenomai, user API header.

Note

Copyright (C) 2005, 2006 Jan Kiszka jan.kiszka@web.de
Copyright (C) 2005 Joerg Langenberg joerg.langenberg@gmx.net

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.


8.11 include/rtdm/serial.h File Reference

Real-Time Driver Model for Xenomai, serial device profile header.

Include dependency graph for serial.h:



This graph shows which files directly or indirectly include this file:



8.11.1 Detailed Description

Real-Time Driver Model for Xenomai, serial device profile header.

Note

Copyright (C) 2005-2007 Jan Kiszka jan.kiszka@web.de

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.12 include/rtdm/uapi/serial.h File Reference

Real-Time Driver Model for Xenomai, serial device profile header.

This graph shows which files directly or indirectly include this file:



Data Structures

- struct rtser config
 - Serial device configuration.
- struct rtser_status
 - Serial device status.
- struct rtser event

Additional information about serial device events.

Macros

• #define RTSER_RTIOC_BREAK_CTL_IOR(RTIOC_TYPE_SERIAL, 0x06, int)

Set or clear break on UART output line.

RTSER_DEF_BAUD

Default baud rate

#define RTSER DEF BAUD 9600

RTSER XXX PARITY

Number of parity bits

- #define RTSER_NO_PARITY 0x00
- #define RTSER_ODD_PARITY 0x01
- #define RTSER_EVEN_PARITY 0x03
- #define RTSER_DEF_PARITY RTSER_NO_PARITY

RTSER XXX BITS

Number of data bits

- #define RTSER_5_BITS 0x00
- #define RTSER 6 BITS 0x01
- #define RTSER 7 BITS 0x02
- #define RTSER 8 BITS 0x03
- #define RTSER DEF BITS RTSER 8 BITS

RTSER xxx STOPB

Number of stop bits

• #define RTSER 1 STOPB 0x00

valid only in combination with 5 data bits

#define RTSER_1_5_STOPB 0x01

valid only in combination with 5 data bits

#define RTSER_2_STOPB 0x01

valid only in combination with 5 data bits

#define RTSER_DEF_STOPB RTSER_1_STOPB

valid only in combination with 5 data bits

RTSER xxx HAND

Handshake mechanisms

- #define RTSER NO HAND 0x00
- #define RTSER RTSCTS HAND 0x01
- #define RTSER DEF HAND RTSER NO HAND

RTSER_RS485_xxx

RS485 mode with automatic RTS handling

- #define RTSER_RS485_DISABLE 0x00
- #define RTSER_RS485_ENABLE 0x01
- #define RTSER_DEF_RS485 RTSER_RS485_DISABLE

RTSER_FIFO_xxx

Reception FIFO interrupt threshold

- #define RTSER_FIFO_DEPTH_1 0x00
- #define RTSER FIFO DEPTH 4 0x40
- #define RTSER_FIFO_DEPTH_8 0x80
- #define RTSER FIFO DEPTH 14 0xC0
- #define RTSER_DEF_FIFO_DEPTH RTSER_FIFO_DEPTH_1

RTSER_TIMEOUT_xxx

Special timeout values, see also RTDM_TIMEOUT_xxx

- #define RTSER_TIMEOUT_INFINITE RTDM_TIMEOUT_INFINITE
- #define RTSER_TIMEOUT_NONE RTDM_TIMEOUT_NONE
- #define RTSER_DEF_TIMEOUT RTDM_TIMEOUT_INFINITE

RTSER XXX TIMESTAMP HISTORY

Timestamp history control

- #define RTSER RX TIMESTAMP HISTORY 0x01
- #define RTSER_DEF_TIMESTAMP_HISTORY 0x00

RTSER EVENT xxx

Events bits

- #define RTSER EVENT RXPEND 0x01
- #define RTSER EVENT ERRPEND 0x02
- #define RTSER EVENT MODEMHI 0x04
- #define RTSER EVENT MODEMLO 0x08
- #define RTSER_EVENT_TXEMPTY 0x10
- #define RTSER DEF EVENT MASK 0x00

RTSER_SET_xxx

Configuration mask bits

- #define RTSER SET BAUD 0x0001
- #define RTSER SET PARITY 0x0002
- #define RTSER SET DATA BITS 0x0004
- #define RTSER SET STOP BITS 0x0008
- #define RTSER_SET_HANDSHAKE 0x0010
- #define RTSER_SET_FIFO_DEPTH 0x0020 #define RTSER_SET_TIMEOUT_RX 0x0100
- #define RTSER_SET_TIMEOUT_TX 0x0200
- #define RTSER_SET_TIMEOUT_EVENT 0x0400
 #define RTSER_SET_TIMESTAMP_HISTORY 0x0800
 #define RTSER_SET_EVENT_MASK 0x1000
 #define RTSER_SET_RS485 0x2000

RTSER LSR xxx

Line status bits

- #define RTSER_LSR_DATA 0x01
- #define RTSER_LSR_OVERRUN_ERR 0x02
- #define RTSER_LSR_PARITY_ERR 0x04
- #define RTSER_LSR_FRAMING_ERR 0x08
- #define RTSER LSR BREAK IND 0x10
- #define RTSER_LSR_THR_EMTPY 0x20
- #define RTSER LSR TRANSM EMPTY 0x40
- #define RTSER LSR FIFO ERR 0x80
- #define RTSER_SOFT_OVERRUN_ERR 0x0100

RTSER MSR xxx

Modem status bits

- #define RTSER MSR DCTS 0x01
- #define RTSER_MSR_DDSR 0x02
- #define RTSER MSR TERI 0x04
- #define RTSER_MSR_DDCD 0x08
- #define RTSER MSR CTS 0x10

- #define RTSER MSR DSR 0x20
- #define RTSER MSR RI 0x40
- #define RTSER_MSR_DCD 0x80

RTSER MCR xxx

Modem control bits

- #define RTSER_MCR_DTR 0x01
- #define RTSER MCR RTS 0x02
- #define RTSER_MCR_OUT1 0x04
- #define RTSER_MCR_OUT2 0x08
- #define RTSER_MCR_LOOP 0x10

Sub-Classes of RTDM CLASS SERIAL

#define RTDM_SUBCLASS_16550A 0

IOCTLs

Serial device IOCTLs

#define RTSER_RTIOC_GET_CONFIG _IOR(RTIOC_TYPE_SERIAL, 0x00, struct rtser_
 config)

Get serial device configuration.

#define RTSER_RTIOC_SET_CONFIG _IOW(RTIOC_TYPE_SERIAL, 0x01, struct rtser_
 config)

Set serial device configuration.

#define RTSER_RTIOC_GET_STATUS _IOR(RTIOC_TYPE_SERIAL, 0x02, struct rtser_
 status)

Get serial device status.

#define RTSER_RTIOC_GET_CONTROL_IOR(RTIOC_TYPE_SERIAL, 0x03, int)

Get serial device's modem contol register.

- #define RTSER_RTIOC_SET_CONTROL_IOW(RTIOC_TYPE_SERIAL, 0x04, int)
 Set serial device's modem contol register.
- #define RTSER_RTIOC_WAIT_EVENT _IOR(RTIOC_TYPE_SERIAL, 0x05, struct rtser_
 event)

Wait on serial device events according to previously set mask.

RTSER BREAK xxx

Break control

#define RTSER_BREAK_CLR 0x00

Serial device configuration.

#define RTSER_BREAK_SET 0x01

Serial device configuration.

#define RTIOC TYPE SERIAL RTDM CLASS SERIAL

Serial device configuration.

typedef struct rtser_config rtser_config_t

Serial device configuration.

typedef struct rtser_status rtser_status_t

Serial device status.

typedef struct rtser_event rtser_event_t

Additional information about serial device events.

8.12.1 Detailed Description

Real-Time Driver Model for Xenomai, serial device profile header.

Note

Copyright (C) 2005-2007 Jan Kiszka jan.kiszka@web.de

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.12.2 Macro Definition Documentation

8.12.2.1 #define RTSER_RTIOC_BREAK_CTL_IOR(RTIOC_TYPE_SERIAL, 0x06, int)

Set or clear break on UART output line.

Parameters

in	arg	RTSER_BREAK_SET or RTSER_BREAK_CLR (int)
----	-----	--

Returns

0 on success, otherwise negative error code

Tags

task-unrestricted

Note

A set break condition may also be cleared on UART line reconfiguration.

8.12.2.2 #define RTSER_RTIOC_GET_CONFIG _IOR(RTIOC_TYPE_SERIAL, 0x00, struct rtser_config)

Get serial device configuration.

Parameters

out	arg	Pointer to configuration buffer (struct rtser_config)
-----	-----	---

Returns

0 on success, otherwise negative error code

Tags

task-unrestricted

 $8.12.2.3 \quad \text{\#define RTSER_RTIOC_GET_CONTROL_IOR} \\ (\textbf{RTIOC_TYPE_SERIAL}, \, 0x03, \, int) \\$

Get serial device's modem contol register.

Parameters

out	arg	Pointer to variable receiving the content (int, see RTSER_MCR_xxx)
-----	-----	--

Returns

0 on success, otherwise negative error code

Tags

task-unrestricted

8.12.2.4 #define RTSER_RTIOC_GET_STATUS _IOR(RTIOC_TYPE_SERIAL, 0x02, struct rtser_status)

Get serial device status.

Parameters

out	arg	Pointer to status buffer (struct rtser_status)

Returns

0 on success, otherwise negative error code

Tags

task-unrestricted

Note

The error states RTSER_LSR_OVERRUN_ERR, RTSER_LSR_PARITY_ERR, RTSER_LSR_FRAMING_ERR, and RTSER_SOFT_OVERRUN_ERR that may have occured during previous read accesses to the device will be saved for being reported via this IOCTL. Upon return from RTSER_RTIOC_GET_STATUS, the saved state will be cleared.

8.12.2.5 #define RTSER_RTIOC_SET_CONFIG _IOW(RTIOC_TYPE_SERIAL, 0x01, struct rtser_config)

Set serial device configuration.

Parameters

in	arg	Pointer to configuration buffer (struct rtser_config)
----	-----	---

Returns

0 on success, otherwise:

- -EPERM is returned if the caller's context is invalid, see note below.
- -ENOMEM is returned if a new history buffer for timestamps cannot be allocated.

Tags

task-unrestricted

Note

If rtser_config contains a valid timestamp_history and the addressed device has been opened in non-real-time context, this IOCTL must be issued in non-real-time context as well. Otherwise, this command will fail.

Examples:

cross-link.c.

8.12.2.6 #define RTSER_RTIOC_SET_CONTROL_IOW(RTIOC_TYPE_SERIAL, 0x04, int)

Set serial device's modem contol register.

Parameters

in	arg	New control register content (int, see RTSER_MCR_xxx)

Returns

0 on success, otherwise negative error code

Tags

task-unrestricted

8.12.2.7 #define RTSER_RTIOC_WAIT_EVENT_IOR(RTIOC_TYPE_SERIAL, 0x05, struct rtser event)

Wait on serial device events according to previously set mask.

Parameters

out	arg	Pointer to event information buffer (struct rtser_event)
-----	-----	--

Returns

0 on success, otherwise:

- -EBUSY is returned if another task is already waiting on events of this device.
- -EBADF is returned if the file descriptor is invalid or the device has just been closed.

Tags

mode-unrestricted


Examples:

cross-link.c.


8.13 include/rtdm/testing.h File Reference

Real-Time Driver Model for Xenomai, testing device profile header.

Include dependency graph for testing.h:



This graph shows which files directly or indirectly include this file:



8.13.1 Detailed Description

Real-Time Driver Model for Xenomai, testing device profile header.

Note

Copyright (C) 2005 Jan Kiszka jan.kiszka@web.de

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


Xenomai is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with Xenomai; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.


8.14 include/rtdm/uapi/testing.h File Reference

Real-Time Driver Model for Xenomai, testing device profile header.

Include dependency graph for testing.h:



This graph shows which files directly or indirectly include this file:



Macros

Sub-Classes of RTDM_CLASS_TESTING

• #define RTDM_SUBCLASS_TIMERBENCH 0

subclass name: "timerbench"

• #define RTDM_SUBCLASS_IRQBENCH 1

subclass name: "irqbench"

#define RTDM SUBCLASS SWITCHTEST 2

subclass name: "switchtest"

• #define RTDM_SUBCLASS_RTDMTEST 3

subclase name: "rtdm"

IOCTLs

Testing device IOCTLs

- #define RTTST_RTIOC_INTERM_BENCH_RES _IOWR(RTIOC_TYPE_TESTING, 0x00, struct rttst_interm_bench_res)
- #define RTTST_RTIOC_TMBENCH_START _IOW(RTIOC_TYPE_TESTING, 0x10, struct rttst_tmbench_config)
- #define RTTST_RTIOC_TMBENCH_STOP _IOWR(RTIOC_TYPE_TESTING, 0x11, struct rttst_overall_bench_res)
- #define RTTST_RTIOC_SWTEST_SET_TASKS_COUNT _IOW(RTIOC_TYPE_TESTING, 0x30, u32)
- #define RTTST RTIOC SWTEST_SET_CPU _IOW(RTIOC_TYPE_TESTING, 0x31, __u32)
- #define RTTST_RTIOC_SWTEST_REGISTER_UTASK _IOW(RTIOC_TYPE_TESTING, 0x32, struct rttst_swtest_task)
- #define RTTST_RTIOC_SWTEST_CREATE_KTASK_IOWR(RTIOC_TYPE_TESTING, 0x33, struct rttst_swtest_task)
- #define RTTST_RTIOC_SWTEST_SWITCH_TO _IOR(RTIOC_TYPE_TESTING, 0x35, struct rttst swtest dir)
- #define RTTST_RTIOC_SWTEST_GET_SWITCHES_COUNT _IOR(RTIOC_TYPE_TESTIN ← G, 0x36, u32)
- #define RTTST_RTIOC_SWTEST_GET_LAST_ERROR _IOR(RTIOC_TYPE_TESTING, 0x37, struct rttst_swtest_error)
- #define RTTST_RTIOC_SWTEST_SET_PAUSE _IOW(RTIOC_TYPE_TESTING, 0x38, __
 u32)
- #define RTTST_RTIOC_RTDM_DEFER_CLOSE _IOW(RTIOC_TYPE_TESTING, 0x40, __
 u32)

8.14.1 Detailed Description

Real-Time Driver Model for Xenomai, testing device profile header.

Note

Copyright (C) 2005 Jan Kiszka jan.kiszka@web.de

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.15 include/cobalt/kernel/rtdm/udd.h File Reference

Copyright (C) 2014 Philippe Gerum rpm@xenomai.org

Include dependency graph for udd.h:



Data Structures

- struct udd_memregion
- struct udd_device
- struct udd device::udd reserved

Reserved to the UDD core.

Macros

• #define UDD IRQ NONE 0

No IRQ managed.

#define UDD_IRQ_CUSTOM (-1)

IRQ directly managed from the mini-driver on top of the UDD core.

Memory types for mapping

Types of memory for mapping

The UDD core implements a default -> mmap() handler which first attempts to hand over the request to the corresponding handler defined by the mini-driver. If not present, the UDD core establishes the mapping automatically, depending on the memory type defined for the region.

• #define UDD MEM NONE 0

No memory region.

#define UDD MEM PHYS 1

Physical I/O memory region.

#define UDD_MEM_LOGICAL 2

Kernel logical memory region (e.g.

#define UDD_MEM_VIRTUAL 3

Virtual memory region with no direct physical mapping (e.g.

Functions

int udd_register_device (struct udd_device *udd)

Register a UDD device.

int udd unregister device (struct udd device *udd)

Unregister a UDD device.

• struct udd device * udd get device (struct rtdm fd *fd)

RTDM file descriptor to target UDD device.

void udd notify event (struct udd device *udd)

Notify an IRQ event for an unmanaged interrupt.

void udd_enable_irq (struct udd_device *udd, rtdm_event_t *done)

Enable the device IRQ line.

• void udd_disable_irq (struct udd_device *udd, rtdm_event_t *done)

Disable the device IRQ line.

8.15.1 Detailed Description

Copyright (C) 2014 Philippe Gerum rpm@xenomai.org

Xenomai is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

8.16 include/rtdm/uapi/udd.h File Reference

This file is part of the Xenomai project.

This graph shows which files directly or indirectly include this file:



Data Structures

struct udd_signotify
 UDD event notification descriptor.

Macros

UDD IOCTL

IOCTL requests

- #define UDD_RTIOC_IRQEN_IO(RTDM_CLASS_UDD, 0) Enable the interrupt line.
- #define UDD_RTIOC_IRQDIS_IO(RTDM_CLASS_UDD, 1)
 Disable the interrupt line.

• #define UDD_RTIOC_IRQSIG_IOW(RTDM_CLASS_UDD, 2, struct udd_signotify)

Enable/Disable signal notification upon interrupt event.

8.16.1 Detailed Description

This file is part of the Xenomai project.

Author

Copyright (C) 2014 Philippe Gerum rpm@xenomai.org

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.


8.17 include/rtdm/analogy.h File Reference

Analogy for Linux, library facilities.

Include dependency graph for analogy.h:



This graph shows which files directly or indirectly include this file:



Data Structures

struct a4l_descriptor

Structure containing device-information useful to users.

Macros

ANALOGY XXX DESC

Constants used as argument so as to define the description depth to recover

- #define A4L_BSC_DESC 0x0
 BSC stands for basic descriptor (device data)
- #define A4L CPLX DESC 0x1

CPLX stands for complex descriptor (subdevice + channel + range data)

8.17.1 Detailed Description

Analogy for Linux, library facilities.

Note

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.18 include/rtdm/uapi/analogy.h File Reference

Analogy for Linux, UAPI bits.

This graph shows which files directly or indirectly include this file:



Data Structures

struct a4l cmd desc

Structure describing the asynchronous instruction.

struct a4l instruction

Structure describing the synchronous instruction.

struct a4l_instruction_list

Structure describing the list of synchronous instructions.

Macros

#define A4L_RNG_FACTOR 1000000

Constant for internal use only (must not be used by driver developer).

• #define A4L RNG VOLT UNIT 0x0

Volt unit range flag.

#define A4L RNG MAMP UNIT 0x1

MilliAmpere unit range flag.

• #define A4L RNG NO UNIT 0x2

No unit range flag.

• #define A4L_RNG_EXT_UNIT 0x4

External unit range flag.

• #define A4L RNG UNIT(x)

Macro to retrieve the range unit from the range flags.

#define A4L_INSN_WAIT_MAX 100000

Maximal wait duration.

ANALOGY_CMD_xxx

Common command flags definitions

#define A4L_CMD_SIMUL 0x1

Do not execute the command, just check it.

• #define A4L_CMD_BULK 0x2

Perform data recovery / transmission in bulk mode.

• #define A4L_CMD_WRITE 0x4

Perform a command which will write data to the device.

TRIG_xxx

Command triggers flags definitions

#define TRIG_NONE 0x00000001

Never trigger.

#define TRIG_NOW 0x00000002

Trigger now + N ns.

• #define TRIG FOLLOW 0x00000004

Trigger on next lower level trig.

• #define TRIG_TIME 0x00000008

Trigger at time N ns.

#define TRIG_TIMER 0x00000010

Trigger at rate N ns.

• #define TRIG COUNT 0x00000020

Trigger when count reaches N.

#define TRIG EXT 0x00000040

Trigger on external signal N.

• #define TRIG INT 0x00000080

Trigger on analogy-internal signal N.

#define TRIG_OTHER 0x00000100

Driver defined trigger.

#define TRIG_WAKE_EOS 0x0020

Wake up on end-of-scan.

#define TRIG ROUND MASK 0x00030000

Trigger not implemented yet.

#define TRIG_ROUND_NEAREST 0x00000000

Trigger not implemented yet.

#define TRIG ROUND DOWN 0x00010000

Trigger not implemented yet.

#define TRIG ROUND UP 0x00020000

Trigger not implemented yet.

#define TRIG_ROUND_UP_NEXT 0x00030000

Trigger not implemented yet.

Channel macros

Specific precompilation macros and constants useful for the channels descriptors tab located in the command structure

#define CHAN(a) ((a) & 0xffff)

Channel indication macro.

#define RNG(a) (((a) & 0xff) << 16)

Range definition macro.

#define AREF(a) (((a) & 0x03) << 24)

Reference definition macro.

#define FLAGS(a) ((a) & CR_FLAGS_MASK)

Flags definition macro.

• #define PACK(a, b, c) (a | RNG(b) | AREF(c))

Channel + range + reference definition macro.

#define PACK_FLAGS(a, b, c, d) (PACK(a, b, c) | FLAGS(d))

Channel + range + reference + flags definition macro.

#define AREF GROUND 0x00

Analog reference is analog ground.

#define AREF COMMON 0x01

Analog reference is analog common.

#define AREF_DIFF 0x02

Analog reference is differential.

#define AREF_OTHER 0x03

Analog reference is undefined.

Subdevices types

Flags to define the subdevice type

#define A4L_SUBD_UNUSED (A4L_SUBD_MASK_SPECIAL|0x1)

Unused subdevice.

#define A4L_SUBD_AI (A4L_SUBD_MASK_READ|0x2)

Analog input subdevice.

#define A4L_SUBD_AO (A4L_SUBD_MASK_WRITE|0x4)

Analog output subdevice.

• #define A4L SUBD DI (A4L SUBD MASK READI0x8)

Digital input subdevice.

#define A4L_SUBD_DO (A4L_SUBD_MASK_WRITE|0x10)

Digital output subdevice.

#define A4L_SUBD_DIO (A4L_SUBD_MASK_SPECIAL|0x20)

Digital input/output subdevice.

#define A4L_SUBD_COUNTER (A4L_SUBD_MASK_SPECIAL|0x40)

Counter subdevice.

• #define A4L_SUBD_TIMER (A4L_SUBD_MASK_SPECIAL|0x80)

Timer subdevice.

#define A4L_SUBD_MEMORY (A4L_SUBD_MASK_SPECIAL|0x100)

Memory, EEPROM, DPRAM.

#define A4L_SUBD_CALIB (A4L_SUBD_MASK_SPECIAL|0x200)

Calibration subdevice DACs.

• #define A4L SUBD PROC (A4L SUBD MASK SPECIAL|0x400)

Processor, DSP.

#define A4L_SUBD_SERIAL (A4L_SUBD_MASK_SPECIAL|0x800)

Serial IO subdevice.

#define A4L_SUBD_TYPES

Mask which gathers all the types.

Subdevice features

Flags to define the subdevice's capabilities

#define A4L SUBD CMD 0x1000

The subdevice can handle command (i.e it can perform asynchronous acquisition)

#define A4L SUBD MMAP 0x8000

The subdevice support mmap operations (technically, any driver can do it; however, the developer might want that his driver must be accessed through read / write.

Subdevice status

Flags to define the subdevice's status

• #define A4L SUBD BUSY NR 0

The subdevice is busy, a synchronous or an asynchronous acquisition is occuring.

#define A4L_SUBD_BUSY (1 << A4L_SUBD_BUSY_NR)

The subdevice is busy, a synchronous or an asynchronous acquisition is occuring.

#define A4L_SUBD_CLEAN_NR 1

The subdevice is about to be cleaned in the middle of the detach procedure.

#define A4L_SUBD_CLEAN (1 << A4L_SUBD_CLEAN_NR)

The subdevice is busy, a synchronous or an asynchronous acquisition is occuring.

Instruction type

Flags to define the type of instruction

#define A4L_INSN_READ (0 | A4L_INSN_MASK_READ)

Read instruction.

#define A4L_INSN_WRITE (1 | A4L_INSN_MASK_WRITE)

Write instruction.

#define A4L INSN BITS

"Bits" instruction

#define A4L INSN CONFIG

Configuration instruction.

#define A4L INSN GTOD

Get time instruction.

• #define A4L INSN WAIT

Wait instruction.

• #define A4L INSN INTTRIG

Trigger instruction (to start asynchronous acquisition)

Configuration instruction type

Values to define the type of configuration instruction

- #define A4L INSN CONFIG DIO INPUT 0
- #define A4L INSN CONFIG DIO OUTPUT 1
- #define A4L INSN CONFIG DIO OPENDRAIN 2
- #define A4L INSN CONFIG ANALOG TRIG 16
- #define A4L INSN CONFIG ALT SOURCE 20
- #define A4L INSN CONFIG DIGITAL TRIG 21
- #define A4L INSN CONFIG BLOCK SIZE 22
- #define A4L INSN CONFIG TIMER 1 23
- #define A4L_INSN_CONFIG_FILTER 24
- #define A4L_INSN_CONFIG_CHANGE_NOTIFY 25
- #define A4L_INSN_CONFIG_SERIAL_CLOCK 26
- #define A4L_INSN_CONFIG_BIDIRECTIONAL_DATA 27
- #define A4L_INSN_CONFIG_DIO_QUERY 28
- #define A4L_INSN_CONFIG_PWM_OUTPUT 29
- #define A4L INSN CONFIG GET PWM OUTPUT 30
- #define A4L INSN CONFIG ARM 31
- #define A4L INSN CONFIG DISARM 32
- #define A4L INSN_CONFIG_GET_COUNTER_STATUS 33
- #define A4L INSN CONFIG RESET 34
- #define A4L_INSN_CONFIG_GPCT_SINGLE_PULSE_GENERATOR 1001 /* Use CTR as single pulsegenerator */
- #define A4L INSN CONFIG GPCT PULSE TRAIN GENERATOR 1002 /* Use CTR as pulsetraingenerator */
- #define A4L INSN CONFIG GPCT QUADRATURE ENCODER 1003 /* Use the counter as encoder */

- #define A4L_INSN_CONFIG_SET_GATE_SRC 2001 /* Set gate source */
 #define A4L_INSN_CONFIG_GET_GATE_SRC 2002 /* Get gate source */
 #define A4L_INSN_CONFIG_SET_CLOCK_SRC 2003 /* Set master clock source */
 #define A4L_INSN_CONFIG_GET_CLOCK_SRC 2004 /* Get master clock source */
 #define A4L_INSN_CONFIG_SET_OTHER_SRC 2005 /* Set other source */
 #define A4L_INSN_CONFIG_SET_COUNTER_MODE 4097

- #define A4L INSN CONFIG SET ROUTING 4099
- #define A4L_INSN_CONFIG_GET_ROUTING 4109

Counter status bits

Status bits for INSN_CONFIG_GET_COUNTER_STATUS

- #define A4L COUNTER ARMED 0x1
- #define A4L COUNTER COUNTING 0x2
- #define A4L COUNTER TERMINAL COUNT 0x4

IO direction

Values to define the IO polarity

- #define A4L INPUT 0
- #define A4L_OUTPUT 1
- #define A4L OPENDRAIN 2

Events types

Values to define the Analogy events. They might used to send some specific events through the instruction interface.

- #define A4L EV START 0x00040000
- #define A4L EV SCAN BEGIN 0x00080000
- #define **A4L_EV_CONVERT** 0x00100000
- #define **A4L_EV_SCAN_END** 0x00200000
- #define A4L EV STOP 0x00400000

8.18.1 Detailed Description

Analogy for Linux, UAPI bits.

Note

```
Copyright (C) 1997-2000 David A. Schleef ds@schleef.org
Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr
```

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.18.2 Macro Definition Documentation

8.18.2.1 #define A4L_RNG_FACTOR 1000000


Constant for internal use only (must not be used by driver developer).

Referenced by a4l_dtoraw(), a4l_find_range(), a4l_ftoraw(), a4l_rawtod(), and a4l_rawtof().

8.19 lib/analogy/calibration.h File Reference

Analogy for Linux, internal calibration declarations.

This graph shows which files directly or indirectly include this file:



8.19.1 Detailed Description

Analogy for Linux, internal calibration declarations.

Note

Copyright (C) 2014 Jorge A Ramirez-Ortiz jro@xenomai.org

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.20 lib/analogy/internal.h File Reference

Analogy for Linux, internal declarations.

Include dependency graph for internal.h:



This graph shows which files directly or indirectly include this file:



8.20.1 Detailed Description

Analogy for Linux, internal declarations.

Note

Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.21 lib/analogy/async.c File Reference

Analogy for Linux, command, transfer, etc.

Include dependency graph for async.c:



Functions

- int a4l_snd_command (a4l_desc_t *dsc, a4l_cmd_t *cmd)
 - Send a command to an Analoy device.
- int a4l_snd_cancel (a4l_desc_t *dsc, unsigned int idx_subd)
 - Cancel an asynchronous acquisition.
- int a4l_set_bufsize (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long size)
 - Change the size of the asynchronous buffer.
- int a4l_get_bufsize (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long *size)
 - Get the size of the asynchronous buffer.
- int a4l_mark_bufrw (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long cur, unsigned long *new)
 - Update the asynchronous buffer state.
- int a4l_poll (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long ms_timeout)

 Get the available data count.
- int a4l_mmap (a4l_desc_t *dsc, unsigned int idx_subd, unsigned long size, void **ptr)

 Map the asynchronous ring-buffer into a user-space.
- int a4l_async_read (a4l_desc_t *dsc, void *buf, size_t nbyte, unsigned long ms_timeout)

 Perform asynchronous read operation on the analog input subdevice.
- int a4l_async_write (a4l_desc_t *dsc, void *buf, size_t nbyte, unsigned long ms_timeout)

 Perform asynchronous write operation on the analog input subdevice.

8.21.1 Detailed Description

Analogy for Linux, command, transfer, etc. related features

Note

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.22 lib/analogy/calibration.c File Reference

Analogy for Linux, device, subdevice, etc.

Include dependency graph for calibration.c:



Functions

- int a4l_read_calibration_file (char *name, struct a4l_calibration_data *data)
 - Read the analogy generated calibration file.
- int a4l_get_softcal_converter (struct a4l_polynomial *converter, int subd, int chan, int range, struct a4l_calibration_data *data)

Get the polynomial that will be use for the software calibration.

• int a4l_rawtodcal (a4l_chinfo_t *chan, double *dst, void *src, int cnt, struct a4l_polynomial *converter)

Convert raw data (from the driver) to calibrated double units.

• int a4l_dcaltoraw (a4l_chinfo_t *chan, void *dst, double *src, int cnt, struct a4l_polynomial *converter)

Convert double values to raw calibrated data using polynomials.

8.22.1 Detailed Description

Analogy for Linux, device, subdevice, etc.

related features

578 File Documentation

Note

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2014 Jorge A. Ramirez-Ortiz jro@xenomai.org

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.23 lib/analogy/descriptor.c File Reference

Analogy for Linux, descriptor related features.

Include dependency graph for descriptor.c:



Functions

- int a4l sys desc (int fd, a4l desc t *dsc, int pass)
 - Get a descriptor on an attached device.
- int a4l_open (a4l_desc_t *dsc, const char *fname)

Open an Analogy device and basically fill the descriptor.

• int a4l close (a4l desc t *dsc)

Close the Analogy device related with the descriptor.

• int a4l fill desc (a4l desc t *dsc)

Fill the descriptor with subdevices, channels and ranges data.

- int a4l get subdinfo (a4l desc t *dsc, unsigned int subd, a4l sbinfo t **info)
 - Get an information structure on a specified subdevice.
- int a4l_get_chinfo (a4l_desc_t *dsc, unsigned int subd, unsigned int chan, a4l_chinfo_t **info)

 Get an information structure on a specified channel.
- int a4l_get_rnginfo (a4l_desc_t *dsc, unsigned int subd, unsigned int chan, unsigned int rng, a4l
 _rnginfo_t **info)

Get an information structure on a specified range.

8.23.1 Detailed Description

Analogy for Linux, descriptor related features.

Note

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.24 lib/analogy/range.c File Reference

Analogy for Linux, range related features.

Include dependency graph for range.c:



Functions

- int a4l_sizeof_chan (a4l_chinfo_t *chan)
 - Get the size in memory of an acquired element.
- int a4l sizeof subd (a4l sbinfo t *subd)
 - Get the size in memory of a digital acquired element.
- int a4l_find_range (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int idx_chan, unsigned long unit, double min, double max, a4l_rnginfo_t **rng)
 - Find the must suitable range.
- int a4l_rawtoul (a4l_chinfo_t *chan, unsigned long *dst, void *src, int cnt)
 - Unpack raw data (from the driver) into unsigned long values.
- int a4l rawtof (a4l chinfo t *chan, a4l rnginfo t *rng, float *dst, void *src, int cnt)
 - Convert raw data (from the driver) to float-typed samples.
- int a4l rawtod (a4l chinfo t *chan, a4l rnginfo t *rng, double *dst, void *src, int cnt)
 - Convert raw data (from the driver) to double-typed samples.
- int a4l_ultoraw (a4l_chinfo_t *chan, void *dst, unsigned long *src, int cnt)
 - Pack unsigned long values into raw data (for the driver)
- int a4l_ftoraw (a4l_chinfo_t *chan, a4l_rnginfo_t *rng, void *dst, float *src, int cnt)
 - Convert float-typed samples to raw data (for the driver)
- int a4l_dtoraw (a4l_chinfo_t *chan, a4l_rnginfo_t *rng, void *dst, double *src, int cnt)
 - Convert double-typed samples to raw data (for the driver)

580 File Documentation

8.24.1 Detailed Description

Analogy for Linux, range related features.

Note

```
Copyright (C) 1997-2000 David A. Schleef ds@schleef.org
Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr
```

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.25 lib/analogy/root leaf.h File Reference

Analogy for Linux, root / leaf system.

This graph shows which files directly or indirectly include this file:



8.25.1 Detailed Description

Analogy for Linux, root / leaf system.

Note

```
Copyright (C) 1997-2000 David A. Schleef ds@schleef.org
Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr
```

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.


This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

8.26 lib/analogy/sync.c File Reference

Analogy for Linux, instruction related features.

Include dependency graph for sync.c:



Functions

- int a4l_snd_insnlist (a4l_desc_t *dsc, a4l_insnlst_t *arg)
 - Perform a list of synchronous acquisition misc operations.
- int a4l_snd_insn (a4l_desc_t *dsc, a4l_insn_t *arg)
 - Perform a synchronous acquisition misc operation.
- int a4l_sync_write (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns_delay, void *buf, size_t nbyte)
 - Perform a synchronous acquisition write operation.
- int a4l_sync_read (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int chan_desc, unsigned int ns delay, void *buf, size t nbyte)
 - Perform a synchronous acquisition read operation.
- int a4l sync dio (a4l desc t *dsc, unsigned int idx subd, void *mask, void *buf)
 - Perform a synchronous acquisition digital acquisition.
- int a4l_config_subd (a4l_desc_t *dsc, unsigned int idx_subd, unsigned int type,...)

 Configure a subdevice.

8.26.1 Detailed Description

Analogy for Linux, instruction related features.

Note

Copyright (C) 1997-2000 David A. Schleef ds@schleef.org Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.


You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

582 File Documentation

8.27 lib/analogy/sys.c File Reference

Analogy for Linux, descriptor related features.

Include dependency graph for sys.c:



Functions

• int a4l_sys_open (const char *fname)

Open an Analogy device.

• int a4l sys close (int fd)

Close an Analogy device.

• int a4l sys read (int fd, void *buf, size t nbyte)

Read from an Analogy device.

int a4l_sys_write (int fd, void *buf, size_t nbyte)

Write to an Analogy device.

• int a4l_sys_attach (int fd, a4l_lnkdesc_t *arg)

Attach an Analogy device to a driver.

• int a4l_sys_detach (int fd)

Detach an Analogy device from a driver.

• int a4l_sys_bufcfg (int fd, unsigned int idx_subd, unsigned long size)

Configure the buffer size.

8.27.1 Detailed Description

Analogy for Linux, descriptor related features.

Note

```
Copyright (C) 1997-2000 David A. Schleef ds@schleef.org
Copyright (C) 2008 Alexis Berlemont alexis.berlemont@free.fr
```

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

Chapter 9

Example Documentation

9.1 bufp-label.c

```
/*
 * Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.
 * This library is free software; you can redistribute it and/or
 * modify it under the terms of the GNU Lesser General Public
* License as published by the Free Software Foundation; either
   version 2 of the License, or (at your option) any later version.
 * This library is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
* MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
 \ensuremath{^{*}} Lesser General Public License for more details.
 * You should have received a copy of the GNU Lesser General Public
 * License along with this library; if not, write to the Free Software
 * Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.
 * BUFP-based client/server demo, using the read(2)/write(2)
 * system calls to exchange data over a socket.
 * In this example, two sockets are created. A server thread (reader)
 \mbox{\ensuremath{^{*}}} is bound to a real-time port and receives a stream of bytes sent to
 * this port from a client thread (writer).
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <signal.h>
#include <string.h>
#include <pthread.h>
#include <errno.h>
#include <rtdm/ipc.h>
pthread_t svtid, cltid;
#define BUFP_PORT_LABEL "bufp-demo"
static const char *msg[] = {
         "Surfing With The Alien",
         "Lords of Karma",
         "Banana Mango",
         "Psycho Monkey"
         "Luminous Flesh Giants",
          "Moroccan Sunset",
         "Satch Boogie"
         "Flying In A Blue Dream",
         "Ride",
         "Summer Song"
         "Speed Of Light",
         "Crystal Planet"
         "Raspberry Jam Delta-V",
         "Champagne?",
         "Clouds Race Across The Sky",
         "Engines Of Creation"
};
static void fail(const char *reason)
```

```
perror(reason);
         exit(EXIT_FAILURE);
}
static void *server(void *arg)
        struct rtipc_port_label plabel;
        struct sockaddr_ipc saddr;
        char buf[128]:
        size_t bufsz;
        int ret. s:
        s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_BUFP);
         if (s < 0)
                fail("socket");
        /*
 * Set a 16k buffer for the server endpoint. This
 * configuration must be done prior to binding the socket to a
        bufsz = 16384; /* bytes */
ret = setsockopt(s, SOL_BUFP, BUFP_BUFSZ,
                          &bufsz, sizeof(bufsz));
        if (ret)
                 fail("setsockopt");
        /*
    * Set a port label. This name will be registered when
    * binding, in addition to the port number (if given).
        strcpy(plabel.label, BUFP_PORT_LABEL);
        ret = setsockopt(s, SOL_BUFP, BUFP_LABEL,
                          &plabel, sizeof(plabel));
        if (ret)
                 fail("setsockopt");
        /*

* Bind the socket to the port. Assign that port a label, so

** descriptive information to locate
         * that peers may use a descriptive information to locate
         * it. Labeled ports will appear in the
         * /proc/xenomai/registry/rtipc/bufp directory once the socket
         * is bound.
         ^{*} saddr.sipc_port specifies the port number to use. If -1 is
         * passed, the BUFP driver will auto-select an idle port.
        saddr.sipc_family = AF_RTIPC;
saddr.sipc_port = -1;
        ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
        if (ret)
                 fail("bind");
         for (;;) {
                 ret = read(s, buf, sizeof(buf));
if (ret < 0) {</pre>
                         close(s);
                          fail("read");
                 printf("%s: received %d bytes, \"%.*s\"\n",
                         __FUNCTION__, ret, ret, buf);
        }
        return NULL;
}
static void *client(void *arg)
        struct rtipc_port_label plabel;
        struct sockaddr_ipc svsaddr;
        int ret, s, n = 0, len;
        struct timespec ts;
        s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_BUFP);
        * port as well (like the server thread did).
```

9.2 bufp-readwrite.c 585

```
if (ret)
                 fail("setsockopt");
        memset(\&svsaddr, 0, sizeof(svsaddr));
        svsaddr.sipc_family = AF_RTIPC;
svsaddr.sipc_port = -1; /* Tell BUFP to search by label. */
        ret = connect(s, (struct sockaddr *)&svsaddr, sizeof(svsaddr));
                 fail("connect");
         for (;;) {
                 len = strlen(msq[n]):
                 ret = write(s, msg[n], len);
                 if (ret < 0) {</pre>
                          close(s);
                          fail("write");
                 printf("%s: sent %d bytes, \"%.*s\"\n",
                         __FUNCTION__, ret, ret, msg[n]);
                 n = (n + 1) \% (sizeof(msg) / sizeof(msg[0]));
                 /*

* We run in full real-time mode (i.e. primary mode),
                  \ensuremath{^{*}} so we have to let the system breathe between two
                  * iterations.
                 ts.tv_sec = 0;
                 ts.tv_nsec = 500000000; /* 500 ms */
                 clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
        return NULL;
}
int main(int argc, char **argv)
         struct sched_param svparam = {.sched_priority = 71 };
        struct sched_param clparam = {.sched_priority = 70 };
        pthread_attr_t svattr, clattr;
         sigset_t set;
        int sig;
        sigemptyset(&set);
        sigaddset(&set, SIGINT);
sigaddset(&set, SIGTERM);
        sigaddset(&set, SIGHUP);
        pthread_sigmask(SIG_BLOCK, &set, NULL);
        pthread_attr_init(&svattr);
        pthread_attr_setdetachstate(&svattr, PTHREAD_CREATE_JOINABLE);
        pthread_attr_setinheritsched(&svattr, PTHREAD_EXPLICIT_SCHED);
        pthread_attr_setschedpolicy(&svattr, SCHED_FIF0);
        pthread_attr_setschedparam(&svattr, &svparam);
        errno = pthread_create(&svtid, &svattr, &server, NULL);
        if (errno)
                 fail("pthread_create");
        pthread_attr_init(&clattr);
        pthread_attr_setdetachstate(&clattr, PTHREAD_CREATE_JOINABLE);
        \verb|pthread_attr_setinheritsched(\&clattr, PTHREAD_EXPLICIT_SCHED)|;\\
        pthread_attr_setschedpolicy(&clattr, SCHED_FIFO);
pthread_attr_setschedparam(&clattr, &clparam);
         errno = pthread_create(&cltid, &clattr, &client, NULL);
        if (errno)
                 fail("pthread_create");
        sigwait(&set. &sig):
        pthread_cancel(svtid);
        pthread_cancel(cltid);
        pthread_join(svtid, NULL);
        pthread_join(cltid, NULL);
        return 0:
```

9.2 bufp-readwrite.c

```
/*
    * Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.
    *
    * This library is free software; you can redistribute it and/or
    * modify it under the terms of the GNU Lesser General Public
```

```
* License as published by the Free Software Foundation; either
 * version 2 of the License, or (at your option) any later version.
 * This library is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
 * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
 * Lesser General Public License for more details.
 ^{\ast} You should have received a copy of the GNU Lesser General Public
 * License along with this library; if not, write to the Free Software
* Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.
 * BUFP-based client/server demo, using the read(2)/write(2)
 * system calls to exchange data over a socket.
 * In this example, two sockets are created. A server thread (reader) * is bound to a real-time port and receives a stream of bytes sent to
 * this port from a client thread (writer).
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <signal.h>
#include <string.h>
#include <pthread.h>
#include <errno.h>
#include <rtdm/ipc.h>
pthread_t svtid, cltid;
#define BUFP_SVPORT 12
static const char *msg[] = {
         "Surfing With The Alien",
"Lords of Karma",
         "Banana Mango",
"Psycho Monkey",
         "Luminous Flesh Giants",
         "Moroccan Sunset",
          "Satch Boogie",
         "Flying In A Blue Dream",
         "Ride",
"Summer Song",
         "Speed Of Light",
"Crystal Planet",
         "Raspberry Jam Delta-V",
"Champagne?",
"Clouds Race Across The Sky",
         "Engines Of Creation"
};
static void fail(const char *reason)
         perror(reason);
         exit(EXIT_FAILURE);
}
static void *server(void *arg)
         struct sockaddr_ipc saddr;
         char buf[128];
         size_t bufsz;
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_BUFP);
         if (s < 0)
                   fail("socket");
         /*
 * Set a 16k buffer for the server endpoint. This
 * configuration must be done prior to binding the socket to a
.
          * port.
         bufsz = 16384; /* bytes */
         ret = setsockopt(s, SOL_BUFP, BUFP_BUFSZ,
                             &bufsz, sizeof(bufsz));
                   fail("setsockopt");
         saddr.sipc_family = AF_RTIPC;
         saddr.sipc_port = BUFP_SVPORT;
         ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
         if (ret)
                   fail("bind");
         for (;;) {
```

```
ret = read(s, buf, sizeof(buf));
                  if (ret < 0) {</pre>
                          close(s);
                          fail("read");
                 printf("%s: received %d bytes, \"%.*s\"\n",
                         __FUNCTION__, ret, ret, buf);
         return NULL;
}
static void *client(void *arg)
         struct sockaddr_ipc svsaddr;
         int ret, s, n = 0, len;
         struct timespec ts:
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_BUFP);
         if (s < 0)
                 fail("socket");
         memset(&svsaddr, 0, sizeof(svsaddr));
         svsaddr.sipc_family = AF_RTIPC;
svsaddr.sipc_port = BUFP_SVPORT;
         ret = connect(s, (struct sockaddr *)&svsaddr, sizeof(svsaddr));
                 fail("connect");
         for (;;) {
                 len = strlen(msg[n]);
                 ret = write(s, msg[n], len);
                  if (ret < 0) {</pre>
                          close(s);
                          fail("write");
                 }
                 n = (n + 1) \% (sizeof(msg) / sizeof(msg[0]));
                 /*

* We run in full real-time mode (i.e. primary mode),
                  \ensuremath{^{*}} so we have to let the system breathe between two
                  \mbox{*} iterations.
                  ts.tv_nsec = 5000000000; /* 500 ms */
                  clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
         return NULL;
}
int main(int argc, char **argv)
        struct sched_param svparam = {.sched_priority = 71 };
struct sched_param clparam = {.sched_priority = 70 };
         pthread_attr_t svattr, clattr;
         sigset_t set;
         int sig;
         sigemptyset(&set);
        sigaddset(&set, SIGINT);
sigaddset(&set, SIGTERM);
         sigaddset(&set, SIGHUP);
         pthread_sigmask(SIG_BLOCK, &set, NULL);
         pthread_attr_init(&svattr);
         pthread_attr_setdetachstate(&svattr, PTHREAD_CREATE_JOINABLE);
         pthread_attr_setinheritsched(&svattr, PTHREAD_EXPLICIT_SCHED);
         pthread_attr_setschedpolicy(&svattr, SCHED_FIF0);
         pthread_attr_setschedparam(&svattr, &svparam);
         errno = pthread_create(&svtid, &svattr, &server, NULL);
         if (errno)
                 fail("pthread_create");
         pthread_attr_init(&clattr);
         pthread_attr_setdetachstate(&clattr, PTHREAD_CREATE_JOINABLE);
         pthread_attr_setinheritsched(&clattr, PTHREAD_EXPLICIT_SCHED);
pthread_attr_setschedpolicy(&clattr, SCHED_FIF0);
         pthread_attr_setschedparam(&clattr, &clparam);
         errno = pthread_create(&cltid, &clattr, &client, NULL);
         if (errno)
                 fail("pthread_create");
         sigwait(&set. &sig):
```

```
pthread_cancel(svtid);
pthread_cancel(cltid);
pthread_join(svtid, NULL);
pthread_join(cltid, NULL);
return 0;
}
```

9.3 can-rtt.c

```
\ensuremath{^{*}} Round-Trip-Time Test - sends and receives messages and measures the
                            time in between.
   Copyright (C) 2006 Wolfgang Grandegger < wg@grandegger.com>
   Based on RTnet's examples/xenomai/posix/rtt-sender.c.
   Copyright (C) 2002 Ulrich Marx <marx@kammer.uni-hannover.de>
                  2002 Marc Kleine-Budde <kleine-budde@gmx.de>
                  2006 Jan Kiszka <jan.kiszka@web.de>
 * This program is free software; you can redistribute it and/or modify * it under the terms of the GNU General Public License as published by
   the Free Software Foundation; either version 2 of the License, or
   (at your option) any later version.
 * This program is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
* MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
   GNU General Public License for more details.
   You should have received a copy of the GNU General Public License
   along with this program; if not, write to the Free Software
   Foundation, Inc., 675 Mass Ave, Cambridge, MA 02139, USA.
 * The program sends out CAN messages periodically and copies the current
 * time-stamp to the payload. At reception, that time-stamp is compared
 * with the current time to determine the round-trip time. The jitter
 * values are printer out regularly. Concurrent tests can be carried out
 * by starting the program with different message identifiers. It is also
 \mbox{\scriptsize *} possible to use this program on a remote system as simple repeater to
 * loopback messages.
#include <errno.h>
#include <mqueue.h>
#include <signal.h>
#include <pthread.h>
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <unistd.h>
#include <limits.h>
#include <getopt.h>
#include <memory.h>
#include <netinet/in.h>
#include <net/if.h>
#include <sys/ioctl.h>
#include <rtdm/can.h>
#include <xenomai/init.h>
#define NSEC_PER_SEC 1000000000
static unsigned int cycle = 10000; /* 10 ms */
static canid_t can_id = 0x1;
static pthread_t txthread, rxthread;
static int txsock, rxsock;
static mqd_t mq;
static int txcount, rxcount;
static int overruns;
static int repeater:
struct rtt_stat {
    long long rtt;
    long long rtt_min;
    long long rtt_max;
    long long rtt_sum;
    long long rtt sum last:
    int counts_per_sec;
```

9.3 can-rtt.c 589

```
void application_usage(void)
     fprintf(stderr, "usage: %s [options] <tx-can-interface> <rx-can-interface>:\n",
             get_program_name());
     fprintf(stderr,
             " -r, --repeater
" -i, --id=ID
                                                       Repeater, send back received messages \n''
                                                       CAN Identifier (default = 0x1)\n"
             " -c, --cycle
                                                       Cycle time in us (default = 10000us)\n");
}
static void *transmitter(void *arg)
{
     struct sched_param param = { .sched_priority = 80 };
     struct timespec next_period;
     struct timespec time;
     struct can frame frame:
     long long *rtt_time = (long long *)&frame.data, t;
     /* Pre-fill CAN frame */
     frame.can_id = can_id;
     frame.can_dlc = sizeof(*rtt_time);
    pthread_setname_np(pthread_self(), "rtcan_rtt_transmitter");
pthread_setschedparam(pthread_self(), SCHED_FIFO, &param);
     clock_gettime(CLOCK_MONOTONIC, &next_period);
     while(1) {
         next_period.tv_nsec += cycle * 1000;
         while (next_period.tv_nsec >= NSEC_PER_SEC) {
                  next_period.tv_nsec -= NSEC_PER_SEC;
                  next_period.tv_sec++;
         }
         clock_nanosleep(CLOCK_MONOTONIC, TIMER_ABSTIME, &next_period, NULL);
         if (rxcount != txcount) {
             overruns++;
              continue;
         clock_gettime(CLOCK_MONOTONIC, &time);
         t = (long long)time.tv_sec * NSEC_PER_SEC + time.tv_nsec;
         memcpy(rtt_time, &t, sizeof(t));
         /* Transmit the message containing the local time */
if (send(txsock, (void *)&frame, sizeof(struct can_frame), 0) < 0) {
   if (errno == EBADF)</pre>
                  printf("terminating transmitter thread\n");
                 perror("send failed");
              return NULL;
         txcount++:
    }
}
static void *receiver(void *arg)
     struct sched_param param = { .sched_priority = 82 };
     struct timespec time;
     struct can_frame frame;
    long long *rtt_time = (long long *)frame.data, t;
struct rtt_stat rtt_stat = {0, 100000000000000000LL, -10000000000000000LL,
                                    0, 0, 0};
    pthread_setname_np(pthread_self(), "rtcan_rtt_receiver");
     pthread_setschedparam(pthread_self(), SCHED_FIFO, &param);
    rtt_stat.counts_per_sec = 1000000 / cycle;
    while (1) {
         if (recv(rxsock, (void *)&frame, sizeof(struct can_frame), 0) < 0) {
   if (errno == EBADF)</pre>
                  printf("terminating receiver thread\n");
                 perror("recv failed");
             return NULL;
         if (repeater) {
              /* Transmit the message back as is */
if (send(txsock, (void *)&frame, sizeof(struct can_frame), 0) < 0) {</pre>
                  if (errno == EBADF)
                      printf("terminating transmitter thread\n");
                  else
```

```
perror("send failed");
                  return NULL;
             }
             txcount++;
         } else {
             memcpy(&t, rtt_time, sizeof(t));
             clock_gettime(CLOCK_MONOTONIC, &time);
             if (rxcount > 0) {
                 rtt_stat.rtt = ((long long)time.tv_sec * 1000000000LL +
                                   time.tv_nsec - t);
                  rtt_stat.rtt_sum += rtt_stat.rtt;
if (rtt_stat.rtt < rtt_stat.rtt_min)
                      rtt_stat.rtt_min = rtt_stat.rtt;
                  if (rtt_stat.rtt > rtt_stat.rtt_max)
                      rtt_stat.rtt_max = rtt_stat.rtt;
             }
         rxcount++;
         if ((rxcount % rtt_stat.counts_per_sec) == 0) {
             mq_send(mq, (char *)&rtt_stat, sizeof(rtt_stat), 0);
             rtt_stat.rtt_sum_last = rtt_stat.rtt_sum;
    }
}
static void catch_signal(int sig)
    mq_close(mq);
    close(rxsock):
    close(txsock):
int main(int argc, char *argv[])
     struct sched_param param = { .sched_priority = 1 };
    pthread_attr_t thattr;
     struct mq_attr mqattr;
     struct sockaddr_can rxaddr, txaddr;
     struct can_filter rxfilter[1];
     struct rtt_stat rtt_stat;
    char mqname[32];
char *txdev, *rxdev;
struct can_ifreq ifr;
    int ret, opt;
    struct option long_options[] = {
    { "id", required_argument, 0, 'i'},
    { "cycle", required_argument, 0, 'c'},
         { "repeater", no_argument, 0, 'r'},
         { 0, 0, 0, 0},
    };
    switch (opt) {
             cycle = atoi(optarg);
             break;
         case 'i':
             can_id = strtoul(optarg, NULL, 0);
             break;
         case 'r':
             repeater = 1;
             break:
             fprintf(stderr, \ "Unknown \ option \ \%c\n", \ opt);
             exit(-1);
         }
    }
    printf("%d %d\n", optind, argc);
     if (optind + 2 != argc) {
         xenomai_usage();
         exit(0);
     txdev = argv[optind];
    rxdev = argv[optind + 1];
    /* Create and configure RX socket */
if ((rxsock = socket(PF_CAN, SOCK_RAW, CAN_RAW)) < 0) {</pre>
         perror("RX socket failed");
```

9.3 can-rtt.c 591

```
return -1;
strncpy(ifr.ifr_name, rxdev, IFNAMSIZ);
printf("RX rxsock=%d, ifr_name=%s\n", rxsock, ifr.ifr_name);
if (ioctl(rxsock, SIOCGIFINDEX, &ifr) < 0) {</pre>
    perror("RX ioctl SIOCGIFINDEX failed");
    goto failure1;
/* We only want to receive our own messages */
rxfilter[0].can_id = can_id;
rxfilter[0].can_mask = 0x3ff;
if (setsockopt(rxsock, SOL_CAN_RAW, CAN_RAW_FILTER,
    &rxfilter, sizeof(struct can_filter)) < 0) {
perror("RX setsockopt CAN_RAW_FILTER failed");
    goto failure1;
memset(&rxaddr, 0, sizeof(rxaddr));
rxaddr.can_ifindex = ifr.ifr_ifindex;
rxaddr.can_family = AF_CAN;
if (bind(rxsock, (struct sockaddr *)&rxaddr, sizeof(rxaddr)) < 0) {</pre>
    perror("RX bind failed\n");
    goto failure1;
/* Create and configure TX socket */
if (strcmp(rxdev. txdev) == 0) {
    txsock = rxsock:
} else {
    if ((txsock = socket(PF_CAN, SOCK_RAW, 0)) < 0) {</pre>
        perror("TX socket failed");
        goto failure1;
    strncpy(ifr.ifr_name, txdev, IFNAMSIZ);
    printf("TX txsock=%d, ifr_name=%s\n", txsock, ifr.ifr_name);
    if (ioctl(txsock, SIOCGIFINDEX, &ifr) < 0) {</pre>
        perror("TX ioctl SIOCGIFINDEX failed");
        goto failure2;
     /* Suppress definiton of a default receive filter list */
    if (setsockopt(txsock, SOL_CAN_RAW, CAN_RAW_FILTER, NULL, 0) < 0) {</pre>
        perror("TX setsockopt CAN_RAW_FILTER failed");
         goto failure2;
    memset(&txaddr, 0, sizeof(txaddr));
    txaddr.can_ifindex = ifr.ifr_ifindex;
    txaddr.can_family = AF_CAN;
    if (bind(txsock, (struct sockaddr *)&txaddr, sizeof(txaddr)) < 0) {
    perror("TX bind failed\n");</pre>
             goto failure2;
    }
}
signal(SIGTERM, catch_signal);
signal(SIGINT, catch_signal);
signal(SIGHUP, catch_signal);
printf("All RTT timing figures are in us.\n");
/* Create statistics message queue */
snprintf(mqname, sizeof(mqname), "/rtcan_rtt-%d", getpid());
mqattr.mq_flags = 0;
mqattr.mq_maxmsg = 100;
mqattr.mq_msgsize = sizeof(struct rtt_stat);
mq = mq_open(mqname, O_RDWR | O_CREAT | O_EXCL, 0600, &mqattr);
if (mq == (mqd_t)-1) {
    perror("opening mqueue failed");
    goto failure2;
/* Create receiver RT-thread */
pthread_attr_init(&thattr);
pthread_attr_setdetachstate(&thattr, PTHREAD_CREATE_JOINABLE);
ret = pthread_create(&rxthread, &thattr, &receiver, NULL);
if (ret) {
    fprintf(stderr, "%s: pthread_create(receiver) failed\n",
```

```
strerror(-ret));
       goto failure3;
   }
   if (!repeater) {
       /* Create transitter RT-thread */
       ret = pthread_create(&txthread, &thattr, &transmitter, NULL);
           fprintf(stderr, \ \ \ \ "%s: \ pthread\_create(transmitter) \ failed \setminus n",
                    strerror(-ret));
           goto failure4;
       }
   }
   pthread_setschedparam(pthread_self(), SCHED_FIFO, &param);
   if (repeater)
       printf("Messages\n");
       printf("Messages RTTlast RTT_avg RTT_min RTT_max Overruns\n");
   while (1) {
       long long rtt_avg;
       ret = mq_receive(mq, (char *)&rtt_stat, sizeof(rtt_stat), NULL);
       if (ret != sizeof(rtt_stat)) {
            if (ret < 0) {</pre>
                if (errno == EBADF)
                    printf("terminating mq_receive\n");
                else
                    perror("mq_receive failed");
               fprintf(stderr,
                         "mq_receive returned invalid length %d\n", ret);
           break:
       }
       if (repeater) {
           printf("%8d\n", rxcount);
           rtt_avg = ((rtt_stat.rtt_sum - rtt_stat.rtt_sum_last) /
           rtt_stat.counts_per_sec);
printf("%8d %71d %71d %71d %8d\n", rxcount,
                   (long)(rtt_stat.rtt / 1000), (long)(rtt_avg / 1000),
                   (long)(rtt_stat.rtt_min / 1000),
(long)(rtt_stat.rtt_max / 1000),
                   overruns);
       }
   }
   /* This call also leaves primary mode, required for socket cleanup. */
   printf("shutting down\n");
   /* Important: First close the sockets! */
   close(rxsock):
   close(txsock);
   pthread_join(txthread, NULL);
   pthread_cancel(rxthread);
   pthread_join(rxthread, NULL);
   return 0:
failure4:
   pthread_cancel(rxthread);
   pthread_join(rxthread, NULL);
failure3:
   mq_close(mq);
failure2:
   close(txsock);
failure1:
   close(rxsock);
   return 1;
```

9.4 cross-link.c

```
/*
    * cross-link.c
    *

* Userspace test program (Xenomai alchemy skin) for RTDM-based UART drivers
    * Copyright 2005 by Joerg Langenberg <joergel75@gmx.net>
```

9.4 cross-link.c 593

```
* Updates by Jan Kiszka <jan.kiszka@web.de>
 * This program is free software; you can redistribute it and/or modify
 * it under the terms of the GNU General Public License as published by
 * the Free Software Foundation; either version 2 of the License, or
 * (at your option) any later version.
 ^{\star} This program is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
 * GNU General Public License for more details.
 * You should have received a copy of the GNU General Public License
 * along with this program; if not, write to the Free Software
 * Foundation, Inc., 675 Mass Ave, Cambridge, MA 02139, USA.
#include <stdio.h>
#include <signal.h>
#include <unistd.h>
#include <sys/mman.h>
#include <alchemy/task.h>
#include <alchemy/timer.h>
#include <rtdm/serial.h>
#define MAIN_PREFIX "main : "
#define MAIN_PREFIX "main : "
#define WTASK_PREFIX "write_task: "
#define RTASK_PREFIX "read_task: "
                       "/dev/rtdm/rtser0"
#define WRITE FILE
                      "/dev/rtdm/rtser1"
#define READ_FILE
int read_fd = -1;
int write_fd = -1;
#define STATE FILE OPENED
#define STATE_TASK_CREATED
unsigned int read_state = 0;
unsigned int write_state = 0;
                              --s-ms-us-ns */
RTIME write_task_period_ns = 1000000000llu;
RT_TASK write_task;
RT_TASK read_task;
static const struct rtser_config read_config = {
        .config_mask = 0xFFFF,
.baud_rate = 115200,
        .baud_rate
                           = RTSER DEF PARITY.
        .parity
        .data_bits
                          = RTSER_DEF_BITS,
                           = RTSER_DEF_STOPB,
        .stop_bits
        .handshake
                           = RTSER_DEF_HAND,
        .fifo_depth
                           = RTSER_DEF_FIFO_DEPTH,
        .rx_timeout
                           = RTSER DEF TIMEOUT.
                          = RTSER_DEF_TIMEOUT,
        .tx timeout
                           = 1000000000, /* 1 s
        .event_timeout
        .timestamp_history = RTSER_RX_TIMESTAMP_HISTORY,
        .event_mask
                           = RTSER_EVENT_RXPEND,
};
.baud_rate
                           = 115200,
        .timestamp_history = RTSER_DEF_TIMESTAMP_HISTORY,
        /* the rest implicitly remains default */
};
static int close_file( int fd, char *name)
{
        int err, i=0;
        do {
                i++;
                err = close(fd):
                switch (err) {
                        printf(MAIN_PREFIX "%s -> EAGAIN (%d times)\n",
                                name, i);
                         rt_task_sleep(50000); /* wait 50us */
                        break:
                case 0:
                         printf(MAIN_PREFIX "%s -> closed\n", name);
                 default:
                         printf(MAIN_PREFIX "%s \rightarrow %s\n", name,
                                strerror(-err));
```

```
} while (err == -EAGAIN && i < 10);</pre>
        return err;
static void cleanup_all(void)
        if (read_state & STATE_FILE_OPENED) {
    close_file(read_fd, READ_FILE" (read)");
    read_state &= ~STATE_FILE_OPENED;
        }
        if (write_state & STATE_FILE_OPENED) {
                 close_file(write_fd, WRITE_FILE " (write)");
                 write_state &= ~STATE_FILE_OPENED;
        if (write_state & STATE_TASK_CREATED) {
                 printf(MAIN_PREFIX "delete write_task\n");
                 rt_task_delete(&write_task);
                 write_state &= ~STATE_TASK_CREATED;
        }
        if (read_state & STATE_TASK_CREATED) {
                printf(MAIN_PREFIX "delete read_task\n");
                 rt_task_delete(&read_task);
                 read_state &= ~STATE_TASK_CREATED;
        }
}
static void catch_signal(int sig)
        cleanup_all();
        printf(MAIN_PREFIX "exit\n");
        return;
}
static void write_task_proc(void *arg)
        int err:
        RTIME write_time;
        ssize t sz = sizeof(RTIME):
        int written = 0;
        err = rt_task_set_periodic(NULL, TM_NOW,
                                     rt_timer_ns2ticks(write_task_period_ns));
        if (err) {
                 printf(WTASK_PREFIX "error on set periodic, %s\n",
                        strerror(-err));
                 goto exit_write_task;
        while (1) {
                 err = rt_task_wait_period(NULL);
                 if (err) {
                         printf(WTASK_PREFIX
                                  "error on rt_task_wait_period, %s\n",
                                  strerror(-err));
                          break:
                 }
                 write_time = rt_timer_read();
                 written = write(write_fd, &write_time, sz);
                 if (written < 0 ) {</pre>
                         printf(WTASK_PREFIX "error on write, %s\n",
                                 strerror(-err));
                 } else if (written != sz) {
                         printf(WTASK_PREFIX "only %d / %zd byte transmitted\n",
                                 written, sz);
                          break;
                 }
        }
 exit_write_task:
        if ((write_state & STATE_FILE_OPENED) &&
    close_file(write_fd, WRITE_FILE " (write)") == 0)
                 write_state &= ~STATE_FILE_OPENED;
        printf(WTASK_PREFIX "exit\n");
}
static void read_task_proc(void *arg)
        int err:
```

9.4 cross-link.c 595

```
int nr = 0;
        RTIME read_time = 0;
        RTIME write_time = 0;
        RTIME irq_time = 0;
        ssize_t sz = sizeof(RTIME);
         int rd = 0:
        struct rtser_event rx_event;
        * We are in secondary mode now due to printf, the next
* blocking Xenomai or driver call will switch us back
         * (here: RTSER_RTIOC_WAIT_EVENT).
        while (1) {
    /* waiting for event */
                 err = ioctl(read_fd, RTSER_RTIOC_WAIT_EVENT, &rx_event);
                         printf(RTASK_PREFIX
                                 "error on RTSER_RTIOC_WAIT_EVENT, %s\n", strerror(-err));
                          if (err == -ETIMEDOUT)
                                 continue;
                         break;
                 }
                 irq_time = rx_event.rxpend_timestamp;
                 rd = read(read_fd, &write_time, sz);
                 if (rd == sz) {
                         read_time = rt_timer_read();
                         printf("%3d |%16llu |%16llu |%16llu\n", nr,
                                irq_time - write_time,
read_time - irq_time,
                                 read_time - write_time);
                         nr++;
                 } else if (rd < 0 ) {</pre>
                         printf(RTASK\_PREFIX "error on read, code %s\n",
                                strerror(-err));
                         break:
                 } else {
                         printf(RTASK_PREFIX "only %d / %zd byte received \n",
                                rd, sz);
                         break:
                 }
        }
        if ((read_state & STATE_FILE_OPENED) &&
             close_file(read_fd, READ_FILE " (read)") == 0)
                 read_state &= ~STATE_FILE_OPENED;
        printf(RTASK_PREFIX "exit\n");
}
int main(int argc, char* argv[])
{
        int err = 0;
        signal(SIGTERM, catch_signal);
        signal(SIGINT, catch_signal);
         /* open rtser0 */
        write_fd = open( WRITE_FILE, 0);
        if (write_fd < 0) {
                printf({\tt MAIN\_PREFIX}\ "can't\ open\ \%s\ ({\tt write})\ ,\ \%s \backslash n"\ ,\ {\tt WRITE\_FILE}\ ,
                        strerror(-write_fd));
                 goto error:
        write_state |= STATE_FILE_OPENED;
printf(MAIN_PREFIX "write-file opened\n");
         /* writing write-config */
        err = ioctl(write_fd, RTSER_RTIOC_SET_CONFIG, &write_config);
         if (err) {
                printf(MAIN_PREFIX "error while RTSER_RTIOC_SET_CONFIG, %s\n",
                        strerror(-err));
                 goto error;
        printf(MAIN_PREFIX "write-config written\n");
        read_fd = open( READ_FILE, 0 );
        if (read_fd < 0) {
                 printf(MAIN_PREFIX "can't open %s (read), %s\n", READ_FILE,
                         strerror(-read_fd));
```

```
goto error;
read_state |= STATE_FILE_OPENED;
printf(MAIN_PREFIX "read-file opened\n");
/* writing read-config */
err = ioctl(read_fd, RTSER_RTIOC_SET_CONFIG, &read_config);
if (err) {
        printf(MAIN_PREFIX "error while ioctl, %s\n",
               strerror(-err));
        goto error:
printf(MAIN_PREFIX "read-config written\n");
/* create write_task */
err = rt_task_create(&write_task, "write_task", 0, 50, 0);
if (err) {
       printf(MAIN_PREFIX "failed to create write_task, %s\n",
               strerror(-err));
        goto error;
write_state |= STATE_TASK_CREATED;
printf(MAIN_PREFIX "write-task created\n");
/* create read_task */
err = rt_task_create(&read_task, "read_task", 0, 51, 0);
if (err) {
       printf(MAIN_PREFIX "failed to create read_task, %s\n",
               strerror(-err));
        goto error:
read_state |= STATE_TASK_CREATED;
printf(MAIN_PREFIX "read-task created\n");
/* start write_task */
printf(MAIN_PREFIX "starting write-task\n");
err = rt_task_start(&write_task, &write_task_proc, NULL);
if (err) {
       printf(MAIN_PREFIX "failed to start write_task, %s\n",
               strerror(-err));
        goto error;
3
/* start read_task */
printf(MAIN_PREFIX "starting read-task\n");
err = rt_task_start(&read_task,&read_task_proc,NULL);
if (err) {
        \label{eq:main_prefix} \mbox{"failed to start read_task, $\%s\n",}
               strerror(-err)):
        goto error:
}
for (;;)
        pause();
return 0:
cleanup_all();
return err;
```

9.5 iddp-label.c

```
/*

* Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.

* This library is free software; you can redistribute it and/or

* modify it under the terms of the GNU Lesser General Public

* License as published by the Free Software Foundation; either

* version 2 of the License, or (at your option) any later version.

* This library is distributed in the hope that it will be useful,

* but WITHOUT ANY WARRANTY; without even the implied warranty of

* MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU

* Lesser General Public License for more details.

* You should have received a copy of the GNU Lesser General Public

* License along with this library; if not, write to the Free Software

* Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

* IDDP-based client/server demo, using the write(2)/recvfrom(2)
```

9.5 iddp-label.c 597

```
* system calls to exchange data over a socket.
    \mbox{*} In this example, two sockets are created. A server thread (reader)
     \ensuremath{^{*}} is bound to a labeled real-time port and receives datagrams sent to
      * this port from a client thread (writer). The client thread attaches
* to the port opened by the server using a labeled connection
* request. The client socket is bound to a different port, only to
      * provide a valid peer name; this is optional.
      * ASCII labels can be attached to bound ports, in order to connect
            sockets to them in a more descriptive way than using plain numeric % \left( 1\right) =\left( 1\right) \left( 1\right) 
          port values.
 #include <stdio.h>
 #include <stdlib.h>
 #include <unistd.h>
 #include <signal.h>
 #include <string.h>
 #include <pthread.h>
 #include <errno.h>
 #include <rtdm/ipc.h>
pthread_t svtid, cltid;
 #define IDDP_CLPORT 27
 #define IDDP_PORT_LABEL "iddp-demo"
 static const char *msg[] = {
                "Surfing With The Alien",
"Lords of Karma",
                "Banana Mango",
"Psycho Monkey"
                "Luminous Flesh Giants",
                "Moroccan Sunset",
                "Satch Boogie"
                "Flying In A Blue Dream",
                "Ride",
                "Summer Song"
                "Speed Of Light",
                "Crystal Planet"
                "Raspberry Jam Delta-V", "Champagne?",
                "Clouds Race Across The Sky",
                "Engines Of Creation"
};
 static void fail(const char *reason)
 {
                              perror(reason):
                              exit(EXIT_FAILURE);
 static void *server(void *arg)
                              struct sockaddr_ipc saddr, claddr;
                              struct rtipc_port_label plabel;
                              socklen_t addrlen;
                              char buf[128];
                              int ret, s;
                              s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_IDDP);
                              if (s < 0)
                                                           fail("socket");
                               /* \phantom{a}^{\prime} % We will use Xenomai's system heap for datagram, so no
                                  * IDDP_POOLSZ required here.
                             /*

* Set a port label. This name will be registered when

the port number (if given).
                                  * binding, in addition to the port number (if given).
                              strcpy(plabel.label, IDDP_PORT_LABEL);
ret = setsockopt(s, SOL_IDDP, IDDP_LABEL
                                                                                            &plabel, sizeof(plabel));
                                                            fail("setsockopt");
                                  \ensuremath{^{*}} Bind the socket to the port. Assign that port a label, so
                                  * that peers may use a descriptive information to locate
                                  * it. Labeled ports will appear in the
                                  * /proc/xenomai/registry/rtipc/iddp directory once the socket
                                  * is bound.
```

```
* saddr.sipc_port specifies the port number to use. If -1 is
           * saddr.sipc_port specifies the port number to use. If -
* passed, the IDDP driver will auto-select an idle port.
*/
          saddr.sipc_family = AF_RTIPC;
saddr.sipc_port = -1;    /* Pick next free */
ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
          if (ret)
                    fail("bind");
          for (;;) {
                    addrlen = sizeof(saddr);
                    ret = recvfrom(s, buf, sizeof(buf), 0,
(struct sockaddr *)&claddr, &addrlen);
                    if (ret < 0) {</pre>
                              close(s);
                              fail("recvfrom");
                    printf("%s: received %d bytes, \"%.*s\" from port %d\n",
                                __FUNCTION__, ret, ret, buf, claddr.sipc_port);
          return NULL:
}
static void *client(void *arg)
          struct sockaddr_ipc svsaddr, clsaddr;
          struct rtipc_port_label plabel;
int ret, s, n = 0, len;
          struct timespec ts;
          s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_IDDP);
          if (s < 0)
                    fail("socket");
           * Set a name on the client socket. This is strictly optional,
           * and only done here for the purpose of getting back a
           * different port number in recvfrom().
          clsaddr.sipc_family = AF_RTIPC;
clsaddr.sipc_port = IDDP_CLPORT;
          ret = bind(s, (struct sockaddr *)&clsaddr, sizeof(clsaddr));
          if (ret)
                    fail("bind");
          /*
    * Set the port label. This name will be used to find the peer
    * when connecting, instead of the port number. The label must
    * the cocket is bound to the port, so that
           * be set _after_ the socket is bound to the port, so that
* IDDP does not try to register this label for the client
           \mbox{\ensuremath{^{\ast}}} port as well (like the server thread did).
          fail("setsockopt");
          {\tt memset(\&svsaddr, \ 0, \ sizeof(svsaddr));}
          svsaddr.sipc_family = AF_RTIPC;
svsaddr.sipc_port = -1; /* Tell IDDP to search by label. */
          ret = connect(s, (struct sockaddr *)&svsaddr, sizeof(svsaddr));
          if (ret)
                    fail("connect");
          for (;;) {
                    len = strlen(msg[n]);
                    /* Send to default destination we connected to. */
                    ret = write(s, msg[n], len);
                    if (ret < 0) {</pre>
                              close(s);
                              fail("sendto");
                    }
                    printf("%s: sent %d bytes, \"%.*s\"\n",
                             __FUNCTION__, ret, ret, msg[n]);
                    n = (n + 1) \% (sizeof(msg) / sizeof(msg[0]));
                    /*

* We run in full real-time mode (i.e. primary mode),
                     * so we have to let the system breathe between two
                     \ast iterations.
                    ts.tv_nsec = 500000000; /* 500 ms */
                    clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
          }
```

9.6 iddp-sendrecv.c 599

```
return NULL;
}
int main(int argc, char **argv)
        struct sched_param svparam = {.sched_priority = 71 };
        struct sched_param clparam = {.sched_priority = 70 };
        pthread_attr_t svattr, clattr;
        sigset_t set;
        int sig;
        sigemptyset(&set):
        sigaddset(&set, SIGINT);
        sigaddset(&set, SIGTERM);
        sigaddset(&set, SIGHUP);
        pthread_sigmask(SIG_BLOCK, &set, NULL);
        pthread_attr_init(&svattr);
        pthread_attr_setdetachstate(&svattr, PTHREAD_CREATE_JOINABLE);
        pthread_attr_setinheritsched(&svattr, PTHREAD_EXPLICIT_SCHED);
        pthread_attr_setschedpolicy(&svattr, SCHED_FIF0);
        pthread_attr_setschedparam(&svattr, &svparam);
        errno = pthread_create(&svtid, &svattr, &server, NULL);
        if (errno)
                fail("pthread_create");
        pthread_attr_init(&clattr);
        pthread_attr_setdetachstate(&clattr, PTHREAD_CREATE_JOINABLE);
        pthread_attr_setinheritsched(&clattr, PTHREAD_EXPLICIT_SCHED);
pthread_attr_setschedpolicy(&clattr, SCHED_FIF0);
        pthread_attr_setschedparam(&clattr, &clparam);
        errno = pthread_create(&cltid, &clattr, &client, NULL);
        if (errno)
                fail("pthread_create");
        sigwait(&set, &sig);
        pthread_cancel(svtid);
        pthread_cancel(cltid);
        pthread_join(svtid, NULL);
        pthread_join(cltid, NULL);
        return 0;
```

9.6 iddp-sendrecv.c

```
* Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.
 * This library is free software; you can redistribute it and/or
 * modify it under the terms of the GNU Lesser General Public
 * License as published by the Free Software Foundation; either
 st version 2 of the License, or (at your option) any later version.
* This library is distributed in the hope that it will be useful,
* but WITHOUT ANY WARRANTY; without even the implied warranty of
 * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
* Lesser General Public License for more details.
 * You should have received a copy of the GNU Lesser General Public
 * License along with this library; if not, write to the Free Software
 * Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.
 * IDDP-based client/server demo, using the sendto(2)/recvfrom(2)
  system calls to exchange data over a socket.
 * In this example, two sockets are created. A server thread (reader)
 * is bound to a real-time port and receives datagrams sent to this
 ^{st} port from a client thread (writer). The client socket is bound to a
 * different port, only to provide a valid peer name; this is
 * optional.
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <signal.h>
#include <string.h>
#include <pthread.h>
#include <errno.h>
#include <rtdm/ipc.h>
```

```
pthread_t svtid, cltid;
#define IDDP_SVPORT 12
#define IDDP_CLPORT 13
static const char *msg[] = {
         "Surfing With The Alien",
         "Lords of Karma",
         "Banana Mango",
"Psycho Monkey",
         "Luminous Flesh Giants",
         "Moroccan Sunset",
         "Satch Boogie",
         "Flying In A Blue Dream",
         "Ride",
"Summer Song"
         "Speed Of Light",
         "Crystal Planet"
         "Raspberry Jam Delta-V",
         "Champagne?",
"Clouds Race Across The Sky",
         "Engines Of Creation"
};
static void fail(const char *reason)
         perror(reason);
         exit(EXIT_FAILURE);
}
static void *server(void *arg)
         struct sockaddr_ipc saddr, claddr;
         socklen_t addrlen;
         char buf[128];
         size_t poolsz;
         int ret, s;
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_IDDP);
         if (s < 0)
                 fail("socket");
        /*

* Set a local 32k pool for the server endpoint. Memory needed

* to convey datagrams will be pulled from this pool, instead
          * of Xenomai's system pool.
         poolsz = 32768; /* bytes */
         ret = setsockopt(s, SOL_IDDP, IDDP_POOLSZ,
                           &poolsz, sizeof(poolsz));
                 fail("setsockopt");
         saddr.sipc_family = AF_RTIPC;
saddr.sipc_port = IDDP_SVPORT;
         ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
         if (ret)
                 fail("bind");
         for (;;) {
                 addrlen = sizeof(saddr);
                 if (ret < 0) {</pre>
                          close(s);
                          fail("recvfrom");
                 printf("%s: received %d bytes, \"%.*s\" from port %d\n",
                         __FUNCTION__, ret, ret, buf, claddr.sipc_port);
         }
         return NULL;
}
static void *client(void *arg)
         struct sockaddr_ipc svsaddr, clsaddr;
         int ret, s, n = 0, len;
         struct timespec ts:
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_IDDP);
                 fail("socket");
        clsaddr.sipc_family = AF_RTIPC;
clsaddr.sipc_port = IDDP_CLPORT;
```

9.7 rtcanconfig.c 601

```
ret = bind(s, (struct sockaddr *)&clsaddr, sizeof(clsaddr));
                fail("bind");
        svsaddr.sipc_family = AF_RTIPC;
        svsaddr.sipc_port = IDDP_SVPORT;
        for (;;) {
                len = strlen(msg[n]);
                if (ret < 0) {</pre>
                         close(s);
                         fail("sendto");
                printf("%s: sent %d bytes, \"%.*s\"\n",
                __FUNCTION__, ret, ret, msg[n]);

n = (n + 1) \% (sizeof(msg) / sizeof(msg[0]));
                /*
 * We run in full real-time mode (i.e. primary mode),
                 * so we have to let the system breathe between two
                 * iterations.
                ts.tv_sec = 0;
ts.tv_nsec = 500000000; /* 500 ms */
                clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
        return NULL:
}
int main(int argc, char **argv)
        struct sched_param svparam = {.sched_priority = 71 };
        struct sched_param clparam = {.sched_priority = 70 };
        pthread_attr_t svattr, clattr;
        sigset_t set;
        int sig;
        sigemptyset(&set);
        sigaddset(&set, SIGINT);
        sigaddset(&set, SIGTERM);
        sigaddset(&set, SIGHUP);
        pthread_sigmask(SIG_BLOCK, &set, NULL);
        pthread_attr_init(&svattr);
        pthread_attr_setdetachstate(&svattr, PTHREAD_CREATE_JOINABLE);
        \tt pthread\_attr\_setinheritsched(\&svattr, PTHREAD\_EXPLICIT\_SCHED);
        pthread_attr_setschedpolicy(&svattr, SCHED_FIF0);
        pthread_attr_setschedparam(&svattr, &svparam);
        errno = pthread_create(&svtid, &svattr, &server, NULL);
                fail("pthread_create");
        pthread_attr_init(&clattr);
        pthread_attr_setdetachstate(&clattr, PTHREAD_CREATE_JOINABLE);
        pthread_attr_setinheritsched(&clattr, PTHREAD_EXPLICIT_SCHED);
        pthread_attr_setschedpolicy(&clattr, SCHED_FIF0);
        pthread_attr_setschedparam(&clattr, &clparam);
        errno = pthread_create(&cltid, &clattr, &client, NULL);
        if (errno)
                fail("pthread_create");
        sigwait(&set, &sig);
        pthread_cancel(svtid);
        pthread_cancel(cltid);
        pthread_join(svtid, NULL);
pthread_join(cltid, NULL);
        return 0;
}
```

9.7 rtcanconfig.c

```
/*
* Program to configuring the CAN controller

* Copyright (C) 2006 Wolfgang Grandegger <wg@grandegger.com>

* Copyright (C) 2005, 2006 Sebastian Smolorz

* <Sebastian.Smolorz@stud.uni-hannover.de>
```

```
* This program is free software; you can redistribute it and/or modify
 * it under the terms of the GNU General Public License as published by
 * the Free Software Foundation; either version 2 of the License, or
 * (at your option) any later version.
 * This program is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
 * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
 * GNU General Public License for more details.
 * You should have received a copy of the GNU General Public License
 * along with this program; if not, write to the Free Software
* Foundation, Inc., 675 Mass Ave, Cambridge, MA 02139, USA.
#include <stdio.h>
#include <stdlib.h>
#include <signal.h>
#include <unistd.h>
#include <string.h>
#include <time.h>
#include <errno.h>
#include <getopt.h>
#include <sys/mman.h>
#include <rtdm/can.h>
static void print_usage(char *prg)
    fprintf(stderr.
             "Usage: %s <can-interface> [Options] [up|down|start|stop|sleep]\n"
             "Options:\n"
             " -v, --verbose
                                          be verbose\n'
             " -h, --help
                                          this help\n"
             "-c, --ctrlmode=CTRLMODE listenonly, loopback or none\n"
             " -b, --baudrate=BPS
                                          baudrate in bits/sec\n"
             " -B, --bittime=BTR0:BTR1 BTR or standard bit-time\n"
             " -B, --bittime=BRP:PROP_SEG:PHASE_SEG1:PHASE_SEG2:SJW:SAM\n",
             prg);
}
static can_baudrate_t string_to_baudrate(char *str)
    can_baudrate_t baudrate;
    if (sscanf(str, "%i", &baudrate) != 1)
        return -1:
    return baudrate;
}
static int string_to_mode(char *str)
    if ( !strcmp(str, "up") || !strcmp(str, "start") )
    return CAN_MODE_START;
else if ( !strcmp(str, "down") || !strcmp(str, "stop") )
        return CAN_MODE_STOP;
    else if ( !strcmp(str, "sleep") )
        return CAN_MODE_SLEEP;
    return -EINVAL;
}
static int string_to_ctrlmode(char *str)
    if ( !strcmp(str, "listenonly") )
         return CAN_CTRLMODE_LISTENONLY;
    else if ( !strcmp(str, "loopback") )
    return CAN_CTRLMODE_LOOPBACK;
    else if ( !strcmp(str, "none") )
        return 0:
    return -1;
}
int main(int argc, char *argv[])
             ifname[16];
    char
    int
             can_fd = -1;
    int
             new_baudrate = -1;
    int
             new_mode = -1;
             new_ctrlmode = 0, set_ctrlmode = 0;
    int
             verbose = 0;
    int
            bittime_count = 0, bittime_data[6];
    int
    struct can_ifreq ifr;
    struct can_bittime *bittime;
    int opt, ret;
char* ptr;
```

9.7 rtcanconfig.c 603

```
struct option long_options[] = {
    { "help", no_argument, 0, 'h' },
{ "verbose", no_argument, 0, 'v'},
{ "baudrate", required_argument, 0, 'b'},
{ "bittime", required_argument, 0, 'B'},
{ "ctrlmode", required_argument, 0, 'c'},
    { 0, 0, 0, 0},
while ((opt = getopt_long(argc, argv, "hvb:B:c:",
                             long_options, NULL)) != -1) {
    switch (opt) {
    case 'h':
        print_usage(argv[0]);
         exit(0);
    case 'v':
         verbose = 1;
         break;
    case 'b':
        new_baudrate = string_to_baudrate(optarg);
         if (new_baudrate == -1) {
             print_usage(argv[0]);
             exit(0);
         break;
    case 'B':
         ptr = optarg;
         while (1) {
             bittime_data[bittime_count++] = strtoul(ptr, NULL, 0);
             if (!(ptr = strchr(ptr, ':')))
                  break;
             ptr++;
         if (bittime_count != 2 && bittime_count != 6) {
             print_usage(argv[0]);
              exit(0);
         break;
    case 'c':
         ret = string_to_ctrlmode(optarg);
         if (ret == -1) {
             print_usage(argv[0]);
              exit(0);
         new ctrlmode |= ret:
         set_ctrlmode = 1;
         break;
        break;
    default:
         fprintf(stderr, "Unknown option %c\n", opt);
}
/* Get CAN interface name */
if (optind != argc - 1 && optind != argc - 2) {
    print_usage(argv[0]);
    return 0;
}
strncpy(ifname, argv[optind], IFNAMSIZ);
strncpy(ifr.ifr_name, ifname, IFNAMSIZ);
if (optind == argc - 2) {
                               /* Get mode setting */
    new_mode = string_to_mode(argv[optind + 1]);
    if (verbose)
         printf("mode: %s (%#x)\n", argv[optind + 1], new\_mode);
    if (new mode < 0) {
        print_usage(argv[0]);
         return 0;
}
can_fd = socket(PF_CAN, SOCK_RAW, CAN_RAW);
if (can_fd < 0) {</pre>
    fprintf(stderr, "Cannot open RTDM CAN socket. Maybe driver not loaded? \n");
    return can_fd;
ret = ioctl(can_fd, SIOCGIFINDEX, &ifr);
if (ret) {
```

```
fprintf(stderr,"Can't get interface index for %s, errno = %d\n", ifname, errno);
   }
   if (new_baudrate != -1) {
       if (verbose)
           printf("baudrate: %d\n", new_baudrate);
       ifr.ifr_ifru.baudrate = new_baudrate;
       ret = ioctl(can_fd, SIOCSCANBAUDRATE, &ifr);
       if (ret) {
           goto abort;
   if (bittime_count) {
   bittime = &ifr.ifr_ifru.bittime;
       if (bittime_count == 2) {
           bittime->type = CAN_BITTIME_BTR;
            bittime->btr.btr0 = bittime_data[0];
            bittime->btr.btr1 = bittime_data[1];
           if (verbose)
    printf("bit-time: btr0=0x%02x btr1=0x%02x\n",
                        bittime->btr.btr0, bittime->btr.btr1);
       } else {
           bittime->type = CAN_BITTIME_STD;
           bittime->std.brp = bittime_data[0];
            bittime->std.prop_seg = bittime_data[1];
           bittime->std.phase_seg1 = bittime_data[2];
bittime->std.phase_seg2 = bittime_data[3];
           bittime->std.sjw = bittime_data[4];
            bittime->std.sam = bittime_data[5];
            if (verbose)
                printf("bit-time: brp=%d prop_seg=%d phase_seg1=%d "
                        "phase_seg2=%d sjw=%d sam=%d\n",
                        bittime->std.brp,
                        bittime->std.prop_seg,
                        bittime->std.phase_seg1,
                        bittime->std.phase_seg2,
                        bittime->std.sjw,
                        bittime->std.sam);
       ret = ioctl(can_fd, SIOCSCANCUSTOMBITTIME, &ifr);
       if (ret) {
           goto abort;
   }
   if (set_ctrlmode != 0) {
       ifr.ifr_ifru.ctrlmode = new_ctrlmode;
       if (verbose)
       printf("ctrlmode: %#x\n", new_ctrlmode);
ret = ioctl(can_fd, SIOCSCANCTRLMODE, &ifr);
       if (ret) {
           goto abort;
   }
   if (new_mode != -1) {
       ifr.ifr_ifru.mode = new_mode;
       ret = ioctl(can_fd, SIOCSCANMODE, &ifr);
       if (ret) {
           goto abort;
   }
   close(can_fd);
   return 0;
abort:
   close(can_fd);
   return ret;
```

9.8 rtcanrecv.c

```
#include <stdio.h>
#include <stdlib.h>
#include <signal.h>
#include <unistd.h>
#include <time.h>
```

9.8 rtcanrecv.c 605

```
#include <errno.h>
#include <getopt.h>
#include <alchemy/task.h>
#include <rtdm/can.h>
static void print_usage(char *prg)
    fprintf(stderr,
             "Usage: %s [<can-interface>] [Options]\n"
             "Options:\n"
             "-f-filter=id:mask[:id:mask]... apply filter\n"
"-e --error=mask receive error messages\n"
"-t, --timeout=MS timeout in ms\n"
             " -T, --timestamp
                                       with absolute timestamp \ensuremath{\texttt{n}}\xspace
             "-R, --timestamp-rel with relative timestamp\n"
             " -v, --verbose
                                      be verbose\n"
             " -p, --print=MODULO
" -h, --help
                                      print every MODULO message\n"
                                       this help\n'',
             prg);
}
extern int optind, opterr, optopt;
static int s = -1, verbose = 0, print = 1;
static nanosecs_rel_t timeout = 0, with_timestamp = 0, timestamp_rel = 0;
RT TASK rt task desc:
#define BUF_SIZ 255
#define MAX_FILTER 16
struct sockaddr_can recv_addr;
struct can_filter recv_filter[MAX_FILTER];
static int filter_count = 0;
static int add_filter(u_int32_t id, u_int32_t mask)
    if (filter_count >= MAX_FILTER)
        return -1;
    recv_filter[filter_count].can_id = id;
    recv_filter[filter_count].can_mask = mask;
    printf("Filter #%d: id=0x%08x mask=0x%08x\n", filter_count, id, mask);
    filter_count++;
    return 0;
}
static void cleanup(void)
{
    int ret;
    if (verbose)
        printf("Cleaning up...\n");
    if (s >= 0) {
        ret = close(s);
        s = -1;
        if (ret) {
             fprintf(stderr, "close: %s\n", strerror(-ret));
        exit(EXIT_SUCCESS);
}
static void cleanup_and_exit(int sig)
    if (verbose)
        printf("Signal %d received\n", sig);
    cleanup();
    exit(0);
}
static void rt_task(void)
    int i, ret, count = 0;
    struct can_frame frame;
    struct sockaddr_can addr;
    socklen_t addrlen = sizeof(addr);
    struct msghdr msg;
    struct iovec iov;
    nanosecs_abs_t timestamp, timestamp_prev = 0;
    if (with_timestamp) {
        msg.msg_iov = &iov;
        msg.msg_iovlen = 1;
```

```
msg.msg_name = (void *)&addr;
          msg.msg_namelen = sizeof(struct sockaddr_can);
msg.msg_control = (void *)&timestamp;
          msg.msg_controllen = sizeof(nanosecs_abs_t);
     while (1) {
           if (with_timestamp) {
                iov.iov_base = (void *)&frame;
iov.iov_len = sizeof(can_frame_t);
                ret = recvmsg(s, &msg, 0);
          } else
                ret = recvfrom(s, (void *)&frame, sizeof(can_frame_t), 0,
                                             (struct sockaddr *)&addr, &addrlen);
          if (ret < 0) {</pre>
                switch (ret) {
                case -ETIMEDOUT:
                    if (verbose)
                         printf("recv: timed out");
                     continue;
                case -EBADF:
                    if (verbose)
                         printf("recv: aborted because socket was closed");
                     break;
                default:
                    fprintf(stderr, "recv: %s\n", strerror(-ret));
                }
                break;
          }
          if (print && (count % print) == 0) {
   printf("#%d: (%d) ", count, addr.can_ifindex);
                if (with_timestamp && msg.msg_controllen) {
                      if (timestamp_rel) {
                     printf("%1ldns ", (long long)(timestamp - timestamp_prev));
   timestamp_prev = timestamp;
                     } else
                          printf("%lldns ", (long long)timestamp);
                if (frame.can_id & CAN_ERR_FLAG)
                printf("!0x%08x!", frame.can_id & CAN_ERR_MASK);
else if (frame.can_id & CAN_EFF_FLAG)
                    printf("<0x%08x>", frame.can_id & CAN_EFF_MASK);
                     printf("<0x%03x>", frame.can_id & CAN_SFF_MASK);
                printf(" [%d]", frame.can_dlc);
                if (!(frame.can_id & CAN_RTR_FLAG))
    for (i = 0; i < frame.can_dlc; i++) {
        printf(" %02x", frame.data[i]);
}</pre>
                if (frame.can_id & CAN_ERR_FLAG) {
   printf(" ERROR ");
                     if (frame.can_id & CAN_ERR_BUSOFF)
                          printf("bus-off"):
                     if (frame.can_id & CAN_ERR_CRTL)
                          printf("controller problem");
                } else if (frame.can_id & CAN_RTR_FLAG)
                     printf(" remote request");
                printf("\n");
          count++;
     }
}
int main(int argc, char **argv)
     int opt. ret:
     u_int32_t id, mask;
     u_int32_t err_mask = 0;
     struct can_ifreq ifr;
     char *ptr;
     char name[32];
     struct option long_options[] = {
             "help", no_argument, 0, 'h' },
          { "help", no_argument, 0, 'n' },
{ "verbose", no_argument, 0, 'v'},
{ "filter", required_argument, 0, 'f'},
{ "error", required_argument, 0, 'e'},
{ "timeout", required_argument, 0, 't'},
{ "timestamp", no_argument, 0, 'T'},
{ "timestamp-rel", no_argument, 0, 'R'},
           { 0, 0, 0, 0},
     };
     signal(SIGTERM, cleanup_and_exit);
     signal(SIGINT, cleanup_and_exit);
```

9.8 rtcanrecv.c 607

```
while ((opt = getopt_long(argc, argv, "hve:f:t:p:RT"
                           long_options, NULL)) != -1) {
    switch (opt) {
    case 'h':
        print_usage(argv[0]);
        exit(0);
    case 'p':
        print = strtoul(optarg, NULL, 0);
        break:
    case 'v':
        verbose = 1;
        break;
    case 'e':
        err_mask = strtoul(optarg, NULL, 0);
        break;
    case 'f':
        ptr = optarg;
        while (1) {
            id = strtoul(ptr, NULL, 0);
ptr = strchr(ptr, ':');
            if (!ptr) {
                fprintf(stderr, "filter must be applied in the form id:mask[:id:mask]...\n");
                exit(1);
            }
            ptr++;
            mask = strtoul(ptr, NULL, 0);
ptr = strchr(ptr, ':');
            add_filter(id, mask);
            if (!ptr)
                break;
            ptr++;
    case 't':
        timeout = (nanosecs_rel_t)strtoul(optarg, NULL, 0) * 1000000;
        break:
    case 'R':
       timestamp_rel = 1;
        with_timestamp = 1;
        break;
        fprintf(stderr, "Unknown option %c\n", opt);
}
ret = socket(PF_CAN, SOCK_RAW, CAN_RAW);
    fprintf(stderr, "socket: %s\n", strerror(-ret));
s = ret:
if (argv[optind] == NULL) {
    if (verbose)
        printf("interface all\n");
    ifr.ifr_ifindex = 0;
} else {
    if (verbose)
        printf("interface %s\n", argv[optind]);
    strncpy(ifr.ifr_name, argv[optind], IFNAMSIZ);
    if (verbose)
        printf("s=%d, ifr_name=%s\n", s, ifr.ifr_name);
    ret = ioctl(s, SIOCGIFINDEX, &ifr);
        fprintf(stderr, "ioctl GET_IFINDEX: %s\n", strerror(-ret));
        goto failure;
    3
}
if (err_mask) {
    ret = setsockopt(s, SOL_CAN_RAW, CAN_RAW_ERR_FILTER,
                            &err_mask, sizeof(err_mask));
    if (ret < 0) {</pre>
        fprintf(stderr, "setsockopt: %s\n", strerror(-ret));
```

```
goto failure;
       if (verbose)
           printf("Using err_mask=%#x\n", err_mask);
   }
   if (filter_count) {
       ret = setsockopt(s, SOL_CAN_RAW, CAN_RAW_FILTER,
                                &recv_filter, filter_count *
                                 sizeof(struct can_filter));
       if (ret < 0) {</pre>
           fprintf(stderr, "setsockopt: %s\n", strerror(-ret));
           goto failure;
   }
   recv_addr.can_family = AF_CAN;
   recv_addr.can_ifindex = ifr.ifr_ifindex;
   ret = bind(s, (struct sockaddr *)&recv_addr,
                     sizeof(struct sockaddr_can));
   if (ret < 0) {</pre>
       fprintf(stderr, "bind: %s\n", strerror(-ret));
       goto failure;
   }
   if (timeout) {
       if (verbose)
           printf("Timeout: %lld ns\n", (long long)timeout);
       ret = ioctl(s, RTCAN_RTIOC_RCV_TIMEOUT, &timeout);
       if (ret) {
           fprintf(stderr, "ioctl RCV_TIMEOUT: %s\n", strerror(-ret));
           goto failure;
   }
   if (with_timestamp) {
    ret = ioctl(s, RTCAN_RTIOC_TAKE_TIMESTAMP,
    RTCAN_TAKE_TIMESTAMPS);
       if (ret) {
           fprintf(stderr, "ioctl TAKE_TIMESTAMP: %s\n", strerror(-ret));
           goto failure;
       }
   }
   snprintf(name, sizeof(name), "rtcanrecv-%d", getpid());
   ret = rt_task_shadow(&rt_task_desc, name, 0, 0);
   if (ret) {
       fprintf(stderr, "rt_task_shadow: %s\n", strerror(-ret));
       goto failure:
   rt_task();
   /* never returns */
failure:
   cleanup();
   return -1;
```

9.9 rtcansend.c

```
#include <stdio.h>
#include <stdlib.h>
#include <signal.h>
#include <unistd.h>
#include <time.h>
#include <errno.h>
#include <getopt.h>
#include <alchemy/task.h>
#include <alchemy/timer.h>
#include <rtdm/can.h>
extern int optind, opterr, optopt;
static void print_usage(char *prg)
    fprintf(stderr,
             "Usage: %s <can-interface> [Options] <can-msg>\n"
            "<can-msg> can consist of up to 8 bytes given as a space separated list\n"
             "Options:\n"
             " -i, --identifier=ID CAN Identifier (default = 1)\n"
```

9.9 rtcansend.c 609

```
" -r --rtr
                                       send remote request\n"
             " -e --extended
" -l --loop=COUNT
                                       send extended frame\n"
                                       send message COUNT times\n"
             " -c, --count
                                       message count in data[0-3]\n''
             " -d, --delay=MS
                                       delay in ms (default = 1ms)\n"
             " -s, --send
                                       use send instead of sendto\n"
             " -t, --timeout=MS
                                       timeout in ms\n"
             " -L, --loopback=0|1
                                       switch local loopback off or on \ensuremath{\text{n}}\xspace
             " -v, --verbose
                                       be verbose\n"
                                       print every MODULO message\n"
this help\n",
             " -p, --print=MODULO
             " -h, --help
             prg);
}
RT_TASK rt_task_desc;
static int s=-1, dlc=0, rtr=0, extended=0, verbose=0, loops=1;
static SRTIME delay=1000000;
static int count=0, print=1, use_send=0, loopback=-1;
static nanosecs_rel_t timeout = 0;
static struct can_frame frame;
static struct sockaddr_can to_addr;
static void cleanup(void)
    int ret:
    if (verbose)
         printf("Cleaning up...\n");
    usleep(100000);
    if (s >= 0) {
    ret = close(s);
         s = -1;
         if (ret) {
             fprintf(stderr, "close: %s\n", strerror(-ret));
         exit(EXIT_SUCCESS);
    }
}
static void cleanup_and_exit(int sig)
    if (verbose)
        printf("Signal %d received\n", sig);
    cleanup();
    exit(0);
}
static void rt_task(void)
    int i, j, ret;
    for (i = 0; i < loops; i++) {</pre>
         rt_task_sleep(rt_timer_ns2ticks(delay));
         if (count)
         memcpy(&frame.data[0], &i, sizeof(i));
/* Note: sendto avoids the definiton of a receive filter list */
         if (use_send)
             ret = send(s, (void *)&frame, sizeof(can_frame_t), 0);
             ret = sendto(s, (void *)&frame, sizeof(can_frame_t), 0,
                                   (struct sockaddr *)&to_addr, sizeof(to_addr));
         if (ret < 0) {</pre>
             switch (ret) {
             case -ETIMEDOUT:
                 if (verbose)
                     printf("send(to): timed out");
                 break:
             case -EBADF:
                 if (verbose)
                      printf("send(to): aborted because socket was closed");
                 break;
             default:
                 fprintf(stderr, "send: %s\n", strerror(-ret));\\
                 break;
             i = loops;
                                 /* abort */
             break;
         if (verbose && (i % print) == 0) {
             if (frame.can_id & CAN_EFF_FLAG)
    printf("<0x%08x>", frame.can_id & CAN_EFF_MASK);
             else
```

```
printf("<0x%03x>", frame.can_id & CAN_SFF_MASK);
                  printf(" [%d]", frame.can_dlc);
for (j = 0; j < frame.can_dlc; j++) {
    printf(" %02x", frame.data[j]);</pre>
                  printf("\n");
           }
      }
}
int main(int argc, char **argv)
      int i, opt, ret;
struct can_ifreq ifr;
      char name[32];
      struct option long_options[] = {
    { "help", no_argument, 0, 'h' },
    { "identifier", required_argument, 0, 'i'},
            { "identifier", required_argument, 0, '
{ "rtr", no_argument, 0, 'r'},
{ "extended", no_argument, 0, 'e'},
{ "verbose", no_argument, 0, 'v'},
{ "count", no_argument, 0, 'c'},
{ "print", required_argument, 0, 'p'},
{ "delay", required_argument, 0, 'd'},
{ "send", no_argument, 0, 's'},
{ "timeout", required_argument, 0, 'd';}
            { "timeout", required_argument, 0, 't'},
{ "loopback", required_argument, 0, 'L'},
{ 0, 0, 0, 0},
      }:
      signal(SIGTERM, cleanup_and_exit);
      signal(SIGINT, cleanup_and_exit);
      frame.can id = 1:
      while ((opt = getopt_long(argc, argv, "hvi:l:red:t:cp:sL:",
                                             long_options, NULL)) != -1) {
            switch (opt) {
            case 'h':
                  print_usage(argv[0]);
                  exit(0):
            case 'p':
                  print = strtoul(optarg, NULL, 0);
            case 'v':
                  verbose = 1;
                  break:
            case 'c':
                  count = 1;
                  break;
            case '1':
                  loops = strtoul(optarg, NULL, 0);
            case 'i':
                  frame.can_id = strtoul(optarg, NULL, 0);
                  break:
            case 'r':
                 rtr = 1;
                  break;
            case 'e':
                  extended = 1;
                  break;
            case 'd':
                  delay = strtoul(optarg, NULL, 0) * 1000000LL;
                  break:
            case 's':
                  use_send = 1;
                  break;
            case 't':
                 timeout = strtoul(optarg, NULL, 0) * 1000000LL;
                  break;
                  loopback = strtoul(optarg, NULL, 0);
                  break:
```

9.9 rtcansend.c 611

```
default:
        fprintf(stderr, "Unknown option %c\n", opt);
}
if (optind == argc) {
    print_usage(argv[0]);
    exit(0);
if (argv[optind] == NULL) {
    fprintf(stderr, "No Interface supplied\n");
if (verbose)
    printf("interface %s\n", argv[optind]);
ret = socket(PF_CAN, SOCK_RAW, CAN_RAW);
    fprintf(stderr, "socket: %s\n", strerror(-ret));
    return -1;
s = ret;
if (loopback >= 0) {
    ret = setsockopt(s, SOL_CAN_RAW, CAN_RAW_LOOPBACK,
                             &loopback, sizeof(loopback));
    if (ret < 0) {</pre>
        fprintf(stderr, "setsockopt: %s\n", strerror(-ret));
        goto failure;
    if (verbose)
        printf("Using loopback=%d\n", loopback);
}
strncpy(ifr.ifr_name, argv[optind], IFNAMSIZ);
if (verbose)
   printf("s=%d, ifr_name=%s\n", s, ifr.ifr_name);
ret = ioctl(s, SIOCGIFINDEX, &ifr);
if (ret < 0) {</pre>
    fprintf(stderr, "ioctl: %s\n", strerror(-ret));
memset(&to_addr, 0, sizeof(to_addr));
to_addr.can_ifindex = ifr.ifr_ifindex;
to_addr.can_family = AF_CAN;
if (use_send) {
    /* Suppress definiton of a default receive filter list */
    ret = setsockopt(s, SOL_CAN_RAW, CAN_RAW_FILTER, NULL, 0);
    if (ret < 0) {</pre>
        fprintf(stderr, "setsockopt: %s\n", strerror(-ret));
        goto failure;
    ret = bind(s, (struct sockaddr *)&to_addr, sizeof(to_addr));
    if (ret < 0) {</pre>
        fprintf(stderr, "bind: %s\n", strerror(-ret));
        goto failure;
}
if (count)
    frame.can_dlc = sizeof(int);
else {
    for (i = optind + 1; i < argc; i++) {</pre>
        frame.data[dlc] = strtoul(argv[i], NULL, 0);
        if( dlc == 8 )
            break;
    frame.can_dlc = dlc;
if (rtr)
    frame.can_id |= CAN_RTR_FLAG;
if (extended)
    frame.can_id |= CAN_EFF_FLAG;
if (timeout) {
    if (verbose)
    printf("Timeout: %1ld ns\n", (long long)timeout);
ret = ioctl(s, RTCAN_RTIOC_SND_TIMEOUT, &timeout);
```

```
if (ret) {
          fprintf(stderr, "ioctl SND_TIMEOUT: %s\n", strerror(-ret));
          goto failure;
    }
}
snprintf(name, sizeof(name), "rtcansend-%d", getpid());
ret = rt_task_shadow(&rt_task_desc, name, 1, 0);
if (ret) {
    fprintf(stderr, "rt_task_shadow: %s\n", strerror(-ret));
    goto failure;
}
rt_task();
cleanup();
return 0;
failure:
    cleanup();
return -1;
}
```

9.10 xddp-echo.c

```
* Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.
  * This library is free software; you can redistribute it and/or
         modify it under the terms of the GNU Lesser General Public
          License as published by the Free Software Foundation; either
         version 2 of the License, or (at your option) any later version.
  * This library is distributed in the hope that it will be useful,
  * but WITHOUT ANY WARRANTY; without even the implied warranty of
    * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
  * Lesser General Public License for more details.
 \ensuremath{^{\star}} You should have received a copy of the GNU Lesser General Public
  * License along with this library; if not, write to the Free Software
         Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.
         XDDP-based RT/NRT threads communication demo.
  * Real-time Xenomai threads and regular Linux threads may want to
          exchange data in a way that does not require the former to leave
          the real-time domain (i.e. secondary mode). Message pipes - as % \left( 1\right) =\left( 1\right) \left( 1\right) =\left( 1\right) \left( 
          implemented by the RTDM-based XDDP protocol - are provided for this
         purpose.
          On the Linux domain side, pseudo-device files named /dev/rtp<minor>
          give regular POSIX threads access to non real-time communication % \left( 1\right) =\left( 1\right) \left( 1\right) \left(
          endpoints, via the standard character-based I/O interface. On the
         Xenomai domain side, sockets may be bound to XDDP ports, which act as proxies to send and receive data to/from the associated \,
          pseudo-device files. Ports and pseudo-device minor numbers are
          paired, meaning that e.g. port 7 will proxy the traffic for
            /dev/rtp7. Therefore, port numbers may range from 0 to
          CONFIG_XENO_OPT_PIPE_NRDEV - 1.
          All data sent through a bound/connected XDDP socket via sendto(2) or
          write(2) will be passed to the peer endpoint in the Linux domain,
          and made available for reading via the standard read(2) system
          call. Conversely, all data sent using write(2) through the non
          real-time endpoint will be conveyed to the real-time socket
          endpoint, and made available to the recvfrom(2) or read(2) system
          Both threads can use the bi-directional data path to send and
          receive datagrams in a FIFO manner, as illustrated by the simple
          echoing process implemented by this program.
          => get socket
                                     bind socket to port 0
                                  write traffic to NRT domain via sendto()
                    => read traffic from NRT domain via recvfrom() <--|
          regular_thread-----
                   => open /dev/rtp0
                  => read traffic from RT domain via read()
                   => echo traffic back to RT domain via write()
```

9.10 xddp-echo.c 613

```
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <signal.h>
#include <string.h>
#include <malloc.h>
#include <pthread.h>
#include <fcntl.h>
#include <errno.h>
#include <rtdm/ipc.h>
pthread_t rt, nrt;
#define XDDP_PORT 0
                           /* [0..CONFIG-XENO_OPT_PIPE_NRDEV - 1] */
static const char *msg[] = {
          "Surfing With The Alien",
"Lords of Karma",
          "Banana Mango",
"Psycho Monkey",
          "Luminous Flesh Giants",
          "Moroccan Sunset",
          "Satch Boogie",
          "Flying In A Blue Dream",
          "Ride",
          "Summer Song",
          "Speed Of Light",
"Crystal Planet",
          "Raspberry Jam Delta-V",
"Champagne?",
          "Clouds Race Across The Sky",
          "Engines Of Creation"
};
static void fail(const char *reason)
{
          perror(reason);
          exit(EXIT_FAILURE);
}
static void *realtime_thread(void *arg)
          struct sockaddr_ipc saddr;
          int ret, s, n = 0, len;
          struct timespec ts;
          size_t poolsz;
          char buf[128];
          / * Get a datagram socket to bind to the RT endpoint. Each * endpoint is represented by a port number within the XDDP
           * protocol namespace.
          s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_XDDP);
          if (s < 0) {
                  perror("socket");
                   exit(EXIT_FAILURE);
          }
          * Set a local 16k pool for the RT endpoint. Memory needed to
* convey datagrams will be pulled from this pool, instead of
           * Xenomai's system pool.
          poolsz = 16384; /* bytes */
ret = setsockopt(s, SOL_XDDP, XDDP_POOLSZ,
                              &poolsz, sizeof(poolsz));
          if (ret)
                   fail("setsockopt");
          * Bind the socket to the port, to setup a proxy to channel * traffic to/from the Linux domain.
           * saddr.sipc_port specifies the port number to use.
          memset(&saddr, 0, sizeof(saddr));
          saddr.sipc_family = AF_RTIPC;
saddr.sipc_port = XDDP_PORT;
          ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
          if (ret)
                   fail("bind");
          for (;;) {
                   len = strlen(msg[n]);
```

```
* Send a datagram to the NRT endpoint via the proxy.
                   * We may pass a NULL destination address, since a
                   * bound socket is assigned a default destination
                   * address matching the binding address (unless
* connect(2) was issued before bind(2), in which case
                   * the former would prevail).
                  ret = sendto(s, msg[n], len, 0, NULL, 0);
                  if (ret != len)
                           fail("sendto");
                  printf("%s: sent %d bytes, \"%.*s\"\n",
                          __FUNCTION__, ret, ret, msg[n]);
                  /* Read back packets echoed by the regular thread */
                  ret = recvfrom(s, buf, sizeof(buf), 0, NULL, 0);
                  if (ret <= 0)</pre>
                           fail("recvfrom");
                  printf(" \Rightarrow \"\%.*s" echoed by peer\n", ret, buf);
                  n = (n + 1) % (sizeof(msg) / sizeof(msg[0]));
                  /*
    * We run in full real-time mode (i.e. primary mode),
                   * so we have to let the system breathe between two
                   \ast iterations.
                  ts.tv_sec = 0;
                  ts.tv_nsec = 5000000000; /* 500 ms */
clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
         }
         return NULL;
}
static void *regular_thread(void *arg)
{
         char buf[128], *devname;
         int fd, ret;
         if (asprintf(&devname, "/dev/rtp%d", XDDP_PORT) < 0)
    fail("asprintf");</pre>
         fd = open(devname, O_RDWR);
         free(devname);
         if (fd < 0)</pre>
                  fail("open");
         for (;;) {
                  /* Get the next message from realtime_thread. */
                  ret = read(fd, buf, sizeof(buf));
                  if (ret <= 0)</pre>
                           fail("read");
                  /* Echo the message back to realtime_thread. */
                  ret = write(fd, buf, ret);
                  if (ret <= 0)</pre>
                           fail("write");
         }
         return NULL:
}
int main(int argc, char **argv)
         struct sched_param rtparam = { .sched_priority = 42 };
         pthread_attr_t rtattr, regattr;
         sigset t set:
         int sig:
         sigemptyset(&set);
         sigaddset(&set, SIGINT);
         sigaddset(&set, SIGTERM);
         sigaddset(&set. SIGHUP):
         pthread_sigmask(SIG_BLOCK, &set, NULL);
         pthread_attr_init(&rtattr);
         pthread_attr_setdetachstate(&rtattr, PTHREAD_CREATE_JOINABLE);
         pthread_attr_setinheritsched(&rtattr, PTHREAD_EXPLICIT_SCHED);
pthread_attr_setschedpolicy(&rtattr, SCHED_FIF0);
pthread_attr_setschedparam(&rtattr, &rtparam);
         errno = pthread_create(&rt, &rtattr, &realtime_thread, NULL);
         if (errno)
                  fail("pthread_create");
         pthread_attr_init(&regattr);
```

9.11 xddp-label.c 615

9.11 xddp-label.c

```
/*
    * Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.
 * This library is free software; you can redistribute it and/or
 * modify it under the terms of the GNU Lesser General Public
  License as published by the Free Software Foundation; either
  version 2 of the License, or (at your option) any later version.
 * This library is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of

* MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
 * Lesser General Public License for more details.
 * You should have received a copy of the GNU Lesser General Public
 * License along with this library; if not, write to the Free Software
  Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.
 * XDDP-based RT/NRT threads communication demo.
 * Real-time Xenomai threads and regular Linux threads may want to
   exchange data in a way that does not require the former to leave
   the real-time domain (i.e. secondary mode). Message pipes – as \,
   implemented by the RTDM-based XDDP protocol - are provided for this
 * On the Linux domain side, pseudo-device files named /dev/rtp<minor>
  give regular POSIX threads access to non real-time communication
   endpoints, via the standard character-based I/O interface. On the
   Xenomai domain side, sockets may be bound to XDDP ports, which act
   as proxies to send and receive data to/from the associated
   pseudo-device files. Ports and pseudo-device minor numbers are
   paired, meaning that e.g. port 7 will proxy the traffic for
   /dev/rtp7. Therefore, port numbers may range from 0 to
   CONFIG_XENO_OPT_PIPE_NRDEV - 1.
   All data sent through a bound/connected XDDP socket via sendto(2) or
   write(2) will be passed to the peer endpoint in the Linux domain,
   and made available for reading via the standard read(2) system
   call. Conversely, all data sent using write(2) through the non
   real-time endpoint will be conveyed to the real-time socket
   endpoint, and made available to the \operatorname{recvfrom}(2) or \operatorname{read}(2) system
   ASCII labels can be attached to bound ports, in order to connect
   sockets to them in a more descriptive way than using plain numeric
   port values.
  The example code below illustrates the following process:
   => get socket
    => bind socket to port "xddp-demo
    => read traffic from NRT domain via recvfrom()
   realtime_thread2-----
         connect socket to port "xddp-demo"
        write traffic to NRT domain via sendto()
   regular_thread-----
     => open /proc/xenomai/registry/rtipc/xddp/xddp-demo |
    => read traffic from RT domain via read()
    => mirror traffic to RT domain via write()
```

```
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <signal.h>
#include <string.h>
#include <malloc.h>
#include <pthread.h>
#include <fcntl.h>
#include <errno.h>
#include <rtdm/ipc.h>
pthread_t rt1, rt2, nrt;
#define XDDP_PORT_LABEL "xddp-demo"
static const char *msg[] = {
          "Surfing With The Alien",
         "Lords of Karma",
         "Banana Mango",
"Psycho Monkey",
         "Luminous Flesh Giants",
          "Moroccan Sunset",
          "Satch Boogie"
         "Flying In A Blue Dream",
          "Summer Song",
         "Speed Of Light",
         "Crystal Planet"
         "Raspberry Jam Delta-V",
"Champagne?",
"Clouds Race Across The Sky",
         "Engines Of Creation"
};
static void fail(const char *reason)
{
         perror(reason);
         exit(EXIT_FAILURE);
}
static void *realtime_thread1(void *arg)
         struct rtipc_port_label plabel;
         struct sockaddr_ipc saddr;
         char buf[128];
         int ret, s;
          * Get a datagram socket to bind to the RT endpoint. Each
          * endpoint is represented by a port number within the XDDP
          * protocol namespace.
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_XDDP);
         if (s < 0) {
                  perror("socket");
                   exit(EXIT_FAILURE);
          \ensuremath{^{*}} Set a port label. This name will be registered when
          * binding, in addition to the port number (if given).
         strcpy(plabel.label, XDDP_PORT_LABEL);
ret = setsockopt(s, SOL_XDDP, XDDP_LABEL
                             &plabel, sizeof(plabel));
         if (ret)
     fail("setsockopt");
          * Bind the socket to the port, to setup a proxy to channel
          \mbox{\ensuremath{\mbox{*}}} traffic to/from the Linux domain. Assign that port a label,
           \ensuremath{^{\star}} so that peers may use a descriptive information to locate
          \mbox{\ensuremath{^{\ast}}} it. For instance, the pseudo-device matching our RT
           * endpoint will appear as
             /proc/xenomai/registry/rtipc/xddp/<XDDP_PORT_LABEL> in the
          * Linux domain, once the socket is bound.
          ^{\ast} saddr.sipc_port specifies the port number to use. If -1 is ^{\ast} passed, the XDDP driver will auto-select an idle port.
         memset(&saddr, 0, sizeof(saddr));
         saddr.sipc_family = AF_RTIPC;
saddr.sipc_port = -1;
         ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
         if (ret)
                   fail("bind");
```

9.11 xddp-label.c 617

```
for (;;) {
                  /* Get packets relayed by the regular thread */
                  ret = recvfrom(s, buf, sizeof(buf), 0, NULL, 0);
                  if (ret <= 0)</pre>
                           fail("recvfrom");
                  printf("%s: \"%.*s" relayed by peer\n", __FUNCTION__, ret, buf);
         return NULL;
}
static void *realtime_thread2(void *arg)
         struct rtipc_port_label plabel;
         struct sockaddr_ipc saddr;
int ret, s, n = 0, len;
         struct timespec ts;
         struct timeval tv;
         socklen_t addrlen;
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_XDDP);
         if (s < 0) {
                  perror("socket");
                  exit(EXIT_FAILURE);
         }
          \ensuremath{^{*}} Set the socket timeout; it will apply when attempting to
          * connect to a labeled port, and to recvfrom() calls. The * following setup tells the XDDP driver to wait for at most
          * one second until a socket is bound to a port using the same
          * label, or return with a timeout error.
         tv.tv_sec = 1;
         tv.tv_usec = 0;
         ret = setsockopt(s, SOL_SOCKET, SO_RCVTIMEO,
                            &tv, sizeof(tv));
         if (ret)
                  fail("setsockopt");
          * Set a port label. This name will be used to find the peer
          * when connecting, instead of the port number.
         strcpy(plabel.label, XDDP_PORT_LABEL);
         ret = setsockopt(s, SOL_XDDP, XDDP_LABEL,
                            &plabel, sizeof(plabel));
         if (ret)
                  fail("setsockopt");
         memset(&saddr, 0, sizeof(saddr));
         saddr.sipc_family = AF_RTIPC;
         ret = connect(s, (struct sockaddr *)&saddr, sizeof(saddr));
         if (ret)
                  fail("connect");
         /*
 * We succeeded in making the port our default destination
 * address by using its label, but we don't know its actual
 * port number yet. Use getpeername() to retrieve it.
         addrlen = sizeof(saddr);
         ret = getpeername(s, (struct sockaddr *)&saddr, &addrlen);
         if (ret || addrlen != sizeof(saddr))
                  fail("getpeername");
         printf("%s: NRT peer is reading from /dev/rtp%d\n",
                 __FUNCTION__, saddr.sipc_port);
         for (;;) {
                  len = strlen(msg[n]);
                  /*
* Send a datagram to the NRT endpoint via the proxy.
*** Send a datagram to the NRT endpoint via the proxy.
                   * We may pass a NULL destination address, since the
                   * socket was successfully assigned the proper default
                    * address via connect(2).
                  ret = sendto(s, msg[n], len, 0, NULL, 0);
                  if (ret != len)
                           fail("sendto");
                  printf("%s: sent %d bytes, \"%.*s\"\n",
                           __FUNCTION__, ret, ret, msg[n]);
                  n = (n + 1) \% (sizeof(msg) / sizeof(msg[0]));
```

```
/*
    * We run in full real-time mode (i.e. primary mode),
                    * so we have to let the system breathe between two
                    * iterations.
                   ts.tv_sec = 0;
                   ts.tv_nsec = 500000000; /* 500 ms */
                   clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
         }
         return NULL:
}
static void *regular_thread(void *arg)
         char buf[128], *devname;
         int fd. ret:
         if (asprintf(&devname,
                         "/proc/xenomai/registry/rtipc/xddp/%s",
                         XDDP_PORT_LABEL) < 0)
                   fail("asprintf");
         fd = open(devname, O_RDWR);
         free(devname);
         if (fd < 0)</pre>
                   fail("open");
         for (;;) {
    /* Get the next message from realtime_thread2. */
                   ret = read(fd, buf, sizeof(buf));
                   if (ret <= 0)</pre>
                           fail("read");
                   /* Relay the message to realtime_thread1. */
ret = write(fd, buf, ret);
                   if (ret <= 0)</pre>
                            fail("write");
         return NULL;
}
int main(int argc, char **argv)
{
         struct sched_param rtparam = { .sched_priority = 42 };
         pthread_attr_t rtattr, regattr;
         sigset_t set;
         int sig;
         sigemptyset(&set);
         sigaddset(&set, SIGINT);
         sigaddset(&set, SIGTERM);
         sigaddset(&set, SIGHUP);
pthread_sigmask(SIG_BLOCK, &set, NULL);
         pthread_attr_init(&rtattr);
         pthread_attr_setdetachstate(&rtattr, PTHREAD_CREATE_JOINABLE);
         pthread_attr_setinheritsched(&rtattr, PTHREAD_EXPLICIT_SCHED);
         pthread_attr_setschedpolicy(&rtattr, SCHED_FIFO);
pthread_attr_setschedparam(&rtattr, &rtparam);
         /* Both real-time threads have the same attribute set. */
         errno = pthread_create(&rt1, &rtattr, &realtime_thread1, NULL);
         if (errno)
                   fail("pthread_create");
         errno = pthread_create(&rt2, &rtattr, &realtime_thread2, NULL);
         if (errno)
                   fail("pthread_create");
         pthread_attr_init(&regattr);
         pthread_attr_setdetachstate(&regattr, PTHREAD_CREATE_JOINABLE); pthread_attr_setinheritsched(&regattr, PTHREAD_EXPLICIT_SCHED); pthread_attr_setschedpolicy(&regattr, SCHED_OTHER);
         errno = pthread_create(&nrt, &regattr, &regular_thread, NULL);
         if (errno)
                   fail("pthread_create");
         sigwait(&set, &sig);
         pthread_cancel(rt1);
         pthread_cancel(rt2);
         pthread_cancel(nrt);
         pthread_join(rt1, NULL);
pthread_join(rt2, NULL);
```

9.12 xddp-stream.c 619

```
pthread_join(nrt, NULL);
    return 0;
}
```

9.12 xddp-stream.c

```
/*
 * Copyright (C) 2009 Philippe Gerum <rpm@xenomai.org>.
 * This library is free software; you can redistribute it and/or
   modify it under the terms of the GNU Lesser General Public
   License as published by the Free Software Foundation; either
   version 2 of the License, or (at your option) any later version.
 ^{\star} This library is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
* MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
 * Lesser General Public License for more details.
   You should have received a copy of the GNU Lesser General Public
 * License along with this library; if not, write to the Free Software
   Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.
 * XDDP-based RT/NRT threads communication demo.
 * Real-time Xenomai threads and regular Linux threads may want to
   exchange data in a way that does not require the former to leave
   the real-time domain (i.e. secondary mode). Message pipes - as
   implemented by the RTDM-based XDDP protocol - are provided for this
  purpose.
 * On the Linux domain side, pseudo-device files named /dev/rtp<minor>
   give regular POSIX threads access to non real-time communication
   endpoints, via the standard character-based \ensuremath{\text{I}}/0 interface. On the
   Xenomai domain side, sockets may be bound to XDDP ports, which act
   as proxies to send and receive data to/from the associated
   pseudo-device files. Ports and pseudo-device minor numbers are
   paired, meaning that e.g. port 7 will proxy the traffic for
   /dev/rtp7. Therefore, port numbers may range from 0 to
   CONFIG_XENO_OPT_PIPE_NRDEV - 1.
 * All data sent through a bound/connected XDDP socket via sendto(2) or
   write(2) will be passed to the peer endpoint in the Linux domain,
   and made available for reading via the standard \operatorname{read}(2) system
 * call. Conversely, all data sent using write(2) through the non
 * real-time endpoint will be conveyed to the real-time socket
   endpoint, and made available to the recvfrom(2) or read(2) system
   calls.
 * In addition to sending datagrams, real-time threads may stream data
 st in a byte-oriented mode through the proxy as well. This increases
 * the bandwidth and reduces the overhead, when a lot of data has to
* flow down to the Linux domain, if keeping the message boundaries is
 * not required. The example code below illustrates such use.
 * realtime_thread----->-
    => bind socket to port 0
    => write scattered traffic to NRT domain via sendto()
    => read traffic from NRT domain via recvfrom()
   regular_thread---
    => open /dev/rtp0
    => read traffic from RT domain via read()
    => echo traffic back to RT domain via write()
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <signal.h>
#include <string.h>
#include <malloc.h>
#include <pthread.h>
#include <fcntl.h>
#include <errno.h>
#include <rtdm/ipc.h>
pthread_t rt, nrt;
#define XDDP_PORT 0
                         /* [0..CONFIG-XENO_OPT_PIPE_NRDEV - 1] */
```

```
static const char *msg[] = {
          "Surfing With The Alien",
          "Lords of Karma",
          "Banana Mango",
"Psycho Monkey"
          "Luminous Flesh Giants",
          "Moroccan Sunset",
          "Satch Boogie",
          "Flying In A Blue Dream",
          "Ride",
"Summer Song",
          "Speed Of Light",
          "Crystal Planet"
          "Raspberry Jam Delta-V",
          "Champagne?",
          "Clouds Race Across The Sky",
          "Engines Of Creation"
};
static void fail(const char *reason)
          perror(reason);
         exit(EXIT_FAILURE);
}
static void *realtime_thread(void *arg)
          struct sockaddr_ipc saddr;
         int ret, s, n = 0, len, b; struct timespec ts;
         size_t streamsz;
         char buf[128];
         /*

* Get a datagram socket to bind to the RT endpoint. Each
           * endpoint is represented by a port number within the XDDP
             protocol namespace.
         s = socket(AF_RTIPC, SOCK_DGRAM, IPCPROTO_XDDP);
         if (s < 0) {
                   perror("socket");
                   exit(EXIT_FAILURE);
         3
         /*
    * Tell the XDDP driver that we will use the streaming
           \ensuremath{^{*}} capabilities on this socket. To this end, we have to
           * specify the size of the streaming buffer, as a count of

* bytes. The real-time output will be buffered up to that

* amount, and sent as a single datagram to the NRT endpoint
           * when fully gathered, or when another source port attempts
           * to send data to the same endpoint. Passing a null size
           \ensuremath{^{*}} would disable streaming.
         streamsz = 1024; /* bytes */
ret = setsockopt(s, SOL_XDDP, XDDP_BUFSZ,
                             &streamsz, sizeof(streamsz));
          if (ret)
                   fail("setsockopt");
          * Bind the socket to the port, to setup a proxy to channel * traffic to/from the Linux domain.
           * saddr.sipc_port specifies the port number to use.
         memset(&saddr, 0, sizeof(saddr));
         saddr.sipc_family = AF_RTIPC;
saddr.sipc_port = XDDP_PORT;
         ret = bind(s, (struct sockaddr *)&saddr, sizeof(saddr));
         if (ret)
                   fail("bind");
          for (;;) {
                   len = strlen(msg[n]);
                   /*
* Send a datagram to the NRT endpoint via the proxy.
                    * The output is artificially scattered in separate
                    \mbox{\scriptsize *} one-byte sendings, to illustrate the use of
                    * MSG_MORE.
                   for (b = 0; b < len; b++) {</pre>
                            ret = sendto(s, msg[n] + b, 1, MSG_MORE, NULL, 0);
                             if (ret != 1)
                                      fail("sendto");
                   }
                   printf("%s: sent (scattered) %d-bytes message, \"%.*s\"\n",
```

```
__FUNCTION__, len, len, msg[n]);
                 /* Read back packets echoed by the regular thread */
                 ret = recvfrom(s, buf, sizeof(buf), 0, NULL, 0);
                 if (ret <= 0)
                          fail("recvfrom");
                 printf(" \Rightarrow \"%.*s\" echoed by peer\n", ret, buf);
                 n = (n + 1) % (sizeof(msg) / sizeof(msg[0]));
                  * We run in full real-time mode (i.e. primary mode),
* so we have to let the system breathe between two
                  * iterations.
                 ts.tv_sec = 0;
ts.tv_nsec = 500000000; /* 500 ms */
                 clock_nanosleep(CLOCK_REALTIME, 0, &ts, NULL);
        return NULL;
static void *regular_thread(void *arg)
{
         char buf[128], *devname;
        int fd, ret;
        fd = open(devname, O_RDWR);
         free(devname);
        if (fd < 0)</pre>
                 fail("open");
        for (;;) {
    /* Get the next message from realtime_thread. */
                 ret = read(fd, buf, sizeof(buf));
                 if (ret <= 0)</pre>
                          fail("read");
                 /* Echo the message back to realtime_thread. */
                 ret = write(fd, buf, ret);
                 if (ret <= 0)</pre>
                         fail("write");
        }
        return NULL:
}
int main(int argc, char **argv)
         struct sched_param rtparam = { .sched_priority = 42 };
        pthread_attr_t rtattr, regattr;
         sigset_t set;
         int sig;
         sigemptyset(&set);
         sigaddset(&set, SIGINT);
        sigaddset(&set, SIGTERM);
sigaddset(&set, SIGHUP);
        pthread_sigmask(SIG_BLOCK, &set, NULL);
        pthread_attr_init(&rtattr);
        {\tt pthread\_attr\_setdetachstate(\&rtattr, PTHREAD\_CREATE\_JOINABLE);}
        pthread_attr_setinheritsched(&rtattr, PTHREAD_EXPLICIT_SCHED);
pthread_attr_setschedpolicy(&rtattr, SCHED_FIFO);
        pthread_attr_setschedparam(&rtattr, &rtparam);
         errno = pthread_create(&rt, &rtattr, &realtime_thread, NULL);
        if (errno)
                 fail("pthread_create");
        pthread_attr_init(&regattr);
        pthread_attr_setdetachstate(&regattr, PTHREAD_CREATE_JOINABLE);
        pthread_attr_setinheritsched(&regattr, PTHREAD_EXPLICIT_SCHED);
        pthread_attr_setschedpolicy(&regattr, SCHED_OTHER);
        errno = pthread_create(&nrt, &regattr, &regular_thread, NULL);
        if (errno)
                 fail("pthread_create");
        sigwait(&set, &sig);
        pthread_cancel(rt);
        pthread_cancel(nrt);
        pthread_join(rt, NULL);
```

```
pthread_join(nrt, NULL);
    return 0;
}
```

Index

xntimer_migrate	Synchronous acquisition API, 362
Timer services, 229	a4l_dcaltoraw
	Software calibration API, 341
A4L_RNG_FACTOR	a4l_descriptor, 476
uapi/analogy.h, 574	board_name, 476
a4l_add_subd	driver_name, 476
Subdevice management services, 249	fd, 476
a4l_alloc_subd	idx_read_subd, 477
Subdevice management services, 249	idx_write_subd, 477
a4l_async_read	magic, 477
Asynchronous acquisition API, 339	nb_subd, 477
a4l_async_write	sbdata, 477
Asynchronous acquisition API, 339	sbsize, 477
a4l_buf_commit_absget	a4l_driver, 477
Buffer management services, 252	a4l_dtoraw
a4l_buf_commit_absput	Range / conversion API, 351
Buffer management services, 253	a4l_fill_desc
a4l_buf_commit_get	Descriptor API, 347
Buffer management services, 253	a4l_find_range
a4l_buf_commit_put	Range / conversion API, 352
Buffer management services, 253	a4l_free_irq
a4l_buf_count	Interrupt management services, 259
Buffer management services, 254 a4l_buf_evt	a4l_ftoraw
	Range / conversion API, 352
Buffer management services, 254 a4l_buf_get	a4l_get_bufsize
Buffer management services, 255	Asynchronous acquisition API, 335
a4l_buf_prepare_absget	a4l_get_chan
Buffer management services, 255	Buffer management services, 258
a4l_buf_prepare_absput	a4l_get_chinfo
Buffer management services, 255	Descriptor API, 347
a4l_buf_prepare_get	a4l_get_cmd
Buffer management services, 256	Buffer management services, 258
a4l_buf_prepare_put	a4l_get_irq
Buffer management services, 256	Interrupt management services, 259
a4l_buf_put	a4l_get_rnginfo
Buffer management services, 256	Descriptor API, 347
a4l_channel, 473	a4l_get_softcal_converter
flags, 473	Software calibration API, 341
nb_bits, 473	a4l_get_subd
a4l_channels_desc, 473	Subdevice management services, 249
chans, 474	a4l_get_subdinfo
length, 474	Descriptor API, 348
mode, 474	a4l_get_time
a4l close	Misc services, 262
Descriptor API, 346	a4l_instruction, 478
a4l_cmd_desc, 474	idx subd, 479
data_len, 475	a4l_instruction_list, 479
idx_subd, 475	a4l mark bufrw
a4l_config_subd	Asynchronous acquisition API, 335
_	, ,

a4l_math_mean	Basic Syscall API, 367
Math API, 349	a4l_sys_desc
a4l_math_polyfit	Descriptor Syscall API, 344
	a4l_sys_detach
Math API, 349	— • —
a4l_math_stddev	Attach / detach Syscall API, 370
Math API, 350	a4l_sys_open
a4l_math_stddev_of_mean	Basic Syscall API, 367
Math API, 350	a4l_sys_read
a4l_mmap	Basic Syscall API, 367
Asynchronous acquisition API, 336	a4l_sys_write
a4l_open	Basic Syscall API, 368
Descriptor API, 348	a4l_ultoraw
a4l_poll	Range / conversion API, 355
Asynchronous acquisition API, 336	a4l_unregister_drv
a4l_range, 480	Driver management services, 245
flags, 480	addr
max, 480	udd_memregion, 510
min, 480	Alarm services, 371
	rt_alarm_create, 371
a4l_rawtod	rt_alarm_delete, 372
Range / conversion API, 353	rt_alarm_inquire, 372
a4l_rawtodcal	rt_alarm_start, 373
Software calibration API, 343	rt_alarm_stop, 373
a4l_rawtof	
Range / conversion API, 353	Alchemy API, 405
a4l_rawtoul	Analogy framework, 243
Range / conversion API, 353	Analogy user API, 365
a4l_read_calibration_file	Asynchronous acquisition API, 333, 339
Software calibration API, 343	a4l_async_read, 339
a4l_register_drv	a4l_async_write, 339
Driver management services, 245	a4l_get_bufsize, 335
a4l_request_irq	a4l_mark_bufrw, 335
Interrupt management services, 259	a4l_mmap, <mark>336</mark>
a4l_set_bufsize	a4l_poll, 336
Asynchronous acquisition API, 337	a4l_set_bufsize, 337
	a4l_snd_cancel, 337
a4l_sizeof_chan	a4l_snd_command, 338
Range / conversion API, 354	Asynchronous Procedure Calls, 83
a4l_sizeof_subd	xnapc_alloc, 83
Range / conversion API, 354	xnapc free, 84
a4l_snd_cancel	xnapc_schedule, 84
Asynchronous acquisition API, 337	atomic_t, 482
a4l_snd_command	Attach / detach Syscall API, 369
Asynchronous acquisition API, 338	a4l_sys_attach, 369
a4l_snd_insn	a4l_sys_bufcfg, 369
Synchronous acquisition API, 359	a4l_sys_buildig, 309 a4l_sys_detach, 370
a4l snd insnlist	a4i_sys_detach, 370
Synchronous acquisition API, 359	B PRIO
a4l subdevice, 480	Buffer services, 376
a4l sync dio	BUFP_BUFSZ
Synchronous acquisition API, 363	Real-time IPC, 69
a4l_sync_read	
Synchronous acquisition API, 363	BUFP_LABEL
·	Real-time IPC, 70
a4l_sync_write	Basic Syscall API, 367
Synchronous acquisition API, 364	a4l_sys_close, 367
a4l_sys_attach	a4l_sys_open, 367
Attach / detach Syscall API, 369	a4l_sys_read, 367
a4l_sys_bufcfg	a4l_sys_write, 368
Attach / detach Syscall API, 369	begin
a4l_sys_close	xnvfile_regular_ops, 516

file anamahat ana 504	CAN EDD LOCTADD UNODEO EO
xnvfile_snapshot_ops, 521	CAN_ERR_LOSTARB_UNSPEC, 50
Big dual kernel lock, 24	CAN_MODE, 59
cobalt_atomic_enter, 24	CAN_MODE_SLEEP, 59
cobalt_atomic_leave, 25	CAN_MODE_START, 59
RTDM_EXECUTE_ATOMICALLY, 25	CAN_MODE_STOP, 59
bindAF_RTIPC	CAN_RAW_ERR_FILTER, 50
Real-time IPC, 77	CAN_RAW_FILTER, 51
board_name	CAN RAW LOOPBACK, 51
a4I_descriptor, 476	CAN_RAW_RECV_OWN_MSGS, 52
Buffer descriptor, 86	CAN STATE, 59
xnbufd_copy_from_kmem, 88	CAN STATE ACTIVE, 59
xnbufd_copy_to_kmem, 89	CAN_STATE_ACTIVE, 39 CAN STATE BUS OFF, 60
xnbufd_invalidate, 89	
xnbufd_map_kread, 90	CAN_STATE_BUS_PASSIVE, 60
	CAN_STATE_BUS_WARNING, 60
xnbufd_map_kwrite, 90	CAN_STATE_ERROR_ACTIVE, 59
xnbufd_map_uread, 90	CAN_STATE_ERROR_PASSIVE, 60
xnbufd_map_uwrite, 91	CAN_STATE_ERROR_WARNING, 60
xnbufd_reset, 91	CAN_STATE_SCANNING_BAUDRATE, 60
xnbufd_unmap_kread, 91	CAN STATE SLEEPING, 60
xnbufd_unmap_kwrite, 92	CAN_STATE_STOPPED, 60
xnbufd_unmap_uread, 92	can filter t, 58
xnbufd_unmap_uwrite, 92	can_frame_t, 59
Buffer management services, 251	RTCAN RTIOC RCV TIMEOUT, 52
a4l buf commit absget, 252	
a4l_buf_commit_absput, 253	RTCAN_RTIOC_SND_TIMEOUT, 53
a4l_buf_commit_get, 253	RTCAN_RTIOC_TAKE_TIMESTAMP, 53
a4l_buf_commit_put, 253	SIOCGCANBAUDRATE, 54
	SIOCGCANCTRLMODE, 54
a4l_buf_count, 254	SIOCGCANCUSTOMBITTIME, 54
a4l_buf_evt, 254	SIOCGCANSTATE, 55
a4l_buf_get, 255	SIOCGIFINDEX, 55
a4l_buf_prepare_absget, 255	SIOCSCANBAUDRATE, 56
a4l_buf_prepare_absput, 255	SIOCSCANCTRLMODE, 56
a4l_buf_prepare_get, 256	SIOCSCANCUSTOMBITTIME, 57
a4l_buf_prepare_put, 256	SIOCSCANMODE, 57
a4l_buf_put, 256	·
a4l_get_chan, 258	SOL_CAN_RAW, 58
a4l_get_cmd, 258	CAN_BITTIME_BTR
Buffer services, 375	CAN Devices, 59
B_PRIO, 376	CAN_BITTIME_STD
rt buffer bind, 376	CAN Devices, 59
rt buffer clear, 377	CAN_BITTIME_TYPE
	CAN Devices, 59
rt_buffer_create, 377	CAN_CTRLMODE_3_SAMPLES
rt_buffer_delete, 378	CAN Devices, 50
rt_buffer_inquire, 378	CAN CTRLMODE LISTENONLY
rt_buffer_read, 379	CAN Devices, 50
rt_buffer_read_timed, 379	CAN_CTRLMODE_LOOPBACK
rt_buffer_read_until, 380	
rt_buffer_unbind, 381	CAN Devices, 50
rt buffer write, 381	CAN_ERR_LOSTARB_UNSPEC
rt_buffer_write_timed, 381	CAN Devices, 50
rt_buffer_write_until, 382	CAN_MODE
11_541161_1111165_4111111, 552	CAN Devices, 59
CAN Devices, 40	CAN_MODE_SLEEP
CAN_BITTIME_BTR, 59	CAN Devices, 59
CAN_BITTIME_STD, 59	CAN_MODE_START
CAN BITTIME TYPE, 59	CAN Devices, 59
CAN_CTRLMODE_3_SAMPLES, 50	CAN_MODE_STOP
CAN_CTRLMODE_3_SAMFLES, 50 CAN_CTRLMODE_LISTENONLY, 50	CAN Devices, 59
CAN_CTRLMODE_LOOPBACK, 50	CAN_RAW_ERR_FILTER

OAN D. ' FO	:6: 1
CAN Devices, 50	can_ifindex
CAN_RAW_FILTER	sockaddr_can, 505
CAN Devices, 51	can_ifreq, 486
CAN_RAW_LOOPBACK	can_mask
CAN Devices, 51	can_filter, 485
CAN_RAW_RECV_OWN_MSGS	Channels and ranges, 21
CAN Devices, 52	chans
CAN_STATE	a4l_channels_desc, 474
CAN Devices, 59	Clock Services, 146
CAN_STATE_ACTIVE	rtdm_clock_read, 146
CAN Devices, 59	rtdm_clock_read_monotonic, 146
CAN_STATE_BUS_OFF	Clock services, 94
CAN Devices, 60	xnclock_adjust, 94
CAN_STATE_BUS_PASSIVE	xnclock_deregister, 94
CAN Devices, 60	xnclock_register, 96
CAN_STATE_BUS_WARNING	xnclock_tick, 96
	-
CAN CTATE EDDOR ACTIVE	clock_getres
CAN_STATE_ERROR_ACTIVE	Clocks and timers, 264
CAN Devices, 59	clock_gettime
CAN_STATE_ERROR_PASSIVE	Clocks and timers, 264
CAN Devices, 60	clock_nanosleep
CAN_STATE_ERROR_WARNING	Clocks and timers, 265
CAN Devices, 60	clock_settime
CAN_STATE_SCANNING_BAUDRATE	Clocks and timers, 266
CAN Devices, 60	Clocks and timers, 263
CAN_STATE_SLEEPING	clock_getres, 264
CAN Devices, 60	clock_gettime, 264
CAN STATE STOPPED	clock_nanosleep, 265
CAN Devices, 60	clock_settime, 266
COMPATrt_alarm_create	nanosleep, 266
Transition Kit, 464	timer_create, 268
COMPATrt_event_clear	timer_delete, 269
Transition Kit, 465	timer_getoverrun, 269
COMPATrt_event_create	timer gettime, 270
Transition Kit, 465	timer_settime, 270
COMPAT_rt_event_signal	close
Transition Kit, 466	rtdm_fd_ops, 500
COMPATrt_pipe_create	udd_device, 507
Transition Kit, 466	closeAF_RTIPC
COMPATrt_task_create	Real-time IPC, 78
Transition Kit, 467	Cobalt, 101
COMPATrt_task_set_periodic	Cobalt kernel, 102
Transition Kit, 469	cobalt_atomic_enter
can_bittime, 482	Big dual kernel lock, 24
can_bittime_btr, 483	cobalt_atomic_leave
can_bittime_std, 484	Big dual kernel lock, 25
can_filter, 484	cobalt_vfroot
can_id, 485	Virtual file services, 242
can_mask, 485	Condition variable services, 384
can filter t	rt_cond_bind, 385
CAN Devices, 58	rt_cond_broadcast, 385
can_frame, 485	rt_cond_create, 386
can_id, 486	rt_cond_delete, 386
can frame t	rt_cond_inquire, 387
CAN Devices, 59	rt_cond_signal, 387
can_id	rt_cond_unbind, 388
can_filter, 485	rt_cond_wait, 388
can_frame, 486	rt_cond_wait_timed, 388
oan namo, too	it cond wait tilled, ooo

who are a supply contil and	uteles condesses bondles 140
rt_cond_wait_until, 389	rtdm_sendmsg_handler, 143
Condition variables, 272	rtdm_socket_handler, 145
pthread_cond_broadcast, 273	rtdm_write_handler, 145
pthread_cond_destroy, 273	device_count
pthread_cond_init, 274	rtdm_driver, 498
pthread_cond_signal, 274	device_flags
pthread_cond_timedwait, 276	rtdm_driver, 499
pthread_cond_wait, 276	udd_device, 507
pthread_condattr_destroy, 277	device_subclass
pthread condattr getclock, 278	udd device, 507
pthread_condattr_getpshared, 278	driver
pthread_condattr_init, 279	rtdm_device, 496
pthread_condattr_setclock, 279	Driver API, 244
pthread_condattr_setpshared, 281	Driver management services, 245
connect AF RTIPC	a4l_register_drv, 245
Real-time IPC, 78	a4l_unregister_drv, 245
cpu	Driver programming interface, 120
xnsched, 513	Driver to driver services, 121
curr	rtdm_accept, 122
xnsched, 513	rtdm_bind, 122
data ta	rtdm_close, 123
data_len	rtdm_connect, 124
a4l_cmd_desc, 475	rtdm_getpeername, 124
databuf	rtdm_getsockname, 125
xnvfile_snapshot_iterator, 520	rtdm_getsockopt, 125
date	rtdm_ioctl, 126
rt_timer_info, 494	rtdm_listen, 126
Debugging services, 97	rtdm_open, 127
Descriptor API, 346	rtdm_read, 127
a4l_close, 346	rtdm_read, 127
a4l_fill_desc, 347	—
a4l_get_chinfo, 347	rtdm_recvfrom, 128
a4l_get_rnginfo, 347	rtdm_recvmsg, 129
a4l get subdinfo, 348	rtdm_send, 130
a4l_get_subdiffic, 348	rtdm_sendmsg, 130
Descriptor Syscall API, 344	rtdm_sendto, 131
	rtdm_setsockopt, 131
a4l_sys_desc, 344	rtdm_shutdown, 132
device	rtdm_socket, 132
rtdm_dev_context, 495	rtdm_write, 133
Device Profiles, 134	driver.h
RTIOC_DEVICE_INFO, 136	RTDM CLASS MAGIC, 533
RTIOC_PURGE, 137	RTDM_PROFILE_INFO, 534
Device Registration Services, 138	rtdm_fd_device, 534
RTDM_DEVICE_TYPE_MASK, 139	rtdm_fd_is_user, 534
RTDM_EXCLUSIVE, 139	rtdm_fd_to_private, 535
RTDM_FIXED_MINOR, 139	rtdm private to fd, 535
RTDM_MAX_MINOR, 139	driver name
RTDM_NAMED_DEVICE, 139	—
RTDM_PROTOCOL_DEVICE, 140	a4l_descriptor, 476
rtdm_close_handler, 140	Dynamic memory allocation services, 98
rtdm_dev_register, 140	xnheap_alloc, 99
	xnheap_destroy, 99
rtdm_dev_unregister, 140	xnheap_free, 99
rtdm_get_unmapped_area_handler, 141	xnheap_init, 100
rtdm_ioctl_handler, 141	xnheap_set_name, 100
rtdm_mmap_handler, 142	
rtdm_open_handler, 142	EV_ANY
rtdm_read_handler, 142	Event flag group services, 391
rtdm_recvmsg_handler, 143	EV_PRIO
rtdm_select_handler, 143	Event flag group services, 391

end	rt_heap_create, 401
xnvfile_regular_ops, 516	rt_heap_delete, 402
xnvfile_snapshot_ops, 522	rt_heap_free, 402
endfn	rt_heap_inquire, 404
xnvfile_snapshot_iterator, 520	rt_heap_unbind, 404
Event flag group services, 390	heapsize
EV_ANY, 391	RT_HEAP_INFO, 491
EV_PRIO, 391	htimer
rt_event_bind, 391	xnsched, 513
rt_event_clear, 392	IDDD I ADEI
rt_event_create, 392	IDDP_LABEL
rt_event_delete, 393	Real-time IPC, 70
rt_event_inquire, 393	IDDP_POOLSZ
rt_event_signal, 394	Real-time IPC, 71
rt_event_unbind, 394	IPCPROTO_BUFP
rt_event_wait, 394	Real-time IPC, 76
rt_event_wait_timed, 396	IPCPROTO_IDDP Real-time IPC, 76
rt_event_wait_until, 397	IPCPROTO IPC
Event Services, 171	Real-time IPC, 76
rtdm_event_clear, 171	IPCPROTO XDDP
rtdm_event_destroy, 171	Real-time IPC, 76
rtdm_event_init, 173	idx_read_subd
rtdm_event_pulse, 173	a4I_descriptor, 477
rtdm_event_select, 173	idx subd
rtdm_event_signal, 174	a4l_cmd_desc, 475
rtdm_event_timedwait, 174	a4I_instruction, 479
rtdm_event_wait, 175	idx write subd
t.i	a4l_descriptor, 477
fd	In-kernel arithmetics, 85
a4l_descriptor, 476	xnarch_generic_full_divmod64, 85
fd.h	include/cobalt/kernel/rtdm/analogy/channel_
rtdm_fd_get, 545	range.h, 525
rtdm_fd_lock, 546	include/cobalt/kernel/rtdm/analogy/driver.h, 528
rtdm_fd_put, 546 rtdm_fd_select, 546	include/cobalt/kernel/rtdm/analogy/subdevice.h,
rtdm_fd_select, 546	535
	include/cobalt/kernel/rtdm/driver.h, 529
flags a4l_channel, 473	include/cobalt/kernel/rtdm/fd.h, 544
a4l range, 480	include/cobalt/kernel/rtdm/udd.h, 565
a41_1a11ge, 400	include/rtdm/analogy.h, 568
get	include/rtdm/can.h, 537
xnvfile_lock_ops, 514	include/rtdm/rtdm.h, 551
get_unmapped_area	include/rtdm/serial.h, 554
rtdm_fd_ops, 500	include/rtdm/testing.h, 562
getpeernameAF_RTIPC	include/rtdm/uapi/analogy.h, 569
Real-time IPC, 79	include/rtdm/uapi/can.h, 538
getsockname AF RTIPC	include/rtdm/uapi/ipc.h, 548
Real-time IPC, 79	include/rtdm/uapi/rtdm.h, 552
getsockopt AF RTIPC	include/rtdm/uapi/serial.h, 555
Real-time IPC, 79	include/rtdm/uapi/testing.h, 563
	include/rtdm/uapi/udd.h, 567
H_PRIO	inesting
Heap management services, 399	xnsched, 513
Heap management services, 398	interrupt
H_PRIO, 399	udd_device, 507
rt_heap_alloc, 399	Interrupt management, 105
rt_heap_alloc_timed, 399	xnintr_affinity, 105
rt_heap_alloc_until, 400	xnintr_attach, 105
rt_heap_bind, 400	xnintr_destroy, 106

xnintr_detach, 106	magic
xnintr_disable, 107	a4l_descriptor, 477
xnintr_enable, 107	Math API, 349
xnintr_init, 107	a4l_math_mean, 349
Interrupt Management Services, 182	a4l_math_polyfit, 349
rtdm_irq_disable, 183	a4l_math_stddev, 350
rtdm_irq_enable, 184	a4l math stddev of mean, 350
rtdm_irq_free, 184	max
rtdm_irq_get_arg, 183	a4l_range, 480
rtdm_irq_handler_t, 183	mem_regions
rtdm_irq_request, 185	udd device, 508
Interrupt management services, 259	Message pipe services, 413
a4l_free_irq, 259	•
a4l_get_irq, 259	P_MINOR_AUTO, 414
a4l_request_irq, 259	P_URGENT, 414
ioctl	rt_pipe_bind, 414
	rt_pipe_create, 415
udd_device, 508	rt_pipe_delete, 416
ioctl_nrt	rt_pipe_read, 416
rtdm_fd_ops, 500	rt_pipe_read_timed, 416
ioctl_rt	rt_pipe_read_until, 418
rtdm_fd_ops, 500	rt_pipe_stream, 419
irq	rt_pipe_unbind, 419
udd_device, 508	rt_pipe_write, 420
	Message queue services, 421
label	Q_PRIO, 422
rtdm_device, 496	rt_queue_alloc, 422
rtipc_port_label, 502	rt_queue_bind, 422
len	rt_queue_create, 423
udd_memregion, 510	rt_queue_delete, 424
length	rt_queue_flush, 425
a4l_channels_desc, 474	
Level 0 API, 366	rt_queue_free, 425
Level 1 API, 356	rt_queue_inquire, 425
Level 2 API, 361	rt_queue_read, 426
Iflags	rt_queue_read_timed, 426
xnsched, 513	rt_queue_read_until, 427
lib/analogy/async.c, 576	rt_queue_receive, 428
lib/analogy/calibration.c, 577	rt_queue_receive_timed, 428
lib/analogy/calibration.h, 574	rt_queue_receive_until, 429
lib/analogy/descriptor.c, 578	rt_queue_send, 429
lib/analogy/internal.h, 575	rt_queue_unbind, 430
lib/analogy/range.c, 579	Message queues, 284
lib/analogy/root_leaf.h, 580	mq_close, 285
lib/analogy/sync.c, 581	mq_getattr, 285
lib/analogy/systc.c, 582	mq_notify, 286
- · ·	mq_open, 286
Lightweight key-to-object mapping service, 111	mq_receive, 287
xnmap_create, 111	mq_send, 288
xnmap_delete, 112	mq_setattr, 289
xnmap_enter, 112	mq_timedreceive, 289
xnmap_fetch, 113	
xnmap_fetch_nocheck, 113	mq_timedsend, 290
xnmap_remove, 113	mq_unlink, 291
Locking services, 109	min
splexit, 109	a4l_range, 480
splhigh, 110	minor
spltest, 110	rtdm_device, 496
·	Misc services, 262
macb_dma_desc, 487	a4l_get_time, 262
macb_tx_skb, 488	mmap

rtdm fd one 500	nanaslaan
rtdm_fd_ops, 500	nanosleep
udd_device, 508	Clocks and timers, 266
mode	nb_bits
a4l_channels_desc, 474	a4l_channel, 473
mq_close	nb_subd
Message queues, 285	a4l_descriptor, 477
mq_getattr	next
Message queues, 285	xnvfile_regular_ops, 516
mq_notify	xnvfile_snapshot_ops, 522
Message queues, 286	Non-Real-Time Signalling Services, 186
mq_open	rtdm_nrtsig_destroy, 187
Message queues, 286	rtdm_nrtsig_handler_t, 186
mq_receive	rtdm_nrtsig_init, 187
Message queues, 287	rtdm_nrtsig_pend, 187
mq_send	rtdm_schedule_nrt_work, 187
Message queues, 288	nrdata
mq_setattr	xnvfile_snapshot_iterator, 520
Message queues, 289	_ ' _ '
mq_timedreceive	open
Message queues, 289	rtdm_fd_ops, 500
mg timedsend	udd_device, 509
Message queues, 290	owner
mq_unlink	RT_MUTEX_INFO, 491
Message queues, 291	<u></u>
	P MINOR AUTO
Mutex services, 179, 407	Message pipe services, 414
rt_mutex_acquire, 408	P URGENT
rt_mutex_acquire_timed, 408	Message pipe services, 414
rt_mutex_acquire_until, 409	POSIX interface, 282
rt_mutex_bind, 409	pSOS® emulator, 463
rt_mutex_create, 410	pid
rt_mutex_delete, 410	udd_signotify, 512
rt_mutex_inquire, 411	pos
rt_mutex_release, 411	xnvfile_regular_iterator, 515
rt_mutex_unbind, 412	private
rtdm_mutex_destroy, 179	•
rtdm_mutex_init, 179	xnvfile_regular_iterator, 515
rtdm_mutex_lock, 180	xnvfile_snapshot_iterator, 521
rtdm_mutex_timedlock, 180	Process scheduling, 303
rtdm_mutex_unlock, 181	sched_get_priority_max, 304
Mutual exclusion, 292	sched_get_priority_max_ex, 305
pthread_mutex_destroy, 293	sched_get_priority_min, 305
pthread_mutex_init, 293	sched_get_priority_min_ex, 306
pthread_mutex_lock, 295	sched_getconfig_np, 306
pthread_mutex_timedlock, 296	sched_getscheduler, 307
pthread_mutex_trylock, 296	sched_getscheduler_ex, 308
pthread_mutex_unlock, 297	sched_setconfig_np, 308
pthread mutexattr destroy, 298	sched_setscheduler, 310
pthread_mutexattr_getprotocol, 298	sched_setscheduler_ex, 311
pthread_mutexattr_getpshared, 299	sched_yield, 312
pthread_mutexattr_gettype, 299	profile_info
pthread_mutexattr_init, 300	rtdm_driver, 499
pthread_mutexattr_setprotocol, 300	program_htick_shot
pthread_mutexattr_setpshared, 301	Timer services, 229
pthread_mutexattr_settype, 302	pthread_cond_broadcast
parioda_matexatii_cottype, coz	Condition variables, 273
nanosecs_abs_t	pthread_cond_destroy
RTDM, 62	Condition variables, 273
nanosecs_rel_t	pthread_cond_init
RTDM, 62	Condition variables, 274
-	,

pthread_cond_signal	pthread_setmode_np
Condition variables, 274	Thread management, 322
pthread_cond_timedwait	pthread_setname_np
Condition variables, 276	Thread management, 324
pthread_cond_wait	pthread_setschedparam
Condition variables, 276	Scheduling management, 326
pthread_condattr_destroy	pthread_setschedparam_ex
Condition variables, 277	Scheduling management, 328
pthread_condattr_getclock	pthread_wait_np
Condition variables, 278	Transition Kit, 470
pthread_condattr_getpshared	pthread_yield
Condition variables, 278	Scheduling management, 329
pthread_condattr_init	put
Condition variables, 279	xnvfile_lock_ops, 514
pthread_condattr_setclock	,
Condition variables, 279	Q_PRIO
pthread_condattr_setpshared	Message queue services, 422
Condition variables, 281	
pthread create	RT_ALARM_INFO, 488
Thread management, 320	RT_BUFFER_INFO, 488
pthread_getschedparam	RT_COND_INFO, 489
	RT_EVENT_INFO, 489
Scheduling management, 325	RT_HEAP_INFO, 490
pthread_getschedparam_ex	heapsize, 491
Scheduling management, 326	usablemem, 491
pthread_join	usedmem, 491
Thread management, 321	RT_MUTEX_INFO, 491
pthread_kill	owner, 491
Thread management, 322	RT_QUEUE_INFO, 492
pthread_make_periodic_np	RT_SEM_INFO, 492
Transition Kit, 470	RT_TASK_INFO, 493
pthread_mutex_destroy	RT TIMER INFO
Mutual exclusion, 293	Timer management services, 459
pthread_mutex_init	RTCAN_RTIOC_RCV_TIMEOUT
Mutual exclusion, 293	CAN Devices, 52
pthread_mutex_lock	RTCAN_RTIOC_SND_TIMEOUT
Mutual exclusion, 295	CAN Devices, 53
pthread_mutex_timedlock	RTCAN_RTIOC_TAKE_TIMESTAMP
Mutual exclusion, 296	CAN Devices, 53
pthread_mutex_trylock	RTDM, 61
Mutual exclusion, 296	nanosecs_abs_t, 62
pthread_mutex_unlock	nanosecs rel t, 62
Mutual exclusion, 297	RTDM_TIMEOUT_INFINITE, 62
pthread_mutexattr_destroy	RTDM_TIMEOUT_NONE, 62
Mutual exclusion, 298	RTDM User API, 63
pthread_mutexattr_getprotocol	RTDM_CLASS_MAGIC
Mutual exclusion, 298	driver.h, 533
pthread_mutexattr_getpshared	RTDM_DEVICE_TYPE_MASK
Mutual exclusion, 299	Device Registration Services, 139
pthread_mutexattr_gettype	RTDM EXCLUSIVE
Mutual exclusion, 299	_
pthread_mutexattr_init	Device Registration Services, 139 RTDM EXECUTE ATOMICALLY
Mutual exclusion, 300	
	Big dual kernel lock, 25
pthread_mutexattr_setprotocol	RTDM_FIXED_MINOR
Mutual exclusion, 300	Device Registration Services, 139
pthread_mutexattr_setpshared	RTDM_MAX_MINOR
Mutual exclusion, 301	Device Registration Services, 139
pthread_mutexattr_settype	RTDM_NAMED_DEVICE
Mutual exclusion, 302	Device Registration Services, 139

RTDM PROFILE INFO	getpeername AF RTIPC, 79
driver.h, 534	getsocknameAF_RTIPC, 79
RTDM PROTOCOL DEVICE	getsockoptAF_RTIPC, 79
Device Registration Services, 140	IDDP LABEL, 70
RTDM_SELECTTYPE_EXCEPT	IDDP POOLSZ, 71
	<u> </u>
Synchronisation Services, 161	IPCPROTO_BUFP, 76
RTDM_SELECTTYPE_READ	IPCPROTO_IDDP, 76
Synchronisation Services, 161	IPCPROTO_IPC, 76
RTDM_SELECTTYPE_WRITE	IPCPROTO_XDDP, 76
Synchronisation Services, 161	recvmsgAF_RTIPC, 80
RTDM_TIMEOUT_INFINITE	SO_RCVTIMEO, 72
RTDM, 62	SO_SNDTIMEO, 72
RTDM_TIMEOUT_NONE	sendmsgAF_RTIPC, 80
RTDM, 62	setsockoptAF_RTIPC, 81
RTDM TIMERMODE ABSOLUTE	socket_AF_RTIPC, 81
Timer Services, 156	XDDP BUFSZ, 72
RTDM TIMERMODE REALTIME	XDDP_EVTDOWN, 73
Timer Services, 156	XDDP EVTIN, 73
RTDM TIMERMODE RELATIVE	XDDP EVTNOBUF, 73
Timer Services, 156	XDDP_EVTOUT, 74
RTIOC_DEVICE_INFO	XDDP_LABEL, 74
Device Profiles, 136	XDDP_MONITOR, 74
RTIOC_PURGE	XDDP_POOLSZ, 75
Device Profiles, 137	recvmsgAF_RTIPC
RTSER_RTIOC_BREAK_CTL	Real-time IPC, 80
rtdm/uapi/serial.h, 559	recvmsg_nrt
RTSER RTIOC GET CONFIG	rtdm_fd_ops, 501
rtdm/uapi/serial.h, 559	recvmsg_rt
RTSER_RTIOC_GET_CONTROL	rtdm_fd_ops, 501
rtdm/uapi/serial.h, 559	Registry services, 116
RTSER RTIOC GET STATUS	xnregistry_bind, 116
rtdm/uapi/serial.h, 561	xnregistry_enter, 117
RTSER_RTIOC_SET_CONFIG	xnregistry lookup, 118
rtdm/uapi/serial.h, 561	xnregistry_remove, 118
RTSER RTIOC SET CONTROL	• •
	xnregistry_unlink, 119
rtdm/uapi/serial.h, 562	resched
RTSER_RTIOC_WAIT_EVENT	xnsched, 513
rtdm/uapi/serial.h, 562	rev
Range / conversion API, 351	xnvfile_rev_tag, 519
a4l_dtoraw, 351	rewind
a4l_find_range, 352	xnvfile_regular_ops, 517
a4l_ftoraw, 352	xnvfile_snapshot_ops, 523
a4l_rawtod, 353	rrbtimer
a4I rawtof, 353	xnsched, 513
a4l rawtoul, 353	rt
a4l_sizeof_chan, 354	xnsched, 513
a4l sizeof subd, 354	rt alarm create
a4l ultoraw, 355	Alarm services, 371
read nrt	rt_alarm_delete
_	Alarm services, 372
rtdm_fd_ops, 500	
read_rt	rt_alarm_inquire
rtdm_fd_ops, 500	Alarm services, 372
Real-time IPC, 67	rt_alarm_start
BUFP_BUFSZ, 69	Alarm services, 373
BUFP_LABEL, 70	rt_alarm_stop
bindAF_RTIPC, 77	Alarm services, 373
closeAF_RTIPC, 78	rt_alarm_wait
connectAF_RTIPC, 78	Transition Kit, 471

rt_buffer_bind	rt_event_wait
Buffer services, 376	Event flag group services, 394
rt_buffer_clear	rt_event_wait_timed
Buffer services, 377	Event flag group services, 396
rt_buffer_create	rt_event_wait_until
Buffer services, 377	Event flag group services, 397
rt_buffer_delete	rt_heap_alloc
Buffer services, 378	Heap management services, 399
rt buffer inquire	rt heap alloc timed
Buffer services, 378	Heap management services, 399
rt_buffer_read	rt_heap_alloc_until
Buffer services, 379	Heap management services, 400
rt_buffer_read_timed	rt_heap_bind
Buffer services, 379	Heap management services, 400
rt_buffer_read_until	rt_heap_create
Buffer services, 380	Heap management services, 401
rt_buffer_unbind	rt_heap_delete
Buffer services, 381	Heap management services, 402
rt_buffer_write	rt heap free
Buffer services, 381	Heap management services, 402
rt_buffer_write_timed	rt_heap_inquire
Buffer services, 381	Heap management services, 404
rt_buffer_write_until	rt_heap_unbind
Buffer services, 382	Heap management services, 404
rt_cond_bind	rt_mutex_acquire
Condition variable services, 385	Mutex services, 408
rt_cond_broadcast	rt_mutex_acquire_timed
Condition variable services, 385	Mutex services, 408
rt_cond_create	rt_mutex_acquire_until
Condition variable services, 386	Mutex services, 409
	•
rt_cond_delete Condition variable services, 386	rt_mutex_bind Mutex services, 409
·	
rt_cond_inquire	rt_mutex_create
Condition variable services, 387	Mutex services, 410
rt_cond_signal	rt_mutex_delete
Condition variable services, 387	Mutex services, 410
rt_cond_unbind	rt_mutex_inquire
Condition variable services, 388	Mutex services, 411
rt_cond_wait	rt_mutex_release
Condition variable services, 388	Mutex services, 411
rt_cond_wait_timed	rt_mutex_unbind
Condition variable services, 388	Mutex services, 412
rt_cond_wait_until	rt_pipe_bind
Condition variable services, 389	Message pipe services, 414
rt_event_bind	rt_pipe_create
Event flag group services, 391	Message pipe services, 415
rt_event_clear	rt_pipe_delete
Event flag group services, 392	Message pipe services, 416
rt_event_create	rt_pipe_read
Event flag group services, 392	Message pipe services, 416
rt_event_delete	rt_pipe_read_timed
Event flag group services, 393	Message pipe services, 416
rt_event_inquire	rt_pipe_read_until
Event flag group services, 393	Message pipe services, 418
rt_event_signal	rt_pipe_stream
Event flag group services, 394	Message pipe services, 419
rt_event_unbind	rt_pipe_unbind
Event flag group services, 394	Message pipe services, 419

rt_pipe_write	rt_task_inquire
Message pipe services, 420	Task management services, 441
	rt task join
rt_queue_alloc	
Message queue services, 422	Task management services, 442
rt_queue_bind	rt_task_receive
Message queue services, 422	Task management services, 442
rt_queue_create	rt_task_receive_timed
Message queue services, 423	Task management services, 443
rt_queue_delete	rt_task_receive_until
Message queue services, 424	Task management services, 444
rt_queue_flush	rt_task_reply
Message queue services, 425	Task management services, 444
rt_queue_free	rt_task_resume
Message queue services, 425	Task management services, 445
rt_queue_inquire	rt_task_same
Message queue services, 425	Task management services, 445
	_
rt_queue_read	rt_task_self
Message queue services, 426	Task management services, 446
rt_queue_read_timed	rt_task_send
Message queue services, 426	Task management services, 446
rt_queue_read_until	rt_task_send_timed
Message queue services, 427	Task management services, 446
rt_queue_receive	rt_task_send_until
Message queue services, 428	Task management services, 448
rt_queue_receive_timed	rt_task_set_affinity
Message queue services, 428	Task management services, 448
rt_queue_receive_until	rt_task_set_mode
Message queue services, 429	Task management services, 449
rt_queue_send	rt_task_set_periodic
Message queue services, 429	Task management services, 450
	_
rt_queue_unbind	rt_task_set_priority
Message queue services, 430	Task management services, 451
rt_sem_bind	rt_task_shadow
Semaphore services, 432	Task management services, 451
rt_sem_broadcast	rt_task_sleep
Semaphore services, 433	Task management services, 452
rt_sem_create	rt_task_sleep_until
Semaphore services, 433	Task management services, 453
rt_sem_delete	rt_task_slice
Semaphore services, 434	Task management services, 453
rt_sem_inquire	rt_task_spawn
Semaphore services, 434	Task management services, 454
rt sem p	rt_task_start
Semaphore services, 434	Task management services, 455
· · · · · · · · · · · · · · · · · · ·	
rt_sem_p_timed	rt_task_suspend
Semaphore services, 435	Task management services, 455
rt_sem_p_until	rt_task_unbind
Semaphore services, 435	Task management services, 456
rt_sem_unbind	rt_task_unblock
Semaphore services, 436	Task management services, 456
rt_sem_v	rt_task_wait_period
Semaphore services, 436	Task management services, 457
rt_task_bind	rt_task_yield
Task management services, 439	Task management services, 457
rt_task_create	rt_timer_info, 493
Task management services, 439	date, 494
rt_task_delete	rt_timer_inquire
Task management services, 441	Timer management services, 460

rt_timer_ns2ticks	Event Services, 173
Timer management services, 460	rtdm_event_signal
rt_timer_read	Event Services, 174
Timer management services, 460	rtdm_event_timedwait
rt_timer_spin	Event Services, 174
Timer management services, 461	rtdm_event_wait
rt_timer_ticks2ns	Event Services, 175
Timer management services, 461	rtdm_fd_device
rtdm/uapi/serial.h	driver.h, 534
RTSER RTIOC BREAK CTL, 559	rtdm fd get
RTSER_RTIOC_GET_CONFIG, 559	
RTSER_RTIOC_GET_CONFIG, 559	fd.h, 545
	rtdm_fd_is_user
RTSER_RTIOC_GET_STATUS, 561	driver.h, 534
RTSER_RTIOC_SET_CONFIG, 561	rtdm_fd_lock
RTSER_RTIOC_SET_CONTROL, 562	fd.h, 546
RTSER_RTIOC_WAIT_EVENT, 562	rtdm_fd_ops, 499
rtdm_accept	close, 500
Driver to driver services, 122	get_unmapped_area, 500
rtdm_bind	ioctl_nrt, 500
Driver to driver services, 122	ioctl_rt, 500
rtdm_clock_read	mmap, <u>500</u>
Clock Services, 146	open, 500
rtdm_clock_read_monotonic	read_nrt, 500
Clock Services, 146	read_rt, 500
rtdm_close	recvmsg_nrt, 501
Driver to driver services, 123	recvmsg_rt, 501
rtdm_close_handler	select, 501
Device Registration Services, 140	sendmsg_nrt, 501
rtdm_connect	sendmsg_rt, 501
Driver to driver services, 124	socket, 501
rtdm_copy_from_user	write_nrt, 501
Utility Services, 191	write_rt, 501
rtdm_copy_to_user	rtdm_fd_put
Utility Services, 191	fd.h, 546
rtdm dev context, 494	rtdm_fd_select
device, 495	fd.h, 546
rtdm dev register	rtdm_fd_to_private
Device Registration Services, 140	driver.h, 535
rtdm dev unregister	rtdm_fd_unlock
Device Registration Services, 140	fd.h, 548
rtdm_device, 495	rtdm_for_each_waiter
driver, 496	Synchronisation Services, 161
label, 496	rtdm_for_each_waiter_safe
minor, 496	Synchronisation Services, 163
rtdm_device_info, 497	rtdm free
rtdm_device_inio, 437	Utility Services, 192
device_count, 498	rtdm_get_unmapped_area_handler
device_flags, 499	Device Registration Services, 141
profile_info, 499	rtdm_getpeername
rtdm_event_clear	Driver to driver services, 124
Event Services, 171	rtdm_getsockname
rtdm_event_destroy	Driver to driver services, 125
Event Services, 171	rtdm_getsockopt
rtdm_event_init	Driver to driver services, 125
Event Services, 173	rtdm_in_rt_context
rtdm_event_pulse	Utility Services, 192
Event Services, 173	rtdm_ioctl
rtdm_event_select	Driver to driver services, 126

rtdm_ioctl_handler	rtdm_nrtsig_handler_t
Device Registration Services, 141	Non-Real-Time Signalling Services, 186
rtdm_iomap_to_user	rtdm_nrtsig_init
Utility Services, 192	Non-Real-Time Signalling Services, 187
rtdm_irq_disable	rtdm_nrtsig_pend
Interrupt Management Services, 183	Non-Real-Time Signalling Services, 187
rtdm_irq_enable	rtdm_open
Interrupt Management Services, 184	Driver to driver services, 127
rtdm_irq_free	rtdm_open_handler
Interrupt Management Services, 184	Device Registration Services, 142
rtdm_irq_get_arg	rtdm_printk
Interrupt Management Services, 183	Utility Services, 196
rtdm_irq_handler_t	rtdm_printk_ratelimited
Interrupt Management Services, 183	Utility Services, 196
rtdm_irq_request	rtdm_private_to_fd
Interrupt Management Services, 185	driver.h, 535
rtdm_listen	rtdm_ratelimit
Driver to driver services, 126	Utility Services, 197
rtdm_lock_get	rtdm_read
Spinlock with preemption deactivation, 29	Driver to driver services, 127
rtdm_lock_get_irqsave	rtdm read handler
Spinlock with preemption deactivation, 27	Device Registration Services, 142
	rtdm read user ok
rtdm_lock_init	
Spinlock with preemption deactivation, 29	Utility Services, 197
rtdm_lock_irqrestore	rtdm_recv
Spinlock with preemption deactivation, 29	Driver to driver services, 128
rtdm_lock_irqsave	rtdm_recvfrom
Spinlock with preemption deactivation, 29	Driver to driver services, 128
rtdm_lock_put	rtdm_recvmsg
Spinlock with preemption deactivation, 30	Driver to driver services, 129
rtdm_lock_put_irqrestore	rtdm_recvmsg_handler
Spinlock with preemption deactivation, 30	Device Registration Services, 143
rtdm_malloc	rtdm_rt_capable
Utility Services, 193	Utility Services, 197
rtdm_mmap_handler	rtdm_rw_user_ok
Device Registration Services, 142	Utility Services, 198
rtdm_mmap_iomem	rtdm_safe_copy_from_user
Utility Services, 193	Utility Services, 198
rtdm_mmap_kmem	rtdm_safe_copy_to_user
Utility Services, 194	Utility Services, 199
rtdm_mmap_to_user	rtdm_schedule_nrt_work
Utility Services, 194	Non-Real-Time Signalling Services, 187
rtdm_mmap_vmem	rtdm_select_handler
Utility Services, 195	Device Registration Services, 143
rtdm_munmap	rtdm_selecttype
Utility Services, 196	Synchronisation Services, 161
rtdm_mutex_destroy	rtdm_sem_destroy
Mutex services, 179	Semaphore Services, 176
rtdm_mutex_init	rtdm_sem_down
Mutex services, 179	Semaphore Services, 176
rtdm_mutex_lock	rtdm_sem_init
Mutex services, 180	Semaphore Services, 177
rtdm_mutex_timedlock	rtdm_sem_select
Mutex services, 180	Semaphore Services, 177
rtdm_mutex_unlock	rtdm_sem_timeddown
Mutex services, 181	Semaphore Services, 177
rtdm_nrtsig_destroy	rtdm_sem_up
Non-Real-Time Signalling Services, 187	Semaphore Services, 178

rtdm_send	Timer Services, 156
Driver to driver services, 130	rtdm_timer_handler_t
rtdm_sendmsg	Timer Services, 155
Driver to driver services, 130	rtdm_timer_init
rtdm_sendmsg_handler	Timer Services, 156
Device Registration Services, 143	rtdm_timer_mode
rtdm sendto	Timer Services, 156
Driver to driver services, 131	rtdm_timer_start
rtdm_setsockopt	Timer Services, 156
Driver to driver services, 131	rtdm_timer_start_in_handler
rtdm shutdown	Timer Services, 157
Driver to driver services, 132	rtdm_timer_stop
rtdm_sm_ops, 501	Timer Services, 157
rtdm socket	rtdm_timer_stop_in_handler
Driver to driver services, 132	Timer Services, 157
rtdm_socket_handler	rtdm_toseq_init
Device Registration Services, 145	Synchronisation Services, 166
rtdm strncpy from user	rtdm_wait
Utility Services, 199	Synchronisation Services, 166
rtdm_task_busy_sleep	rtdm_wait_condition
Task Services, 149	Synchronisation Services, 167
rtdm task busy wait	rtdm_wait_condition_locked
Task Services, 149	Synchronisation Services, 167
rtdm_task_current	rtdm_wait_locked
Task Services, 150	Synchronisation Services, 168
•	rtdm_waitqueue_broadcast
rtdm_task_destroy	Synchronisation Services, 168
Task Services, 150	rtdm_waitqueue_destroy
rtdm_task_init	Synchronisation Services, 168
Task Services, 150	rtdm_waitqueue_flush
rtdm_task_join	Synchronisation Services, 169
Task Services, 151	rtdm_waitqueue_init
rtdm_task_proc_t	Synchronisation Services, 169
Task Services, 149	rtdm_waitqueue_lock
rtdm_task_set_period	Synchronisation Services, 169
Task Services, 151	rtdm_waitqueue_signal
rtdm_task_set_priority	Synchronisation Services, 170
Task Services, 152	rtdm_waitqueue_unlock
rtdm_task_should_stop	Synchronisation Services, 170
Task Services, 152	rtdm_waitqueue_wakeup
rtdm_task_sleep	Synchronisation Services, 170
Task Services, 152	rtdm write
rtdm_task_sleep_abs	Driver to driver services, 133
Task Services, 153	rtdm write handler
rtdm_task_sleep_until	Device Registration Services, 145
Task Services, 153	rtipc_port_label, 502
rtdm_task_unblock	label, 502
Task Services, 153	rtser_config, 502
rtdm_task_wait_period	rtser_event, 503
Task Services, 154	rtser_status, 504
rtdm_timedwait	
Synchronisation Services, 163	S_PRIO
rtdm_timedwait_condition	Semaphore services, 432
Synchronisation Services, 164	SCHED_QUOTA scheduling policy, 201
rtdm_timedwait_condition_locked	SIOCGCANBAUDRATE
Synchronisation Services, 164	CAN Devices, 54
rtdm_timedwait_locked	SIOCGCANCTRLMODE
Synchronisation Services, 165	CAN Devices, 54
rtdm_timer_destroy	SIOCGCANCUSTOMBITTIME

CAN Davison F4	Comprhess 215
CAN Devices, 54	Semaphores, 315
SIOCGCANSTATE CAN Devices 55	sem_post
CAN Devices, 55	Semaphores, 316
SIOCGIFINDEX CAN Devices, 55	sem_timedwait
SIOCSCANBAUDRATE	Semaphores, 317
CAN Devices, 56	sem_trywait
SIOCSCANCTRLMODE	Semaphores, 318
	sem_unlink
CAN Devices, 56 SIOCSCANCUSTOMBITTIME	Semaphores, 318
	sem_wait
CAN Devices, 57 SIOCSCANMODE	Semaphores, 319 Semaphore Services, 176
CAN Devices, 57	rtdm_sem_destroy, 176
SO_RCVTIMEO	rtdm_sem_down, 176
Real-time IPC, 72	rtdm_sem_init, 177
SO_SNDTIMEO	rtdm_sem_select, 177
Real-time IPC, 72	rtdm_sem_timeddown, 177
SOL CAN RAW	rtdm_sem_timeddown, 177
CAN Devices, 58	Semaphore services, 431
sbdata	rt_sem_bind, 432
a4l_descriptor, 477	rt_sem_broadcast, 433
sbsize	rt_sem_create, 433
a4l_descriptor, 477	rt_sem_delete, 434
sched_get_priority_max	rt_sem_inquire, 434
Process scheduling, 304	rt_sem_p, 434
sched_get_priority_max_ex	rt_sem_p_timed, 435
Process scheduling, 305	rt_sem_p_until, 435
sched_get_priority_min	rt_sem_unbind, 436
Process scheduling, 305	rt_sem_v, 436
sched_get_priority_min_ex	S PRIO, 432
Process scheduling, 306	Semaphores, 313
sched_getconfig_np	sem_close, 313
Process scheduling, 306	sem_destroy, 315
sched getscheduler	sem_init, 315
Process scheduling, 307	sem_post, 316
sched_getscheduler_ex	sem_timedwait, 317
Process scheduling, 308	sem_trywait, 318
sched_setconfig_np	sem_unlink, 318
Process scheduling, 308	sem_wait, 319
sched_setscheduler	sendmsg_AF_RTIPC
Process scheduling, 310	Real-time IPC, 80
sched_setscheduler_ex	sendmsg_nrt
Process scheduling, 311	rtdm_fd_ops, 501
sched_yield	sendmsg_rt
Process scheduling, 312	rtdm_fd_ops, 501
Scheduling management, 325	seq
pthread getschedparam, 325	xnvfile regular iterator, 515
pthread_getschedparam_ex, 326	xnvfile_snapshot_iterator, 521
pthread_setschedparam, 326	Serial Devices, 64
pthread_setschedparam_ex, 328	setsockoptAF_RTIPC
pthread_yield, 329	Real-time IPC, 81
select	show
rtdm_fd_ops, 501	xnvfile_regular_ops, 517
sem_close	xnvfile_snapshot_ops, 523
Semaphores, 313	sig
sem_destroy	udd_signotify, 512
Semaphores, 315	sipc_port
sem_init	sockaddr_ipc, 506
	300aaap3, 000

Smokey API, 330	rtdm_waitqueue_init, 169
sockaddr_can, 504	rtdm_waitqueue_lock, 169
can_ifindex, 505	rtdm_waitqueue_signal, 170
sockaddr_ipc, 505	rtdm_waitqueue_unlock, 170
sipc_port, 506	rtdm waitqueue wakeup, 170
socket	Synchronous acquisition API, 357, 362
rtdm_fd_ops, 501	a4l_config_subd, 362
socket_AF_RTIPC	a4l snd insn, 359
	a4l_snd_insnlist, 359
Real-time IPC, 81	
Software calibration API, 341	a4l_sync_dio, 363
a4l_dcaltoraw, 341	a4l_sync_read, 363
a4l_get_softcal_converter, 341	a4l_sync_write, 364
a4l_rawtodcal, 343	Synchronous I/O multiplexing, 204
a4l_read_calibration_file, 343	xnselect, 205
Spinlock with preemption deactivation, 27	xnselect_bind, 205
rtdm_lock_get, 29	xnselect_destroy, 206
rtdm_lock_get_irqsave, 27	xnselect_init, 206
rtdm_lock_init, 29	xnselect_signal, 206
rtdm_lock_irqrestore, 29	xnselector_destroy, 207
rtdm_lock_irqsave, 29	xnselector init, 207
·	
rtdm_lock_put, 30	T_LOCK
rtdm_lock_put_irqrestore, 30	Task management services, 439
splexit	T LOPRIO
Locking services, 109	Task management services, 439
splhigh	T WARNSW
Locking services, 110	Task management services, 439
spltest	Task management services, 437
Locking services, 110	rt_task_bind, 439
status	rt_task_create, 439
xnsched, 513	rt_task_delete, 441
store	rt_task_inquire, 441
xnvfile_regular_ops, 518	
xnvfile_snapshot_ops, 524	rt_task_join, 442
Subdevice management services, 247	rt_task_receive, 442
a4l_add_subd, 249	rt_task_receive_timed, 443
a4l_alloc_subd, 249	rt_task_receive_until, 444
a4l_get_subd, 249	rt_task_reply, 444
switch htick mode	rt_task_resume, 445
	rt_task_same, 445
Timer services, 229	rt_task_self, 446
Synchronisation Services, 160	rt_task_send, 446
RTDM_SELECTTYPE_EXCEPT, 161	rt_task_send_timed, 446
RTDM_SELECTTYPE_READ, 161	rt_task_send_until, 448
RTDM_SELECTTYPE_WRITE, 161	rt_task_set_affinity, 448
rtdm_for_each_waiter, 161	rt_task_set_mode, 449
rtdm_for_each_waiter_safe, 163	rt_task_set_periodic, 450
rtdm_selecttype, 161	rt_task_set_priority, 451
rtdm_timedwait, 163	rt_task_shadow, 451
rtdm_timedwait_condition, 164	rt_task_sleep, 452
rtdm_timedwait_condition_locked, 164	rt_task_sleep_until, 453
rtdm_timedwait_locked, 165	rt_task_slice, 453
rtdm_toseq_init, 166	rt_task_spawn, 454
rtdm_wait, 166	rt task start, 455
rtdm_wait_condition, 167	rt_task_start, 455 rt_task_suspend, 455
rtdm_wait_condition, 167	·
rtdm_wait_condition_locked, 167	rt_task_unbind, 456
	rt_task_unblock, 456
rtdm_waitqueue_broadcast, 168	rt_task_wait_period, 457
rtdm_waitqueue_destroy, 168	rt_task_yield, 457
rtdm_waitqueue_flush, 169	T_LOCK, 439

T_LOPRIO, 439	xnsynch_destroy, 209
T_WARNSW, 439	xnsynch_flush, 209
Task Services, 148	xnsynch_init, 210
rtdm_task_busy_sleep, 149	xnsynch_peek_pendq, 211
rtdm_task_busy_wait, 149	xnsynch_release, 211
rtdm_task_current, 150	xnsynch_sleep_on, 212
rtdm_task_destroy, 150	xnsynch_try_acquire, 212
rtdm_task_init, 150	xnsynch_wakeup_one_sleeper, 213
rtdm_task_join, 151	xnsynch_wakeup_this_sleeper, 213
rtdm_task_proc_t, 149	Timer management services, 459
rtdm_task_set_period, 151	RT_TIMER_INFO, 459
rtdm_task_set_priority, 152	rt_timer_inquire, 460
rtdm_task_should_stop, 152	rt_timer_ns2ticks, 460
rtdm_task_sleep, 152	rt timer read, 460
rtdm_task_sleep_abs, 153	rt_timer_spin, 461
rtdm_task_sleep_until, 153	rt_timer_ticks2ns, 461
rtdm_task_unblock, 153	Timer Services, 155
rtdm task wait period, 154	RTDM TIMERMODE ABSOLUTE, 156
Testing Devices, 66	RTDM_TIMERMODE_REALTIME, 156
Thread information flags, 39	RTDM_TIMERMODE_RELATIVE, 156
Thread management, 320	rtdm_timer_destroy, 156
pthread_create, 320	rtdm_timer_handler_t, 155
pthread_join, 321	rtdm_timer_init, 156
pthread_kill, 322	rtdm_timer_mode, 156
pthread_setmode_np, 322	rtdm_timer_start, 156
pthread_setname_np, 324	rtdm_timer_start_in_handler, 157
Thread scheduling control, 202	rtdm_timer_start_m_nandier, 107
xnsched_rotate, 202	rtdm_timer_stop_in_handler, 157
	Timer services, 228
xnsched_run, 203	•
Thread services, 215	xntimer_migrate, 229
xnthread_cancel, 216	program_htick_shot, 229
xnthread_current, 216	switch_htick_mode, 229
xnthread_from_task, 217	xntimer_destroy, 230
xnthread_harden, 217	xntimer_get_date, 230
xnthread_init, 217	xntimer_get_overruns, 230
xnthread_join, 218	xntimer_get_timeout, 232
xnthread_map, 219	xntimer_grab_hardware, 232
xnthread_migrate, 220	xntimer_init, 232
xnthread_relax, 220	xntimer_interval, 233
xnthread_resume, 220	xntimer_release_hardware, 233
xnthread_set_mode, 221	xntimer_start, 234
xnthread_set_periodic, 222	xntimer_stop, 234
xnthread_set_schedparam, 223	timer_create
xnthread_set_slice, 224	Clocks and timers, 268
xnthread_start, 224	timer_delete
xnthread_suspend, 225	Clocks and timers, 269
xnthread_test_cancel, 226	timer_getoverrun
xnthread_unblock, 226	Clocks and timers, 269
xnthread_wait_period, 227	timer_gettime
Thread state flags, 37	Clocks and timers, 270
XNHELD, 38	timer_settime
XNMIGRATE, 38	Clocks and timers, 270
XNPEND, 38	Transition Kit, 464
XNREADY, 38	COMPATrt_alarm_create, 464
XNSUSP, 38	COMPATrt_event_clear, 465
XNTRAPLB, 38	COMPATrt_event_create, 465
Thread synchronization services, 208	COMPATrt_event_signal, 466
xnsynch_acquire, 208	COMPATrt_pipe_create, 466
· — ·	

COMPATrt_task_create, 467	RT_HEAP_INFO, 491
COMPATrt_task_set_periodic, 469	usedmem
pthread_make_periodic_np, 470	RT_HEAP_INFO, 491
pthread_wait_np, 470	User-space driver core, 31
rt_alarm_wait, 471	UDD_IRQ_CUSTOM, 32
type	UDD_IRQ_NONE, 32
udd_memregion, 510	UDD_MEM_LOGICAL, 33
LIDD IDO CHCTOM	UDD_MEM_NONE, 33
UDD_IRQ_CUSTOM	UDD_MEM_PHYS, 33
User-space driver core, 32	UDD_MEM_VIRTUAL, 33
UDD_IRQ_NONE	UDD_RTIOC_IRQDIS, 33
User-space driver core, 32	UDD_RTIOC_IRQEN, 33
UDD_MEM_LOGICAL	UDD_RTIOC_IRQSIG, 33
User-space driver core, 33	udd_disable_irq, 34
UDD_MEM_NONE	udd_enable_irq, 34
User-space driver core, 33	udd_get_device, 35
UDD_MEM_PHYS	udd_notify_event, 35
User-space driver core, 33	udd_register_device, 35
UDD_MEM_VIRTUAL	udd_unregister_device, 36
User-space driver core, 33	Utility Services, 190
UDD_RTIOC_IRQDIS	rtdm_copy_from_user, 191
User-space driver core, 33	rtdm_copy_to_user, 191
UDD_RTIOC_IRQEN	rtdm_free, 192
User-space driver core, 33	rtdm_in_rt_context, 192
UDD RTIOC IRQSIG	rtdm_iomap_to_user, 192
User-space driver core, 33	rtdm_malloc, 193
uapi/analogy.h	
A4L_RNG_FACTOR, 574	rtdm_mmap_iomem, 193
udd_device, 506	rtdm_mmap_kmem, 194
close, 507	rtdm_mmap_to_user, 194
device_flags, 507	rtdm_mmap_vmem, 195
device_subclass, 507	rtdm_munmap, 196
interrupt, 507	rtdm_printk, 196
ioctl, 508	rtdm_printk_ratelimited, 196
irq, 508	rtdm_ratelimit, 197
	rtdm_read_user_ok, 197
mem_regions, 508	rtdm_rt_capable, 197
mmap, 508	rtdm_rw_user_ok, 198
open, 509	rtdm_safe_copy_from_user, 198
udd_device::udd_reserved, 510	rtdm_safe_copy_to_user, 199
udd_disable_irq	rtdm_strncpy_from_user, 199
User-space driver core, 34	
udd_enable_irq	vfile
User-space driver core, 34	xnvfile_regular_iterator, 515
udd_get_device	xnvfile_snapshot_iterator, 521
User-space driver core, 35	Virtual file services, 236
udd_memregion, 509	cobalt_vfroot, 242
addr, 510	xnvfile_destroy, 237
len, 510	xnvfile_get_blob, 238
type, 510	xnvfile_get_integer, 238
udd_notify_event	xnvfile_get_string, 239
User-space driver core, 35	xnvfile_init_dir, 239
udd_register_device	xnvfile_init_link, 239
User-space driver core, 35	xnvfile_init_regular, 241
udd_signotify, 511	xnvfile_init_snapshot, 241
pid, 512	VxWorks® emulator, 462
sig, 512	
udd_unregister_device	write_nrt
User-space driver core, 36	 rtdm_fd_ops, 501
usablemem	write_rt

utaliza fal aira E01	Duffey descriptor 00
rtdm_fd_ops, 501	Buffer descriptor, 92
XDDP BUFSZ	xnbufd_unmap_uwrite
Real-time IPC, 72	Buffer descriptor, 92
	xnclock_adjust
XDDP_EVTDOWN	Clock services, 94
Real-time IPC, 73	xnclock_deregister
XDDP_EVTIN	Clock services, 94
Real-time IPC, 73	xnclock_register
XDDP_EVTNOBUF	Clock services, 96
Real-time IPC, 73	xnclock_tick
XDDP_EVTOUT	_
Real-time IPC, 74	Clock services, 96
XDDP LABEL	xnheap::xnbucket, 512
Real-time IPC, 74	xnheap_alloc
XDDP MONITOR	Dynamic memory allocation services, 99
Real-time IPC, 74	xnheap_destroy
	Dynamic memory allocation services, 99
XDDP_POOLSZ	xnheap_free
Real-time IPC, 75	Dynamic memory allocation services, 99
XNHELD	xnheap init
Thread state flags, 38	Dynamic memory allocation services, 100
XNMIGRATE	xnheap_set_name
Thread state flags, 38	• = =
XNPEND	Dynamic memory allocation services, 100
Thread state flags, 38	xnintr_affinity
XNREADY	Interrupt management, 105
Thread state flags, 38	xnintr_attach
XNSUSP	Interrupt management, 105
Thread state flags, 38	xnintr_destroy
XNTRAPLB	Interrupt management, 106
	xnintr_detach
Thread state flags, 38	Interrupt management, 106
xnapc_alloc	xnintr disable
Asynchronous Procedure Calls, 83	Interrupt management, 107
xnapc_free	xnintr enable
Asynchronous Procedure Calls, 84	-
xnapc_schedule	Interrupt management, 107
Asynchronous Procedure Calls, 84	xnintr_init
xnarch_generic_full_divmod64	Interrupt management, 107
In-kernel arithmetics, 85	xnmap_create
xnbufd_copy_from_kmem	Lightweight key-to-object mapping service,
Buffer descriptor, 88	111
xnbufd copy to kmem	xnmap_delete
Buffer descriptor, 89	Lightweight key-to-object mapping service,
xnbufd_invalidate	112
Buffer descriptor, 89	xnmap_enter
·	Lightweight key-to-object mapping service,
xnbufd_map_kread	112
Buffer descriptor, 90	
xnbufd_map_kwrite	xnmap_fetch
Buffer descriptor, 90	Lightweight key-to-object mapping service,
xnbufd_map_uread	113
Buffer descriptor, 90	xnmap_fetch_nocheck
xnbufd_map_uwrite	Lightweight key-to-object mapping service,
Buffer descriptor, 91	113
xnbufd reset	xnmap_remove
Buffer descriptor, 91	Lightweight key-to-object mapping service,
xnbufd_unmap_kread	113
Buffer descriptor, 91	xnregistry_bind
·	Registry services, 116
xnbufd_unmap_kwrite	
Buffer descriptor, 92	xnregistry_enter
xnbufd_unmap_uread	Registry services, 117

xnregistry_remove Registry services, 118 xnregistry_remove Registry services, 118 xnregistry_unlink Registry services, 119 xnsched, 512 cpu, 513 curr, 513 htimer, 513 inesting, 513 lilags, 513 resched, 513 rrbtimer, 513 rtbtimer, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_destroy Synchronous I/O multiplexing, 207 xnsploch_destroy Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 211 xnsynch_peek_pend Thread synchronization services, 211 xnsynch_gleep_on Thread synchronization services, 211 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 118 Thread services, 217 xnthread_jnit Thread services, 218 xnthread_services, 219 xnthread_services, 219 xnthread_services, 219 xnthread_services, 220 xnthread_services, 220 xnthread_services, 221 xnthread_services, 222 xnthread_services, 224 xnthread_services, 224 xnthread_services, 225 xnthread_services, 226 xnthread_services, 226 xnthread_services, 227 xntimer_destroy Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_init Timer services, 233 xntimer_release, 1 merchal services, 217 xnthread_services, 211 xnsynch_yelepale Thread services, 210 xnthread_services, 220 xnthread_services, 221 xnthread_services, 221 xnthread_services, 221 xnthread_services, 221 xnthread_services, 221 xnthread_services, 221 xnthread_services, 222 xntimer_destroy Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_services,		
xnregistry_remove Registry_services, 118 xnregistry_unlink Registry services, 119 xnsched, 512 cpu, 513 cpu, 513 nhimer, 513 nimeting, 513 liflags, 513 resched, 513 rrbtimer, 513 rrbtimer, 513 rrbtimer, 513 rrbtimer, 513 rrbtimer, 513 rrsthed_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 202 xnselect_fun Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_linit Synchronous I/O multiplexing, 206 xnselect_olinit Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multip	xnregistry_lookup	xnthread_from_task
Registry services, 118 xnregistry_unlink Registry services, 119 xnsched, 512 cpu, 513 curr, 513 htimer, 513 inesting, 513 resched, 513 rrbtimer, 513 resched, 513 rrbtimer, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 206 xnselect_obind Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_wakeup_one sleeper Thread synchronization serv	Registry services, 118	Thread services, 217
Registry services, 118 xnregistry_unlink Registry services, 119 xnsched, 512 cpu, 513 curr, 513 htimer, 513 inesting, 513 resched, 513 rrbtimer, 513 resched, 513 rrbtimer, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 206 xnselect_obind Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_wakeup_one sleeper Thread synchronization serv	xnregistry_remove	xnthread_harden
xnregistry_unlink Registry services, 119 xnsched, 512 cpu, 513 htimer, 513 inesting, 513 ifflags, 513 resched, 513 rrbtimer, 513 xnsched, 513 rrbtimer, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_linit Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselect_orinit Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_link Thread synchronization services, 209 xnsynch_lius Thread synchronization services, 211 xnsynch_selep_on Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_cancel Thread services, 216 xnthread_cancel Thread services, 216 xnthread_current xnthread_init Thread services, 218 xnthread_services, 219 xnthread_services, 220 xnthread_services, 221 xnthread_services, 220 xnthread_services, 222 xnthread_services, 220 xnthread_services, 222 xnthread_services, 220 xnthread_service	Registry services, 118	
Registry services, 119 xnsched, 512 cpu, 513 curr, 513 htimer, 513 inesting, 513 lflags, 513 resched, 513 rrbtimer, 513 rrbtimer, 513 rrbtimer, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 202 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 206 xnselector_instruction services, 208 xnselect signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnsplector_instruction services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_carcel Thread services, 216 xnthread_imap Thread services, 220 xnthread_relax Thread services, 220 xnthread_set_eloac Thread services, 220 xnthread_set_eloac Thread services, 221 xnthread_set_eloac Thread services, 222 xnthread_set_eloac Thread services, 224 xnthread_set_eloac Thread services, 224 xnthread_set_eloac Thread services, 224 xnthread_set_eloac Thread services, 224 xnthread_set_eloac Thread services, 226 xnthread_set_eloac Thread services, 226 xnthread_set_eloac Thread services, 226 xnthread_set_eloac Thread services, 227 xntimer_lease Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_oreruns Timer services,		
xnsched, 512	• •	_
cpu, 513 curr, 513 htimer, 513 inesting, 513 iflags, 513 resched, 513 rrbtimer, 513 rrbread services, 220 xnthread services, 220 xnthread services, 220 xnthread services, 221 xnthread services, 222 xnthread services, 224 xnthread services, 225 xnthread services, 226 xnthread services Thread servi		
nitmer, 513 Intimer, 513 Intesting, 513 Iresched, 513 Irhead services, 220 Intread services, 220 Intread services, 220 Intread, set, 516 Iread services, 220 Intread services, 221 Iresched, 513 Irhead services, 220 Intread services, 221 Iresched, 513 Irhead services, 220 Intread services, 221 Iread services, 221 Iread services, 222 Intread, set, 516 Irhead services, 220 Intread services, 221 Irhead services, 220 Intread services, 221 Irhead services, 220 Intread services, 221 Irhead services, 222 Intread, set, 516 Irhead services, 220 Intread, set, 516 Irhead services, 220 Intread, set, 516 Irhead services, 220 Intread services, 221 Intread, set, 516 Irhead services, 222 Intread, set, 516 Irhead services, 225 Intread, set, 516 Irhead services, 226 Ir	•	
htimer, 513 inesting, 513 inesting, 513 resched, 513 resched, 513 rrbtimer, 513 rt, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_of estroy Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 212 xnsynch_wakeup_this_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 220 xnthread_set_periodic Thread services, 222 xnthread_set_slice Thread services, 222 xnthread_set_schedparam Thread services, 223 xnthread_set_slice Thread services, 223 xnthread_set_periodic Thread services, 222 xnthread_set_schedparam Thread services, 222 xnthread_set_slice Thread services, 223 xnthread_set_periodic Thread services, 222 xnthread_set_schedparam Thread services, 222 xnthread_set_slice Thread services, 223 xnthread_set_eriodic Thread services, 222 xnthread_set_schedparam Thread services, 222 xnthread_set_schedparam Thread services, 222 xnthread_set_slice Thread services, 222	•	
inesting, 513 Iflags, 513 Iresched, 513 Irrbitmer, 513 Irthimer, 513 Irthimed, 514 Irthied, 514 Irthi		
Iflags, 513 resched, 513 rrebimer, 513 rrbimer, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 205 xnselect_linit Synchronous I/O multiplexing, 206 xnselect_ginit Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 209 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_gepe_on Thread synchronization services, 212 xnsynch_wakeup_this_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 220 xnthread_set_periodic Thread services, 222 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 224 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 224 xnthread_set_schedparam Thread services, 224 xnthread_set_schedparam Thread services, 225 xnthread_set_sche		•
resched, 513 rrbtimer, 513 tt, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_signal Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnspch_caquire Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_peek_pendq Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_gelepen Thread synchronization services, 211 xnsynch_gelepen Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 225 xnthread_elax Thread services, 220 xnthread_set_mode Thread services, 221 xnthread_set_periodic Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_scheacle Thread services, 224 xnthread_set_scheacle Thread services, 225 xnthread_set_scheacle Thread services, 225 xnthread_set_scheacle Thread services, 226 xnthread_set_schea		_ •
rrbtimer, 513 rt, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_rotate Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_gleep_on Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnshread_cancel Thread services, 220 xnthread_set_schedparam Thread services, 222 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 224 xnthread_set_schedparam Thread services, 224 xnthread_set_cancel Thread services, 225 xnthread_set_vices, 226 xnthread_set_vices, 226 xnthread_set_otile Thread services, 223 xntimer_get_date Timer services, 230 xntimer_get_date Timer services, 232 xntimer_get_date Timer services, 232 xntimer_get_date Timer services, 232 xntimer_get_		
rt, 513 status, 513 xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselect_ofestroy Synchronous I/O multiplexing, 206 xnselect_ofestroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnsplector_destroy Thread synchronization services, 208 xnsynch_acquire Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 226 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 226 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 226 xnthread_set_olde Thread services, 226 xnthread_set_slice Thread services, 226 xnthread_set_slice Thread services, 226 xnthread_set_slice Thread services, 226 xnthread_set_olde Thread services, 226 xnthread_set_olde Thread services, 227 xntimer_get_date Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_imeout Timer services, 232 xntimer_get_imeout Timer services, 232 xntimer_get_imeout Timer services, 232 xntimer_services, 232 xntimer_start Timer services, 233 xntimer_start		-
xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_init Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnsph_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 211 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_geleape Thread synchronization services, 211 xnsynch_gleap_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 220 xnthread_set_periodic Thread services, 222 xnthread_set_schedparam Thread services, 223 xnthread_set_periodic Thread services, 223 xnthread_set_schedparam Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_vices, 224 xnthread_set_slice Thread services, 225 xnthread_set_orices, 224 xnthread_set_slice Thread services, 225 xnthread_set_orices, 224 xnthread_set_orices, 224 xnthread_set_orices, 225 xnthread_set_schedparam Thread services, 225 xnthread_set_orices, 224 xnthread_set_orices, 226 xnt	·	
xnsched_rotate Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_peek_pendq Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_sleep_ on Thread synchronization services, 211 xnsynch_sleep_ on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread_set_vices, 222 xnthread_set_slice Thread services, 223 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 226 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread_services, 226 xnthread_set_slice Thread_services, 226 xnthread_set_slice Thread services, 220 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_get_overruns Ti		
Thread scheduling control, 202 xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_gleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_carcel Thread services, 216 xnthread_set_set_epriodic Thread services, 222 xnthread_set_schedparam Thread services, 223 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_start Thread services, 225 xnthread_start Thread services, 225 xnthread_start Thread services, 225 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_solice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 226 xnthread_services, 22		
xnsched_run Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread services, 222 xnthread_set_slice Thread services, 224 xnthread_set_vices, 223 xnthread_set_slice Thread services, 224 xnthread_start Thread services, 225 xnthread_services, 225 xnthread_services, 225 xnthread_services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_wait_period Thread services, 226 xnthread_wait_period Thread services, 226 xnthread_wait_period Thread services, 226 xnthread_wait_period Thread services, 226 xnthread_umblock Thread services, 226 xnthread_vait_period Thread services, 226 xnthread_services, 220 xntimer_get_date Timer services, 230 xntimer_get_imeout Timer services, 232 xntimer_jet_imeout Timer servi		
Thread scheduling control, 203 xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_current Thread services, 222 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 223 xnthread_set_schedparam Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 224 xnthread_set_slice Thread services, 225 xnthread_set_slice Thread services, 226 xnthread_set_init Thread services, 226		
xnselect Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsplector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_peek_pendq Thread synchronization services, 210 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 224 xnthread_set_slice Thread services, 224 xnthread_set_sice Thread services, 224 xnthread_suspend Thread services, 225 xnthread_set_sice Thread services, 224 xnthread_set_sice Thread services, 225 xnthread_set_sice Thread services, 226 xnthread_set_sice Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_services, 226 xnthread_unblock Thread services, 226 xnthread_services, 226 xntimer_get_date Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_get_date Timer services, 230 xntimer_get_overrun	—	
Synchronous I/O multiplexing, 205 xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_services, 224 xnthread_setrices, 224 xnthread_services, 224 xnthread_setrices, 224 xnthread_services, 225 xnthread_services, 225 xnthread_services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_services, 226 xnthread_services, 227 xntimer_get_date Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_	Thread scheduling control, 203	Thread services, 222
xnselect_bind Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_init Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 224 xnthread_surcices, 225 xnthread_services, 225 xnthread_surcices, 226 xnthread_services, 225 xnthread_services, 225 xnthread_services, 225 xnthread_services, 225 xnthread_services, 225 xnthread_services, 226 xnthread_services, 226 xnthread_services, 225 xnthread_services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 224 xnthread_surcices, 225 xnthread_services, 226 xntimer_destroy Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_oate Timer services, 230 xntimer_get_oate Timer services, 232 xntimer_init Timer services, 232 xntimer_release_hardware Timer services, 233 xntimer_services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 232 xntimer_get_date Timer services, 230 xntimer_get_oate Timer services,	xnselect	xnthread_set_schedparam
Synchronous I/O multiplexing, 205 xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 224 xnthread_suspend Thread services, 226 xnthread_test_cancel Thread services, 226 xnthread_test_cancel Thread services, 226 xnthread_eunblock Thread services, 226 xnthread_eunblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_eunblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Thread services, 226 xnthread_unblock Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_get_timeout Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 232 xntimer_start Timer services, 232 xntimer_start Timer services, 233 xntimer_start Timer services, 232 xntimer_start Timer services,	Synchronous I/O multiplexing, 205	Thread services, 223
xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 226 xnthread_unblock Thread services, 226 xnthread_estroy Timer services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 226 xnthread services, 226 xnthread_services, 226 xnthread services, 226 xnthread_services, 226 xnthread_services, 226 xnthread services, 226 xnthread_services, 226 xnthread_services, 226 xnthread services, 226 xnthread_estroy Timer services, 227 xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_get_timeout Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_services, 233 xntimer_services, 233 xntimer_start Timer services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 227 xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_get_tim	xnselect_bind	xnthread_set_slice
xnselect_destroy Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 226 xnthread_unblock Thread services, 226 xnthread_estroy Timer services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 226 xnthread services, 226 xnthread_services, 226 xnthread services, 226 xnthread_services, 226 xnthread_services, 226 xnthread services, 226 xnthread_services, 226 xnthread_services, 226 xnthread services, 226 xnthread_estroy Timer services, 227 xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_get_timeout Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_services, 233 xntimer_services, 233 xntimer_start Timer services, 226 xnthread_services, 226 xnthread_services, 226 xnthread_services, 227 xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_get_tim	Synchronous I/O multiplexing, 205	
Synchronous I/O multiplexing, 206 xnselect_init Synchronous I/O multiplexing, 206 xnselects signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_niit Thread synchronization services, 209 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 225 xnthread_test_cancel Thread services, 226 xnthread_test_cancel Thread services, 225 xnthread_test_cancel Thread services, 226 xnthread_test_cancel Thread services, 225 xnthread_test_cancel Thread services, 226 xnthread_usit_period Thread services, 226 xnthread_usit_period Thread services, 226 xnthread_unblock Thread services, 226 xnthread_estrov xntimer_get_date Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_get_imeout Timer services, 232 xntimer_get_		
xnselect_init Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 209 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 225 xnthread_test_cancel Thread services, 226 xnthread_etst_cancel Thread services, 226 xnthread_etst_cancel Thread services, 226 xnthread_exit_period Thread services, 227 xntimer_get_date Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 237 xntimer_get_ber Timer services, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 230 xntimer_get_overruns Timer services, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_sterices, 232 xntimer_get_oterices,	_	
Synchronous I/O multiplexing, 206 xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 225 xnthread_test_cancel Thread services, 226 xnthread_unblock Thread services, 226 xnthread_exity Thread services, 227 xntimer_destroy Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_oate Timer servic		
xnselect_signal Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 212 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 226 xnthread_unblock Thread services, 226 xnthread_wait_period Thread services, 227 xntimer_destroy Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 237 xntimer_get_bate		
Synchronous I/O multiplexing, 206 xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 209 xnsynch_nit Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 226 xnthread_unblock Thread services, 226 xnthread_services, 227 xntimer_destroy Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_ouer Timer services, 230 xntimer_get_ouer Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_get_date Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_ouer Timer services, 232 xn		
xnselector_destroy Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_unblock Thread services, 226 xnthread_wait_period Thread services, 227 xntimer_destroy Timer services, 230 xntimer_get_date Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 237 xntimer_stop	_ •	
Synchronous I/O multiplexing, 207 xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_services, 216 xnthread_services, 227 xntimer_destroy Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 237 xntimer_stop Timer services, 237 xntimer_stop		
xnselector_init Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xntimer_destroy Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 233 xntimer_start Timer services, 232 xntimer_init		
Synchronous I/O multiplexing, 207 xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 220 xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_release_hardware Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 232 xntimer_stop Timer services, 233 xntimer_stop Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 232 xntimer_stop Timer services, 232 xntimer_stop Timer services, 232		
xnsynch_acquire Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_destroy Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 237 xntimer_stop Virtual file services, 237 xnvfile_get_blob	<u> </u>	
Thread synchronization services, 208 xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread_carrent Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_timeout Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 237 xntille_destroy Virtual file services, 237 xntille_get_blob		The state of the s
xnsynch_destroy Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_get_date Timer services, 230 xntimer_get_timeout Timer services, 230 xntimer_get_overruns Timer services, 230 xntimer_get_overruns Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 237 xntile_destroy Virtual file services, 237 xntifile_get_blob		_ ,
Thread synchronization services, 209 xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xntimer_services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 237 xntimer_stop Timer services, 231	•	
xnsynch_flush Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread_current xntimer_get_overruns Timer services, 232 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 237 xntimer_start Timer services, 233 xntimer_release_hardware Timer services, 232 xntimer_init Timer services, 233 xntimer_init		
Thread synchronization services, 209 xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current Timer services, 230 xntimer_grab_hardware Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 237 xntyfile_destroy Virtual file services, 237 xntyfile_get_blob		
xnsynch_init Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_get_timeout Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop		_ -
Thread synchronization services, 210 xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Timer services, 232 xntimer_init Timer services, 232 xntimer_init Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 237 xnvfile_get_blob		
xnsynch_peek_pendq Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_grab_hardware Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 237 xntimer_init		
Thread synchronization services, 211 xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 237 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 237 xntimer_release_hardware Timer services, 233 xntimer_services, 233 xntimer_services, 233 xntimer_services, 233		
xnsynch_release Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_init Timer services, 232 xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 237 xntimer_lease_hardware		_5 _
Thread synchronization services, 211 xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 237 xnthread_current Xnvfile_destroy Virtual file services, 237 xnvfile_get_blob		
xnsynch_sleep_on Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_interval Timer services, 233 xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_elease_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_orlease_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 237 xntimer_orlease_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_start Timer services, 234 xntimer_start Timer services, 237	xnsynch_release	xntimer_init
Thread synchronization services, 212 xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current Timer services, 234 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 234 xnvfile_destroy Virtual file services, 237 xnvfile_get_blob	Thread synchronization services, 211	Timer services, 232
xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xnthread_cancel xnvfile_destroy Virtual file services, 237 xnvfile_get_blob	xnsynch_sleep_on	xntimer_interval
xnsynch_try_acquire Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_release_hardware Timer services, 233 xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xnthread_cancel xnvfile_destroy Virtual file services, 237 xnvfile_get_blob		Timer services, 233
Thread synchronization services, 212 xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Virtual file services, 234 xnvfile_destroy Virtual file services, 237 xnvfile_get_blob		
xnsynch_wakeup_one_sleeper Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_start Timer services, 234 xntimer_stop Timer services, 234 xntyfile_destroy Virtual file services, 237 xnvfile_get_blob		
Thread synchronization services, 213 xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current Timer services, 234 xntimer_stop Timer services, 234 xntimer_stop Timer services, 234 xntfile_destroy Virtual file services, 237 xnvfile_get_blob		
xnsynch_wakeup_this_sleeper Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current xntimer_stop Timer services, 234 xnvfile_destroy Virtual file services, 237 xnvfile_get_blob		-
Thread synchronization services, 213 xnthread_cancel Thread services, 216 xnthread_current Timer services, 234 xnvfile_destroy Virtual file services, 237 xnvfile_get_blob		
xnthread_cancelxnvfile_destroyThread services, 216Virtual file services, 237xnthread_currentxnvfile_get_blob		
Thread services, 216 Virtual file services, 237 xnthread_current xnvfile_get_blob		
xnthread_current xnvfile_get_blob		
VII (udi file Services, 210		_ -
	THEAU SELVICES, 210	viituai ille sei vices, 230

xnvfile_get_integer
Virtual file services, 238
xnvfile_get_string
Virtual file services, 239
xnvfile_init_dir
Virtual file services, 239
xnvfile_init_link
Virtual file services, 239
xnvfile_init_regular
Virtual file services, 241
xnvfile_init_snapshot
Virtual file services, 241
xnvfile_lock_ops, 514
get, 514
put, 514
xnvfile_regular_iterator, 514
pos, 515
private, 515
seq, 515
vfile, 515
xnvfile_regular_ops, 515
begin, 516
end, <u>516</u>
next, 516
rewind, 517
show, 517
store, 518
xnvfile_rev_tag, 518
rev, 519
xnvfile_snapshot, 519
xnvfile_snapshot_iterator, 519
databuf, 520
endfn, 520
nrdata, 520
private, 521
seq, 521
vfile, 521
xnvfile_snapshot_ops, 521
begin, 521
end, 522 next, 522
rewind, 523
show, 523 store, 524
SIUIE, 324