
# Processing Big Data with Hive



What is Hive?




- A metadata service that projects tabular schemas over folders
- Enables the contents of folders to be queried as tables, using SQL-like query semantics
- Queries are translated into jobs
  - Execution engine can be Tez or MapReduce

set hive.execution.engine=mr;
SELECT...


Map Map Reduce Reduce 📉 Map Map <sup>\*</sup> Map Map \* Reduce 💢 Reduce Map 🍹 Map 💢 Reduce

set hive.execution.engine=tez;
SELECT...




### Hive client tools include...


#### **Hive Shell**




**Visual Studio** 




**Any ODBC Client** 



**Query Console (Hue)** 



**PowerShell** 



How do I create and load Hive tables?


- Use the CREATE TABLE HiveQL statement
  - Defines schema metadata to be projected onto data in a folder when the table is queried (not when it is created)
- Specify file format and file location
  - Defaults to textfile format in the <database>/<table\_name> folder
    - Default database is in /hive/warehouse
    - Create additional databases using CREATE DATABASE
- Create internal or external tables
  - Internal tables manage the lifetime of the underlying folders
  - External tables are managed independently from folders

```
Internal table (folders
   deleted when table is
   dropped)
Default location
(/hive/warehouse/table1)
```

```
CREATE TABLE table1
(col1 STRING,
 col2 INT)
            DELIMITED
                        FIELDS TERMINATED
CREATE TABLE table2
(col1 STRING,
                                                             Stored in a custom folder (but
 col2 INT)
                                                             still internal, so the folder is
             DELIMITED
                         FIELDS TERMINATED BY
                                                             deleted when table is dropped)
STORED AS TEXTFILE LOCATION '/data/table2';
CREATE EXTERNAL TABLE table3
(coll STRING,
                                                             External table (folders and files
 col2 INT)
                                                             are left intact in Azure Blob Store
                                                             when the table is dropped)
STORED AS TEXTFILE
                      LOCATION
                                 '/data/table3';
```

## Hive data types:

- Numeric
  - Integers: TINYINT, SMALLINT, INT, BIGINT
  - Fractional: FLOAT, DOUBLE, DECIMAL
- Character
  - STRING, VARCHAR, CHAR
- Date/Time
  - TIMESTAMP
  - DATE
- Special
  - BOOLEAN, BINARY, ARRAY, MAP, STRUCT, UNIONTYPE



• Save data files in table folders (or create table on existing files!)

PUT myfile.txt /data/table1

Use the LOAD statement

LOAD DATA [LOCAL] INPATH '/data/source' INTO TABLE MyTable;

Use the INSERT statement

```
INSERT INTO TABLE Table2
SELECT Col1, UPPER(Col2),
FROM Table1;
```

• Use a CREATE TABLE AS SELECT (CTAS) statement

```
CREATE TABLE Table3
ROW FORMAT DELIMITED FIELDS TERMINATED BY '\t'
STORED AS TEXTFILE LOCATION '/data/summarytable'
AS
SELECT Col1, SUM(Col2) As Total
FROM Table1
GROUP BY Col1;
```

How do I query Hive tables?


Query data using the SELECT HiveQL statement

```
SELECT Col1, SUM(Col2) AS TotalCol2 FROM MyTable WHERE Col3 = 'ABC' AND Col4 < 10 GROUP BY Col1 ORDER BY Col4;
```

 Hive translates the query into jobs and applies the table schema to the underlying data files Views are named queries that abstract underlying tables


```
CREATE VIEW v_SummarizedData
AS
SELECT col1, SUM(col2) AS TotalCol2
FROM mytable
GROUP BY col1;

SELECT col1, TotalCol2
FROM v_SummarizedData;
```



Partitioning, Skewing, and Clustering Tables


```
CREATE TABLE part table
(coll INT,
 col2 STRING)
PARTITIONED BY (col3 STRING);
INSERT INTO TABLE part table PARTITION(col3='A')
SELECT col1, col2, col3
FROM stg table
WHERE col3 = 'A';
SET hive.exec.dynamic.partition = true;
SET hive.exec.dynamic.partition.mode=nonstrict;
INSERT INTO TABLE part table PARTITION(col3)
SELECT col1, col2, col3
FROM stg table;
```



```
CREATE TABLE skewed table
(coll INT,
                                                       skewed_table
 col2 STRING,
 col3 STRING)
SKEWED BY (col3) ON ('A') [STORED AS DIRECTORIES];
                                                                 col3='A'
INSERT INTO TABLE skewed table
SELECT col1, col2, col3
FROM stg table;
                                                                 Others
```

```
CREATE TABLE clust_table
(col1 INT,
  col2 STRING,
  col3 STRING)
CLUSTERED BY (col3) INTO 3 BUCKETS;
```


INSERT INTO TABLE clust\_table
SELECT col1, col2, col3
FROM stg\_table;



How do I use Hive in Visual Studio?


## Azure SDK for .NET includes HDInsight tools for Visual Studio

- Visual Hive table designer
- Hive query editor



How do I access Hive via ODBC?

- Download and install the Hive ODBC Driver for HDInsight
  - 32-bit and 64-bit versions
- 2. Optionally, create a data source name (DSN) for your HDInsight cluster
- 3. Use an ODBC connection to query Hive tables





©2014 Microsoft Corporation. All rights reserved. Microsoft, Windows, Office, Azure, System Center, Dynamics and other product names are or may be registered trademarks and/or trademarks in the U.S. and/or other countries. The information herein is for informational purposes only and represents the current view of Microsoft Corporation as of the date of this presentation. Because Microsoft must respond to changing market conditions, it should not be interpreted to be a commitment on the part of Microsoft, and Microsoft cannot guarantee the accuracy of any information provided after the date of this presentation. MICROSOFT MAKES NO WARRANTIES, EXPRESS, IMPLIED OR STATUTORY, AS TO THE INFORMATION IN THIS PRESENTATION.