
Main Memory





Chapter 9: Memory Management

- Background
- Contiguous Memory Allocation
- Paging
- Structure of the Page Table
- Swapping
- Example: The Intel 32 and 64-bit Architectures
- Example: ARMv8 Architecture





Background


- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage CPU can access directly
- Memory unit only sees a stream of:
 - addresses + read requests, or
 - address + data and write requests
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation





Protection

- Need to ensure that a process can access only those addresses in its address space.
- We can provide this protection by using a pair of base and limit registers define the logical address space of a process








Hardware Address Protection

 CPU must check every memory access generated in user mode to be sure it is between base and limit for that user




the instructions to loading the base and limit registers are privileged





Address Binding

- Programs on disk, ready to be brought into memory to execute form an input queue
 - Without support, must be loaded into address 0000
- Addresses represented in different ways at different stages of a program's life
 - Source code addresses usually symbolic
 - Compiled code addresses bind to relocatable addresses
 - i.e., "14 bytes from beginning of this module"
 - Linker or loader will bind relocatable addresses to absolute addresses
 - ▶ i.e., 74014
 - Each binding maps one address space to another






Binding of Instructions and Data to Memory

- Address binding of instructions and data to memory addresses can happen at three different stages
 - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
 - Load time: Must generate relocatable code if memory location is not known at compile time
 - Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
 - Need hardware support for address maps (e.g., base and limit registers)





Multistep Processing of a User Program







Logical vs. Physical Address Space


- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
 - Logical address generated by the CPU; also referred to as virtual address
 - Physical address address seen by the memory unit
- Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program






Memory-Management Unit (MMU)

Hardware device that at run time maps virtual to physical address




Many methods possible, covered in the rest of this chapter





Memory-Management Unit (Cont.)


- Consider simple scheme. which is a generalization of the baseregister scheme.
- The base register now called relocation register
- The value in the relocation register is added to every address generated by a user process at the time it is sent to memory
- The user program deals with logical addresses; it never sees the real physical addresses
 - Execution-time binding occurs when reference is made to location in memory
 - Logical address bound to physical addresses





Memory-Management Unit (Cont.)

- Consider simple scheme. which is a generalization of the baseregister scheme.
- The base register now called relocation register
- The value in the relocation register is added to every address generated by a user process at the time it is sent to memory







Dynamic Loading

- The entire program does need to be in memory to execute
- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded
- All routines kept on disk in relocatable load format
- Useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required
 - Implemented through program design
 - OS can help by providing libraries to implement dynamic loading





Dynamic Linking


- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking –linking postponed until execution time
- Small piece of code, stub, used to locate the appropriate memoryresident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
 - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries
- System also known as shared libraries
- Consider applicability to patching system libraries
 - Versioning may be needed





Contiguous Allocation

- Main memory must support both OS and user processes
- Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- Main memory usually into two partitions:
 - Resident operating system, usually held in low memory with interrupt vector
 - User processes then held in high memory
 - Each process contained in single contiguous section of memory






Contiguous Allocation (Cont.)

- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
 - Base register contains value of smallest physical address
 - Limit register contains range of logical addresses each logical address must be less than the limit register
 - MMU maps logical address dynamically
 - Can then allow actions such as kernel code being transient and kernel changing size



Hardware Support for Relocation and Limit Registers








Variable Partition

- Multiple-partition allocation
 - Degree of multiprogramming limited by number of partitions
 - Variable-partition sizes for efficiency (sized to a given process' needs)
 - Hole block of available memory; holes of various size are scattered throughout memory
 - When a process arrives, it is allocated memory from a hole large enough to accommodate it
 - Process exiting frees its partition, adjacent free partitions combined
 - Operating system maintains information about:
 a) allocated partitions
 b) free partitions (hole)





How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the first hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough; must search entire list, unless ordered by size
 - Produces the smallest leftover hole
- Worst-fit: Allocate the *largest* hole; must also search entire list
 - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization



Example: Given memory partitions of 100K, 500K, 200K, 300K, and 600K (in order), how would each of the First-fit, Best-fit, and Worst-fit algorithms place processes of 212K, 417K, 112K, and 426K (in order)? Which algorithm makes the most efficient use of memory?

Answer:

First-fit:

212K is put in 500K partition

417K is put in 600K partition

112K is put in 288K partition (new partition 288K = 500K - 212K)

426K must wait

Best-fit:

212K is put in 300K partition

417K is put in 500K partition

112K is put in 200K partition

426K is put in 600K partition

Worst-fit:

212K is put in 600K partition

417K is put in 500K partition

112K is put in 388K partition (600K – 212K)

426K must wait

In this example, Best-fit turns out to be the best.





Fragmentation

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used
- The solutions of external fragmentation are such as
 - Compaction, Segmentation and Paging





Fragmentation (Cont.)

- Reduce external fragmentation by compaction
 - Shuffle memory contents to place all free memory together in one large block
 - Compaction is possible only if relocation is dynamic, and is done at execution time
 - I/O problem
 - Handle job in memory while it is involved in I/O
 - Do I/O only into OS buffers
- Now consider that backing store has same fragmentation problems





Paging

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
 - Avoids external fragmentation
 - Avoids problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
 - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size N pages, need to find N free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation





Address Translation Scheme

- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory
 - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit


page number	page offset
р	d
m -n	n

For given logical address space 2^m and page size 2ⁿ





Paging Hardware







Paging Model of Logical and Physical Memory

frame

page 0

page 1

page 2

page 3

logical memory






Paging Example

 Logical address: n = 2 and m = 4. Using a page size of 4 bytes and a physical memory of 32 bytes (8 pages)

0	a
- 1	b
2	С
3	d
4	е
5	e f
6	g
7	g h
	Ì
9	i
10	j k
11	1
12	m
13	n
14	0
15	р

0	5
1	6
2	1
3	2








Paging -- Calculating internal fragmentation

- Page size = 2,048 bytes
- Process size = 72,766 bytes
- 35 pages + 1,086 bytes
- Internal fragmentation of 2,048 1,086 = 962 bytes
- Worst case fragmentation = 1 frame 1 byte
- On average fragmentation = 1 / 2 frame size
- So small frame sizes desirable?
- But each page table entry takes memory to track
- Page sizes growing over time
 - Solaris supports two page sizes 8 KB and 4 MB





Free Frames



Before allocation

After allocation






Implementation of Page Table

- Page table is kept in main memory
 - Page-table base register (PTBR) points to the page table
 - Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
 - One for the page table and one for the data / instruction
- The two-memory access problem can be solved by the use of a special fast-lookup hardware cache called translation look-aside buffers (TLBs) (also called associative memory).






Hardware

Associative memory – parallel search

Page #	Frame #

- Address translation (p, d)
 - If p is in associative register, get frame # out
 - Otherwise get frame # from page table in memory





Shared Pages

Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed


Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space





Shared Pages Example








Swapping

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
 - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk





Schematic View of Swapping



main memory





- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
 - Swap out time of 2000 ms
 - Plus swap in of same sized process
 - Total context switch swapping component time of 4000ms (4 seconds)





Context Switch Time and Swapping (Cont.)

- Other constraints as well on swapping
 - Pending I/O can't swap out as I/O would occur to wrong process
 - Or always transfer I/O to kernel space, then to I/O device
 - Known as double buffering, adds overhead
- Standard swapping not used in modern operating systems
 - But modified version common
 - Swap only when free memory extremely low






Swapping on Mobile Systems

- Not typically supported
 - Flash memory based
 - Small amount of space
 - Limited number of write cycles
 - Poor throughput between flash memory and CPU on mobile platform
- Instead use other methods to free memory if low
 - iOS asks apps to voluntarily relinquish allocated memory
 - Read-only data thrown out and reloaded from flash if needed
 - Failure to free can result in termination
 - Android terminates apps if low free memory, but first writes application state to flash for fast restart
 - Both OSes support paging as discussed below





Swapping with Paging







Segmentation

- Segmentation is a memory-management scheme that supports this programmer view of memory. A logical address space is a collection of segments.
- Each segment has a name and a length.
- The addresses specify both the segment name and the offset within the segment.
- The programmer therefore specifies each address by two quantities:
 - a segment name and an offset

<segment-number, offset>.






Figure 7: Programmer's view of a program and logical view of segmentation





Segmentation Hardware

- Each entry in the segment table has a segment base and a segment limit.
 - The segment base contains the starting physical address where the segment resides in memory,
 - the segment limit specifies the length of the segment






Figure 8: Segmentation hardware



Example




Figure 9: Example of segmentation.

Examples:

- A reference to byte 53 of segment 2 is mapped onto location 4300 + 53 = 4353.
- A reference to segment 3, byte 852, is mapped to 3200 + 852 = 4052.

What about a reference to byte 1222 of segment 0?

