Equations of planes

We have touched on equations of planes previously. Here we will fill in some of the details.

Planes in point-normal form

The basic data which determines a plane is a point P_0 in the plane and a vector \mathbf{N} orthogonal to the plane. We call \mathbf{N} a *normal* to the plane and we will sometimes say \mathbf{N} is *normal* to the plane, instead of orthogonal.

Now, suppose we want the equation of a plane and we have a point $P_0 = (x_0, y_0, z_0)$ in the plane and a vector $\overrightarrow{\mathbf{N}} = \langle a, b, c \rangle$ normal to the plane.


Let P = (x, y, z) be an arbitrary point in the plane. Then the vector $\overrightarrow{\mathbf{P_0P}}$ is in the plane and therefore orthogonal to \mathbf{N} . This means

$$\mathbf{N} \cdot \overrightarrow{\mathbf{P_0 P}} = 0$$

$$\Leftrightarrow \langle a, b, c \rangle \cdot \langle x - x_0, y - y_0, z - z_0 \rangle = 0$$

$$\Leftrightarrow a(x - x_0) + b(y - y_0) + c(z - z_0) = 0$$

We call this last equation the point-normal form for the plane.




Example 1: Find the plane through the point (1,4,9) with normal (2,3,4).

Answer: Point-normal form of the plane is 2(x-1)+3(y-4)+4(z-9)=0. We can also write this as 2x+3y+4z=50.

Example 2: Find the plane containing the points $P_1 = (1,2,3)$, $P_2 = (0,0,3)$, $P_3 = (2,5,5)$.

<u>Answer:</u> The goal is to find the basic data, i.e. a point in the plane and a normal to the plane. The point is easy, we already have three of them. To get the normal we note (see figure below) that $\overrightarrow{P_1P_2}$ and $\overrightarrow{P_1P_3}$ are vectors in the plane, so their cross product is orthogonal (normal) to the plane. That is,


$$\mathbf{N} = \overrightarrow{\mathbf{P_1 P_2}} \times \overrightarrow{\mathbf{P_1 P_3}} = \begin{pmatrix} \mathbf{i} & \mathbf{j} & \mathbf{k} \\ -1 & -2 & 0 \\ 1 & 3 & 2 \end{pmatrix} = -4\mathbf{i} - \mathbf{j}(-2) + \mathbf{k}(-1) = \langle -4, 2, -1 \rangle.$$



Using point-normal form (with point P_1) the equation of the plane is

$$-4(x-1) + 2(y-2) - (z-3) = 0$$
, or equivalently $-4x + 2y - z = -3$.

Example 3: Find the plane with normal $\mathbf{N} = \hat{\mathbf{k}}$ containing the point (0,0,3) Eq. of plane: $\langle 0,0,1 \rangle \cdot \langle x,y,z-3 \rangle = 0 \Leftrightarrow z=3$.



Example 4: Find the plane with x, y and z intercepts a, b and c.

<u>Answer:</u> We could find this using the method example 1. Instead, we'll use a shortcut that works when all the intercepts are known. In this case, the intercepts are

and we simply write the plane as

$$x/a + y/b + z/c = 1.$$


You can easily check that each of the given points is on the plane. For completeness we'll do this using the more general method of example 1.

The 3 points give us 2 vectors in the plane, $\langle -a, b, 0 \rangle$ and $\langle -a, 0, c \rangle$.

$$\Rightarrow$$
 N = $\langle -a, b, 0 \rangle \times \langle -a, 0, c \rangle = \langle bc, ac, ab \rangle$.

Point-normal form: bc(x-a) + ac(y-0) + ab(z-0) = 0

$$\Leftrightarrow bc x + ac y + ab z = abc \Leftrightarrow x/a + y/b + z/c = 1.$$



Lines in the plane


While we're at it, let's look at two ways to write the equation of a line in the xy-plane.

Slope-intercept form: Given the slope m and the y-intercept b the equation of a line can be written y = mx + b.

Point-normal form:

We can also use point-normal form to find the equation of a line.

Given a point (x_0, y_0) on the line and a vector $\langle a, b \rangle$ normal to the line the equation of the line can be written $a(x - x_0) + b(y - y_0) = 0$.



MIT OpenCourseWare http://ocw.mit.edu

18.02SC Multivariable Calculus Fall 2010

For information about citing these materials or our Terms of Use, visit: http://ocw.mit.edu/terms.