#### CentOS 丛书目录 - 系统管理 - 网络服务 - 应用部署

## 创建 LVM 系统

#### 内容提要

- 1. 理解在新硬盘上创建 LVM 系统的过程。
- 2. 掌握常用的物理卷操作命令: pvcreate、pvscan、pvdisplay
- 3. 掌握常用的卷组操作命令: vgcreate、vgdisplay
- 4. 掌握常用的逻辑卷操作命令: lvcreate、lvdisplay

### 概述

创建 LVM 系统可以在安装 Linux 过程中进行,参见 使用 LVM 安装 CentOS。本节讲述在安装好系统后创建 LVM 系统的过程。

#### 本节的操作目的:

- 1. 在系统中添加一块新硬盘
- 2. 在新硬盘上创建物理卷
- 3. 将新创建的物理卷添加到卷组
- 4. 在卷组中创建逻辑卷
- 5. 在逻辑卷中创建 ext3 文件系统
- 6. 将创建的文件系统挂装到 /srv/www

### 在磁盘或磁盘分区上创建物理卷PV

分配磁盘用于 LVM2 有如下三种方式:

- 1. 在未分区的磁盘上创建单个物理卷
- 2. 在有一个分区的磁盘上创建单个的物理卷
- 3. 在有多个分区的磁盘上创建多个的物理卷

由于现在的磁盘容量很大,建议使用第三种方式避免因磁盘局部损坏造成整盘数据丢失。每个磁盘分区的大小建议为 40G 左右。

# 创建 LVM 类型的分区

可以使用 fdisk 或 parted 命令创建 LVM 类型的分区, LVM 分区的类型 ID 为 8e。下面给出一个分区过程示例。

#### # fdisk /dev/sdb

Device contains neither a valid DOS partition table, nor Sun, SGI or OSF disklabel Building a new DOS disklabel. Changes will remain in memory only, until you decide to write them. After that, of course, the previous content won't be recoverable.

The number of cylinders for this disk is set to 1044.

There is nothing wrong with that, but this is larger than 1024,

and could in certain setups cause problems with:

1) software that runs at boot time (e.g., old versions of LILO)

第1页 共9页 2008-10-17 17:59

```
2) booting and partitioning software from other OSs
   (e.g., DOS FDISK, OS/2 FDISK)
Warning: invalid flag 0x0000 of partition table 4 will be corrected by w(rite)
Command (m for help): n
Command action
       extended
       primary partition (1-4)
Partition number (1-4): 1
First cylinder (1-1044, default 1):
Using default value 1
Last cylinder or +size or +sizeM or +sizeK (1-1044, default 1044): +4G
Command (m for help): n
Command action
   е
       extended
       primary partition (1-4)
Partition number (1-4): 2
First cylinder (488-1044, default 488):
Using default value 488
Last cylinder or +size or +sizeM or +sizeK (488-1044, default 1044):
Using default value 1044
Command (m for help): n
Command action
   1
       logical (5 or over)
       primary partition (1-4)
First cylinder (488-1044, default 488):
Using default value 488
Last cylinder or +size or +sizeM or +sizeK (488-1044, default 1044):
Using default value 1044
Command (m for help): p
Disk /dev/sdb: 8589 MB, 8589934592 bytes
255 heads, 63 sectors/track, 1044 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
   Device Boot
                    Start
                                   End
                                            Blocks
                                                      \operatorname{Id}
                                                         System
/dev/sdb1
                                                      83
                                   487
                                           3911796
                                                         Linux
                         1
/dev/sdb2
                       488
                                  1044
                                           4474102+
                                                      5
                                                         Extended
                                                     83
/dev/sdb5
                       488
                                  1044
                                           4474071
                                                         Linux
Command (m for help): t
Partition number (1-5): 1
Hex code (type L to list codes): 8e
Changed system type of partition 1 to 8e (Linux LVM)
Command (m for help): t
Partition number (1-5): 5
Hex code (type L to list codes): 8e
Changed system type of partition 5 to 8e (Linux LVM)
Command (m for help): p
Disk /dev/sdb: 8589 MB, 8589934592 bytes
255 heads, 63 sectors/track, 1044 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
   Device Boot
                    Start
                                   End
                                            Blocks
                                                      Id System
/dev/sdb1
                         1
                                   487
                                           3911796
                                                      8e
                                                         Linux LVM
/dev/sdb2
                       488
                                  1044
                                           4474102+
                                                       5
                                                         Extended
/dev/sdb5
                       488
                                  1044
                                           4474071
                                                      8e Linux LVM
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
# partprobe
```

- 1. 作为演示,本例创建了一个主分区,大小为4G,和一个基于扩展分区的逻辑分区,其大小也为4G。在实际环境中每个分区建议使用 40G 左右的大小。
- 2. 磁盘划分为主分区还是逻辑分区对 LVM 来说无关紧要。

### 创建物理卷

要将分区分配给物理卷可以使用 pvcreate [http://www.proxyserve.net /index.php?q=aHR0cDovL21hbi5jeC9wdmNyZWF0ZQ%3D%3D] 命令,其格式为:

pvcreate 〈磁盘或分区设备名〉

下面将在刚刚创建的两个 LVM 分区上创建物理卷。

# pvcreate /dev/sdb1

Physical volume "/dev/sdb1" successfully created

# pvcreate /dev/sdb5

Physical volume "/dev/sdb5" successfully created

创建的物理卷之后可以使用 pvscan [http://www.proxyserve.net /index.php?q=aHR0cDovL21hbi5jeC9wdnNjYW4%3D] 命令查看物理卷对应的设备名称。

# pvscan

PV /dev/sda2 VG VolGroup00 1vm2 [7.88 GB / 0 free] # 此为安装系统时创建的物理卷

Total: 3 [15.87 GB] / in use: 1 [7.88 GB] / in no VG: 2 [8.00 GB]

还可以使用 pvdisplay [http://www.proxyserve.net

/index.php?q=aHR0cDovL21hbi5jeC9wdmRpc3BsYXk%3D] 命令查看新创建的物理卷的状态和大小,其命令格式为:

pvdisplay [<物理卷设备名>]

# pvdisplay

--- Physical volume --- # 此为安装系统时创建的物理卷

PV Name /dev/sda2 VG Name VolGroup00

PV Size 7.90 GB / not usable 23.41 MB

Allocatable yes (but full)

 PE Size (KByte)
 32768

 Total PE
 252

 Free PE
 0

 Allocated PE
 252

PV UUID wy2NBg-eIiF-0QC6-DX1a-20MA-NE3I-pK3J4f

--- NEW Physical volume --PV Name /dev/sdb1

VG Name

PV Size 3.73 GB
Allocatable NO
PE Size (KByte) 0
Total PE 0

第3页 共9页

```
0
Free PE
Allocated PE
                       0
PV UUID
                       JxaDHJ-P4YC-0WeS-pEe0-rEG9-Pq5S-tVNtrE
--- NEW Physical volume --
PV Name
                       /dev/sdb5
VG Name
PV Size
                       4.27 GB
Allocatable
                       NO
PE Size (KByte)
Total PE
                       0
Free PE
                       0
Allocated PE
PV UUID
                       EOui8b-J5qS-3aMd-hw1H-roAu-GY8r-BORHIm
```

## 使用物理卷创建卷组VG

要使用物理卷创建卷组,可以使用 vgcreate [http://www.proxyserve.net /index.php?q=aHR0cDovL21hbi5jeC92Z2NyZWF0ZQ%3D%3D] 命令,其格式为:

```
vgcreate〈卷组名〉〈物理卷设备名〉[〈物理卷设备名〉...]
```

要使用上面创建的2个物理卷创建名为 wwwVG 的卷组,使用如下的命令:

```
# vgcreate wwwVG /dev/sdb1 /dev/sdb5
Volume group "wwwVG" successfully created
```

卷组创建之后,可以使用 vgdisplay [http://www.proxyserve.net /index.php?q=aHR0cDovL21hbi5jeC92Z2Rpc3BsYXk%3D] 命令查看卷组的状态,命令格式为:

vgdisplay [<卷组名>]

```
# vgdisplay
  --- Volume group -
 VG Name
                        wwwVG
 System ID
 Format
                        1vm2
                        2
 Metadata Areas
 Metadata Sequence No
                        1
 VG Access
                        read/write
 VG Status
                        resizable
 MAX LV
                        0
 Cur LV
                        0
 Open LV
                        0
 Max PV
                        0
                        2
 Cur PV
 Act PV
 VG Size
                        7.99 GB
 PE Size
                        4.00 MB
 Total PE
                        2046
 Alloc PE / Size
                        0 / 0
 Free PE / Size
                        2046 / 7.99 GB
 VG UUID
                        RZI9pk-r0ix-u8p8-ieu2-W67A-Ujfo-Z1jNq0
  --- Volume group -
                                                      # 此为安装系统时创建卷组
 VG Name
                        VolGroup00
```

System ID	
Format	1vm2
Metadata Areas	1
Metadata Sequence No	4
VG Access	read/write
VG Status	resizable
MAX LV	0
Cur LV	3
Open LV	3
Max PV	0
Cur PV	1
Act PV	1
VG Size	7.88 GB
PE Size	32.00 MB
Total PE	252
Alloc PE / Size	252 / 7.88 GB
Free PE / Size	0 / 0
VG UUID	p3q80x-Gxrf-qGH1-G0kq-91Gu-ZefK-F8r0tb

### 在卷组VG中创建逻辑卷LV

要在卷组中创建逻辑卷需要使用 lvcreate [http://www.proxyserve.net /index.php?q=aHR0cDovL21hbi5jeC9sdmNyZWF0ZQ%3D%3D] 命令,格式为:

```
格式1: lvcreate <-L/--size 逻辑卷大小[kKmMgGtT]> <-n/--name 逻辑卷名称> <卷组名称>
格式2: lvcreate <-l/--extents LogicalExtentsNumber> <-n/--name 逻辑卷名称> <卷组名称>
```

- 1. 格式1: 在创建逻辑卷时直接指定大小,单位可以是 kK、mM、gG、tT,默认为 M。
- 2. 格式2: 在创建逻辑卷时使用 LogicalExtentsNumber 指定大小,LogicalExtentsNumber 可以通过如下命令或得:

上面的 2046 就是卷组 wwwVG 当前可用的最大 LogicalExtentsNumber。

使用 LVM 的最大好处在于"按需分配、动态调整"。通常在创建逻辑卷时只分配卷组中的部分空间给逻辑卷,剩余空间可以创建其他的逻辑卷,或留作日后再分配。

下面的命令用于在 wwwVG 卷组中创建大小为 2G, 名字为 www 的逻辑卷:

# lvcreate -L 2G -n www wwwVG Logical volume "www" created

若将卷组中的所有空间都分配给逻辑卷 www,可以使用如下命令:

# lvcreate -1 2047 -n www wwwVG Logical volume "www" created

然后可以使用 lvdisplay [http://www.proxyserve.net /index.php?q=aHR0cDovL21hbi5jeC9sdmRpc3BsYXk%3D] 命令查看刚创建的逻辑卷的信息:

```
# lvdisplay
  --- Logical volume
                                   # 此为新创建的逻辑卷,其他逻辑卷是系统安装过程中创建的
 LV Name
                         /dev/wwwVG/www
 VG Name
                         wwwVG
                         KL8CNA-e11x-z6bd-QzvU-Gwju-v41b-Nj3YfX
 LV UUID
                         read/write
 LV Write Access
 LV Status
                         available
 # open
                          0
 LV Size
                         2.00 GB
 Current LE
                         512
 Segments
                         1
 Allocation
                         inherit
 Read ahead sectors
                         0
 Block device
                         253:3
  --- Logical volume
 LV Name
                         /dev/VolGroup00/LogVolRoot
 VG Name
                         VolGroup00
 LV UUID
                         Rzmk2c-KDy1-mjGF-QZKM-dOy7-98c6-o4p8Ig
 LV Write Access
                         read/write
 LV Status
                         available
 # open
                         1
 LV Size
                         3.97 GB
 Current LE
                         127
 Segments
                         1
 Allocation
                         inherit
 Read ahead sectors
                         0
 Block device
                         253:0
  --- Logical volume
 LV Name
                         /dev/VolGroup00/LogVolHome
 VG Name
                         VolGroup00
 LV UUID
                         q6j2U1-g5u9-inAj-zWNy-hrK7-T71j-N59hMZ
 LV Write Access
                         read/write
 LV Status
                         available
 # open
                          1
 LV Size
                         2.91 GB
 Current LE
                         93
 Segments
 Allocation
                         inherit
 Read ahead sectors
                         0
                         253:1
 Block device
 --- Logical volume
 LV Name
                         /dev/VolGroup00/LogVolSWAP
 VG Name
                         VolGroup00
 LV UUID
                         oZ01Rm-fh3g-u7Ij-GsMc-PpkS-DugJ-Bku7DF
 LV Write Access
                         read/write
 LV Status
                         available
 # open
                          1
 LV Size
                         1.00 GB
 Current LE
                         32
 Segments
                         1
 Allocation
                         inherit
 Read ahead sectors
 Block device
                         253:2
```

从上面的显示可以看出新创建的逻辑卷的设备名是 /dev/www/G/www, 它是使用 lvcreate 命令创建该逻辑卷时创建的。创建逻辑卷时,LVM 系统还在 /dev/mapper/ 目录下创建了该逻辑卷的控制设备,将逻辑卷映射到创建它的物理卷。如下所示:

第6页 共9页 2008−10−17 17:59

```
# 1s -1 /dev/wwwVG/
total 0
lrwxrwxrwx 1 root root 21 Dec 15 18:08 www -> /dev/mapper/wwwVG-www
# 1s -1 /dev/mapper/
total 0
crw------ 1 root root 10, 63 Dec 15 16:25 control
brw-rw---- 1 root disk 253, 1 Dec 15 16:25 VolGroup00-LogVolHome
brw-rw---- 1 root disk 253, 0 Dec 15 16:25 VolGroup00-LogVolRoot
brw-rw---- 1 root disk 253, 2 Dec 15 16:25 VolGroup00-LogVolSWAP
brw-rw---- 1 root disk 253, 3 Dec 15 18:08 wwwVG-www
```

#### 创建了逻辑卷之后使用 vgdisplay 命令查看卷组状态的变化。

```
# vgdisplay
  --- Volume group ---
 VG Name
                         wwwVG
  System ID
 Format
                         1 \text{vm} 2
 Metadata Areas
                        2
 Metadata Sequence No 2
  VG Access
                        read/write
  VG Status
                        resizable
 MAX LV
 Cur LV
                         1
  Open LV
                        0
                        0
 Max PV
                        2
 Cur PV
  Act PV
  VG Size
                        7.99 GB
 PE Size
                        4.00 MB
                        2046
 Total PE
  Alloc PE / Size
                        512 / 2.00 GB
 Free PE / Size
                        1534 / 5.99 GB
                        RZI9pk-r0ix-u8p8-ieu2-W67A-Ujfo-Z1jNq0
  VG UUID
  --- Volume group ---
  VG Name
                        VolGroup00
  System ID
  Format
                         1vm2
 Metadata Areas
                         1
 Metadata Sequence No 4
  VG Access
                        read/write
                        resizable
  VG Status
  MAX LV
 Cur LV
                        3
  Open LV
                        3
                        0
 Max PV
 Cur PV
                        1
 Act PV
                        1
 VG Size
                        7.88 GB
 PE Size
                        32.00 MB
 Total PE
                        252
                        252 / 7.88 GB
 Alloc PE / Size
 Free PE / Size
                        0 / 0
  VG UUID
                        p3q80x-Gxrf-qGH1-G0kq-91Gu-ZefK-F8r0tb
```

从上面的输出可以看出在卷组 wwwVG 中使用了 512 个物理区域(PE),即分配了 2G 给 www 逻辑卷,并且还有

第7页 共9页 2008−10−17 17:59

#### 1534 的 PE (6.0G) 剩余空间。

创建了逻辑卷之后使用 pvdisplay 命令查看物理卷的状态变化。

```
# pvdisplay
  --- Physical volume -
  PV Name
                         /dev/sdb1
  VG Name
                         wwwVG
 PV Size
                         3.73 GB / not usable 4.11 MB
  Allocatable
                        yes
 PE Size (KByte)
                         4096
 Total PE
                         954
 Free PE
                         954
 Allocated PE
 PV UUID
                        JxaDHJ-P4YC-OWeS-pEeO-rEG9-Pq5S-tVNtrE
  --- Physical volume -
                         /dev/sdb5
  PV Name
  VG Name
                         wwwVG
 PV Size
                         4.27 GB / not usable 1.21 MB
  Allocatable
                         yes
  PE Size (KByte)
                         4096
 Total PE
                         1092
 Free PE
                         580
  Allocated PE
                         512
 PV UUID
                        EOui8b-J5qS-3aMd-hw1H-roAu-GY8r-BORHIm
  --- Physical volume ---
 PV Name
                         /dev/sda2
  VG Name
                        VolGroup00
  PV Size
                        7.90 GB / not usable 23.41 MB
 Allocatable
                        ves (but full)
                         32768
 PE Size (KByte)
  Total PE
                         252
 Free PE
                         0
 Allocated PE
                         252
  PV UUID
                         wy2NBg-eIiF-OQC6-DX1a-20MA-NE3I-pK3J4f
```

从上面的输出可以看出, 2G 的 www 逻辑卷被分配到了物理卷 /dev/sdb5 上, Allocated PE 的值从原来的 0 变为了现在的 512。

### 在逻辑卷LV上创建文件系统FS

要在系统中使用逻辑卷,下面的任务就是在其上创建文件系统。有关文件系统的详细内容请参见下一章。

使用如下命令创建 ext3 类型的文件系统。

```
# mkfs -t ext3 /dev/wwwVG/www
mke2fs 1.39 (29-May-2006)
Filesystem label=
0S type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
262144 inodes, 524288 blocks
26214 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=536870912
16 block groups
```

 32768 blocks per group, 32768 fragments per group
16384 inodes per group
Superblock backups stored on blocks:
32768, 98304, 163840, 229376, 294912
Writing inode tables: done
Creating journal (16384 blocks): done
Writing superblocks and filesystem accounting information: done
This filesystem will be automatically checked every 39 mounts or

180 days, whichever comes first. Use tune2fs -c or -i to override.

然后编辑 /etc/fstab, 在文件末添加如下的行,以便每次启动系统时自动挂装此文件系统。

/dev/wwwVG/www /srv/www ext3 defaults 0 0

为了使其在当前生效,需要执行如下命令:

- # mkdir /srv/www
- # mount -a
- 显示源文件
- 登录

第9页 共9页