

一、先决条件

1、关闭 NetworkManager

systemctl stop NetworkManager systemctl disable NetworkManager

2、关闭防火墙

systemctl disable firewalld
systemctl stop firewalld

3、设置主机名

hostnamectl set-hostname xx. xx. xx

二、配置 Dns 服务器或者使用 hosts 进行主机名的 IP 对应

 controller. nice. com
 192. 168. x. 5

 network. nice. com
 192. 168. x. 6

 computel. nice. com
 192. 168. x. 10

 compute2. nice. com
 192. 168. x. 11

 block1. nice. com
 192. 168. x. 20

 block2. nice. com
 192. 168. x. 21

 object. nice. com
 192. 168. x. 30

 object. nice. com
 192. 168. x. 31

三、配置时间同步服务器

controller.nice.com ntp server controller other server ntp client

四、安装 OpenStack 预备包

- 1、安装 yum-plugin-priorities 包,防止高优先级软件被低优先级软件覆盖 yum -y install yum-plugin-priorities
- 2、安装 epel 扩展 YUM 源

yum -y install

http://dl.fedoraproject.org/pub/epel/7/x86_64/e/epel-release-7-2.noarch.rpm

3、安装 OpenStack YUM 源

yum -y install

http://rdo.fedorapeople.org/openstack-juno/rdo-release-juno.rpm

4、更新操作系统

yum upgrade

5、安裝 OpenStack-selinux 自动管理 Selinux yum -y install openstack-selinux



五、为 controller 节点安装数据库

- 1、安装 mariadb 软件包 yum -y install mariadb mariadb-server MySQL-python
- 2、编辑 /etc/yum.cnf 软件,设置绑定 IP,默认数据库引擎及默认字符集为 UTF-8 [mysq1]

bind-address = 192.168.x.5
default-storage-engine = innodb
innodb_file_per_table
collation-server = utf8_general_ci
init-connect = 'SET NAMES utf8'
character-set-server = utf8

- 3、启动数据库并设置为开机自启动 systemctl enable mariadb systemctl start mariadb
- 4、初始化数据库脚本 mysql_secure_installation

六、安装 Messaing Server 服务

- 1、功能: 协调操作和状态信息服务
- 2、常用的消息代理软件 RabbitMQ Qpid ZeroMQ
- 3、在 controller 节点安装 RabbitMQ
 - a、安装 RabbitMQ 软件包 yum -y install rabbitmg-server
 - b、启动服务并设置开机自启动 systemctl enable rabbitmq-server systemctl start rabbitmq-server
 - c、rabbitmq 默认用户名和密码是 guest,可以通过下列命令修改 rabbitmqctl change_password guest new_password