

Draft February 24, 2014



Device Abstraction Layer Functions

Draft

68 Pages

Abstract

Defines a core set of functions to RFC-0196 Device Abstraction Layer. They provide an interoperability between the different specific domains.

February 24, 2014

0 Document Information

0.1 License

DISTRIBUTION AND FEEDBACK LICENSE, Version 2.0

The OSGi Alliance hereby grants you a limited copyright license to copy and display this document (the "Distribution") in any medium without fee or royalty. This Distribution license is exclusively for the purpose of reviewing and providing feedback to the OSGi Alliance. You agree not to modify the Distribution in any way and further agree to not participate in any way in the making of derivative works thereof, other than as a necessary result of reviewing and providing feedback to the Distribution. You also agree to cause this notice, along with the accompanying consent, to be included on all copies (or portions thereof) of the Distribution. The OSGi Alliance also grants you a perpetual, non-exclusive, worldwide, fully paid-up, royalty free, limited license (without the right to sublicense) under any applicable copyrights, to create and/or distribute an implementation of the Distribution that: (i) fully implements the Distribution including all its required interfaces and functionality; (ii) does not modify, subset, superset or otherwise extend the OSGi Name Space, or include any public or protected packages, classes, Java interfaces, fields or methods within the OSGi Name Space other than those required and authorized by the Distribution. An implementation that does not satisfy limitations (i)-(ii) is not considered an implementation of the Distribution, does not receive the benefits of this license, and must not be described as an implementation of the Distribution. "OSGi Name Space" shall mean the public class or interface declarations whose names begin with "org.osgi" or any recognized successors or replacements thereof. The OSGi Alliance expressly reserves all rights not granted pursuant to these limited copyright licenses including termination of the license at will at any time.

EXCEPT FOR THE LIMITED COPYRIGHT LICENSES GRANTED ABOVE, THE OSGI ALLIANCE DOES NOT GRANT, EITHER EXPRESSLY OR IMPLIEDLY, A LICENSE TO ANY INTELLECTUAL PROPERTY IT, OR ANY THIRD PARTIES, OWN OR CONTROL. Title to the copyright in the Distribution will at all times remain with the OSGI Alliance. The example companies, organizations, products, domain names, e-mail addresses, logos, people, places, and events depicted therein are fictitious. No association with any real company, organization, product, domain name, email address, logo, person, place, or event is intended or should be inferred.

THE DISTRIBUTION IS PROVIDED "AS IS," AND THE OSGI ALLIANCE (INCLUDING ANY THIRD PARTIES THAT HAVE CONTRIBUTED TO THE DISTRIBUTION) MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, NON-INFRINGEMENT, OR TITLE; THAT THE CONTENTS OF THE DISTRIBUTION ARE SUITABLE FOR ANY PURPOSE; NOR THAT THE IMPLEMENTATION OF SUCH CONTENTS WILL NOT INFRINGE ANY THIRD PARTY PATENTS, COPYRIGHTS, TRADEMARKS OR OTHER RIGHTS.

NEITHER THE OSGI ALLIANCE NOR ANY THIRD PARTY WILL BE LIABLE FOR ANY DIRECT, INDIRECT, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF OR RELATING TO ANY USE OR DISTRIBUTION OF THE DISTRIBUTION.

Implementation of certain elements of this Distribution may be subject to third party intellectual property rights, including without limitation, patent rights (such a third party may or may not be a member of the OSGi Alliance). The OSGi Alliance is not responsible and shall not be held responsible in any manner for identifying or failing to identify any or all such third party intellectual property rights.

The Distribution is a draft. As a result, the final product may change substantially by the time of final publication, and you are cautioned against relying on the content of this Distribution. You are encouraged to update any implementation of the Distribution if and when such Distribution becomes a final specification.

The OSGi Alliance is willing to receive input, suggestions and other feedback ("Feedback") on the Distribution. By providing such Feedback to the OSGi Alliance, you grant to the OSGi Alliance and all its Members a non-exclusive, non-transferable,



February 24, 2014

worldwide, perpetual, irrevocable, royalty-free copyright license to copy, publish, license, modify, sublicense or otherwise distribute and exploit your Feedback for any purpose. Likewise, if incorporation of your Feedback would cause an implementation of the Distribution, including as it may be modified, amended, or published at any point in the future ("Future Specification"), to necessarily infringe a patent or patent application that you own or control, you hereby commit to grant to all implementers of such Distribution or Future Specification an irrevocable, worldwide, sublicenseable, royalty free license under such patent or patent application to make, have made, use, sell, offer for sale, import and export products or services that implement such Distribution or Future Specification. You warrant that (a) to the best of your knowledge you have the right to provide this Feedback, and if you are providing Feedback on behalf of a company, you have the rights to provide Feedback on behalf of your company; (b) the Feedback is not confidential to you and does not violate the copyright or trade secret interests of another; and (c) to the best of your knowledge, use of the Feedback would not cause an implementation of the Distribution or a Future Specification to necessarily infringe any third-party patent or patent application known to you. You also acknowledge that the OSGi Alliance is not required to incorporate your Feedback into any version of the Distribution or a Future Specification.

I HEREBY ACKNOWLEDGE AND AGREE TO THE TERMS AND CONDITIONS DELINEATED ABOVE.

0.2 Trademarks

OSGi™ is a trademark, registered trademark, or service mark of the OSGi Alliance in the US and other countries. Java is a trademark, registered trademark, or service mark of Oracle Corporation in the US and other countries. All other trademarks, registered trademarks, or service marks used in this document are the property of their respective owners and are hereby recognized.

0.3 Feedback

This document can be downloaded from the OSGi Alliance design repository at https://github.com/osgi/design The public can provide feedback about this document by opening a bug at https://www.osgi.org/bugzilla/.

0.4 Table of Contents

0 Document Information		. 2
0.1 License		
0.2 Trademarks	3	
0.3 Feedback	3	
0.4 Table of Contents		
0.5 Terminology and Document Conventions	4	
0.6 Revision History	4	
1 Introduction		.4
2 Application Domain		. 5
3 Problem Description		. 5
4 Requirements		. 6
5 Technical Solution		. 7
5.1 Core Functions		
5.1.1 BooleanControl Function		
5.1.2 BooleanSensor Function	8	
5.1.3 MultiLevelControl Function	8	
5.1.4 MultiLevelSensor Function	9	
5.1.5 Meter Function	9	
5.1.6 Alarm Function	10	
5.1.7 Keypad Function	10	



Alliance	Draft	
5.1.8 WakeUp Function		11
6 Data Transfer Objects		12
7 Javadoc		13
8 Considered Alternatives		67
9 Security Considerations		67
10 Document Support		67
10.1 References		67
10.3 End of Document		68

0.5 Terminology and Document Conventions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY" and "OPTIONAL" in this document are to be interpreted as described in 10.1.

Source code is shown in this typeface.

0.6 Revision History

The last named individual in this history is currently responsible for this document.

Revision	Date	Comments
Initial	Feb 21 2013	Detach the core functions from RFC-0196 Device Abstraction Layer. Evgeni Grigorov, ProSyst Software, <u>e.grigorov@prosyst.com</u>

1 Introduction

OSGi is gaining popularity as enabling technology for building embedded system in residential and M2M markets. In these contexts it is often necessary to communicate with IP and non-IP devices by using various protocols such as ZigBee, Z-Wave, KNX, UPnP etc. In order to provide a convenient programming model suitable for the realization of end-to-end services it is very useful to define and apply an abstraction layer which unifies the work with devices supporting different protocols.

This RFC defines a core set of functions to RFC-0196 Device Abstraction Layer. They provide an interoperability between the different specific domains. The set can be reused, extended or fully replaced into specific domain.

2 Application Domain

OSGi Device Abstraction Layer RFC-0196 don't define functions, but their common representation. It doesn't guarantee interoperability between the different domains. In this way, the same functionality can be modeled in different ways and the applications will be bind to the specific interfaces.

For example, a meter function can be defined in the smart home domain as an energy meter, but in the security domain as a time meter (timer).


In order to unify the application access to the basic functionalities, a core of functions is required.

3 Problem Description


The applications need to know about a set of OSGi Device Abstraction Layer functions to operate with them. They can execute operations, set and receive property values.

Illustration 1 shows one possible approach for working with heterogeneous functions, which are related to the same functionality. The smart home meter and vendor specific meter are all about the same kind of information. They collect metering information.

In this case each application must use specific API for this function. One obvious disadvantage of this model is that when a new function type is added the applications must be modified in order to support it.



Much better is the approach from Illustration 2 which is defined by this RFC.





App1 App2 App3

use use use

Meter

Illustration2

In this case a core functions are introduced to ensure the interoperability between the different domains. Thus the following advantages are achieved:

- The application programmers can work with the same set of functions.
- The functions can be reused or extended.
- The application can work without modifications when a new vendor function types are registered.

4 Requirements

- Requirement 1. The solution MUST define API for controlling devices which is applicable for all relevant device protocols.
- Requirement 2. The solution MUST define API for controlling devices which is independent from the device protocols.
- Requirement 3. The solution MUST include device access control based on user and application permissions compliant with the OSGi security model.
- Requirement 4. The solution SHOULD be mappable to other relevant standards such as HGI, ETSI M2M and BBF handling the remote access to device networks.
- Requirement 5. The solution MUST be applicable to the changeable device behavior. Sleeping/power saving devices can go and stay offline for a long time, but should be available in the defined API.



5 Technical Solution

5.1 Core Functions

Concrete function interfaces have to be defined to unify the access and control of the basic operations and related properties. The current section specifies the minimal basic set of such functionality. It can be reused and extended to cover more specific scenarios. They are about the control, monitoring and metering information.

5.1.1 BooleanControl Function

BooleanControl function provides a binary control support. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later. The full function definition is available in the next table.

Boolean Control		
Name	Description	
Opera	ations	
reverse	Reverses the BooleanControl state. If the current state represents true value, it'll be reversed to false. If the current state represents false value, it'll be reversed to true.	
setTrue	Sets the BooleanControl state to true value.	
setFalse	Sets the BooleanControl state to false value.	
Properties		
data	Contains the current state of BooleanControl. The property access can be: readable, writable and eventable.	
Types		
light, door, window, power, other type defined in org.osgi.service.dal.functions.Types or vendor specific type.		

BooleanData data structure is used to provide information about the function state. That data object contains the boolean value, the value collecting time and additional metadata. The immutable BooleanData.value field is accessible with BooleanData.getValue() getter.

The function class diagram is depicted on Illustration 3. The next code snippet sets to true all BooleanControl functions.



February 24, 2014

```
for (int i = 0; i < booleanControlSRefs.length; i++) {
  final BooleanControl booleanControl = (BooleanControl) context.getService(
     binaryControlSRefs[i]);
  if (null != booleanControl) {
    booleanControl.setTrue();
  }
}</pre>
```

5.1.2 BooleanSensor Function

BooleanSensor function provides binary sensor monitoring. It reports its state when an important event is available. There are no operations. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later. The full function definition is available in the next table.

BooleanSensor		
Name	Description	
Properties		
data	Contains the current state of BooleanSensor. The property access can be: readable and eventable.	
Types		
light, gas, smoke, door, window, power, rain, contact, fire, occupancy, water, motion, other type defined in org.osgi.service.dal.functions.Types or vendor specific type.		

BooleanSensor and BooleanControl are using the same BooleanData data structure to provide information about the state. For more details see the definition in BooleanControl Function. The function class diagram is depicted on Illustration 3.

5.1.3 MultiLevelControl Function

MultilevelControl function provides multi-level control support. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later. The full function definition is available in the next table.

MultiLevelControl		
Name	Description	
Properties		
data	Contains the current state of MultiLevelControl. The property access can be: readable, writable and eventable.	
Types		
light, temperature, flow, pressure, humidity, gas, smoke, door, window, liquid, power, noisiness, other type defined in org.osgi.service.dal.functions.Types or vendor specific type.		

LevelData data structure is used to provide information about the function level. That data object contains the BigDecimal value and the value unit. The measurement unit is used as it's defined in RFC-0196 OSGi Device



February 24, 2014

Abstraction Later. The immutable LevelData.unit field is accessible with LevelData.getUnit() getter. The immutable LevelData.level field is accessible with LevelData.getLevel() getter.

The function class diagram is depicted on Illustration 3.

5.1.4 MultiLevelSensor Function

MultiLevelSensor function provides multi-level sensor monitoring. It reports its state when an important event is available. There are no operations. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later. The full function definition is available in the next table.

MultiLevelSensor		
Name	Description	
Properties		
data	Contains the current state of MultiLevelSensor. The property access can be: readable and eventable.	
Types		
light, temperature, flow, pressure, humidity, gas, smoke, door, window, liquid, power, noisiness, rain, other type defined in org.osgi.service.dal.functions.Types or vendor specific type.		

MultiLevelSensor and MultiLevelControl are using the same LevelData data structure to provide information about the level. For more details see the definition in MultiLevelControl Function. The function class diagram is depicted on Illustration 3.

5.1.5 Meter Function

Meter function can measure metering information.

Meter Meter		
Name	Description	
Oper	ations	
resetTotal	Resets the total metering info.	
Properties		
total	Contains the total consumption. It has been measured since the last call of resetTotal or device initial run. The property access is readable.	
current	Contains the current consumption. The property is readable.	
Service Properties		
dal.meter.flow	Contains the metering flow. Currently, it can be "in" and "out".	
Types		
pressure, gas, power, water, heat, cold, other type defined in org.osgi.service.dal.functions.Types or vendor specific type.		



February 24, 2014

Meter function is using the same LevelData data structure as MultiLevelSensor and MultiLevelControl to provide metering information. For more details see the definition in MultiLevelControl Function. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later. The function class diagram is depicted on Illustration 3.

5.1.6 Alarm Function

Alarm function provides alarm sensor support. There is only one eventable property and no operations. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later.

Ak	arm	
Name	Description	
Properties		
alarm	Specifies the alarm property name. The property is eventable.	

AlarmData data structure is used to provide information about the available alarm. That data object contains the alarm type and severity.

The function class diagram is depicted on Illustration 3.

5.1.7 Keypad Function

Keypad function provides support for keypad control. A keypad typically consists of one or more keys/buttons, which can be discerned. Different types of key presses like short and long press can typically also be detected. There is only one eventable property and no operations. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later.

Keypad		
Name	Description	
Properties		
key	Specifies a property name for a key from the keypad. The property is eventable.	

KeypadData data structure is used to provide information when a change with some key from device keypad has occurred. That data object contains the event type, key code and key name. Currently, there are a few predefined event types:

- EVENT TYPE PRESSED used for a key pressed;
- EVENT TYPE PRESSED LONG used for a long key pressed;
- EVENT TYPE PRESSED DOUBLE used for a double key pressed;
- EVENT TYPE PRESSED DOUBLE LONG used for a double and long key pressed;
- EVENT TYPE RELEASED used for a key released.
- EVENT TYPE UNKNOWN represents an unknown keypad event type.

The function class diagram is depicted on Illustration 3.



February 24, 2014

5.1.8 WakeUp Function

WakeUp function provides device awake monitoring and management. It's especially applicable to battery-operated devices. Such device can notify the system that it's awake and can receive commands with an event to property PROPERTY_AWAKE. The property eventing must follow the definition in RFC-0196 OSGi Device Abstraction Later.


The device can periodically wake up for commands. The interval can be managed with PROPERTY WAKE UP INTERVAL property.

The application can minimize the power consumption with sleep() operation. As a result, the device will sleep and will not receive commands to the next awake.

WakeUp		
Name	Description	
Prop	erties	
awake	Specifies the awake eventable property name. If the device is awake, it will trigger a property event. The property value type is BooleanData.	
wakeUpInterval	Specifies the wake up interval. The device can periodically wake up and receive commands. That interval is managed by this property. The property can be readable and writable. The property value type is LevelData.	
Operations		
sleep	The device is forced to sleep to minimize the power consumption.	

February 24, 2014

The function class diagram is depicted on Illustration 3.



6 Data Transfer Objects

TODO: Do we need those objects?



7 Javadoc



Draft February 24, 2014

OSGi Javadoc

2/24/14 10:32 AM

Package Sum	mary	Page
org.osgi.servic e.dal.functions	Functions 1.0.	15
org.osgi.servic e.dal.functions. data	Function Data 1.0.	45

Package org.osgi.service.dal.functions

Functions 1.0.

See:

Description

Interface Sum	Interface Summary	
<u>Alarm</u>	Alarm function provides alarm sensor support.	16
<u>BooleanControl</u>	BooleanControl function provides a boolean control support.	17
<u>BooleanSensor</u>	BooleanSensor function provides boolean sensor monitoring.	21
<u>Keypad</u>	Keypad function provides support for keypad control.	23
<u>Meter</u>	Meter function can measure metering information.	24
<u>MultiLevelControl</u>	MultiLevelControl function provides multi-level control support.	28
<u>MultiLevelSensor</u>	MultiLevelSensor function provides multi-level sensor monitoring.	31
<u>Types</u>	Shares common constants for all functions defined in this package.	33
<u>WakeU</u> p	WakeUp function provides device awake monitoring and management.	42

Package org.osgi.service.dal.functions Description

Functions 1.0.

Bundles wishing to use this package must list the package in the Import-Package header of the bundle's manifest. This package has two types of users: the consumers that use the API in this package and the providers that implement the API in this package.

Example import for consumers using the API in this package:

```
Import-Package: org.osgi.service.dal.functions; version="[1.0,2.0)"
```

Example import for providers implementing the API in this package:

OSGiJavadoc-- 1/22/13 Page 15 of 68

Interface Alarm

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

public interface Alarm
extends org.osgi.service.dal.Function

Alarm function provides alarm sensor support. There is only one eventable property and no operations.

See Also:

AlarmData

Field Su	ımmary	Page
String	PROPERTY_ALARM	40
	Specifies the alarm property name.	16

Fields inherited from interface org.osgi.service.dal.Function

SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE_REFERENCE_UIDS, SERVICE_TYPE, SERVICE_UID, SERVICE_VERSION

Methods inherited from interface org.osgi.service.dal.Function

 $\verb"getOperationMetadata", getPropertyMetadata", getServiceProperty$

Field Detail

PROPERTY_ALARM

public static final String PROPERTY_ALARM = "alarm"

Specifies the alarm property name. The property is eventable.

See Also:

AlarmData

OSGiJavadoc-- 1/22/13 Page 16 of 68

Interface BooleanControl

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

public interface BooleanControl
extends org.osgi.service.dal.Function

BooleanControl function provides a boolean control support. The function state is accessible with getData() getter and setData(boolean) setter. The state can be reversed with reverse() method, can be set to true value with setTrue() method and can be set to false value with setTrue() method.

As an example, the function is easily mappable to ZigBee OnOff cluster and Z-Wave Binary Switch command class. The control type can be:

- Types.TYPE LIGHT
- Types.TYPE_DOOR
- Types.TYPE WINDOW
- Types.TYPE POWER
- other type defined in <u>Types</u>
- · custom vendor specific type

See Also:

BooleanData

Field Summary		Page
String	OPERATION_REVERSE Specifies the reverse operation name.	18
String	OPERATION_SET_FALSE Specifies the operation name, which sets the control state to false value.	18
String	OPERATION SET TRUE Specifies the operation name, which sets the control state to true value.	18
String	PROPERTY_DATA Specifies the state property name.	18

Fields inherited from interface org.osgi.service.dal.Function SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE REFERENCE UIDS, SERVICE TYPE, SERVICE UID, SERVICE VERSION

Method	Method Summary	
BooleanDat a	<pre>getData() Returns the current state of BooleanControl.</pre>	18
void	reverse() Reverses the BooleanControl state.	19
void	setData (boolean data) Sets the BooleanControl state to the specified value.	19
void	<pre>setFalse() Sets the BooleanControl state to false value.</pre>	20

OSGiJavadoc-- 1/22/13 Page 17 of 68

```
void setTrue()
Sets the BooleanControl state to true value.
```

Methods inherited from interface org.osgi.service.dal.Function

getOperationMetadata, getPropertyMetadata, getServiceProperty

Field Detail

OPERATION REVERSE

```
public static final String OPERATION REVERSE = "reverse"
```

Specifies the reverse operation name. The operation can be executed with <u>reverse()</u> method.

OPERATION_SET_TRUE

```
public static final String OPERATION_SET_TRUE = "setTrue"
```

Specifies the operation name, which sets the control state to true value. The operation can be executed with setTrue () method.

OPERATION SET FALSE

```
public static final String OPERATION SET FALSE = "setFalse"
```

Specifies the operation name, which sets the control state to false value. The operation can be executed with setFalse() method.

PROPERTY_DATA

```
public static final String PROPERTY DATA = "data"
```

Specifies the state property name. The property value is accessible with getData() method.

See Also:

<u>BooleanData</u>

Method Detail

getData

Returns the current state of BooleanControl. It's a getter method for PROPERTY DATA property.

Returns:

The current state of BooleanControl.

OSGiJavadoc-- 1/22/13 Page 18 of 68

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

See Also:

BooleanData, PROPERTY DATA

setData

Sets the BooleanControl state to the specified value. It's setter method for PROPERTY DATA property.

Parameters:

data - The new function value.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

IllegalArgumentException - If there is an invalid argument.

See Also:

PROPERTY_DATA

reverse

Reverses the BooleanControl state. If the current state represents true value, it'll be reversed to false. If the current state represents false value, it'll be reversed to true. The operation name is OPERATION_REVERSE.

Throws:

```
UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.
```

setTrue

Sets the BooleanControl state to true value. The operation name is OPERATION SET TRUE.

Throws:

UnsupportedOperationException - If the operation is not supported.

OSGiJavadoc-- 1/22/13 Page 19 of 68

IllegalStateException - If this function service object has already been unregistered. org.osgi.service.dal.DeviceException - If an operation error is available.

setFalse

void setFalse()

Sets the BooleanControl state to false value. The operation name is OPERATION SET FALSE.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

OSGiJavadoc-- 1/22/13 Page 20 of 68

Interface BooleanSensor

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

```
public interface BooleanSensor
extends org.osgi.service.dal.Function
```

BooleanSensor function provides boolean sensor monitoring. It reports its state when an important event is available. The state is accessible with getData() getter. There are no operations.

As an example, the function is easily mappable to ZigBee Occupancy Sensing cluster and Z-Wave Binary Sensor command class. The sensor type can be:

- Types.TYPE_LIGHT
- Types.TYPE GAS
- Types.TYPE SMOKE
- Types.TYPE DOOR
- Types.TYPE WINDOW
- Types.TYPE_POWER
- Types.TYPE RAIN
- Types.TYPE CONTACT
- Types.TYPE FIRE
- Types.TYPE_OCCUPANCY
- Types.TYPE WATER
- Types.TYPE MOTION
- other type defined in Types
- custom vendor specific type

See Also:

BooleanData

Field Su	mmary	Page	
String	PROPERTY_DATA		
	Specifies the state property name.	22	

Fields inherited from interface org.osgi.service.dal.Function SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE_REFERENCE_UIDS, SERVICE_TYPE, SERVICE_UID, SERVICE_VERSION SERVICE_VERSION

Method	Summary	Page
	getData()	22
•	Returns the BooleanSensorcurrent state.	22

Methods inherited from interface org.osgi.service.dal.Function getOperationMetadata, getPropertyMetadata, getServiceProperty

OSGiJavadoc-- 1/22/13 Page 21 of 68

Field Detail

PROPERTY_DATA

```
public static final String PROPERTY_DATA = "data"
```

Specifies the state property name. The property value is accessible with getData() getter.

Method Detail

getData

Returns the BooleanSensorcurrent state. It's a getter method for PROPERTY DATA property.

Returns:

The BooleanSensor current state.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

See Also:

<u>BooleanData</u>

OSGiJavadoc-- 1/22/13 Page 22 of 68

Interface Keypad

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

```
public interface Keypad
extends org.osgi.service.dal.Function
```

Keypad function provides support for keypad control. A keypad typically consists of one or more keys/buttons, which can be discerned. Different types of key presses like short and long press can typically also be detected. There is only one eventable property and no operations.

Keypad can enumerate all supported keys in the key property metadata, org.osgi.service.dal.PropertyMetadata.getEnumValues(String). KeypadData event type will be KeypadData.event type unknown in this case.

See Also:

KeypadData

Field Su	mmary	Page
String	PROPERTY_KEY	00
	Specifies a property name for a key from the keypad.	23

Fields inherited from interface org.osgi.service.dal.Function SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE_REFERENCE_UIDS, SERVICE_TYPE, SERVICE_UID, SERVICE_VERSION

Methods inherited from	interface org.osgi.servic	e.dal.Function
getOperationMetadata,	<pre>getPropertyMetadata,</pre>	getServiceProperty

Field Detail

PROPERTY_KEY

```
public static final String PROPERTY KEY = "key"
```

Specifies a property name for a key from the keypad. The property is eventable.

See Also:

KeypadData

OSGiJavadoc-- 1/22/13 Page 23 of 68

Interface Meter

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

```
public interface Meter
extends org.osgi.service.dal.Function
```

Meter function can measure metering information. The function provides three properties and one operation:

- PROPERTY CURRENT
- - property accessible with getCurrent() getter;
- PROPERTY TOTAL
- property accessible with getTotal() getter;
- SERVICE FLOW
- - property accessible with getTotal() getter;
- OPERATION RESET TOTAL
- operation can be executed with <u>resetTotal()</u>.

As an example, the function is easily mappable to ZigBee Simple Metering cluster and Z-Wave Meter command class. The sensor type can be:

- Types.TYPE PRESSURE
- Types.TYPE GAS
- Types.TYPE POWER
- Types.TYPE WATER
- Types.TYPE HEAT
- Types.TYPE COLD
- other type defined in <u>Types</u>
- · custom vendor specific type

See Also:

<u>LevelData</u>

Field Su	eld Summary	
String	<u>FLOW_IN</u>	0.5
	Represents the metering consumption flow.	25
String	<u>FLOW_OUT</u>	0.5
	Represents the metering generation flow.	25
String	OPERATION_RESET_TOTAL	
	Specifies the reset total operation name.	26
String	PROPERTY_CURRENT	0.5
	Specifies the current consumption property name.	25
String	PROPERTY_TOTAL	0.5
	Specifies the total consumption property name.	25
String	SERVICE_FLOW	25
	The service property value contains the metering flow.	25

OSGiJavadoc-- 1/22/13 Page 24 of 68

Fields inherited from interface org.osgi.service.dal.Function

SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE REFERENCE UIDS, SERVICE TYPE, SERVICE UID, SERVICE VERSION

Method	Method Summary	
LevelData	<pre>getCurrent()</pre>	26
	Returns the current metering info.	20
LevelData	<pre>getTotal()</pre>	26
	Returns the total metering info.	20
void	<pre>resetTotal()</pre>	26
	Resets the total metering info.	20

Methods inherited from interface org.osgi.service.dal.Function

getOperationMetadata, getPropertyMetadata, getServiceProperty

Field Detail

FLOW_IN

public static final String FLOW_IN = "in"

Represents the metering consumption flow. It can be used as **SERVICE FLOW** property value.

FLOW_OUT

public static final String FLOW OUT = "out"

Represents the metering generation flow. It can be used as <u>SERVICE FLOW</u> property value.

SERVICE_FLOW

public static final String SERVICE FLOW = "dal.meter.flow"

The service property value contains the metering flow. It's an optional property and available only if it's supported by the meter. The value type is <code>java.lang.String</code>. Possible property values:

- FLOW IN
- <u>FLOW_OUT</u>

PROPERTY_CURRENT

```
public static final String PROPERTY_CURRENT = "current"
```

Specifies the current consumption property name. The property can be read with getCurrent() getter.

PROPERTY_TOTAL

```
public static final String PROPERTY_TOTAL = "total"
```

OSGiJavadoc-- 1/22/13 Page 25 of 68

Specifies the total consumption property name. It has been measured since the last call of resetTotal()
or device initial run. The property can be read with getTotal() getter.

OPERATION_RESET_TOTAL

```
public static final String OPERATION_RESET_TOTAL = "resetTotal"
```

Specifies the reset total operation name. The operation can be executed with resetTotal () method.

Method Detail

getCurrent

Returns the current metering info. It's a getter method for **PROPERTY CURRENT** property.

Returns:

The current metering info.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

See Also:

LevelData

getTotal

Returns the total metering info. It's a getter method for PROPERTY TOTAL property.

Returns:

The total metering info.

Throws:

```
UnsupportedOperationException - If the operation is not supported. IllegalStateException - If this function service object has already been unregistered. org.osgi.service.dal.DeviceException - If an operation error is available.
```

See Also:

<u>LevelData</u>

resetTotal

OSGiJavadoc-- 1/22/13 Page 26 of 68

Resets the total metering info.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

OSGiJavadoc-- 1/22/13 Page 27 of 68

Interface MultiLevelControl

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

public interface MultiLevelControl
extends org.osgi.service.dal.Function

MultiLevelControl function provides multi-level control support. The function level is accessible with getData(BigDecimal) setter and setData(BigDecimal) setter.

As an example, the function is easily mappable to ZigBee Level Control and Z-Wave Multilevel Switch command class. The control type can be:

- Types.TYPE_LIGHT
- Types.TYPE TEMPERATURE
- Types.TYPE FLOW
- Types.TYPE PRESSURE
- Types.TYPE HUMIDITY
- Types.TYPE_GAS
- Types.TYPE_SMOKE
- Types.TYPE_DOOR
- Types.TYPE WINDOW
- Types.TYPE_LIQUID
- Types.TYPE POWER
- Types.TYPE_NOISINESS
- other type defined in <u>Types</u>
- custom vendor specific type

See Also:

LevelData

Field Su	Field Summary	
String	PROPERTY_DATA	-
	Specifies the level property name.	29

Fields inherited from interface org.osgi.service.dal.Function SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE_REFERENCE_UIDS, SERVICE_TYPE, SERVICE_UID, SERVICE_VERSION

Method	Summary	Page
LevelData	<pre>getData() Returns MultiLevelControl level.</pre>	29
void	<pre>setData (BigDecimal level) Sets MultiLevelControl level to the specified value.</pre>	29
void	<pre>setData(BigDecimal level, String unit) Sets MultiLevelControl level according to the specified unit.</pre>	30

OSGiJavadoc-- 1/22/13 Page 28 of 68

Methods inherited from interface org.osgi.service.dal.Function

getOperationMetadata, getPropertyMetadata, getServiceProperty

Field Detail

PROPERTY_DATA

```
public static final String PROPERTY_DATA = "data"
```

Specifies the level property name. The property can be read with getData() getter and can be set with setData(BigDecimal) or setData(BigDecimal), String) setters.

Method Detail

getData

Returns MultiLevelControl level. It's a getter method for PROPERTY_DATA property.

Returns:

MultiLevelControl level.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

See Also:

LevelData

setData

Sets MultiLevelControl level to the specified value. It's a setter method for PROPERTY DATA property.

Parameters:

level - The new control level.

Throws:

```
UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

IllegalArgumentException - If there is an invalid argument.
```

OSGiJavadoc-- 1/22/13 Page 29 of 68

setData

Sets MultiLevelControl level according to the specified unit. It's a setter method for PROPERTY_DATA property.

Parameters:

level - The new control level. unit - The level unit.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

IllegalArgumentException - If there is an invalid argument.

OSGiJavadoc-- 1/22/13 Page 30 of 68

Interface MultiLevelSensor

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

public interface MultiLevelSensor
extends org.osgi.service.dal.Function

MultiLevelSensor function provides multi-level sensor monitoring. It reports its state when an important event is available. The state is accessible with getter. There are no operations.

As an example, the function is easily mappable to ZigBee Illuminance Measurement, Temperature Measurement, Pressure Measurement, Flow Measurement and Relative Humidity Measurement cluster and Z-Wave Multilevel Sensor command class. The sensor type can be:

- Types.TYPE_LIGHT
- Types.TYPE_TEMPERATURE
- Types.TYPE FLOW
- Types.TYPE PRESSURE
- Types.TYPE HUMIDITY
- Types.TYPE GAS
- Types.TYPE SMOKE
- Types.TYPE DOOR
- Types.TYPE WINDOW
- Types.TYPE LIQUID
- Types.TYPE POWER
- Types.TYPE NOISINESS
- Types.TYPE RAIN
- other type defined in <u>Types</u>
- custom vendor specific type

See Also:

<u>LevelData</u>

Field Summary		Page
String	PROPERTY_DATA	
	Specifies the state property name.	32

Fields inherited from interface org.osgi.service.dal.Function SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE_REFERENCE_UIDS, SERVICE_TYPE, SERVICE_UID, SERVICE_VERSION

Method Summary		Page
<u>LevelData</u>	<pre>getData()</pre>	20
	Returns the MultiLevelSensor current state.	32

Methods inherited from interfa	ce org.osgi.service.dal.Function
getOperationMetadata, getP	ropertyMetadata, getServiceProperty

OSGiJavadoc-- 4/8/13 Page 31 of 68

Field Detail

PROPERTY_DATA

```
public static final String PROPERTY_DATA = "data"
```

Specifies the state property name. The property can be read with getData() getter.

See Also:

<u>LevelData</u>

Method Detail

getData

Returns the MultiLevelSensor current state. It's a getter method for PROPERTY_DATA property.

Returns:

The MultiLevelSensor current state.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

See Also:

<u>LevelData</u>

OSGiJavadoc-- 4/8/13 Page 32 of 68

Interface Types

org.osgi.service.dal.functions

public interface Types

Shares common constants for all functions defined in this package. The defined function types are mapped as follow:

- TYPE LIGHT MultiLevelControl, MultiLevelSensor, BooleanSensor and BooleanControl
- TYPE TEMPERATURE MultiLevelControl and MultiLevelSensor
- TYPE FLOW MultiLevelControl and MultiLevelSensor
- TYPE_PRESSURE MultiLevelControl, MultiLevelSensor and Meter
- TYPE HUMIDITY MultiLevelControl and MultiLevelSensor
- TYPE_GAS MultiLevelControl, MultiLevelSensor, BooleanSensor and Meter
- TYPE_SMOKE MultiLevelControl, MultiLevelSensor and BooleanSensor
- TYPE DOOR MultiLevelControl, MultiLevelSensor, BooleanSensor and BooleanControl
- TYPE WINDOW MultiLevelControl, MultiLevelSensor, BooleanSensor and BooleanControl
- TYPE LIQUID MultiLevelControl and MultiLevelSensor
- TYPE_POWER MultiLevelControl, MultiLevelSensor, BooleanSensor, BooleanControl and Meter
- TYPE NOISINESS MultiLevelControl and MultiLevelSensor
- TYPE RAIN MultiLevelSensor and BooleanSensor
- TYPE CONTACT BooleanSensor
- TYPE FIRE BooleanSensor
- TYPE OCCUPANCY BooleanSensor
- TYPE WATER BooleanSensor and Meter
- TYPE MOTION BooleanSensor
- TYPE HEAT Meter
- TYPE COLD Meter

The mapping is not mandatory. The function can use custom defined types.

Field Su	ımmary									Page
String	TYPE_COLD The fun	ction type is	• Mete		cates that the source.	Meter	measures	thermal	energy	41
	This org.osgi.ser	type vice.dal.I	can Function.	be SERVICE	- 1	as	а	value	of	
String	_	ction type is		rySensor	· - indicates th	nat the	BinarySe	nsor can	detect	39

OSGiJavadoc-- 4/8/13 Page 33 of 68

String	TYPE DOOR	
	The function type is applicable to:	
	• MultiLevelControl - indicates that the MultiLevelControl can control the door position.	38
String	TYPE_FIRE The function type is applicable to:	
	The function type is applicable to:	39
	BinarySensor - indicates that the BinarySensor can detect fire.	
String	TYPE_FLOW	
	The function type is applicable to:	
	 MultiLevelControl - indicates that the MultiLevelControl can control the flow level. 	36
String	TYPE_GAS	
	The function type is applicable to:	
	• MultilevelControl - indicates that the MultilevelControl can control the gas level.	37
String	TYPE_HEAT	
	The function type is applicable to:	
	• Meter - indicates that the Meter measures thermal energy provided by a source.	40
	This type can be specified as a value of org.osgi.service.dal.Function.SERVICE_TYPE.	
String	TYPE_HUMIDITY	
	The function type is applicable to:	
	 MultiLevelControl - indicates that the MultiLevelControl can control the humidity level. 	37
String	TYPE_LIGHT	
	The function type is applicable to:	
	 MultiLevelControl - indicates that the MultiLevelControl can control light devices. 	36
String	TYPE_LIQUID	
	The function type is applicable to:	
	• MultiLevelControl - indicates that the MultiLevelControl can control the liquid level.	38
String	TYPE_MOTION	
	The function type is applicable to:	40
	BinarySensor - indicates that the BinarySensor can detect motion.	70

OSGiJavadoc-- 4/8/13 Page 34 of 68

String		
	TYPE_NOISINESS	
	The function type is applicable to:	
	MultiLevelControl - indicates that the MultiLevelControl can control the noise level.	39
String	TYPE OCCUPANCY	
	The function type is applicable to:	
	BinarySensor - indicates that the BinarySensor can detect presence.	40
String	TYPE POWER	
	The function type is applicable to:	
	 MultiLevelControl - indicates that the MultiLevelControl can control the power level. 	38
String	TYPE PRESSURE	
	The function type is applicable to:	
		36
	 MultiLevelControl - indicates that the MultiLevelControl can control the pressure level. 	
String	TYPE_RAIN	
	The function type is applicable to:	
	MultiLevelSensor - indicates that the MultiLevelSensor can monitor the rain rate.	39
String	TYPE_SMOKE The function type is applicable to:	
	The function type is applicable to:	
	 MultiLevelControl - indicates that the MultiLevelControl can control the smoke level. 	37
String	TYPE TEMPERATURE	
	The function type is applicable to:	
	MultiLevelControl - indicates that the MultiLevelControl can control	36
	temperature devices.	
String	temperature devices. TYPE_WATER	
String		
String	TYPE_WATER	40
	TYPE_WATER The function type is applicable to:	40
	TYPE_WATER The function type is applicable to: • BinarySensor - indicates that the BinarySensor can detect water leak.	40
	TYPE_WATER The function type is applicable to: • BinarySensor - indicates that the BinarySensor can detect water leak. TYPE_WINDOW	40

OSGiJavadoc-- 4/8/13 Page 35 of 68

Field Detail

TYPE_LIGHT

public static final String TYPE_LIGHT = "light"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control light devices. Usually, such devices are called dimmable. MultiLevelControl minimum value can switch off the device and MultiLevelControl maximum value can increase the device light to the maximum possible value.
- MultiLevelSensor indicates that the sensor can monitor the light level.
- BinarySensor indicates that the BinarySensor can detected light. true state means that there is light. false state means that there is no light.
- BinaryControl indicates that there is a light device control. true state means that the light device will be turned on. false state means that the light device will be turned off.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_TEMPERATURE

public static final String TYPE_TEMPERATURE = "temperature"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control temperature devices. For example, such device can be thermostat. MultiLevelControl minimum value is the lowest supported temperature. MultiLevelControl maximum value is the highest supported temperature.
- MultiLevelSensor indicates that the sensor can monitor the temperature.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE FLOW

public static final String TYPE FLOW = "flow"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the flow level. MultiLevelControl minimum value is the minimum supported flow level. MultiLevelControl maximum value is the maximum supported flow level.
- MultiLevelSensor indicates that the sensor can monitor the flow level.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_PRESSURE

public static final String TYPE_PRESSURE = "pressure"

The function type is applicable to:

OSGiJavadoc-- 4/8/13 Page 36 of 68

- MultiLevelControl indicates that the MultiLevelControl can control the pressure level.

 MultiLevelControl minimum value is the lowest supported pressure level. MultiLevelControl maximum value is the highest supported pressure level.
- MultiLevelSensor indicates that the sensor can monitor the pressure level.
- Meter Indicates that the Meter measures pressure.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_HUMIDITY

public static final String TYPE_HUMIDITY = "humidity"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the humidity level. It's typical functionality for HVAC (heating, ventilation, and air conditioning) devices. MultiLevelControl minimum value is the lowest supported humidity level. MultiLevelControl maximum value is the highest supported humidity level.
- MultiLevelSensor indicates that the sensor can monitor the humidity level.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_GAS

public static final String TYPE_GAS = "gas"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the gas level. MultiLevelControl minimum value is the lowest supported gas level. MultiLevelControl maximum value is the highest supported gas level.
- MultiLevelSensor indicates that the sensor can monitor the gas level.
- BinarySensor indicates that the BinarySensor supports gas detection. true state means there is gas. false state means that there is no gas.
- Meter indicates that the Meter measures the gas consumption.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE SMOKE

public static final String TYPE_SMOKE = "smoke"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the smoke level. MultiLevelControl minimum value is the lowest supported smoke level. MultiLevelControl maximum value is the highest supported smoke level.
- MultiLevelSensor indicates that the sensor can monitor the smoke level.
- BinarySensor indicates that the BinarySensor can detect smoke. true state means that there is smoke. false state means that there is no rain.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

OSGiJavadoc-- 4/8/13 Page 37 of 68

TYPE_DOOR

public static final String TYPE DOOR = "door"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the door position. MultiLevelControl minimum value can completely close the door. MultiLevelControl maximum value can open the door to the maximum allowed position.
- MultiLevelSensor indicates that the sensor can monitor the door position.
- BinarySensor indicates that the BinarySensor can detect the door state. true state means that the door is opened. false state means that the door is closed.
- BinaryControl indicates that there is a door position control. true state means that the door will be opened. false state means that the door will be closed.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE WINDOW

public static final String TYPE WINDOW = "window"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the window position. MultiLevelControl minimum value can completely close the window. MultiLevelControl maximum value can open the window to the maximum allowed position.
- MultiLevelSensor indicates that the sensor can monitor the window position.
- BinarySensor indicates that the BinarySensor can window state. true state means that the window is opened. false state means that the window is closed.
- BinaryControl indicates that there is a window position control. true state means that the window will be opened. false state means that the window will be closed.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE_TYPE.

TYPE LIQUID

public static final String TYPE LIQUID = "liquid"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the liquid level. MultiLevelControl minimum value is the lowest supported liquid level. MultiLevelControl maximum value is the highest supported liquid level.
- MultiLevelSensor indicates that the sensor can monitor the liquid level.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE_TYPE.

TYPE POWER

```
public static final String TYPE_POWER = "power"
```

The function type is applicable to:

OSGiJavadoc-- 4/8/13 Page 38 of 68

- MultiLevelControl indicates that the MultiLevelControl can control the power level.
 MultiLevelControl minimum value is the lowest supported power level.
 MultiLevelControl maximum value is the highest supported power level.
- MultiLevelSensor indicates that the sensor can monitor the power level.
- BinarySensor indicates that the BinarySensor can detect motion. true state means that there is power restore. false state means that there is power cut.
- BinaryControl indicates that there is electricity control. true state means that the power will be restored. false state means that the power will be cut.
- Meter indicates that the Meter measures the power consumption.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_NOISINESS

public static final String TYPE_NOISINESS = "noisiness"

The function type is applicable to:

- MultiLevelControl indicates that the MultiLevelControl can control the noise level.

 MultiLevelControl minimum value is the lowest supported noise level. MultiLevelControl maximum value is the highest supported noise level.
- MultiLevelSensor indicates that the sensor can monitor the noise level.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE RAIN

public static final String TYPE_RAIN = "rain"

The function type is applicable to:

- MultiLevelSensor indicates that the MultiLevelSensor can monitor the rain rate. It's not applicable to MultiLevelControl.
- BinarySensor indicates that the BinarySensor can detect rain. true state means that there is rain. false state means that there is no rain.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_CONTACT

public static final String TYPE_CONTACT = "contact"

The function type is applicable to:

• BinarySensor - indicates that the BinarySensor can detect contact. true state means that there is contact. false state means that there is no contact.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_FIRE

public static final String TYPE_FIRE = "fire"

OSGiJavadoc-- 4/8/13 Page 39 of 68

The function type is applicable to:

• BinarySensor - indicates that the BinarySensor can detect fire. true state means that there is fire. false state means that there is no fire.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_OCCUPANCY

```
public static final String TYPE_OCCUPANCY = "occupancy"
```

The function type is applicable to:

• BinarySensor - indicates that the BinarySensor can detect presence. true state means that someone is detected. false state means that nobody is detected.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

TYPE_WATER

```
public static final String TYPE WATER = "water"
```

The function type is applicable to:

- BinarySensor indicates that the BinarySensor can detect water leak. true state means that there is water leak. false state means that there is no water leak.
- Meter indicates that the Meter measures water consumption.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE_TYPE.

TYPE_MOTION

```
public static final String TYPE MOTION = "motion"
```

The function type is applicable to:

• BinarySensor - indicates that the BinarySensor can detect motion. true state means that there is motion detection. false state means that there is no motion detection.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE_TYPE.

TYPE HEAT

```
public static final String TYPE_HEAT = "heat"
```

The function type is applicable to:

Meter - indicates that the Meter measures thermal energy provided by a source.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE TYPE.

OSGiJavadoc-- 4/8/13 Page 40 of 68

TYPE_COLD

public static final String TYPE_COLD = "cold"

The function type is applicable to:

• Meter - indicates that the Meter measures thermal energy provided by a source.

This type can be specified as a value of org.osgi.service.dal.Function.SERVICE_TYPE.

OSGiJavadoc-- 4/8/13 Page 41 of 68

Interface WakeUp

org.osgi.service.dal.functions

All Superinterfaces:

org.osgi.service.dal.Function

```
public interface WakeUp
extends org.osgi.service.dal.Function
```

WakeUp function provides device awake monitoring and management. It's especially applicable to battery-operated devices. Such device can notify the system that it's awake and can receive commands with an event to property PROPERTY AWAKE.

The device can periodically wake up for commands. The interval can be managed with PROPERTY WAKE UP INTERVAL property.

The application can minimize the power consumption with steep() operation. As a result, the device will sleep and will not receive commands to the next awake.

See Also:

LevelData, BooleanData

Field Su	ımmary	Page
String	OPERATION_SLEEP Specifies the sleep operation name.	43
String	PROPERTY_AWAKE Specifies the awake property name.	43
String	PROPERTY_WAKE_UP_INTERVAL Specifies the wake up interval.	43

Fields inherited from interface org.osgi.service.dal.Function

SERVICE_DESCRIPTION, SERVICE_DEVICE_UID, SERVICE_OPERATION_NAMES, SERVICE_PROPERTY_NAMES, SERVICE REFERENCE UIDS, SERVICE TYPE, SERVICE UID, SERVICE VERSION

Method	Summary	Page
<u>LevelData</u>	getWakeUpInterval () Returns the current wake up interval.	43
void	<pre>setWakeUpInterval (BigDecimal interval) Sets wake up interval according to the default unit.</pre>	44
void	<pre>setWakeUpInterval (BigDecimal interval, String unit) Sets wake up interval according to the specified unit.</pre>	44
void	Sleep() The device is forced to sleep to minimize the power consumption.	44

Methods inherited from interface org.osgi.service.dal.Function getOperationMetadata, getPropertyMetadata, getServiceProperty

OSGiJavadoc-- 4/8/13 Page 42 of 68

Field Detail

PROPERTY AWAKE

public static final String PROPERTY_AWAKE = "awake"

Specifies the awake property name. The property access type can be org.osgi.service.dal.PropertyMetadata.PROPERTY_ACCESS_EVENTABLE. If the device is awake, it will trigger a property event.

The property value type is BooleanData. The boolean data is always true. It marks that the device is awake.

PROPERTY_WAKE_UP_INTERVAL

```
public static final String PROPERTY WAKE UP INTERVAL = "wakeUpInterval"
```

Specifies the wake up interval. The device can periodically wake up and receive commands. That interval is managed by this property. The current property value is available with getWakeUpInterval() and can be modified with setWakeUpInterval(BigDecimal) and setWakeUpInterval(BigDecimal).

OPERATION_SLEEP

```
public static final String OPERATION SLEEP = "sleep"
```

Specifies the sleep operation name. The operation can be executed with sleep() method.

Method Detail

getWakeUpInterval

Returns the current wake up interval. It's a getter method for PROPERTY_WAKE_UP_INTERVAL property. The device can periodically wake up and receive command based on this interval.

The interval can be measured in different units like hours, minutes, seconds etc. The unit is specified in LevelData instance.

Returns:

The current wake up interval.

Throws:

```
UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.
```

See Also:

<u>LevelData</u>

OSGiJavadoc-- 4/8/13 Page 43 of 68

setWakeUpInterval

Sets wake up interval according to the default unit. It's a setter method for PROPERTY_WAKE_UP_INTERVAL property. The device can periodically wake up and receive command based on this interval.

Parameters:

interval - The new wake up interval.

Throws:

UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

IllegalArgumentException - If there is an invalid argument.

setWakeUpInterval

Sets wake up interval according to the specified unit. It's a setter method for PROPERTY_WAKE_UP_INTERVAL property. The device can periodically wake up and receive command based on this interval.

Parameters:

```
interval - The new wake up interval. unit - The interval unit.
```

Throws:

```
UnsupportedOperationException - If the operation is not supported.

IllegalStateException - If this function service object has already been unregistered.

org.osgi.service.dal.DeviceException - If an operation error is available.

IllegalArgumentException - If there is an invalid argument.
```

sleep

The device is forced to sleep to minimize the power consumption.

Throws:

```
UnsupportedOperationException - If the operation is not supported. IllegalStateException - If this function service object has already been unregistered. org.osgi.service.dal.DeviceException - If an operation error is available.
```

OSGiJavadoc-- 4/8/13 Page 44 of 68

Package org.osgi.service.dal.functions.data

Function Data 1.0.

See:

Description

Class Summary		Page
<u>AlarmData</u>	Function alarm data.	46
<u>BooleanData</u>	Function boolean data wrapper.	53
<u>KeypadData</u>	Represents a keypad event data that is collected when a change with some key from device keypad has occurred.	57
<u>LevelData</u>	Function level data wrapper.	63

Package org.osgi.service.dal.functions.data Description

Function Data 1.0.

Bundles wishing to use this package must list the package in the Import-Package header of the bundle's manifest. This package has two types of users: the consumers that use the API in this package and the providers that implement the API in this package.

Example import for consumers using the API in this package:

```
Import-Package: org.osgi.service.dal.functions.data; version="[1.0,2.0)"
```

Example import for providers implementing the API in this package:

```
Import-Package: org.osgi.service.dal.functions.data; version="[1.0,1.1)"
```

OSGiJavadoc-- 4/8/13 Page 45 of 68

Class AlarmData

org.osgi.service.dal.functions.data

```
java.lang.Object
    Lorg.osgi.service.dal.FunctionData
    Lorg.osgi.service.dal.functions.data.AlarmData
```

All Implemented Interfaces:

Comparable

```
public class AlarmData
extends org.osgi.service.dal.FunctionData
```

Function alarm data. It cares about the alarm type, severity, timestamp and additional metadata. It doesn't support unit. The alarm type is mapped to FunctionData value.

See Also:

Alarm, org.osgi.service.dal.FunctionData

Field Sur	nmary	Page
	FIELD_SEVERITY	47
String	Represents the severity field name.	47
	FIELD_TYPE	47
String	Represents the type field name.	47
int	severity	40
	Represents the alarm severity.	49
static int	SEVERITY_HIGH	40
	The severity rating indicates that there is an alarm with high priority.	49
static int	SEVERITY_LOW	49
	The severity rating indicates that there is an alarm with lowest priority.	49
static int	SEVERITY_MEDIUM	49
	The severity rating indicates that there is an alarm with medium priority.	49
static int	SEVERITY_NONE	49
	The severity constant indicates that there is no severity rating for this alarm.	45
static int	SEVERITY_URGENT	49
	The severity rating indicates that there an urgent alarm.	45
int	<u>type</u>	50
	Represents the alarm type.	30
static int	TYPE_COLD	48
	The alarm type indicates that temperature is too low.	40
static int	TYPE_GAS_CO	48
	The alarm type indicates that carbon monoxide is detected.	
static int	TYPE_GAS_CO2	48
	The alarm type indicates that carbon dioxide is detected.	,,,
static int	TYPE_HEAT	48
	The alarm type indicates that temperature is too high.	,,,
static int	TYPE_HW_FAIL	49
	The alarm type indicates that there is hardware failure.	

OSGiJavadoc-- 4/8/13 Page 46 of 68

static int	TYPE POWER FAIL	40
	The alarm type indicates a power cut.	48
static int	TYPE_SMOKE	40
	The alarm type indicates that smoke is detected.	48
static int	TYPE_SW_FAIL	40
	The alarm type indicates that there is software failure.	49
static int	TYPE_WATER	40
	The alarm type indicates that water leak is detected.	48

Fields inherited from class org.osgi.service.dal.FunctionData

FIELD_METADATA, FIELD_TIMESTAMP, META_INFO_DESCRIPTION, metadata, timestamp

Constructor Summary	Page	
AlarmData (Map fields)	50	
Constructs new AlarmData instance with the specified field values.	50	
<u>AlarmData</u> (long timestamp, Map metadata, int severity, int type)	50	
Constructs new AlarmData instance with the specified arguments.	50	

Method	Summary	Page
int	<pre>compareTo (Object o)</pre>	50
	Compares this AlarmData instance with the given argument.	52
boolean	equals (Object other)	
	Two AlarmData instances are equal if they contain equal metadata, timestamp, type and	51
	severity.	
int	<pre>getSeverity()</pre>	51
	Returns the alarm severity.	31
int	<pre>getType()</pre>	50
	Returns the alarm type.	30
int	hashCode ()	F.4
	Returns the hash code for this AlarmData object.	51

Methods inherited from class org.osgi.service.dal.FunctionData

getMetadata, getTimestamp

Field Detail

FIELD_SEVERITY

```
public static final String FIELD_SEVERITY = "severity"
```

Represents the severity field name. The field value is available with $\underline{\text{severity}}$ and $\underline{\text{getSeverity}}$. The field type is int. The constant can be used as a key to $\underline{\text{AlarmData}}(\underline{\text{Map}})$.

FIELD_TYPE

```
public static final String FIELD_TYPE = "type"
```

OSGiJavadoc-- 4/8/13 Page 47 of 68

Represents the type field name. The field value is available with $\underline{\text{type}}$ and $\underline{\text{getType}}$ (). The field type is int. The constant can be used as a key to $\underline{\text{AlarmData}}$ (Map).

TYPE_SMOKE

```
public static final int TYPE_SMOKE = 1
```

The alarm type indicates that smoke is detected.

TYPE_HEAT

```
public static final int TYPE_HEAT = 2
```

The alarm type indicates that temperature is too high.

TYPE_COLD

```
public static final int TYPE_COLD = 3
```

The alarm type indicates that temperature is too low.

TYPE_GAS_CO2

```
public static final int TYPE_GAS_CO2 = 4
```

The alarm type indicates that carbon dioxide is detected.

TYPE_GAS_CO

```
public static final int TYPE GAS CO = 5
```

The alarm type indicates that carbon monoxide is detected.

TYPE_WATER

```
public static final int TYPE_WATER = 6
```

The alarm type indicates that water leak is detected.

TYPE_POWER_FAIL

```
public static final int TYPE POWER FAIL = 7
```

The alarm type indicates a power cut.

OSGiJavadoc-- 4/8/13 Page 48 of 68

TYPE_HW_FAIL

```
public static final int TYPE_HW_FAIL = 8
```

The alarm type indicates that there is hardware failure.

TYPE_SW_FAIL

```
public static final int TYPE SW FAIL = 9
```

The alarm type indicates that there is software failure.

SEVERITY_NONE

```
public static final int SEVERITY_NONE = 0
```

The severity constant indicates that there is no severity rating for this alarm.

SEVERITY_LOW

```
public static final int SEVERITY_LOW = 1
```

The severity rating indicates that there is an alarm with lowest priority.

SEVERITY MEDIUM

```
public static final int SEVERITY_MEDIUM = 2
```

The severity rating indicates that there is an alarm with medium priority. The severity priority is higher than SEVERITY LOW and lower than SEVERITY HIGH.

SEVERITY_HIGH

```
public static final int SEVERITY_HIGH = 3
```

The severity rating indicates that there is an alarm with high priority. The severity priority is higher than SEVERITY MEDIUM and lower than SEVERITY URGENT.

SEVERITY_URGENT

```
public static final int SEVERITY_URGENT = 4
```

The severity rating indicates that there an urgent alarm. That severity has highest priority.

severity

```
public final int severity
```

OSGiJavadoc-- 4/8/13 Page 49 of 68

Represents the alarm severity. The field is accessible with getSeverity() getter. The vendor can define own alarm severity ratings with negative values.

type

```
public final int type
```

Represents the alarm type. The field is accessible with getType() getter. The vendor can define own alarm types with negative values.

Constructor Detail

AlarmData

```
public AlarmData(Map fields)
```

Constructs new AlarmData instance with the specified field values. The map keys must match to the field names. The map values will be assigned to the appropriate class fields. For example, the maps can be: {"severity"=Integer(1)...}. That map will initialize the FIELD_SEVERITY field with 1. If severity is missing, SEVERITY NONE is used.

FIELD SEVERITY field value type must be Integer. FIELD TYPE field value type must be Integer.

Parameters:

fields - Contains the new AlarmData instance field values.

Throws:

```
ClassCastException - If the field value types are not expected. IllegalArgumentException - If the alarm type is missing. NullPointerException - If the fields map is null.
```

AlarmData

Constructs new AlarmData instance with the specified arguments.

Parameters:

```
timestamp - The alarm data timestamp.
metadata - The alarm data metadata.
severity - The alarm data severity.
type - The alarm data type.
```

Method Detail

getType

```
public int getType()
```

Returns the alarm type. The type can be one of the predefined:

OSGiJavadoc-- 4/8/13 Page 50 of 68

- TYPE SMOKE
- TYPE HEAT
- TYPE COLD
- TYPE GAS CO
- TYPE GAS CO2
- TYPE WATER
- TYPE POWER FAIL
- TYPE HW FAIL
- TYPE SW FAIL

The vendor can define own alarm types with negative values.

Returns:

The alarm type.

getSeverity

```
public int getSeverity()
```

Returns the alarm severity.

Returns:

The alarm severity.

equals

```
public boolean equals(Object other)
```

Two AlarmData instances are equal if they contain equal metadata, timestamp, type and severity.

Overrides:

equals in class org.osgi.service.dal.FunctionData

Parameters:

other - The object to compare this data.

Returns:

true if this object is equivalent to the specified one.

See Also:

org.osgi.service.dal.FunctionData.equals(java.lang.Object)

hashCode

```
public int hashCode()
```

Returns the hash code for this AlarmData object. The hash code is a sum of org.osgi.service.dal.FunctionData.hashCode(), the alarm severity and the alarm type.

Overrides:

hashCode in class org.osgi.service.dal.FunctionData

Returns:

The hash code of this AlarmData object.

See Also:

org.osgi.service.dal.FunctionData.hashCode()

OSGiJavadoc-- 4/8/13 Page 51 of 68

compareTo

```
public int compareTo(Object o)
```

Compares this AlarmData instance with the given argument. The argument can be:

- AlarmData the method returns -1 if metadata, timestamp, type or severity are not equivalent. 0 if all fields are equivalent. 1 if all fields are equivalent and this instance severity is greater than the severity of the specified argument.
- Map the map must be built according the rules of AlarmData(Map). Metadata, timestamp, type and severity are compared according AlarmData argument rules.

Specified by:

compareTo in interface Comparable

Parameters:

o - An argument to be compared.

Returns:

-1, 0 or 1 depending on the comparison rules.

Throws:

ClassCastException - If the method is called with Map and the field value types are not expected. IllegalArgumentException - If the method is called with Map and the alarm type is missing. NullPointerException - If the argument is null.

See Also:

Comparable.compareTo(java.lang.Object)

OSGiJavadoc-- 4/8/13 Page 52 of 68

Class BooleanData

org.osgi.service.dal.functions.data

```
java.lang.Object
    Lorg.osgi.service.dal.FunctionData
    Lorg.osgi.service.dal.functions.data.BooleanData
```

All Implemented Interfaces:

Comparable

```
public class BooleanData
extends org.osgi.service.dal.FunctionData
```

Function boolean data wrapper. It can contain a boolean value, timestamp and additional metadata. It doesn't support measurement unit.

See Also:

<u>BooleanControl</u>, <u>BooleanSensor</u>, org.osgi.service.dal.FunctionData

Field Su	mmary	Page
static	FIELD_VALUE	
String	Represents the value field name.	54
boolean	<u>value</u>	
	Represents the boolean value.	54

Fields inherited from class org.osgi.service.dal.FunctionData FIELD_METADATA, FIELD_TIMESTAMP, META_INFO_DESCRIPTION, metadata, timestamp

Constructor Summary	Page
BooleanData (Map fields)	54
Constructs new BooleanData instance with the specified field values.	54
BooleanData (long timestamp, Map metadata, boolean value)	
Constructs new BooleanData instance with the specified arguments.	54

Method	Summary	Page
int	CompareTo (Object o) Compares this BooleanData instance with the given argument.	55
boolean	Equals (Object other) Two BooleanData instances are equal if they contain equal metadata, timestamp and boolean value.	55
boolean	getValue() Returns BooleanData value.	54
int	hashCode () Returns the hash code for this BooleanData object.	55

Methods inherited from class org.osgi.service.dal.FunctionData getMetadata, getTimestamp

OSGiJavadoc-- 4/8/13 Page 53 of 68

Field Detail

FIELD_VALUE

```
public static final String FIELD_VALUE = "value"
```

Represents the value field name. The field value is available with <u>value</u> and <u>getValue()</u>. The field type is boolean. The constant can be used as a key to <u>BooleanData(Map)</u>.

value

```
public final boolean value
```

Represents the boolean value. The field is accessible with getValue() getter.

Constructor Detail

BooleanData

```
public BooleanData(Map fields)
```

Constructs new BooleanData instance with the specified field values. The map keys must match to the field names. The map values will be assigned to the appropriate class fields. For example, the maps can be: {"value"=Boolean(true)...}. That map will initialize the FIELD VALUE field with true.

FIELD VALUE field value type must be Boolean.

Parameters:

fields - Contains the new BooleanData instance field values.

Throws:

```
ClassCastException - If the field value types are not expected. IllegalArgumentException - If the value is missing. NullPointerException - If the fields map is null.
```

BooleanData

Constructs new BooleanData instance with the specified arguments.

Parameters:

```
timestamp - The boolean data timestamp. metadata - The boolean data metadata. value - The boolean value.
```

Method Detail

getValue

```
public boolean getValue()
```

OSGiJavadoc-- 4/8/13 Page 54 of 68

Returns BooleanData value.

Returns:

BooleanData value.

equals

```
public boolean equals(Object other)
```

Two BooleanData instances are equal if they contain equal metadata, timestamp and boolean value.

Overrides:

equals in class org.osgi.service.dal.FunctionData

Parameters:

other - The object to compare this data.

Returns:

true if this object is equivalent to the specified one.

See Also:

org.osgi.service.dal.FunctionData.equals(java.lang.Object)

hashCode

```
public int hashCode()
```

Returns the hash code for this BooleanData object. The hash code is a sum of org.osgi.service.dal.FunctionData.hashCode() and Boolean.hashCode(), where Boolean.hashCode() represents the boolean value hash code.

Overrides:

hashCode in class org.osgi.service.dal.FunctionData

Returns:

The hash code of this BooleanData object.

See Also:

org.osgi.service.dal.FunctionData.hashCode()

compareTo

```
public int compareTo(Object o)
```

Compares this BooleanData instance with the given argument. The argument can be:

- Boolean the method returns 0 if this instance contains equivalent boolean value. -1 if this instance contains false and the argument is true. 1 if this instance contains true and the argument is false.
- BooleanData the method returns -1 if metadata or timestamp are not equivalent. Otherwise, the boolean value is compared with the same rules as Boolean argument.
- Map the map must be built according the rules of BooleanData(Map). Metadata, timestamp and value are compared according BooleanData and <

Specified by:

compareTo in interface Comparable

OSGiJavadoc-- 4/8/13 Page 55 of 68

Parameters:

 $_{\circ}$ - An argument to be compared.

Returns:

-1, 0 or 1 depending on the comparison rules.

Throws:

ClassCastException - If the method is called with Map and field value types are not expected. IllegalArgumentException - If the method is called with Map and the value is missing. NullPointerException - If the argument is null.

See Also:

Comparable.compareTo(java.lang.Object)

OSGiJavadoc-- 4/8/13 Page 56 of 68

Class KeypadData

org.osgi.service.dal.functions.data

```
java.lang.Object
    Lorg.osgi.service.dal.FunctionData
    Lorg.osgi.service.dal.functions.data.KeypadData
```

All Implemented Interfaces:

Comparable

```
public class KeypadData
extends org.osgi.service.dal.FunctionData
```

Represents a keypad event data that is collected when a change with some key from device keypad has occurred. The key code is mapped to FunctionData value.

See Also:

Keypad, org.osgi.service.dal.FunctionData

Field Su	mmary	Page
static int	EVENT_TYPE_PRESSED Represents a keypad event type for a key pressed.	59
static int	EVENT_TYPE_PRESSED_DOUBLE Represents a keypad event type for a double key pressed.	59
static int	EVENT TYPE PRESSED DOUBLE LONG Represents a keypad event type for a double and long key pressed.	59
static int	EVENT_TYPE_PRESSED_LONG Represents a keypad event type for a long key pressed.	59
static int	EVENT_TYPE_RELEASED Represents a keypad event type for a key released.	59
static int	EVENT_TYPE_UNKNOWN Represents an unknown keypad event type.	59
int	eventType Represents the keypad event type.	59
static String	FIELD_EVENT_TYPE Represents the event type field name.	58
static String	FIELD_KEY_CODE Represents the key code field name.	58
static String	FIELD_KEY_NAME Represents the key name field name.	58
int	keyCode Represents the key code.	60
String	keyName Represents the key name, if it's available.	59

Fields inherited from class org.osgi.service.dal.FunctionData FIELD_METADATA, FIELD_TIMESTAMP, META_INFO_DESCRIPTION, metadata, timestamp

OSGiJavadoc-- 4/8/13 Page 57 of 68

Constructor Summary	Page
KeypadData (Map fields)	-00
Constructs new KeypadData instance with the specified field values.	60
KeypadData (long timestamp, Map metadata, int eventType, int keyCode, String keyName)	-00
Constructs new KeypadData instance with the specified arguments.	60

Method Summary		Page
int	Compared (Confect C)	62
	Compares this KeypadData instance with the given argument.	OZ.
boolean	<pre>equals(Object other)</pre>	
	Two KeypadData instances are equal if they contain equal metadata, timestamp, event	61
	type, key code and key name.	
int	<pre>getEventType()</pre>	60
	Returns the event type.	00
int	<pre>getKeyCode()</pre>	61
	The code of the key.	61
String	<pre>getKeyName ()</pre>	0.4
	Represents a human readable name of the corresponding key code.	61
int	<u>hashCode</u> ()	61
	Returns the hash code for this KeypadData object.	67

Methods inherited from class org.osgi.service.dal.FunctionData	
getMetadata, getTimestamp	

Field Detail

FIELD KEY NAME

```
public static final String FIELD_KEY_NAME = "keyName"
```

Represents the key name field name. The field value is available with $\underline{\text{keyName}}$ and $\underline{\text{getKeyName}}$. The field type is $\underline{\text{String}}$. The constant can be used as a key to $\underline{\text{KeypadData}}$ (Map).

FIELD_EVENT_TYPE

```
public static final String FIELD_EVENT_TYPE = "eventType"
```

Represents the event type field name. The field value is available with $\frac{\text{eventType}}{\text{ond}}$ and $\frac{\text{getEventType}}{\text{onstant}}$. The field type is int. The constant can be used as a key to $\frac{\text{KeypadData}}{\text{onstant}}$.

FIELD_KEY_CODE

```
public static final String FIELD_KEY_CODE = "keyCode"
```

Represents the key code field name. The field value is available with keyCode (). The field type is int. The constant can be used as a key to KeypadData(Map).

OSGiJavadoc-- 4/8/13 Page 58 of 68

EVENT_TYPE_UNKNOWN

```
public static final int EVENT_TYPE_UNKNOWN = 0
```

Represents an unknown keypad event type.

EVENT_TYPE_PRESSED

```
public static final int EVENT TYPE PRESSED = 1
```

Represents a keypad event type for a key pressed.

EVENT_TYPE_PRESSED_LONG

```
public static final int EVENT_TYPE_PRESSED_LONG = 2
```

Represents a keypad event type for a long key pressed.

EVENT_TYPE_PRESSED_DOUBLE

```
public static final int EVENT_TYPE_PRESSED_DOUBLE = 3
```

Represents a keypad event type for a double key pressed.

EVENT_TYPE_PRESSED_DOUBLE_LONG

```
public static final int EVENT TYPE PRESSED DOUBLE LONG = 4
```

Represents a keypad event type for a double and long key pressed.

EVENT_TYPE_RELEASED

```
public static final int EVENT_TYPE_RELEASED = 5
```

Represents a keypad event type for a key released.

eventType

```
public final int eventType
```

Represents the keypad event type. The vendor can define own event types with negative values. The field is accessible with getEventType() getter.

keyName

```
public final String keyName
```

Represents the key name, if it's available. The field is accessible with getKeyName() getter.

OSGiJavadoc-- 4/8/13 Page 59 of 68

keyCode

```
public final int keyCode
```

Represents the key code. This field is mandatory and it holds the semantics(meaning) of the key. The field is accessible with getKeyCode () getter.

Constructor Detail

KeypadData

```
public KeypadData(Map fields)
```

Constructs new KeypadData instance with the specified field values. The map keys must match to the field names. The map values will be assigned to the appropriate class fields. For example, the maps can be: {"eventType"=Integer(1)...}. That map will initialize the <u>FIELD_EVENT_TYPE</u> field with 1.

FIELD EVENT TYPE field value type must be Integer. FIELD KEY NAME field value type must be Integer. FIELD KEY NAME field value type must be String.

Parameters:

fields - Contains the new KeypadData instance field values.

Throws

```
ClassCastException - If the field value types are not expected. IllegalArgumentException - If the event type or key code is missing. NullPointerException - If the fields map is null.
```

KeypadData

Constructs new KeypadData instance with the specified arguments.

Parameters:

```
timestamp - The data timestamp.
metadata - The data metadata.
eventType - The data event type.
keyCode - The data key code.
keyName - The data key name.
```

Method Detail

getEventType

```
public int getEventType()
```

Returns the event type. The vendor can define own event types with negative values.

OSGiJavadoc-- 4/8/13 Page 60 of 68

Returns:

The event type.

getKeyCode

```
public int getKeyCode()
```

The code of the key. This field is mandatory and it holds the semantics(meaning) of the key.

Returns:

The key code.

getKeyName

```
public String getKeyName()
```

Represents a human readable name of the corresponding key code. This field is optional and sometimes it could be missed(might be null).

Returns:

A string with the name of the key or null if not specified.

equals

```
public boolean equals(Object other)
```

Two KeypadData instances are equal if they contain equal metadata, timestamp, event type, key code and key name.

Overrides:

equals in class org.osgi.service.dal.FunctionData

Parameters:

other - The object to compare this data.

Returns:

true if this object is equivalent to the specified one.

See Also:

org.osgi.service.dal.FunctionData.equals(java.lang.Object)

hashCode

```
public int hashCode()
```

Returns the hash code for this KeypadData object. The hash code is a sum of org.osgi.service.dal.FunctionData.hashCode(), String.hashCode(), event type and key code, where String.hashCode() represents the key name hash code if available.

Overrides:

hashCode in class org.osgi.service.dal.FunctionData

Returns:

The hash code of this LevelData object.

OSGiJavadoc-- 4/8/13 Page 61 of 68

See Also:

org.osgi.service.dal.FunctionData.hashCode()

compareTo

```
public int compareTo(Object o)
```

Compares this KeypadData instance with the given argument. The argument can be:

- KeypadData the method returns -1 if metadata, timestamp, event type, key code or key name are not equivalent. 0 if all fields are equivalent.
- Map the map must be built according the rules of KeypadData(Map). Metadata, timestamp, event type, key code and key name are compared according KeypadData argument rules.

Specified by:

compareTo in interface Comparable

Parameters:

o - An argument to be compared.

Returns:

-1 or 0 depending on the comparison rules.

Throws:

ClassCastException - If the method is called with Map and the field value types are not expected. IllegalArgumentException - If the method is called with Map and the event type or key code is missing.

NullPointerException - If the argument is null.

See Also:

Comparable.compareTo(java.lang.Object)

OSGiJavadoc-- 4/8/13 Page 62 of 68

Class LevelData

org.osgi.service.dal.functions.data

```
java.lang.Object
    Lorg.osgi.service.dal.FunctionData
    Lorg.osgi.service.dal.functions.data.LevelData
```

All Implemented Interfaces:

Comparable

```
public class LevelData
extends org.osgi.service.dal.FunctionData
```

Function level data wrapper. It supports all properties defined in FunctionData.

See Also:

 $\underline{\texttt{MultiLevelControl}}, \underline{\texttt{MultiLevelSensor}}, \underline{\texttt{Meter}}, \texttt{org.osgi.service.dal.FunctionData}$

Field Summary		Page
static String	Represents the level field name.	64
static String	FIELD_UNIT Represents the unit field name.	64
BigDecimal	Represents the current level.	64
String	<pre>unit Represent the unit as it's defined in org.osgi.service.dal.PropertyMetadata.UNITS.</pre>	64

Fields inherited from class org.osgi.service.dal.FunctionData FIELD_METADATA, FIELD_TIMESTAMP, META_INFO_DESCRIPTION, metadata, timestamp

Constructor Summary	Page	
LevelData (Map fields)		
Constructs new LevelData instance with the specified field values.	64	
LevelData (long timestamp, Map metadata, String unit, BigDecimal level)	65	
Constructs new LevelData instance with the specified arguments.		

Method Summary		Page
int	<pre>compareTo (Object o) Compares this LevelData instance with the given argument.</pre>	66
boolean	equals (Object other) Two LevelData instances are equal if they contain equal metadata, timestamp, unit and level.	65
BigDecimal	<pre>getLevel() Returns LevelData value.</pre>	65
String	<pre>getUnit() Returns LevelData</pre>	65

OSGiJavadoc-- 4/8/13 Page 63 of 68

```
int hashCode ()
```

Returns the hash code for this LevelData object.

66

Methods inherited from class org.osgi.service.dal.FunctionData

getMetadata, getTimestamp

Field Detail

FIELD LEVEL

```
public static final String FIELD_LEVEL = "level"
```

Represents the level field name. The field value is available with \underline{level} and $\underline{getLevel()}$. The field type is $\underline{BigDecimal}$. The constant can be used as a key to $\underline{LevelData(Map)}$.

FIELD_UNIT

```
public static final String FIELD UNIT = "unit"
```

Represents the unit field name. The field value is available with <u>unit</u> and <u>getUnit()</u>. The field type is String. The constant can be used as a key to <u>LevelData(Map)</u>.

unit

public final String unit

Represent the unit as it's defined in org.osgi.service.dal.PropertyMetadata.UNITS. The field is optional. The field is accessible with getUnit() getter.

level

public final BigDecimal level

Represents the current level. It's mandatory field. The field is accessible with getLevel() getter.

Constructor Detail

LevelData

```
public LevelData(Map fields)
```

Constructs new LevelData instance with the specified field values. The map keys must match to the field names. The map values will be assigned to the appropriate class fields. For example, the maps can be: {"level"=BigDecimal(1)...}. That map will initialize the FIELD LEVEL field with 1.

FIELD UNIT field value type must be String. FIELD LEVEL field value type must be BigDecimal.

Parameters:

fields - Contains the new LevelData instance field values.

OSGiJavadoc-- 4/8/13 Page 64 of 68

Throws:

```
ClassCastException - If the field value types are not expected. IllegalArgumentException - If the level is missing. NullPointerException - If the fields map is null.
```

LevelData

Constructs new LevelData instance with the specified arguments.

Parameters:

```
timestamp - The data timestamp.
metadata - The data metadata.
unit - The data unit.
level - The level value.
```

Method Detail

getLevel

```
public BigDecimal getLevel()
```

Returns LevelData value. The value type is BigDecimal instead of double to guarantee value accuracy.

Returns:

The LevelData value.

getUnit

```
public String getUnit()
```

Returns LevelData unit as it's specified in org.osgi.service.dal.PropertyMetadata.UNITS or null if the unit is missing.

Returns:

The value unit or null if the unit is missing.

equals

```
public boolean equals(Object other)
```

Two LevelData instances are equal if they contain equal metadata, timestamp, unit and level.

Overrides:

```
equals in class org.osgi.service.dal.FunctionData
```

Parameters:

other - The object to compare this data.

OSGiJavadoc-- 4/8/13 Page 65 of 68

Returns:

true if this object is equivalent to the specified one.

See Also:

org.osgi.service.dal.FunctionData.equals(java.lang.Object)

hashCode

```
public int hashCode()
```

Returns the hash code for this LevelData object. The hash code is a sum of org.osgi.service.dal.FunctionData.hashCode(), String.hashCode() and BigDecimal.hashCode(), where String.hashCode() represents the unit hash code and BigDecimal.hashCode() represents the level hash code.

Overrides:

hashCode in class org.osgi.service.dal.FunctionData

Returns:

The hash code of this LevelData object.

See Also:

org.osgi.service.dal.FunctionData.hashCode()

compareTo

```
public int compareTo(Object o)
```

Compares this LevelData instance with the given argument. The argument can be:

- BigDecimal the method returns the result of BigDecimal.compareTo(Object) for this instance level and the specified argument.
- LevelData the method returns -1 if metadata, timestamp or unit are not equivalent. Otherwise, the level is compared with the same rules as BigDecimal argument.
- Map the map must be built according the rules of <u>LevelData(Map)</u>. Metadata, timestamp, unit and level are compared according BigDecimal and LevelData argument rules.

Specified by:

compareTo in interface Comparable

Parameters:

o - An argument to be compared.

Returns:

-1, 0 or 1 depending on the comparison rules.

Throws:

ClassCastException - If the method is called with Map and the field value types are not expected. IllegalArgumentException - If the method is called with Map and the level is missing. NullPointerException - If the argument is null.

See Also:

Comparable.compareTo(java.lang.Object)

Java API documentation generated with <u>DocFlex/Doclet</u> v1.5.6

DocFlex/Doclet is both a multi-format Javadoc doclet and a free edition of DocFlex/Javadoc. If you need to customize your Javadoc without writing a full-blown doclet from scratch, DocFlex/Javadoc may be the only tool able to help you! Find out more at www.docflex.com

OSGiJavadoc-- 4/8/13 Page 66 of 68



Draft

8 Considered Alternatives

Currently, there are no alternatives.

9 Security Considerations

Currenty, the security is covered by OSGi Device Abstraction Layer.

10 Document Support

10.1 References

- [1]. Bradner, S., Key words for use in RFCs to Indicate Requirement Levels, RFC2119, March 1997.
- [2]. Software Requirements & Specifications. Michael Jackson. ISBN 0-201-87712-0

10.2 Author's Address

Name	Evgeni Grigorov
Company	ProSyst Software
Address	Aachenerstr. 222, 50935 Cologne, Germany
Voice	+49 221 6604 501
e-mail	e.grigorov@prosyst.com



Draft

February 24, 2014

10.3 End of Document