OPENVPN配置

惨绿少年 Linux运维, 运维基本功 0评论 来源:本站原创 47℃ 字体:



1,

openvpn介绍与图解

1.1 openvpn介绍

OpenVPN是一个基于 OpenSSL库的应用层 VPN 实现。和传统VPN 相比,它的优点是简单易用。vpn直译就是虚拟专用通道,是提供企业之间或者公司之间安全数据传输的隧道。OpenVPN是一个全特性的SSL VPN,它使用2层或3层的安全网络技术,使用的是工业标准的SSL/TLS协议。SSL(Secure Sockets Layer 安全套接层),及其继任者传输层安全(TransportLayer Security,TLS)是为网络通信提供安全及数据完整性的一种安全协议。OpenVPN支持灵活的客户端授权方式,支持证书、智能卡、用户名和密码,允许用户可以通过防火墙连接到VPN的虚拟接口,OpenVPN不是一个基于web代理的应用,也不是基于浏览器访问。

1.2 openvpn使用场景

- a) 企业员工远程办公,通过远程VPN连接到公司的服务器,访问公司ERP、OA等系统。IT技术人员通过VPN远程连接到机房进行系统维护。
- b) 总部与分支机构之间联通,打通分支与总部的连接
- c) 多IDC机房之间的互联,实现多机房之间的互联互通,数据共享,文件传送


注意: OpenVPN适用于功能性实现,对于大流量大带宽应用,建议使用点对点专线实现互联

2、openvpn服务端安装与配置

2.1 环境介绍

实现模拟OpenVPN功能的实验环境介绍:

使用两台内网内段192.168.3.0/24的机器模拟公网环境,左侧的Iclient与右侧的Ianserver在不同的网段,正常情况下不能通信



openvpn服务器配置图解

制作: sunny

本次实验使用vpnclient的另外一个接口eth1模拟lclient,IP地址为10.0.0.17

2.2 基础环境配置及依赖包安装

2.2.1 开启内核参数ip转发

在vpnserver上开启ip转发功能,编辑/etc/sysctl.conf,修改net.ipv4.ip_forward为1

```
net.ipv4.ip_forward = 1
```

使用-p选项使参数修改生效

```
[root@vpnserver ~]# sysctl -p
net.ipv4.ip_forward = 1
```

2.2.2 停止iptables

在全部测试完成前,暂时先停掉iptables,以防止由于iptables的原因造成的问题,全部调试完成后再对iptables 进行设置

2.2.3 安装基础依赖包

安装openssl相关的依赖包

```
yum install openssl* -y
```

2.2.4 更新系统时间

使用ntp同步系统时间

```
ntpdate -u pool.ntp.org
```

制定计划任务,每隔5分钟进行时间同步

```
echo '#sync system date from ntpserver'>>/var/spool/cron/root
echo '*/5 * * * * /usr/sbin/ntpdate -u pool.ntp.org >/dev/null 2>&1' >>/var/spool/cron/root
```

检查配置信息

```
[root@vpnserver ~]# crontab -l
#sync system date from ntpserver
*/5 * * * * /usr/sbin/ntpdate -u pool.ntp.org >/dev/null 2>&1
```

2.3 安装Izo包

创建相应的安装包目录

```
mkdir -p /server/tools
cd /server/tools/
```

将相应的安装包上传至tools目录

```
[root@vpnserver tools]# 11
total 1476
-rw-r--r-- 1 root root 594855 Jul 5 08:33 lzo-2.09.tar.gz
-rw-r--r-- 1 root root 911158 Jul 5 08:33 openvpn-2.2.2.tar.gz
```

安装lzo源码包

```
cd /server/tools/
tar xf lzo-2.09.tar.gz
cd lzo-2.09
./configure
make
make install
```

2.4 安装openvpn软件

2.4.1 源码包安装

版本选择:目前最新的版本为2.3.1,本次选用Linux客户端和服务端的版本为2.2.2,windows客户端软件依然使用的是2.3.1

解压安装OpenVPN源码包

```
mkdir /application
tar xf openvpn-2.2.2.tar.gz -C /application/
cd /application/openvpn-2.2.2/
./configure --with-lzo-lib=/usr/local/lib--with-lzo-headers=/usr/local/include
make
make install
```

检查安装结果

```
[root@vpnserver openvpn-2.2.2]# which openvpn
/usr/local/sbin/openvpn
```

生成软链接

```
ln -s /application/openvpn-2.2.2/ /application/openvpn
```

2.4.2 生成CA证书

讲入制作证书所在目录,后续很多的操作都在此目录

```
cd /application/openvpn-2.2.2/easy-rsa/2.0
[root@vpnserver 2.0]# 11
total 128
-rwxrwxr-x. 1 sunny sunny 119 Nov 25 2011 build-ca #生成CA证书
-rwxrwxr-x. 1 sunny sunny 352 Nov 25 2011 build-dh #生成密码协议交换文件
-rwxrwxr-x. 1 sunny sunny 188 Nov 25 2011 build-inter
-rwxrwxr-x. 1 sunny sunny 163 Nov 25 2011 build-key
                                                        #生成免密码客户端密钥对
-rwxrwxr-x. 1 sunny sunny 157 Nov 25 2011 build-key-pass #生成带密码客户端密钥对
-rwxrwxr-x. 1 sunny sunny 249 Nov 25 2011 build-key-pkcs12
-rwxrwxr-x. 1 sunny sunny 268 Nov 25 2011 build-key-server
                                                           #生成服务端密钥对
-rwxrwxr-x. 1 sunny sunny 213 Nov 25 2011 build-req
-rwxrwxr-x. 1 sunny sunny 158 Nov 25 2011 build-req-pass
                                                     #初始化配置,清空所有keys
-rwxrwxr-x. 1 sunny sunny 428 Nov 25 2011 clean-all
-rwxrwxr-x. 1 sunny sunny 1457 Nov 25 2011 inherit-inter
-rwxrwxr-x. 1 sunny sunny 295 Nov 25 2011 list-crl
-rw-rw-r--. 1 sunny sunny 413 Nov 25 2011 Makefile
-rwxrwxr-x. 1 sunny sunny 7768 Oct 21 2010openssl-0.9.6.cnf
-rwxrwxr-x. 1 sunny sunny 8325 Nov 25 2011openssl-0.9.8.cnf
-rwxrwxr-x. 1 sunny sunny 8222 Nov 25 2011openssl-1.0.0.cnf
-rwxrwxr-x. 1 sunny sunny 12675 Nov 25 2011 pkitool #各证书生成主要调用此命令执行
-rw-rw-r--. 1 sunny sunny 9299 Nov 25 2011 README
-rwxrwxr-x. 1 sunny sunny 918 Nov 25 2011 revoke-full
                                                       #证书吊销
-rwxrwxr-x. 1 sunny sunny 178 Nov 25 2011 sign-req
                                                  #预先定义的证书基本信息
-rwxrwxr-x. 1 sunny sunny 1841 Nov 25 2011 vars
-rwxrwxr-x. 1 sunny sunny 714 Nov 25 2011 whichopensslcnf
```

修改证书预定义信息vars

首先对vars进行备份

```
cp vars vars.sunny.ori
```

编辑最后11行修改为如下内容:

```
export KEY_COUNTRY="CN"
export KEY_PROVINCE="HB"
export KEY_CITY="WuHan"
export KEY_ORG="sunny"
export KEY_EMAIL="519209@qq.com"
export KEY_EMAIL=519209@qq.com
export KEY_EMAIL=519209@qq.com
```

```
export KEY_NAME=sunny
export KEY_OU=sunny
export PKCS11_MODULE_PATH=changeme
export PKCS11_PIN=1234
```

注意:如果是AD或者ldap请根据自身内容进行填写

载入vars配置,新开窗口制作证书时,需要重新加载vars文件

```
[root@vpnserver 2.0]# source vars
NOTE: If you run ./clean-all, I will be doing a rm -rf on/application/openvpn-2.2.2/easy-rsa/2.6
```

第一次会提示初始化配置,按提示操作,后续正常使用时不可执行此操作,它会清空keys目录,并初始化序列

```
[root@vpnserver 2.0]# ./clean-all
[root@vpnserver 2.0]# ll keys/
total 4
-rw-r--r-. 1 root root 0 Jul 7 16:57 index.txt
-rw-r--r-. 1 root root 3 Jul 7 16:57 serial
```

制作CA证书,由于已经预先定义好了各个配置,一路回车,表示使用默认配置

```
[root@vpnserver 2.0]# ./build-ca
Generating a 1024 bit RSA private key
...+++++
.....+++++
writing new private key to 'ca.key'
You are about to be asked to enter information that will beincorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Nameor a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
Country Name (2 letter code) [CN]:
State or Province Name (full name) [HB]:
Locality Name (eg, city) [WuHan]:
Organization Name (eg, company) [sunny]:
Organizational Unit Name (eg, section) [sunny]:
Common Name (eg, your name or your server's hostname) [sunny]:
Name [sunny]:
Email Address [519209@qq.com]:
```

查看生成的证书文件,ca.crt就是新生成的证书文件,ca.key就是私钥

```
[root@vpnserver 2.0]# ls -l keys
total 12
-rw-r--r-- 1 root root 1277 Jul 7 16:58 ca.crt CA证书文件
-rw------ 1 root root 916Jul 7 16:58 ca.key CA的私钥
-rw-r--r-- 1 root root 0Jul 7 16:57 index.txt
-rw-r--r-- 1 root root 3Jul 7 16:57 serial
```

2.4.3 生成服务端证书与密钥

生成服务端证书调用的命令为build-key-server,后面直接跟服务端证书名即可,这里服务端证书名取为server

```
[root@vpnserver 2.0]# ./build-key-server server
Generating a 1024 bit RSA private key
........................
.....+++++
writing new private key to 'server.key'
You are about to be asked to enter information that will beincorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Nameor a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
Country Name (2 letter code) [CN]:
State or Province Name (full name) [HB]:
Locality Name (eg, city) [WuHan]:
Organization Name (eg, company) [sunny]:
Organizational Unit Name (eg, section) [sunny]:
Common Name (eg, your name or your server's hostname) [server]:
Name [sunny]:
Email Address [519209@qq.com]:
Please enter the following 'extra' attributes
to be sent with your certificate request
A challenge password []:123456
An optional company name []:sunny
Using configuration from/application/openvpn-2.2.2/easy-rsa/2.0/openssl-1.0.0.cnf
Check that the request matches the signature
Signature ok
The Subject's Distinguished Name is as follows
countryName
                    :PRINTABLE: 'CN'
stateOrProvinceName :PRINTABLE: 'HB'
localityName
                    :PRINTABLE:'WuHan'
organizationName
                    :PRINTABLE: 'sunny'
organizationalUnitName:PRINTABLE:'sunny'
commonName
                     :PRINTABLE: 'server'
name
                    :PRINTABLE: 'sunny'
                    :IA5STRING:'519209@qq.com'
emailAddress
Certificate is to be certified until Jul 5 09:04:46 2026 GMT (3650 days)
Sign the certificate? [y/n]:y
1 out of 1 certificate requests certified, commit? [y/n]y
Write out database with 1 new entries
Data Base Updated
```

着色的是手动输入的,需要两次确认

检查生成的证书密钥对

```
[root@vpnserver 2.0]# ll keys/server*
-rw-r--r-. 1 root root 3943 Jul 7 17:04 keys/server.crt #服务端证书
-rw-r--r-. 1 root root 757Jul 7 17:04 keys/server.csr #服务端证书请求文件
-rw-----. 1 root root 916Jul 7 17:04 keys/server.key #服务端私钥
```

2.4.4 生成客户端证书与密钥

客户端生成证书是与客户的账号是一一对应的,每一个账号对应一个服务端证书文件

生成一个无密码验证密钥,使用命令build-key

新建一个test客户端密钥,此账号无需密码验证

```
[root@vpnserver 2.0]# ./build-key test
Generating a 1024 bit RSA private key
.......+++++
..+++++
writing new private key to 'test.key'
You are about to be asked to enter information that will beincorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Nameor a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
Country Name (2 letter code) [CN]:
State or Province Name (full name) [HB]:
Locality Name (eg, city) [WuHan]:
Organization Name (eg, company) [sunny]:
Organizational Unit Name (eg, section) [sunny]:
Common Name (eg, your name or your server's hostname) [test]:
Name [sunny]:
Email Address [519209@qq.com]:
Please enter the following 'extra' attributes
to be sent with your certificate request
A challenge password []:123456
An optional company name []:sunny
Using configuration from/application/openvpn-2.2.2/easy-rsa/2.0/openssl-1.0.0.cnf
Check that the request matches the signature
Signature ok
The Subject's Distinguished Name is as follows
countryName
                    :PRINTABLE: 'CN'
stateOrProvinceName :PRINTABLE: 'HB'
localityName
                    :PRINTABLE:'WuHan'
organizationName
                    :PRINTABLE: 'sunny'
organizationalUnitName:PRINTABLE:'sunny'
                     :PRINTABLE: 'test'
commonName
name
                     :PRINTABLE: 'sunny'
                     :IA5STRING:'519209@qq.com'
emailAddress
Certificate is to be certified until Jul 5 09:13:01 2026 GMT (3650 days)
Sign the certificate? [y/n]:y
1 out of 1 certificate requests certified, commit? [y/n]y
Write out database with 1 new entries
Data Base Updated
```

生成一个需要密码验证的客户端密钥sunny,密码为123456,生产环境此密码需要设置较复杂

```
[root@vpnserver 2.0]# ./build-key-pass sunny
Generating a 1024 bit RSA private key
```

```
...+++++
writing new private key to 'sunny.key'
                                             #此处需要输入用户密码
Enter PEM pass phrase:
Verifying - Enter PEM pass phrase: #此处需要确认用户密码
You are about to be asked to enter information that will beincorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Nameor a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
Country Name (2 letter code) [CN]:
State or Province Name (full name) [HB]:
Locality Name (eg, city) [WuHan]:
Organization Name (eg, company) [sunny]:
Organizational Unit Name (eg, section) [sunny]:
Common Name (eg, your name or your server's hostname) [sunny]:
Name [sunny]:
Email Address [519209@qq.com]:
Please enter the following 'extra' attributes
to be sent with your certificate request
A challenge password []:123456
An optional company name []:sunny
Using configuration from/application/openvpn-2.2.2/easy-rsa/2.0/openssl-1.0.0.cnf
Check that the request matches the signature
Signature ok
The Subject's Distinguished Name is as follows
countryName
                   :PRINTABLE: 'CN'
stateOrProvinceName :PRINTABLE:'HB'
localityName
                   :PRINTABLE:'WuHan'
organizationName
                    :PRINTABLE: 'sunny'
organizationalUnitName:PRINTABLE:'sunny'
                   :PRINTABLE: 'sunny'
name
                    :PRINTABLE: 'sunny'
emailAddress
                    :IA5STRING:'519209@gg.com'
Certificate is to be certified until Jul 5 09:16:29 2026 GMT (3650 days)
Sign the certificate? [y/n]:
1 out of 1 certificate requests certified, commit? [y/n]y
Write out database with 1 new entries
Data Base Updated
```

查看生成的客户端密钥

```
[root@vpnserver 2.0]# ls -1 keys/{test,sunny}*
-rw-r--r-. 1 root root 3821 Jul 7 17:16 keys/sunny.crt
-rw-r--r-. 1 root root 757Jul 7 17:16 keys/sunny.csr
-rw-----. 1 root root 1041 Jul 7 17:16 keys/sunny.key
-rw-r--r-. 1 root root 3816 Jul 7 17:13 keys/test.crt
-rw-r--r-. 1 root root 757Jul 7 17:13 keys/test.csr
-rw-----. 1 root root 916Jul 7 17:13 keys/test.key
```

2.4.5 生成密码协议交换文件

使用命令build-dh命令生成密码协议交换文件,直接执行命令即可。

2.4.6 生成防攻击key文件

生成防止攻击的key文件

```
[root@vpnserver 2.0]# openvpn --genkey --secret keys/ta.key
[root@vpnserver 2.0]# 11 keys/ta.key
-rw-----. 1 root root 636 Jul 7 17:22 keys/ta.key
```

2.4.7 编辑服务端配置文件

创建配置文件目录

```
mkdir /etc/openvpn
cd /etc/openvpn
```

将keys目录拷贝到配置文件目录

```
[root@vpnserver openvpn]# cp -ap /application/openvpn/easy-rsa/2.0/keys.
[root@vpnserver openvpn]# 11
total 4
drwx-----. 2 root root 4096 Jul 7 17:22 keys
```

将服务端配置文件拷贝到/etc/openvpn目录

```
cp /application/openvpn/sample-config-files/server.conf server.bak
```

将server.bak中的有效指令重定向至server.conf

```
grep -Ev "#|;|^$" server.bak >server.conf
```

编辑server.conf文件,修改后的文件内容如下:

```
local 192.168.3.201

port 52115

proto tcp

dev tun

ca /etc/openvpn/keys/ca.crt

cert /etc/openvpn/keys/server.crt

key /etc/openvpn/keys/server.key

dh /etc/openvpn/keys/dh1024.pem

server 10.8.0.0 255.255.255.0

push "route 192.168.18.0 255.255.255.0"

ifconfig-pool-persist ipp.txt

keepalive 10 120
```

comp-lzo
persist-key
persist-tun
status openvpn-status.log
log /var/log/openvpn.log
duplicate-cn
client-to-client
verb 3

local本地监听的IP地址

port本地监听的端口,默认为1194,安全起见,建议修改

proto协议,这里使用tcp协议,稳定性更好

dev tun,使用tunnel接口,另外还有一种为tap

ca CA证书文件路径

cert服务端证书路径

key服务端密钥文件路径

dh证书密钥交换文件路径

server分配给客户端的IP地址,即客户端拔号成功后获取到的IP地址

push推送到客户端的路由信息,一般这里推送的是vpnserver端的本地子网

ifconfig-pool-persist记录客户端所获取到的IP地址信息列表,客户端重启后获取到与上次分配的IP相同的IP地址信息

keepalive 10 120每隔10秒客户端ping服务端,确保服务端没有离线,超长为120秒

comp-lzo允许压缩传输

status openvpn-status.log连接状态日志

log连接日志信息

duplicate-cn允许同一账号多人同时使用

client-to-client允许客户端与客户端之间通信

verb日志级别

;max-clients 100最大客户端数量默认为100个

- 2.5 启动服务端
- 2.5.1 启动服务端

报错处理一:

```
[root@vpnserver openvpn]# less /var/log/openvpn.log
Options error: You must define private key file (--key) or PKCS#12file (--pkcs12)
Use --help for more information.
```

根据提示,表明配置文件中没有加入服务端的密钥文件路径,或者路径不对,检查server.conf文件中key文件的配置

key /etc/openvpn/keys/server.key

2.5.2 将OpenVPN加入开机自启动

需要将OpenVPN加入开机自启动

方法一:

将启动命令加入到/etc/rc.local

echo "/usr/local/sbin/openvpn --config /etc/openvpn/server.conf>/dev/null &">>/etc/rc.local

方法二:

利用sample-scripts下面的脚本

```
cp /application/openvpn/sample-scripts/openvpn.init /etc/init.d/openvpn
chkconfig openvpn on
chkconfig --list openvpn
openvpn 0:off 1:off 2:on 3:on 4:on 5:on 6:off
```

3、 openvpn客户端安装与配置

3.1 windows客户端安装与配置

3.1.1 查看操作系统版本

这里提供了不同操作系统版本,可以根据自己操作系统的版本选择对应的客户端软件进行安装,win8和win10选择win7客户端安装,在我的电脑上右键属性可以查看操作系统版本

3.1.2 安装windows客户端软件

win10可以使用win7客户端,这里以win7-64位操作系统为例,进入windows-win7-64位

双击 "openvpn-install-2.3.11-l601-x86 64(win7).exe"

点击"next"

点击 "I Agree"

不做任何修改,点击Next

选择安装路径,按默认路径即可,64位系统默认为"C:\Program Files\OpenVPN",其它系统路径会略有不同

点击Install,如果提示是否信任,勾选"Always trust software from ...",点击Install

点击next进入下一步

点击Finish完成安装

3.1.3 windows客户端软件配置

3.1.4 拷坝证书文件

进入到openvpn安装目录下的config文件夹中,我的路径为"C:\Program Files\OpenVPN\config",新建test目录,将openvpnserver上/etc/openvpn/keys目录下的证书文件ca.crt,test.crt,test.key拷贝到config目录中config目录拷贝

在test目录下新建test.ovpn文件,此文件的模板为/application/openvpn/sample-config-files/client.conf,此文件test.ovpn内容如下:

```
client
dev tun
proto tcp
remote 192.168.3.201 52115
resolv-retry infinite
nobind
persist-key
persist-tun
ca ca.crt
cert test.crt
key test.key
ns-cert-type server
comp-lzo
verb 3
```

3.1.5 连接测试

安装完成后桌面会出现一个图标,双击点开,右下角会出现一个带小锁的小图标,在图标上点击右键,选中账号test,点击Connect,如果没有密码,会直接连接,如果需要密码,则会提示输入密码

拔号成功后, 右下角会弹出提示

并且原来灰色的图标会变为绿色,表示已经连接上了

3.1.6 连通性测试

此时ping VPN服务器的内网口192.168.18.201已通,但到lanserver192.168.18.203不通

```
C:\Users\Administrator>ping 192.168.18.201
正在 Ping 192.168.18.201 具有 32 字节的数据:
来自 192.168.18.201 的回复:字节=32 时间<1ms TTL=64
来自 192.168.18.201 的回复:字节=32 时间=1ms TTL=64
C:\Users\Administrator>ping 192.168.18.203
正在 Ping 192.168.18.203 具有 32 字节的数据:请求超时。
请求超时。
```

查看lanserver上的路由

```
[root@lanserver ~]# route -n
Kernel IP routing table
Destination
               Gateway
                              Genmask
                                              Flags Metric Ref
                                                               Use Iface
192.168.18.0
               0.0.0.0
                              255.255.255.0
                                                  0
                                                         0
                                                                  0 eth0
                                                                  0 eth0
169.254.0.0
               0.0.0.0
                              255.255.0.0
                                             U
                                                  1002
                                                         0
0.0.0.0
              192.168.18.2
                             0.0.0.0
                                                        0
                                                                 0 eth0
                                             UG 0
```

在windows上ping 192.168.18.203,然后在lanserver上抓包测试

```
[root@lanserver ~]# tcpdump icmp
tcpdump: verbose output suppressed, use -v or -vv for full protocoldecode
listening on eth0, link-type EN10MB (Ethernet), capture size 65535bytes
18:47:48.676249 IP 10.8.0.6 > 192.168.18.203: ICMP echo request,id 1, seq 17288, length 40
18:47:48.676288 IP 192.168.18.203 > 10.8.0.6: ICMP echo reply, id1, seq 17288, length 40
```

可见有包过来,但没有回包,原因是lanserver上有一条默认网关,但是指向的不是vpnserver,解决办法有两个:

方法一:将lanserver上的网关指向vpnserver

```
[root@lanserver ~]# route del default gw 192.168.18.2
[root@lanserver ~]# route add default gw 192.168.18.201
[root@lanserver ~]# route -n
Kernel IP routing table
Destination
                                                                  Use Iface
               Gateway
                               Genmask
                                              Flags Metric Ref
192.168.18.0
               0.0.0.0
                               255.255.255.0
                                              U 0
                                                          0
                                                                   0 eth0
169.254.0.0
               0.0.0.0
                                                                   0 eth0
                               255.255.0.0
                                              U
                                                   1002
                                                          0
0.0.0.0
              192.168.18.201 0.0.0.0
                                             UG 0
                                                         0
                                                                  0 eth0
```

添加完成后,windows客户端与lanserver立刻就通了

方法二:单独添加一条到10.8.0.0/24的路由

首先删除默认路由,删除成功后,客户端与lanserver立马就不通了

```
route del default gw 192.168.18.201
```

添加到10.8.0.0/24网段的路由

route add -net 10.8.0.0/24 gw 192.168.18.201

方法三: 网关不在vpnserver上,在vpnserver上添加一条NAT地址转换,将所有的10.8.0.0/24网段的IP都转成192.168.18.201,在iptables上添加如下语句

iptables -t nat -APOSTROUTING -s 10.8.0.0/24 -o eth0 -j MASQUERADE

上面的命令也可以用如下命令替换

iptables -t nat -APOSTROUTING -s 10.8.0.0/24 -o eth0 -j SNAT --to-source 192.168.18.201

在windows客户端上ping,实际IP为10.8.0.6,而在lanserver上抓包看到的源地址显示为192.168.18.201

```
[root@lanserver ~]# tcpdump -i eth0 icmp
tcpdump: verbose output suppressed, use -v or -vv for full protocoldecode
listening on eth0, link-type EN10MB (Ethernet), capture size 65535bytes
19:21:52.889132 IP 192.168.18.201 >192.168.18.203: ICMP echo request, id 1, seq 18615, length 40
19:21:52.889154 IP 192.168.18.203 > 192.168.18.201: ICMP echoreply, id 1, seq 18615, length 40
19:21:53.904123 IP 192.168.18.201 > 192.168.18.203: ICMP echorequest, id 1, seq 18616, length 40
19:21:53.904144 IP 192.168.18.203 > 192.168.18.201: ICMP echoreply, id 1, seq 18616, length 40
```

小结:

方法一优点实施简单,只需lanserver网关指向vpnserver即可,在某些网关指向路由器的情形下,可以在路由器上添加一条到远端10.8.0.0/24的路由即可,缺点是需要经过路由器跳转,多了一跳

方法二需要在所有的lanserver上添加路由,实施起来较麻烦。

方法三针对方法2进行改进,不需要在每台机器上配置路由,缺点是无法显示出源IP信息

- 3.2 linux客户端安装与配置
- 3.2.1 安装linux客户端软件

linux客户端软件的安装与服务端软件安装过程一样,也是需要先安装lzo,然后源码编译openvpn2.2.2,具体安装操作过程可参照服务端源码包安装2.4.1

3.2.2 编辑客户端配置文件

新建配置文件目录/etc/openvpn

mkdir /etc/openvpn
cd /etc/openvpn

将ca.crt,test.crt,test.key,client.conf上传

1 [root@vpnclient openvpn]# ls

```
ca.crt client.conf test.crt test.key
```

client.conf内容与windows客户端下的test.ovpn内容一样

```
[root@vpnclient openvpn]# cat client.conf
client
dev tun
proto tcp
remote 192.168.3.201 52115
resolv-retry infinite
nobind
persist-key
persist-tun
ca ca.crt
cert test.crt
key test.key
ns-cert-type server
comp-lzo
verb 3
```

3.2.3 远程拔入vpn

使用与服务端类似的启动方式进行启动,开机自启方式可以加入/etc/rc.local

```
[root@vpnclient openvpn]# /usr/local/sbin/openvpn --config/etc/openvpn/client.conf &
[1] 16347
[root@vpnclient openvpn]# Thu Jul 7 19:49:00 2016 OpenVPN 2.2.2 x86 64-unknown-linux-gnu [SSL] [
Thu Jul 7 19:49:00 2016 NOTE:OpenVPN 2.1 requires '--script-security 2' or higher to call user-
...此处省略若干行
Thu Jul 7 19:49:03 2016 ROUTEdefault_gateway=192.168.3.251
Thu Jul 7 19:49:04 2016TUN/TAP device tun0 opened
Thu Jul 7 19:49:04 2016TUN/TAP TX queue length set to 100
Thu Jul 7 19:49:04 2016/sbin/ifconfig tun0 10.8.0.10 pointopoint 10.8.0.9 mtu 1500
Thu Jul 7 19:49:04 2016/sbin/route add -net 192.168.18.0 netmask 255.255.255.0 gw 10.8.0.9
Thu Jul 7 19:49:04 2016/sbin/route add -net 10.8.0.0 netmask 255.255.255.0 gw 10.8.0.9
Thu Jul 7 19:49:04 2016Initialization Sequence Completed
拔号成功后,会多出一个接口tun0
[root@vpnclient openvpn]# ifconfig tun0
tun0
         inetaddr:10.8.0.10 P-t-P:10.8.0.9 Mask:255.255.255.255
         UP POINTOPOINTRUNNING NOARP MULTICAST MTU:1500 Metric:1
         RX packets:0errors:0 dropped:0 overruns:0 frame:0
         TX packets:0errors:0 dropped:0 overruns:0 carrier:0
         collisions:0txqueuelen:100
         RX bytes:0 (0.0b) TX bytes:0 (0.0 b)
```

如果是带密码认证的用户,以sunny为例,将sunny.crt,sunny.key,sunny.ovpn上传至/etc/openvpn,sunny.ovpn的内容如下:

```
client
dev tun
proto tcp
remote 192.168.3.204 52115
resolv-retry infinite
```

nobind
persist-key
persist-tun
ca ca.crt
cert sunny.crt
key sunny.key
ns-cert-type server
comp-lzo
verb 3
--script-security 3

在/etc/openvpn下新建密码文件pass.txt

123456

安全起见,修改pass.txt权限为400

chmod 400 /etc/openvpn/pass.txt

启动客户端

openvpn--config /etc/openvpn/sunny.ovpn --askpass /etc/openvpn/pass.txt &

加入开机自启的方法:

echo 'openvpn --config /etc/openvpn/sunny.ovpn --askpass/etc/openvpn/pass.txt >/dev/null &'>>/et

3.2.4 检查路由变化和连通性

测试到192.168.18.203网络是通的,停掉openvpn服务(pkill openvpn)后,网络又断开了,linux客户端配置成功


连通性问题处理方案与windows客户端上一致,见3.1.6

4、 openvpn高可用方案

- 4.1 使用openvpn实现代理访问
- 4.1.1 翻墙解决方案需求分析

 才会走vpnserver,其它外网访问依然走客户端本地网络,如果这台vpnserver在国外,可以通过此服务器访问 国外的网站,请不要使用此方法用于非法用途,否则后果自负。

具体逻辑如下图所示:



OpenVPN代理访问逻辑图

制作: sunny

4.1.2 代理访问解决方案配置

和普通配置相比,在server.conf上增加如下配置

```
push "redirect-gateway def1 bypass-dhcp bypass-dns"
push "dhcp-option DNS 8.8.8.8"
push "dhcp-option DNS 8.8.4.4"
```

启动转发功能

```
sed -i 's#net.ipv4.ip_forward= 0# net.ipv4.ip_forward= 1#g'/etc/sysctl.conf
sysctl -p
```

开启防火墙NAT映射


```
iptables -t nat -A POSTROUTING -s 10.8.0.0/24 -o eth0 -j MASQUERADE
```

开放防火墙

```
iptables -A INPUT -p udp -m state -state NEW -m udp --dport 52115 -j ACCEPT
```

4.2 同一账号拔入不同服务器

4.2.1 实现原理



OpenVPN负载均衡轮巡逻辑图

制作: sunny

配置两台vpnserver,第2台服务器上同样也需要开启net.ipv4.ip_forward,源码编译安装完成后,所有的证书制作过程不需要了,直接将vpnserver1下/etc/openvpn/keys目录拷贝到vpnserver2中,这样两台vpnserver的内容是一样的,除了接入的IP地址不一样,只需要在客户端生成一个新的配置文件(client.conf/test2.ovpn),

4.2.2 同一账号拔入不同vpnserver方案

在vpnserver1上对证书文件目录打包

```
[root@vpnserver openvpn]# cd /tmp
[root@vpnserver tmp]# tar zcvf openvpn.tar.gz /etc/openvpn/
[root@vpnserver tmp]# scp openvpn.tar.gz 192.168.3.204:/tmp
```

在vpnserver2上解包

```
[root@vpnserver2 tmp]# tar xf openvpn.tar.gz -C /
[root@vpnserver2 tmp]# ls /etc/openvpn/
ipp.txt keys openvpn-status.log server.bak server.conf
```

修改vpnsever2上的server.conf文件

```
local 192.168.3.204
server10.8.1.0 255.255.255.0
```

启动vpnserver2

```
/usr/local/sbin/openvpn --config /etc/openvpn/server.conf &
```

加入开机自启动

echo "/usr/local/sbin/openvpn --config /etc/openvpn/server.conf>/dev/null &">>/etc/rc.local

修改客户端配置文件,新增一个配置文件,除IP地址外,其它均一样


一旦一台vpnserver停掉了,需要手动将此链接断开,拔号到另外一台vpnserver

优点:无额外单点故障,配置简单

缺点: 需要手工切换拔号服务器

4.3 OPENVPN负载均衡

4.3.1 原理图解



OpenVPN负载均衡轮巡逻辑图

制作: sunny

4.3.2 负载均衡实现

配置server客户端分配不同的IP地址

```
server1
server 10.8.0.0 255.255.255.0
server2
server 10.8.1.0255.255.255.0
server3
server 10.8.2.0 255.255.255.0
```

在vpnserver2上添加如下命令中的一条,做地址转换

方法1:

```
iptables -t nat -APOSTROUTING -s 10.8.1.0/24 -o eth0 -j MASQUERADE
```

方法2:

iptables -t nat -APOSTROUTING -s 10.8.1.0/24 -o eth0 -j SNAT --to-source 192.168.18.204

客户端配置配置文件修改

remote 192.168.3.201 52115 remote 192.168.3.204 52115 remote-random resolv-retry 20

这样只需要建一个配置文件即可,当一台vpnserver断掉时,20秒后自动连另外一台vpnserver

5、 openvpn统一身份认证体系解决方案

- 5.1 OpenVPN统一身份验证分类
 - 1) 通过本地证书密钥认证
 - 2) 本地文件认证

本地新建账号密码文件, 通过脚本验证本地的密码文件

3) 通过数据库认证

方法1:利用脚本程序或PHP程序不从本地文件读,从Mysql数据库中读取

方法2: 使用pam mysql模块

4) LDAP统一用户认证

方法1: openvpn-auth-ldap

方法2: 利用第一个文件认证的思路,去LDAP查询,也可以和本地文件做比较

- 5) Radis (Remote Authentication Dial In User Service) 认证,主要用来验证、授权、计费
- 6) 利用微软的活动目录认证(可以和LDAP打通)
- 7) 结合U盾等设备认证
- 5.2 OpenVPN本地身份认证
- 5.2.1 服务端配置

在/etc/openvpn/server.conf中添加如下配置

#auth password added by sunny
script-security 3
auth-user-pass-verify /etc/openvpn/checkpsw.sh via-env

```
client-cert-not-required
username-as-common-name
```

说明:

script-security 3 使用3级别开启脚本使用功能

auth-user-pass-verify /etc/openvpn/checkpsw.sh via-env使用脚本验证本地文件

client-cert-not-required 不验证客户端证书,如果启用证书和密码双重认证注释此行username-as-

common-name 使用客户提供的UserName作为CommonName

在/etc/openvpn下新建脚本文件checkpsw.sh

```
#!/bin/sh
# checkpsw.sh (C) 2004 Mathias Sundman
# This script will authenticate OpenVPN users against
# a plain text file. The passfile should simply contain
# one row per user with the username first followed by
# one or more space(s) or tab(s) and then the password.
PASSFILE="/etc/openvpn/psw-file"
LOG FILE="/var/log/openvpn-password.log"
TIME_STAMP=`date "+%Y-%m-%d %T"`
if [ ! -r "${PASSFILE}" ]; then
echo "${TIME STAMP}: Could not open password file\"${PASSFILE}\" for reading." >> ${LOG FILE}
exit 1
fi
CORRECT_PASSWORD=`awk'!/^;/&&!/^#/&&$1=="'${username}'"{print $2;exit}'${PASSFILE}`
if [ "${CORRECT_PASSWORD}" = "" ]; then
echo "${TIME STAMP}: User does not exist: username=\"${username}\",password=\"${password}\"." >>
exit 1
fi
if [ "${password}" = "${CORRECT_PASSWORD}" ]; then
echo "${TIME STAMP}: Successful authentication:username=\"${username}\"." >> ${LOG FILE}
exit 0
echo "${TIME_STAMP}: Incorrect password:username=\"${username}\", password=\"${password}\".">> $
exit 1
```

赋予可执行权限

```
chmod u+x checkpsw.sh
```

新建密码文件/etc/openvpn/psw-file,前面是用户,后面是密码,每行一条,中间用空格或者tab键隔开

```
client01 111111
client02 123456
```

修改密码文件权限

```
chmod 400 psw-file
```

重启openvpn

```
pkill openvpn
ps -ef|grep openvpn
/etc/init.d/openvpn start
ps -ef|grep openvpn
```

5.2.2 客户端配置

5.2.2.1 windows客户端配置

编辑test用户的客户端配置文件test-192.168.3.201.ovpn,新增红色部分配置,修改后的配置如下:

```
client
dev tun
proto tcp
remote 192.168.3.201 52115
resolv-retry infinite
nobind
persist-key
persist-tun
ca ca.crt
;cert test.crt
;key test.key
ns-cert-type server
comp-lzo
verb 3
auth-user-pass
```

5.2.2.2 linux客户端配置

Linux客户端配置文件如下:

```
;cert test.crt
;key test.key
auth-user-pass auth-user-pass/etc/openvpn/psw-file
```

新建密码文件/etc/openvpn/psw-file,第一行为用户名,第二行为密码

```
client02
123456
```

修改权限为400

```
chmod 400 /etc/openvpn/psw-file
```

添加到开机自启动

echo "/usr/local/sbin/openvpn--config /etc/openvpn/client.conf >/dev/null &">>/etc/rc.local

此功能需要编译时加入-enable-password-save参数,即

./configure --enable-password-save --with-lzo-lib=/usr/local/lib --with-lzo-headers=/usr/local/i

否则会报如下错误:

'Auth' password cannot be read from a file

5.2.3 连接测试

windows客户端直接拔号测试,会弹出用户密码输入框,输入client01,111111

linux客户端直接启动服务即可

http://blog.51cto.com/francis198/1830639

赞0

如无特殊说明,文章均为本站原创,转载请注明出处

- 转载请注明来源: openvpn配置
- 本文永久链接地址: https://www.nmtui.com/clsn/lx283.html

该文章由 惨绿少年 发布



惨绿少年Linux www.nmtui.com