NTP时间服务器与chrony时间服务器部署

原创

GeorgeKai

2018-03-13 14:50:32

评论(0)

1404人阅读

.1 NTP简介

NTP时间协议

NTP(Network Time Protocol,网络时间协议) 是用来使网络中的各个计算机时间同步的一种协 议。它的用途是把计算机的时钟同步到世界协调 时UTC, 其精度在局域网内可达0.1ms, 在互联网 上绝大多数的地方其精度可以达到1-50ms。



NTP服务器就是利用NTP协议提供时间同步服务的。

ntp软件(支持ntp协议)

CentOS6自带

CentOS7需要安装的

chronv软件(支持ntp协议) CentOS7自带



NTP (Network Time Protocol, 网络时间协议)是用来使网络中的各个计算机时间同步的一种协议。它的用途是把 计算机的时钟同步到世界协调时UTC,其精度在局域网内可达0.1ms,在互联网上绝大多数的地方其精度可以达 到1-50ms。

NTP服务器就是利用NTP协议提供时间同步服务的。

系统版本(这里已7.2的系统为例)

- 1 [root@test ~]# cat /etc/redhat-release
- 2 CentOS Linux release 7.2.1511 (Core)

1.2 NTP服务器安装

[root@test ~]# rpm -qa ntp

ntpdate-4.2.6p5-22.el7.centos.x86 64

如果没有安装就yum install ntp -y进行安装



备份配置文件

[root@test ~]# cp /etc/ntp.conf{,.bak}

[root@test ~]# || /etc/ntp.conf*

-rw-r--r-. 1 root root 1778 Jan 11 2017 /etc/ntp.conf

```
-rw-r--r-- 1 root root 1778 Oct 23 23:10 /etc/ntp.conf.bak
精简化配置文件
[root@test ~] # egrep -v "^$|#" /etc/ntp.conf.bak >/etc/ntp.conf
修改配置文件(红色字体表示修改的内容)
1 # For more information about this file, see the man pages
2 # ntp.conf(5), ntp acc(5), ntp auth(5), ntp clock(5), ntp misc(5), ntp mon(5).
4 driftfile /var/lib/ntp/drift
6 # Permit time synchronization with our time source, but do not
7 # permit the source to query or modify the service on this system.
8 #restrict default kod nomodify notrap nopeer noquery
                                                        #控制nto服务器的权限,默认为最低,注释掉
9 restrict default nomodify
10
11 # Permit all access over the loopback interface. This could
12 # be tightened as well, but to do so would effect some of
13 # the administrative functions.
14 restrict 127.0.0.1
15 restrict -6 ::116
17 # Hosts on local network are less restricted.
18 #restrict 192.168.1.0 mask 255.255.255.0 nomodify notrap
19 # 允许内网其他机器同步时间
20 restrict 172.16.1.0 mask 255.255.255.0 nomodify notrap
22 # Use public servers from the pool.ntp.org project.
23 # Please consider joining the pool
(http://www.pool.ntp.org/join.html) . 24 #server 0.centos.pool.ntp.org iburst
25 #server 1.centos.pool.ntp.org iburst
26 #server 2.centos.pool.ntp.org iburst
27 #server 3.centos.pool.ntp.org iburst
28
29 # 定义使用的上游 ntp服务器,将原来的注释
30 server time1.aliyun.com
31 server ntp1.aliyun.com
33 #broadcast 192.168.1.255 autokey # broadcast server
34 #broadcastclient # broadcast client
35 #broadcast 224.0.1.1 autokey # multicast server
36 #multicastclient 224.0.1.1 # multicast client
37 #manycastserver 239.255.254.254 # manycast server
38 #manycastclient 239.255.254.254 autokey # manycast client
40 # 允许上层时间服务器主动修改本机时间
41 restrict time1.aliyun.com nomodify notrap noquery
42 restrict ntp1.aliyun.com nomodify notrap noquery
44 # 外部时间服务器不可用时,以本地时间作为时间服务
45 server 127.127.1.0
46 fudge 127.127.1.0 stratum 1047
48 # Enable public key cryptography.
49 #crypto
```

50

51 includefile /etc/ntp/crypto/pw

52

- 53 # Key file containing the keys and key identifiers used when operating
- 54 # with symmetric key cryptography.
- 55 keys /etc/ntp/keys

56

- 57 # Specify the key identifiers which are trusted.
- 58 #trustedkey 4 8 4259
- 60 # Specify the key identifier to use with the ntpdc utility.
- 61 #requestkey 862
- 63 # Specify the key identifier to use with the ntpq utility.
- 64 #controlkey 865
- 66 # Enable writing of statistics records.
- 67 #statistics clockstats cryptostats loopstats peerstats



注意: 如果有同步时间的定时任务要将其注销, 否则会冲突

[root@test ~]# systemctl start ntpd

显示节点列表

[root@test ~]# ntpq -p

remote refid st t when poll reach delay offset jitter

time5.aliyun.co 10.137.38.86 2 **U** 28 64 3 5.092 6241215 185.623 132.163.96.4 .**INIT**. 16 **U** - 64 0 0.000 0.000

[root@m01 ~]# ntpstat

unsynchronised

#出现一下情况,需要等待一定时间即可同步

time server re-starting polling server every 8 s

1.5 客户机时间同步

客户端推荐使用ntpdate同步时间,如开启ntp服务不安全

CentOS7默认没有这个命令,需要安装:

yum install ntpdate -y

同步内网时间服务器:

ntpdate 172.16.1.61

说明:客户机要等几分钟再与新启动的ntp服务器进行时间同步,否则会提示 "no server suitable for synchronization found错误"

配置chrony时间服务器:

1.停止ntpd服务,避免占用123端口 systemctl stop ntpd.service

2.安装chrony服务

yum -y install chrony

3.备份配置文件

cp /etc/chrony.conf{,.ori}

4.编辑配置文件

vim /etc/chrony.conf

#注释3-6行,在下面加入新的上游服务器

2# Please consider joining the pool (http://www.pool.ntp.org/join.html).

3#server 0. centos. pool. ntp. org iburst

4#server 1. centos. pool. ntp. org iburst

5#server 2. centos. pool. ntp. org iburst

6#server 3. centos. pool. ntp. org iburst

server ntp2.aliyun.com

#注释25-26行,在下面加入允许同步的网段

Allow NTP client access from local network. #allow 192.168.0.0/16 allow 172.16.1.0/24

5. 对比检查一下配置文件

diff /etc/chrony.conf{,.ori}

6.启动chrony服务

systemctl start chronyd

小伙伴们可以关注我的微信公众号: linux运维菜鸟之旅



关注"中国电信天津网厅"公众号,首次绑定可免费领2G流量,为你的学习提供流量!



版权声明:原创作品,如需转载,请注明出处。否则将追究法律责任