

Chapter 2: Static Routing



Routing and Switching Essentials v6.0

Cisco | Networking Academy® | Mind Wide Open®



2.1 Static Routing Implementation

- Explain the advantages and disadvantages of static routing.
- Explain the purpose of different types of static routes.

2.2 Configure Static and Default Routes

- Configure IPv4 and IPv6 static routes by specifying a next-hop address.
- Configure IPv4 and IPv6 default routes.
- Configure a floating static route to provide a backup connection.
- Configure IPv4 and IPv6 static host routes that direct traffic to a specific host

2.3 Troubleshoot Static and Default Route Issues

- Explain how a router processes packets when a static route is configured.
- Troubleshoot common static and default route configuration issues.



2.1 Static Routing Implementation



Cisco Networking Academy® Mind Wide Open™


Static Routing

Reach Remote Networks

A router can learn about remote networks in one of two ways:

- Manually Remote networks are manually entered into the route table using static routes.
- Dynamically Remote routes are automatically learned using a dynamic routing protocol.

Static and Default Route Scenario





Why Use Static Routing?

Static routing provides some advantages over dynamic routing, including:

- Static routes are not advertised over the network, resulting in better security.
- Static routes use less bandwidth than dynamic routing protocols, no CPU cycles are used to calculate and communicate routes.
- The path a static route uses to send data is known.


	Dynamic Routing	Static Routing
Configuration Complexity	Generally independent of the network size	Increases with network size
Topology Changes	Automatically adapts to topology changes	Administrator intervention required
Scaling	Suitable for simple and complex topologies	Suitable for simple topologies
Security	Less secure	More secure
Resource Usage	Uses CPU, memory, link bandwith	No extra resources needed
Predictability	Route depends on the current topology	Route to destination is always the same

Static Routing

When to Use Static Routes

Static routing has three primary uses:

- Providing ease of routing table maintenance in smaller networks.
- Routing to and from stub networks. A stub network is a network accessed by a single route, and the router has no other neighbors.
- Using a single default route to represent a path to any network that does not have a more specific match with another route in the routing table.





Static Route Applications


Static Routes are often used to:

- Connect to a specific network.
- Provide a Gateway of Last Resort for a stub network.
- Reduce the number of routes advertised by summarizing several contiguous networks as one static route.
- Create a backup route in case a primary route link fails.

Types of Static Routes


Standard Static Route

Connecting to a Stub Network



Types of Static Routes Default Static Route

- A default static route is a route that matches all packets.
- A default route identifies the gateway IP address to which the router sends all IP packets that it does not have a learned or static route.
- A default static route is simply a static route with 0.0.0.0/0 as the destination IPv4 address.




Presentation_ID ntial

Types of Static Routes

Summary Static Route


Using One Summary Static Route



Types of Static Routes

Floating Static Route

Configuring a Backup Route





6.2 Configure Static and Default Routes



Cisco Networking Academy® Mind Wide Open™



Router(config)# ip route network-address subnet-mask {ip-address | exit-intf}

Parameter	Description Destination network address of the remote network to be added to the routing table	
network- address		
subnet-mask	 Subnet mask of the remote network to be added to the routing table The subnet mask can be modified to summarize a group of networks 	
ip-address	 Commonly referred to as the next-hop router's IP address Typically used when connecting to a broadcast media (i.e., Ethernet) Commonly creates a recursive lookup 	
exit-intf	 Use the outgoing interface to forward packets to the destination network Also referred to as a directly attached static route Typically used when connecting in a point-to-point configuration 	
distance	 (Optional) Configures an administrative distance Typically used to configure a floating static route 	




Next-Hop Options

The next hop can be identified by an IP address, exit interface, or both. How the destination is specified creates one of the three following route types:


- Next-hop route Only the next-hop IP address is specified.
- Directly connected static route Only the router exit interface is specified.
- Fully specified static route The next-hop IP address and exit interface are specified.

Configure a Next-Hop Static Route

Configuring Next-Hop Static Routes on R1




Configure Directly Connected Static Route




Configure a Fully Specified Static Route

Configure Directly Attached Static Routes on R1



Verify a Static Routes Verify a Static Route



```
Rl# show ip route 192.168.2.1

Routing entry for 192.168.2.0/24

Known via "static", distance 1, metric 0

Routing Descriptor Blocks:

* 172.16.2.2

Route metric is 0, traffic share count is 1

Rl#
```

```
R1# show running-comfig | section ip route
ip route 172.16.1.0 255.255.255.0 172.16.2.2
ip route 192.168.1.0 255.255.255.0 172.16.2.2
ip route 192.168.2.0 255.255.255.0 172.16.2.2
si#
```



Default Static Route


Default Static Route Syntax

Router(config) #ip route 0.0.0.0 0.0.0.0 {ip-address | exit-intf}

Parameter	Description	
0.0.0.0 0.0.0.0	Matches any network address.	
ip-address	 Commonly referred to as the next-hop router's IP address. Typically used when connecting to a broadcast media (i.e., Ethernet). Commonly creates a recursive lookup. 	
exit-intf	 Use the outgoing interface to forward packets to the destination network. Also referred to as a directly attached static route. Typically used when connecting in a point-to-point configuration. 	

Configure a Default Static Route


Configuring a Default Static Route



Presentation_ID 20



Verify a Default Static Route







IPv6 Command Syntax

Router(config)# ipv6 route ipv6-prefix/prefix-length {ipv6-address | exit-intf}

Parameter	Description	
ipv6-prefix	Destination network address of the remote network to be added to the routing table.	
prefix-length	Prefix length of the remote network to be added to the routing table.	
ipv6-address	 Commonly referred to as the next-hop router's IP address. Typically used when connecting to a broadcast media (i.e., Ethernet). Commonly creates a recursive lookup. 	
exit-intf	 Use the outgoing interface to forward packets to the destination network. Also referred to as a directly attached static route. Typically used when connecting in a point-to-point configuration. 	




Next-Hop Options

- Next-hop static IPv6 route Only the next-hop IPv6 address is specified
- Directly connected static IPv6 route Only the router exit interface is specified
- Fully specified static IPv6 route The next-hop IPv6 address and exit interface are specified



Configure a Next-Hop Static IPv6 Route


Configure Next-Hop Static IPv6 Routes





Directly Connected Static IPv6 Route

Configure Directly Connected Static IPv6 Routes on R1





Fully Specified Static IPv6 Route

Configure Fully Specified Static IPv6 Routes on R1




```
R1(config)# ipv6 route 2001:db8:acad:2::/64 fe80::2
% Interface has to be specified for a link-local nexthop
R1(config)# ipv6 route 2001:db8:acad:2::/64 s0/0/0 fe80::2
R1(config)#
```



Verify IPv6 Static Routes

In addition to ping and traceroute, commands to verify static routes include:

- show ipv6 route
- show ipv6 route static
- show ipv6 route
 network







Default Static IPv6 Route

Default Static IPv6 Route Syntax


Router(config) # ipv6 route ::/0 {ipv6-address | exit-intf}

Parameter	Description	
::/0	Matches any IPv6 prefix regardless of prefix length.	
ipv6-address	 Commonly referred to as the next-hop router's IPv6 address. Typically used when connecting to a broadcast media (i.e., Ethernet). Commonly creates a recursive lookup. 	
exit-intf	 Use the outgoing interface to forward packets to the destination network. Also referred to as a directly attached static route. Typically used when connecting in a point-to-point configuration. 	




Configure a Default Static IPv6 Route

Configuring a Default Static IPv6 Route





Verify a Default IPv6 Static Route






Floating Static Routes

Floating static routes have an administrative distance greater than the administrative distance of another static route or dynamic routes.


- The static route "floats" and is not used when the route with the better administrative distance is active.
- If the preferred route is lost the floating static route can take over.





Configure an IPv4 Floating Static Route

Configuring a Floating Static Route to R3





Test the IPv4 Floating Static Route

To test a floating static route:


- Use the show ip route command to verify that the routing table is using the default static route.
- Use the traceroute command to follow the traffic flow out the primary route.
- Disconnect the link or shutdown the primary interface(s). In the curriculum example the serial interfaces on R2 are shutdown.
- Use a show ip route command to verify that the routing table is using the floating static route.
- Use a traceroute command to follow the traffic flow out the backup route.





Configure Static Host Routes

Automatically Installed Host Routes



A host route is an IPv4 address with a 32-bit mask or an IPv6 address with a 128-bit mask.

- Automatically installed when an IP address is configured on the router.
- The local routes are marked with "L" in the output of the routing table.





Configure Static Host Routes

Configure IPv4 and IPv6 Static Host Routes

2001:DB:ACAD:2::99/64 209.165.200.238/27 2001:DB:ACAD:1::/64 Fa0/5 Server Server Sololo Sololo Sololo Branch

```
Branch (config) # ip route 209.165.200.238 255.255.255.255 198.51.100.2
Branch(config) # ipv6 route 2001:db8:acad:2::99/128 2001:db8:acad:1::2
Branch (config) # end
Branch# show ip route | begin Gateway
Gateway of last resort is not set
      198.51.100.0/24 is variably subnetted, 2 subnets, 2 masks
         198.51.100.0/30 is directly connected, Serial0/0/0
         198.51.100.1/32 is directly connected, Serial0/0/0
      209.165.200.0/32 is subnetted, 1 subnets
         209.165.200.38 [1/0] via 198.51.100.2
Branch# show ipv6 route
<output omitted>
   2001:DB8:ACAD:1::/64 [0/0]
     via Serial0/0/0, directly connected
  2001:DB8:ACAD:1::1/128 [0/0]
    via Serial0/0/0, receive
    2001:DB8:ACAD:2::99/128 [1/0]
    via 2001:DB8:ACAD:1::2
   FF00::/8 [0/0]
     via Null0, receive
Branch#
```





Configure Static Host Routes

Configure IPv4 and IPv6 Static Host Routes

Fully Specified IPv6 Host Route with the Next-Hop Link-Local Address

```
2001:DB:ACAD:2::99/64
209.165.200.238/27
2001:DB:ACAD:1::/64
Fa0/5
Server ISP S0/0/0 Branch
```

```
Branch (config) # no ipv6 route 2001:db8:acad:2::99/128 2001:db8:acad:1::2
Branch(config) # ipv6 route 2001:db8:acad:2::99/128 serial 0/0/0 fe80::2
Branch (config) # end
Branch# show ipv6 route
<output omitted>
   ::/0 [1/0]
    via 2001:DB8:ACAD:1::2
   2001:DB8:ACAD:1::/64 [0/0]
    via Serial0/0/0, directly connected
   2001:DB8:ACAD:1::1/128 [0/0]
   via Serial0/0/0, receive
   2001:DB8:ACAD:2::99/128 [1/0]
    via FE80::2, Serial0/0/0
   FF00::/8 [0/0]
    via NullO, receive
Branch#
```




6.2 Troubleshoot Static and Default Route Issues



Cisco Networking Academy® Mind Wide Open®

Packet Processing with Static Routes

Static Routes and Packet Forwarding






Troubleshoot IPv4 Static and Default Route Configuration

Troubleshoot a Missing Route

IOS troubleshooting commands include:

- ping
- Extended **ping** enables you to specify the source IP address for the ping packets.
- traceroute
- show ip route
- show ip interface brief
- show cdp neighbors detail





Solve a Connectivity Problem

- Finding a missing (or misconfigured) route requires using the right tools in a methodical manner.
- Use the ping command to confirm the destination can't be reached.
- A traceroute would also reveal the closest router (or hop) that fails to respond as expected. In this case, the router would then send an Internet Control Message Protocol (ICMP) destination unreachable message back to the source.
- The next step is to investigate the routing table using the show ip route command. Look for missing or misconfigured routes.
- Incorrect static routes are a common cause of routing problems.



2.4 Chapter Summary



Cisco Networking Academy® Mind Wide Open®

41

Summary Summary

- Explain the advantages and disadvantages of static routing.
- Explain the purpose of different types of static routes.
- Configure IPv4 and IPv6 static routes by specifying a next-hop address.
- Configure IPv4 and IPv6 default routes.
- Configure a floating static route to provide a backup connection.
- Configure IPv4 and IPv6 static host routes that direct traffic to a specific host.
- Explain how a router processes packets when a static route is configured.
- Troubleshoot common static and default route configuration issues.

Cisco | Networking Academy® | Mind Wide Open™

#