Pathfinding Tools in the Second Life Viewer

Pathfinding in Second Life

- LSL functions
- Viewer tools
- Pathfinding Quick Start Guide

Contents

Introduction

Pathfinding UI Elements

Pathfinding Icons in SLURL Bar

Rebake Region

Right-click context menu behavior

Additional field on the Build floater

Additional field on the Object Profile floater

Additional simulator metrics on the Statistics floater

Pathfinding Floaters

Pathfinding Linksets Floater

Overview

Controls

Notes

Example use

Pathfinding Characters Floater

Overview

Controls

Example use

Pathfinding View/Test Floater

Overview

Controls

View tab

Test tab

Example Use


Known Issues

Introduction

For pathfinding, each region has a navigation mesh, commonly referred to as a "**navmesh**". The **navmesh** is a representation of the region's geometry generated and used by the physics simulator to determine paths for the pathfinding characters. The navmesh may be in one of the following three states:

- Up-to-date
- Has pending changes
- Building (a.k.a. rebaking)

The navmesh will transition through these states according to the following diagram:



Six new elements have been added to the SL Viewer interface to communicate the navmesh state for the current region. These new elements are:

- icon representations of the pathfinding region state for the SLURL bar
- a right-click context menu option addition
- an additional field on the Build floater
- an additional field on the Object Profile floater
- additional simulator metrics on the Statistics floater

In addition to these new elements, three new floaters allow users to more efficiently create, visualize, test, and debug pathfinding-enabled characters. These tools are not required to create pathfinding behaviors but are particularly useful to builders and experienced creators in Second Life. These new floaters are:

- Pathfinding linksets
- Pathfinding characters
- Pathfinding view / test


Pathfinding UI Elements

Note that other residents editing pathfinding objects on the same region may create pending changes to the navmesh. When this occurs, all residents on the same region and with build rights will see the appropriate SLURL bar icons.

Pathfinding Icons in SLURL Bar

The SLURL bar indicates the three pathfinding states of the current region.

1. **Navmesh is up-to-date** The current region's navmesh is up-to-date. No icon is shown as this is the expected default state.



2. **Navmesh has pending changes** The region has pending changes that have not yet been baked into the navmesh. A pathfinding icon with a construction symbol is shown.




3. **Dynamic pathfinding is disabled** The region has dynamic pathfinding disabled. Pathfinding characters will not work as expected. A pathfinding icon with a disabled symbol is shown.



Rebake Region

When a region has pending changes, the appropriate icon will be shown in the SLURL bar, as described above. In addition, if the user has build rights for any parcel on the current region, the "Rebake region" item under the Build menu will be active.




When the user picks this menu item, a request is sent to the region to rebake the navmesh for the current region. Rebaking a region may be a time intensive process. After the rebaking is complete, the pathfinding icon in the navigation bar will vanish.

Right-click context menu behavior

When right-clicking on an object in-world, pathfinding-specific menu options may be included in the pop-up context menu.

If the user right-clicks on a **linkset** object in-world, a menu option "Show in linksets" will allow the user to open the Pathfinding Linksets floater with the current object selected.




If the user right-clicks on a pathfinding **character** object in-world, a menu option "Show in characters" will allow the user to open the Pathfinding Characters floater with the current object selected.




Additional field on the Build floater

The Build floater has also been updated with an additional field indicating the pathfinding attributes of the current object.


The following image is a screenshot of the Build floater with a *character* object selected.



The following image is a screenshot of the Build floater with an object that *affects navmesh* selected. This object could be a *walkable*, *static obstacle*, *material volume*, or *exclusion volume*.




Warning: For linksets that do affect the navmesh, it will be impossible to modify the object across the region boundary. The user and the object affecting a navmesh must be in the same region to enable modification of the object. This will be indicated on the General tab of the Build floater as illustrated in the following screenshot.



Additional field on the Object Profile floater

Similar to the afore-described Build floater, the Object Profile floater has also been updated with an additional field indicating the pathfinding attributes of the current object. The following image is a screenshot of the Object Profile floater with an *affects navmesh* object selected.




Additional simulator metrics on the Statistics floater

For advanced users, additional simulator metrics have been added to the Statistics floater. The Statistics floater, available from the main menu Advanced > Performance Tools > Statistics Bar, has the following 3 additional fields reporting statistics from the simulator regarding pathfinding activity:


- AI Step Time The average time spent during each frame computing character AI events.
- **Skipped Silhouette Steps** The number of steps that are skipped per second in computing the influence of objects of type *Movable Obstacles* on the navmesh. A high value here means that objects on the region are marked as *Movable Obstacles* and could be contributing to improper pathfinding behavior on the region. To lower this value, set all objects that do not move to either type *Walkable* or *Static Obstacle*, and optimize any *Movable Obstacle* shapes to meet the Good Building Practices Guide.

• Characters Updated - The average percentage of characters updated during each frame. A low value here means that character AI computations are taking too long during each frame, and thus some character updates are skipped during subsequent frames. This could be contributing to improper pathfinding behavior on the region. To increase this value, decrease the number of characters on the region, and optimize any Movable Obstacle shapes to meet the Good Building Practices Guide. Note that the Pathfinding Characters floater (described below) may also be used to determine which characters on the region are contributing the most to the region's CPU time.



Pathfinding Floaters

These three pathfinding floaters may all be accessed through the Build->Pathfinding menu in the Project Viewer - Pathfinding.



Pathfinding Linksets Floater

Overview


The intent of the Pathfinding Linksets floater is to give advanced users and builders the ability to customize an area to achieve interesting effects with pathfinding-enabled characters. It can be initiated using the Build->Pathfinding->LinkSets options in the viewer menu.

The floater displays information for all linksets within the current region for which the user has the ability to alter. The table reports useful information including

- Linkset Name
- Description
- Owner
- Whether the object is Scripted
- Land Impact
- Distance from the resident's avatar
- Linkset Use
 - Potential values
 - Walkable
 - Static Obstacle
 - Movable Obstacle
 - Material Volume
 - Exclusion Volume
 - Movable Phantom

- Walkability Coefficients
 - Character Type A (example use: humanoid)
 - Character Type B (example use: creature)
 - Character Type C (example use: mechanical)
 - Character Type D (example use: other)

Additionally, selecting any linksets within the floater will also select the object(s) within the Viewer.



Controls

Filter by:

Filter by Enter text by which to filter the linkset list based on

Name Name attribute.

Filter by Enter text by which to filter the linkset based on the

Description Description attribute.

Filter by linkset Click to display only the linksets that match

use... selected use.

Apply Click to apply the filters to the linkset list.

Clear Click to clear the filters and return the linkset list back to the

original un-filtered contents.

Refresh Click to refresh the linkset list from the server. Use after you add

list or delete a linkset inworld.

Select all Click to select all linksets in the list.

Select none Click to deselect all selected linksets in the list.

Show Beacon

Select to display a beacon indicating the inworld location of each selected linkset. Use to locate hard-to-find or invisible linksets in

the region.

Take Click to take the selected linkset(s) into your inventory.

Take Copy Click to take a copy of the selected linkset(s) into your inventory.

Teleport MeTeleports you to the selected linkset. Useful to find faraway linksets. **Note** this button is only enabled when you have

To It selected one linkset.

Return Click to returns the selected linkset(s) to the owner's inventory.

Delete Click to delete the selected linkset(s) from the region.

Choose Linkset Change the linkset use attribute of the selected

Use linkset(s).

Walkability

Coefficients

Enter individual walkability coefficients for each character

type (A, B, C, D).

Walkability coefficients range from 0% to 100% to determine the influence the effect the linkset has on a character's speed while the character is traversing across

the linkset object.

For example, a linkset with Walkability Coefficient of 50% for character type A will cause characters of type A to reduce their speed by half while the character is traversing

the object.

Apply Changes

Click to apply changes to the selected linkset(s) use type and/ or walkability coefficients.

Notes

- For linksets with use fields marked as "[restricted]", only certain linkset use modes are available. This restriction is the result of the object not having modifiable permission enabled for the user.
- For linksets with use fields marked as "[concave]", the linkset use modes for Material Volume and Exclusion Volume are not available. This restriction is the result of the shape object not being convex. All pathfinding volumes **must** be convex.
- The "[Terrain]" linkset is available to be viewed and edited by the estate managers only. Additionally, while the walkability coefficients for the "[Terrain]" linkset are modifiable by estate managers, the Linkset Use field of "[Terrain]" linkset is not modifiable by anyone and will always be "Walkable".

Example use

The advanced users and builders will use the Pathfinding Linksets floater to customize areas to create interesting effects for pathfinding-enabled characters. For instance, imagine the scenario of a builder constructing a single room in a pathfinding-enabled house. For the single room, the builder would use the following types as follows:

Linkset Use	Description
Walkable	The floor linkset would be set to be Walkable to allow characters to move across the floor.
Static Obstacle	A desk linkset in the room would be set to be Static Obstacle to block characters from walking through or across the object. NOTE Any object that should block character movement and that does not move should be marked as Static Obstacle to improve performance of pathfinding characters.
Movable Obstacle	A door linkset in the room would be set to be Movable Obstacle . This will still block characters but, in contrast to Static Obstacles, Movable Obstacles will allow the linkset itself to move. In the case of the door, this will allow the door to open and close, but will still prevent characters from walking through the door.
Material Volume	Material Volumes are phantom objects that can be used to affect the walkability coefficients of intersecting objects. Imagine that the builder applied a texture to the floor. Also, imagine that the floor texture includes small throw rug in the middle of the room. (The builder did not want to create a separate object for the rug, so is using a texture on the floor to give the appearance of a rug). The builder can then create a Material Volume object intersecting the

floor at the location of the rug. Then, by setting a lower walkability

coefficient for the Material Volume, the builder will create the affect of slowing down characters as the characters traverse across the painted rug area.

Exclusion Volume

Exclusion Volumes are phantom objects that can be used to create areas where characters are prevented from moving. For instance, the builder can use an Exclusion Volume to create a section of the room where avatars would be able to move, but characters would be blocked from following.

Movable

Movable Phantoms are phantom objects that have no affect on Phantom pathfinding-enabled characters.

In addition to linkset use attributes, builders can achieve additional effects by modifying the walkability coefficients for linksets. The walkability coefficients are values, ranging from 0% to 100%, that affect a characters speed. A walkability coefficient of 50% will reduce a character's speed by half while the character is traversing across the linkset.


Pathfinding Characters Floater

Overview

The intent of Pathfinding Characters floater is primarily for users to locate characters moving throughout a region and to identify the CPU cost of characters affecting the performance of a region. It can be initiated using the Build->Pathfinding->Characters options in the viewer menu.

The floater displays information for all characters within the current region for which the user has the ability to manipulate. The table reports useful information including

- Character Name
- Description
- Owner
- CPU Time
- Altitude



Controls

Refresh List Click to refresh the character list from the server. Typically used

after a character is added or deleted in-world.

Select All Click to select all characters in the list.

Select None Click to deselect all selected characters in the list.

Show Beacon Select to display a beacon indicating the in-world location of each selected character. Use this option to locate hard-to-find or invisible characters in the region.

Show Physics Capsule Select to display the physics capsule representation of the currently selected character. Use this option to illustrate how the pathfinding physics engine sees the character shape for collisions. **Note**: this checkbox is only enabled when you select one character.

Take Click to take the selected character(s) into the user's inventory.

Take Click to take a copy of the selected character(s) into the user's inventory.

Teleport Me To It Click to teleport to the selected character. Use this function to rapidly find faraway characters. **Note**: this button is only enabled when you select one character.

Return Click to return the selected character(s) to the owner's inventory.

Delete Click to delete the selected character(s) from the region.

Example use

- 1. If a region owner has created a pathfinding-enabled character but is unable to find the character within the region, the Characters floater can be used to locate and select the character.
- Additionally, the Pathfinding Characters floater reports the CPU time cost for each character within the region. This functionality can be used by advanced users to identify which characters are impacting performance the most.

Pathfinding View/Test Floater


Overview

The intent of the Pathfinding View/Test floater is for advanced users who are building pathfinding-enabled objects and characters. It can be initiated using the Build->Pathfinding->View/Test options in the viewer menu.


This floater consists of 3 basic areas.

- 1. Status area (illustrating both the Viewer and Simulator status of the region's navmesh)
- 2. View tab Controls
- 3. Test Path tab Controls


The following image is a screenshot of the Pathfinding View/Test floater with the navmesh displayed.



The following image is a screenshot of the Pathfinding View/Test floater with the pathfinding object types displayed.



The following image is a screenshot of the Pathfinding View/Test floater with a test path displayed.



Controls

Viewer Status Reports the status of the pathfinding navmesh including the download process of retrieving the navmesh data from the simulator.

Simulator Status Reports the status of the region's navmesh on the simulator including when the navmesh has pending changes, is building, or is up-to-date.

View tab

Show

World Select to display the normal world view of the region's objects.

Movables Only Select to display only the region's objects that are **not** marked as affecting the navmesh (Walkable, Static Obstacle, Material Volume, or Exclusion Volume). This is useful to determine which objects on the region are still

movable and thus contributing to increase pathfinding time on the simulator. **Note:** this checkbox is only enabled when World is also selected.

Navmesh Toggles the display of the navmesh within the Viewer.

Show Walkability Map If the navmesh is displayed, the drop-down enables you to view the navmesh as a heatmap. This mode enables you to view the walkability values baked into the navmesh in the style of a heatmap illustrating the respective values across the navmesh.

Walkables

Select to display the walkables used when the navmesh was generated. Use this option to visualize how objects of type walkable affected the navmesh generation.

Material Volumes Select to display of material volumes used when the navmesh was generated. Use this option to visualize how objects of type *material volume* affected the navmesh generation.

Static Obstacles Select to display static obstacles used when the navmesh was generated. Use this option to visualize how objects of type *static obstacle* affected the navmesh generation.

Exclusion Volumes

Select to display exclusion volumes used when the navmesh was generated. Use this option to visualize how objects of type *exclusion volume* affected the navmesh generation.

Water Plane Select to display a simple plane representation of the water. Use this option when the World is hidden to visualize where the water-line is in the world.

With Xray Vision Select to alter the rendering into x-ray mode allowing for partial visibility through other objects. Use this option to get a better visualization of the world in complex situations.

Test tab

To specify the starting point of the test character path, hold down the <CTRL> key and click the left mouse button in the Viewer window.

To specify the ending point of the test character path, hold down the <SHIFT> key and click the left mouse button in the Viewer window.

Character Width

Use the slider to specify the width of the test character, ranging from 0.1 meter to 2 meters.

Character Type Specify the character type of the test character.

Clear Path Click to clear a path generated and displayed in the Viewer.

Example Use

1. The advanced user will use the Visualization controls to visualize how the navmesh and related permanent objects have been generated. By seeing this visualization of how the physics engine interprets the navigation

- information, the advanced user can understand how to better customize the pathfinding-enabled objects to obtain the desired behaviors of characters.
- 2. The advanced user will use the Test Tab to visualize how a test character would choose the path between selected start and end points.

Known Issues

JIRA	Summary	Hardware	Fixed in Version
MAINT-1291 (https:// jira.secondlife.co m/browse/ MAINT-1291)	Enable Debug GL crashes the viewer to the desktop	Mac Pro running 10.7.4 with AMD Radeon HD5770 iMac running Mac OS X Lion 10.7.4 (11E53) with AMD Radeon HD 6770M (512 MB) PC Clone running XP Pro with GeForce2 Ultra	
MAINT-1745 (https:// jira.secondlife.co m/browse/ MAINT-1745)	Crash in the viewer relating to LLLoginInstance and constructAuthParams		
MAINT-2071 (https:// jira.secondlife.co m/browse/ MAINT-2071)	Underwater 'Walkables' shapes are reflected about the water plane		
MAINT-2072 (https:// jira.secondlife.co m/browse/ MAINT-2072)	navmesh being drawn over worn flexi prims and under avatar		
MAINT-2073 (https:// jira.secondlife.co m/browse/ MAINT-2073)	Physics capsule rendering of character shapes is broken after zooming		
MAINT-2074 (https:// jira.secondlife.co m/browse/ MAINT-2074)	Configuration with ATI Radeon 7500 can launch Viewer, serious GFx issues	AMD Athlon64 3000+ with ATI Radeon 7500 video card	

MAINT-2075 (https:// jira.secondlife.co m/browse/ MAINT-2075) VWR-29500 (https:// jira.secondlife.co m/browse/ VWR-29500)	Shadows not operational under Second Life Beta 3.4.0.262596	Mac OS X 10.7.4 with ATI Radeon X1600 OpenGL Engine video card	
MAINT-2076 (https:// jira.secondlife.co m/browse/ MAINT-2076)	The navmesh starts blinking on empty regions while 'Movables only' and 'Navmesh' checkboxes are checked in View/test floater		
MAINT-2093 (https:// jira.secondlife.co m/browse/ MAINT-2093)	Navmesh objects disappear in 'Movables only' view while user turning around		
MAINT-2094 (https:// jira.secondlife.co m/browse/ MAINT-2094)	[BetaBreakers] - Sony VAIO PCG-71211 laptop displays black environment	Sony VAIO PCG-71211 laptop with AMD Radeon HD5650M Mobile graphics	

Retrieved from "https://wiki.secondlife.com/w/index.php? title=Pathfinding_Tools_in_the_Second_Life_Viewer&oldid=1186059"

This page was last edited on 31 December 2013, at 09:08.

Copyright © 2023 Linden Research, Inc. Licensed under Creative Commons Attribution-Share Alike 3.0 unless otherwise noted.