The Impulse Response and Convolution

The Impulse Response and Convolution

Scope and Background Reading

This section is an introduction to the impulse response of a system and time convolution. Together, these can be used to determine a Linear Time Invariant (LTI) system's time response to any signal.

As we shall see, in the determination of a system's response to a signal input, time convolution involves integration by parts and is a tricky operation. But time convolution becomes multiplication in the Laplace Transform domain, and is much easier to apply.

The material in this presentation and notes is based on Chapter 6 of (Karris, 2012).

Agenda

The material to be presented is:

- · Even and Odd Functions of Time
- Time Convolution
- Graphical Evaluation of the Convolution Integral
- System Response by Laplace

Even and Odd Functions of Time

(This should be revision!)

We need to be reminded of *even* and *odd* functions so that we can develop the idea of time convolution which is a means of determining the time response of any system for which we know its *impulse response* to any signal.

The development requires us to find out if the Dirac delta function $(\delta(t)\delta(t))$ is an even or an odd function of time.

Even Functions of Time

A function f(t) f(t) is said to be an even function of time if the following relation holds

$$f(-t) = f(t)$$

that is, if we relace tt with -t-t the function f(t) f(t) does not change.

about:srcdoc Page 1 of 13


Polynomials with even exponents only, and with or without constants, are even functions.

For example:

$$\cos t = 1 - \frac{t^2}{2!} + \frac{t^4}{4!} - \frac{t^6}{6!} + \dots$$

is even.

Other Examples of Even Functions



Odd Functions of Time

A function f(t) f(t) is said to be an *odd function* of time if the following relation holds

$$-f(-t) = f(t)$$

that is, if we relace tt with -t-t, we obtain the negative of the function f(t) f(t).


Polynomials with odd exponents only, and no constants, are odd functions.

For example:

$$\sin t = t - \frac{t^3}{3!} + \frac{t^5}{5!} - \frac{t^7}{7!} + \dots$$

is odd.

Other Examples of Odd Functions



Observations

• For odd functions f(0) = 0 f(0) = 0.

about:srcdoc Page 2 of 13

• If f(0) = 0 f(0) = 0 we should not conclude that f(t) f(t) is an odd function. c.f. $f(t) = t^2$ $f(t) = t^2$ is even, not odd.

- The product of two even or two odd functions is an even function.
- The product of an even and an odd function, is an odd function.

In the following $f_e(t)f_e(t)$ will denote an even function and $f_o(t)f_o(t)$ an odd function.

Time integrals of even and odd functions

For an even function $f_e(t)f_e(t)$

$$\int_{-T}^{T} f_e(t)dt = 2 \int_{0}^{T} f_e(t)dt$$

For an odd function $f_o(t)f_o(t)$

$$\int_{-T}^{T} f_o(t)dt = 0$$

Even/Odd Representation of an Arbitrary Function

A function f(t) f(t) that is neither even nor odd can be represented as an even function by use of:

$$f_e(t) = \frac{1}{2} [f(t) + f(-t)]$$

or as an odd function by use of:

$$f_o(t) = \frac{1}{2} [f(t) - f(-t)]$$

Adding these together, an abitrary signal can be represented as

$$f(t) = f_e(t) + f_o(t)$$

That is, any function of time can be expressed as the sum of an even and an odd function.

Example 1

Is the Dirac delta $\delta(t)\delta(t)$ an even or an odd function of time?

We'll decide in class.

about:srcdoc Page 3 of 13

Solution

Let f(t) f(t) be an arbitrary function of time that is continuous at $t = t_0 t = t_0$. Then by the sifting property of the delta function

$$\int_{-\infty}^{\infty} f(t)\delta(t - t_0)dt = f(t_0)$$

and for $t_0 = 0$ $t_0 = 0$

$$\int_{-\infty}^{\infty} f(t)\delta(t)dt = f(0)$$

Also for an even function $f_e(t)f_e(t)$

$$\int_{-\infty}^{\infty} f_e(t)\delta(t)dt = f_e(0)$$

and for an odd function $f_o(t)f_o(t)$

$$\int_{-\infty}^{\infty} f_o(t)\delta(t)dt = f_o(0)$$

Even or odd?

An odd function $f_o(t)f_o(t)$ evaluated at t=0 is zero, that is $f_o(0)=0$ $f_o(0)=0$.

Hence

$$\int_{-\infty}^{\infty} f_o(t)\delta(t)dt = f_o(0) = 0$$

Hence the product $f_o(t)\delta(t)f_o(t)\delta(t)$ is odd function of tt.

Since $f_o(t)f_o(t)$ is odd, $\delta(t)\delta(t)$ must be even because only an *even* function multiplied by an *odd* function can result in an *odd* function.


(Even times even or odd times odd produces an even function. See earlier slide)

Time Convolution


Consider a system whose input is the Dirac delta $(\delta(t)\delta(t))$, and its output is the **impulse response** h(t)h(t).

We can represent the input-output relationship as a block diagram

about:srcdoc Page 4 of 13



In general



Add an arbitrary input

Let u(t)u(t) be any input whose value at $t = \tau t = \tau$ is $u(\tau)u(\tau)$, Then because of the sampling property of the delta function

$$u(z)\delta(t-z)$$
 System \rightarrow $tr(t)h(t-z)$


(output is $u(\tau)h(t-\tau)u(\tau)h(t-\tau)$)

Integrate both sides

Integrating both sides over all values of $\tau \tau$ ($-\infty < \tau < \infty - \infty < \tau < \infty$) and making use of the fact that the delta function is even, i.e.

$$\delta(t - \tau) = \delta(\tau - t)$$


we have:



Use the sifting property of delta

The second integral on the left side reduces to u(t)u(t)

about:srcdoc Page 5 of 13



The Convolution Integral

The integral

$$\int_{-\infty}^{\infty} u(\tau)h(t-\tau)d\tau$$

or

$$\int_{-\infty}^{\infty} u(t-\tau)h(\tau)d\tau$$

is known as the *convolution integral*; it states that if we know the impulse response of a system, we can compute its time response to any input by using either of the integrals.

The convolution integral is usually written u(t) * h(t)u(t) * h(t) or h(t) * u(t)h(t) * u(t) where the asterisk (* *) denotes convolution.

Graphical Evaluation of the Convolution Integral

The convolution integral is most conveniently evaluated by a graphical evaluation. The text book gives three examples (6.4-6.6) which we will demonstrate in class using a graphical visualization tool developed by Teja Muppirala of the Mathworks.

The tool: convolutiondemo.m (see license.txt).

```
clear all
cd ../matlab/convolution_demo
pwd
format compact

ans =
   '/Users/eechris/dev/eg-247-textbook/content/laplace_transform/matlab/convolution_demo'

convolutiondemo % ignore warnings
```

about:srcdoc Page 6 of 13

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 398)
 - In convolutiondemo>gui_mainfcn (line 1188)

In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 449)
 - In convolutiondemo>gui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 500)
 - In convolutiondemo>qui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 551)
 - In convolutiondemo>gui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 621)
 - In convolutiondemo>qui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 672)
 - In convolutiondemo>gui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 723)
 - In convolutiondemo>qui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Warning: The EraseMode property is no longer supported and will error in a future release.

- > In convolutiondemo>convolutiondemo_LayoutFcn (line 774)
 - In convolutiondemo>qui_mainfcn (line 1188)
 - In convolutiondemo (line 44)

Convolution by Graphical Method - Summary of Steps

For simplicity, we give the rules for u(t)u(t), but the procedure is the same if we reflect and slide h(t)h(t)

- 1. Substitute u(t)u(t) with $u(\tau)u(\tau)$ this is a simple change of variable. It doesn't change the definition of u(t)u(t).
- 1. Reflect $u(\tau)u(\tau)$ about the vertical axis to form $u(-\tau)u(-\tau)$
- 1. Slide $u(-\tau)u(-\tau)$ to the right a distance tt to obtain $u(t-\tau)u(t-\tau)$
- 1. Multiply the two signals to obtain the product $u(t-\tau)h(\tau)u(t-\tau)h(\tau)$
- 1. Integrate the product over all $\tau \tau$ from $-\infty \infty$ to $\infty \infty$.

about:srcdoc Page 7 of 13


Examples

We will do these live in class.

Example 2


(This is example 6.4 in the textbook)

The signals h(t)h(t) and u(t)u(t) are shown below. Compute h(t)*u(t)h(t)*u(t) using the graphical technique.



h(t)

The signal h(t)h(t) is the straight line f(t) = -t + 1 f(t) = -t + 1 but this is defined only between t = 0 and t = 1 t = 1. We thus need to gate the function by multiplying it by $u_0(t) - u_0(t - 1)u_0(t) - u_0(t - 1)$ as illustrated below:



Thus

$$h(t) \Leftrightarrow H(s)$$

$$h(t) = (-t+1)(u_0(t)-u_0(t-1)) = (-t+1)u_0(t) - (-(t-1)u_0(t-1)) = -tu_0(t) + u_0(t) + (t-1)u_0(t-1)$$

$$-tu_0(t) + u_0(t) + (t-1)u_0(t-1) \Leftrightarrow -\frac{1}{s^2} + \frac{1}{s} + \frac{e^{-s}}{s^2}$$

$$H(s) = \frac{s + e^{-s} - 1}{s^2}$$

u(t)

The input u(t)u(t) is the gating function:

about:srcdoc Page 8 of 13

$$u(t) = u_0(t) - u_0(t-1)$$

so

$$U(s) = \frac{1}{s} - \frac{e^{-s}}{s} = \frac{1 - e^{-s}}{s}$$

Prepare for convolutiondemo

To prepare this problem for evaluation in the convolutiondemo tool, we need to determine the Laplace Transforms of h(t)h(t) and u(t)u(t).

convolutiondemo settings

- Let $g = (1 \exp(-s))/s$
- Let $h = (s + exp(-s) 1)/s^2$
- Set range $-2 < \tau < -2 2 < \tau < -2$

Summary of result

1. For t < 0t < 0:

$$u(t-\tau)h(\tau) = 0$$

- 2. For t = 0: $u(t \tau) = u(-\tau)u(t \tau) = u(-\tau)$ and $u(-\tau)h(\tau) = 0$.
- 3. For $0 < t \le 10 < t \le 1$:

$$h * u = \int_0^t (1)(-\tau + 1)d\tau = \tau - \tau^2/2 \Big|_0^t = t - t^2/2$$

4. For $1 < t \le 21 < t \le 2$:

$$h * u = \int_{t-1}^{1} (-\tau + 1)d\tau = \tau - \tau^2/2 \Big|_{t-1}^{1} = t^2/2 - 2t + 2$$

5. For $2 \le t2 \le t$:

$$u(t-\tau)h(\tau)=0$$

Example 3

This is example 6.5 from the text book.

$$h(t) = e^{-t}$$

$$u(t) = u_0(t) - u_0(t-1)$$

Answer 3

$$y(t) = \begin{cases} 0 : t \le 0 \\ 1 - e^{-t} : 0 < t \le 1 \\ e^{-t} (e - 1) : 1 < t < \infty \end{cases}$$

Check with MATLAB

```
syms t tau
x1=int(exp(-tau),tau,0,t)

x1 =
1 - exp(-t)

x2=int(exp(-tau),tau,t-1,t)
```

$$x2 = \exp(-t)*(\exp(1) - 1)$$

Example 4

This is example 6.6 from the text book.

$$h(t) = 2(u_0(t) - u_0(t-1))$$

$$u(t) = u_0(t) - u_0(t-2)$$

Answer 4

$$y(t) = \begin{cases} 0 : t \le 0 \\ 2t : 0 < t \le 1 \\ 2 : 1 < t \le 2 \\ -2t + 6 : 2 < t \le 3 \\ 0 : 3 \le t \end{cases}$$

System Response by Laplace

In the discussion of Laplace, we stated that


$$\mathcal{L}\left\{f(t) * g(t)\right\} = F(s)G(s)$$

We can use this property to make the solution of convolution problems even simpler.

about:srcdoc Page 10 of 13

Impulse Response and Transfer Functions

Returning to the example we started with



Then the impulse response of the system h(t)h(t) will be given by:

$$\mathcal{L}\left\{h(t) * \delta(t)\right\} = H(s)\Delta(s)$$

Where H(s)H(s) be the laplace transform of the impulse response of the system h(t)h(t). From properties of the Laplace transform we know that

$$\delta(t) \Leftrightarrow 1$$

so that $\Delta(s) = 1\Delta(s) = 1$ and

$$h(t) * \delta(t) \Leftrightarrow H(s).1 = H(s)$$

A consequence of this is that the transform of the impulse response h(t)h(t) of a system with transfer function H(s)H(s) is completely defined by the transfer function itself.

Previously we argued that the response of system with impulse response h(t)h(t) was given by the convolution integrals:

$$h(t) * u(t) = \int_{-\infty}^{\infty} u(\tau)h(t-\tau)d\tau = \int_{-\infty}^{\infty} u(t-\tau)h(\tau)d\tau$$

Thus the Laplace transform of any system subject to an input u(t)u(t) is simply

$$Y(s) = H(s)U(s)$$

and

$$y(t) = \mathcal{L}^{-1} \left\{ G(s)U(s) \right\}$$

Using tables, solution of a convolution problem by Laplace is usually simpler than using convolution directly.


about:srcdoc Page 11 of 13

Examples

We will work through these in class

Example 5

This is example 6.7 from the textbook.



For the circuit shown above, show that the transfer function of the circuit is:

$$H(s) = \frac{V_c(s)}{V_s(s)} = \frac{1/RC}{s + 1/RC}$$

Hence determine the impulse respone h(t)h(t) of the circuit and the response of the capacitor voltage when the input is the unit step function $u_0(t)u_0(t)$ and $v_c(0^-) = 0v_c(0^-) = 0$.

Assume C = 1 FC = 1 F and R = 1 $\Omega R = 1$ Ω .

Solution 5a - Impulse response

$$h(t) = \frac{1}{RC}e^{-t/RC}u_0(t)$$

which when C=1 FC=1 F and R=1 $\Omega R=1$ Ω reduces to

$$h(t) = e^{-t}u_0(t)$$

Solution 5b - Step response

$$h(t) = e^{-t}u_0(t) \Leftrightarrow H(s) = \frac{1}{s+1}$$

about:srcdoc Page 12 of 13

$$u(t) = u_0(t) \Leftrightarrow U(s) = \frac{1}{s}$$

$$y(t) = h(t) * u(t) \Leftrightarrow Y(s) = H(s)U(s) = \left(\frac{1}{s+1}\right) \times \left(\frac{1}{s}\right)$$

By PFE

$$Y(s) = \frac{r_1}{s+1} + \frac{r_2}{s}$$

The residues are $r_1 = -1$, $r_1 = -1$, $r_2 = 1$, so

$$Y(s) = -\frac{1}{s+1} + \frac{1}{s} \Leftrightarrow y(t) = (1 - e^{-t}) u_0(t)$$

Homework

Verify this result using the convolution integral

$$h(t) * u(t) = \int_{-\infty}^{\infty} u(\tau)h(t-\tau)d\tau$$

Reference

1. Karris, S. T. (2012). Signals and systems with MATLAB computing and Simulink modeling. Orchard Publishing. https://ebookcentral.proquest.com/lib/swansea-ebooks/reader.action?docID=3384197

about:srcdoc Page 13 of 13