How to Use SMF Data Set Support for Postprocessor Reports with z/OS V2R3 RMF Distributed Data Server

Copyright 2017 IBM Corporation

Table of Contents

1 Overview	2
2 Postprocessor HTTP request parameters	
3 RMF Postprocessor job template in SYS1.SERBPWSV	
4 RACF security considerations	6
5 Customizing GPMPPJV2 for variants of HTTP_NOAUTH 5.1 DDS running with HTTP_NOAUTH(*) 5.2 DDS running with HTTP_NOAUTH() 5.3 DDS running with HTTP_NOAUTH(<ip-addr>)</ip-addr>	6
6 New XML elements in the <ddsml> Schema</ddsml>	8
7 Example screen shots from RMF Data Portal	g
8 New GPM messages	11
9 Bibliography	12

1 Overview

With z/OS V2R3, the RMF Distributed Data Sever introduces support to use pre-allocated SMF data from data sets or logstreams as input source for historical Postprocessor requests.

The RMF DDS Postprocessor HTTP API offers three new parameters: smfdata, sortsmf and joboutdel to be used with the rmfpp.xml request type. For example, a request for a RMF Postprocessor CPU activity report might look like this:

```
http://<hostname>:8803/gpm/rmfpp.xml?
reports=CPU&sortsmf=YES&smfdata=IFASMF.PERF.SYSDPLEX&joboutdel=YES
```

Section 2 on p. 3 provides a detailed description of these new parameters. In section 6 on p. 8, new XML tags introduced with the SMF data set support are listed.

The usage of SMF data sets is also integrated into the RMF Data Portal. SMF data set names and YES/NO values for SORTSMF and JOBOUTDEL can be defined with new input fields in the "Explore" menu. (Supported browser versions are Internet Explorer 11 and with Firefox ESR 52.) Section 7 on p. 9 lists screen shots of the new parts in the RMF Data Portal.

If you intend to use this new RMF DDS functionality, you have to switch to an extended GPMPPJCL job template which is provided in SYS1:SERBPWSV(GPMPPJV2). You will find the template in section 3 on p. 4 for your reference.

Depending on your DDS configuration option HTTP_NOAUTH(), you must customize this job template. The rules for customization are explained in section 5 on p. 6. After you adapted the JCL to match your installation, you have to reference it in your GPMSERVE started task with the GPMPPJCL DD card.

Section 4 on p. 6 explains which steps you have to take in your SAF definition (e.g. RACF) to enable this new functionality of RMF DDS.

2 Postprocessor HTTP request parameters

The RMF Distributed Data Server HTTP API is extended with the following request parameters which are valid in the context of requests for historical Postprocessor reports:

- &joboutdel: Specify whether the held output of the PP job (which has to be hold in order to read the PP output and to generate the XML response) should be deleted by the DDS after processing the PP job output.
- &smfdata: Specify one or multiple names of SMF data sets or logstreams.
- &sortsmf: Specify whether the input data has to be sorted before being processed by the Postprocessor.

The joboutdel parameter

joboutdel=[YES | NO]

This parameter specifies whether the held output of the Postprocessor job should be deleted by the RMF Distributed Data Server after it has been processed successfully.

Default: NO

Examples:

joboutdel=NO

The smfdata parameter

smfdata=smf_data_1[,smf_data_2,...,smf_data_k]

This parameter contains a list of names of SMF data sets or logstreams which are used as input for the generation of Postprocessor reports. The names must be fully qualified and valid z/OS data set names.

Examples:

smfdata=RMF.SMFDATA.SYSA,RMF.SMFDATA.SYSB,RMF.SMFDATA.SYSC smfdata=IFASMF.PERF.SYSDPLEX

The sortsmf parameter

sortsmf=[YES | NO]

This parameter specifies whether the SMF data which is defined with the &smfdata parameter is sorted before it is used as input for the generation of Postprocessor reports.

Default: NO

Examples:

sortsmf=YES

3 RMF Postprocessor job template in SYS1.SERBPWSV

A new Postprocessor job template GPMPPJV2 is added to SYS1.SERBPWSV (the name stands for "GPMPPJCL version 2"). This template has to be activated in the GPMSERVE procedure if exploiters of the RMF DDS (i.e. the GPMSERVE started task) want to use the new &SMFDATA parameter.

The GPMPPJV2 template contains some JCL comment cards with special strings. These are used by GPMSERVE as markers to enable GPMSERVE to generate a correct JCL together with the parameters supplied with the RMF DDS rmfpp.xml HTTP request. The marker lines must not be deleted from the JCL, otherwise the JCL is considered incorrect and the SMF data set functionality cannot be used.

The special strings are:

- //*UID,
- //*LOGSTR-START,
- //*LOGSTR-END.
- //*SORT-START,
- //*SORT-END,
- //*SORTIN,
- //*MFPINPUT.

The job template looks like the following:

```
//GPMDDSPP JOB MSGCLASS=H, CLASS=A, MSGLEVEL=(1,1), REGION=256M,
      USER=<uid>
//*UID
/*JOBPARM SYSAFF=*
//***********************
//*
//* NAME:
              GPMPPJV2
//*
//* DESCRIPTION: RMF POSTPROCESSOR JCL FOR THE RMF DISTRIBUTED DATA
        SERVER HOST ADDRESS SPACE (GPMSERVE)
//*
//*
//* COPYRIGHT: LICENSED MATERIALS - PROPERTY OF IBM
//*
               "RESTRICTED MATERIALS OF IBM"
//*
               5650-ZOS
//*
              COPYRIGHT IBM CORP. 2017
//*
              STATUS=HRM77B0 (Z/OS V2R3 RMF)
//****************
//*
//* NOTES:
//*
//*
     1. YOU MAY CHANGE THE SPECIFICATIONS IN THE JOB AND EXEC CARDS
//*
        TO SUIT YOUR INSTALLATION, I.E. CHOOSE A DIFFERENT CLASS=,
        MSGCLASS= OR REGION= PARAMETER OR ADD A NOTIFY=
//*
//*
       PARAMETER.
//*
//*
     2. PREPARE THE JOB CARD TO BE USED WITH THE SMFDATA PARAMETER:
     A) IF GPMSERVE RUNS WITH "HTTP NOAUTH(*)" OR
//*
//*
         WITH ANY "HTTP NOAUTH (<IP-ADDR>)" OPTION,
//*
         SPECIFY AN APPROPRIATE GENERAL USER= PARAMETER,
//*
        E.G. "//*UID USER=GPMUID".
//*
     B) IF GPMSERVE RUNS WITH AUTHORISATION (I.E. EITHER NO
//*
         "HTTP NOAUTH" OPTION DEFINED OR "HTTP NOAUTH()" SPECIFIED,
```

```
//*
        LEAVE THE *UID LINE AS IS.
//*
     C) IF YOU DO NOT PLAN TO USE THE SMFDATA PARAMETER AT ALL,
//*
        STAY WITH THE TEMPLATE IN GPMPPJCL, DO NOT USE GPMPPJV2.
//*
//*
        (SEE RMF USER'S GUIDE OR RMF WEB HOME PAGE FOR MORE
//*
        INFORMATION ON SECURITY SETTINGS.)
//*
//*
     3. DO NOT CHANGE THE DD CARD SPECIFICATIONS FOR THE XML
//*
       OUTPUT DATASETS. THE DDS NEEDS THESE SYSOUT DATA SETS TO
       RESIDE ON SPOOL. BE SURE TO USE A 'MSGCLASS' WITH AN
//*
//*
       OUTPUT DISPOSITION OF 'HOLD'.
//*
//*
     4.A) DO NOT CHANGE THE LINES BEGINNING WITH
//*
         //*LOGSTR-, //*SORT-, //*SORTIN, //*MFPINPUT
//*
         BECAUSE THE DDS USES THEM TO GENERATE THE ACTUAL JCL.
//*
      B) DO NOT INSERT A COMMENT LINE RIGHT BEFORE THE //*UID LINE.
//*
//* CHANGE ACTIVITY:
//*
   $80=SMFDS, HRM77B0, , KGE: SMF DATA SET SUPPORT
//*********************
//*LOGSTR-START
//*********************
//* RMF DATA EXTRACTING
//*********************
//RMFDUMP EXEC PGM=IFASMFDL
//OUTDD1
         DD DISP=(NEW, PASS), UNIT=SYSDA, SPACE=(CYL, (500, 500))
//SYSPRINT DD
            SYSOUT=*
            SYSOUT=*
//SYSOUT DD
//SYSIN
         DD
//*LOGSTR-END
//*SORT-START
//*********************
//* RMF SORT PROCESSING
//***********************
//RMFSORT EXEC PGM=SORT
//*SORTIN
//SORTOUT DD
             DISP=(NEW, PASS), UNIT=SYSDA, SPACE=(CYL, (200, 200))
//SORTWK01 DD
             DISP=(NEW, DELETE), UNIT=SYSDA, SPACE=(CYL, (200, 200))
//SORTWK02 DD
            DISP=(NEW, DELETE), UNIT=SYSDA, SPACE=(CYL, (200, 200))
//SORTWK03 DD
            DISP=(NEW, DELETE), UNIT=SYSDA, SPACE=(CYL, (200, 200))
//SYSPRINT DD
             SYSOUT=*
//SYSOUT
            SYSOUT=*
         DD
//SYSIN
         DD
 SORT FIELDS=(11, 4, CH, A, 7, 4, CH, A, 15, 4, CH, A), EQUALS
 MODS E15=(ERBPPE15, 36000,, N), E35=(ERBPPE35, 3000,, N)
//*SORT-END
//*********************
//* RMF POSTPROCESSING
//**********************
//RMFPP
         EXEC PGM=ERBRMFPP
//*MFPINPUT
//MFPMSGDS DD
             SYSOUT=*
            SYSOUT=*
//XPRPTS DD
//XPXSRPTS DD
            SYSOUT=*
//XPOVWRPT DD
            SYSOUT=*
//SYSOUT DD
            SYSOUT=*
//SYSIN DD
```

4 RACF security considerations

As long as the Postprocessor job submitted by the RMF DDS does not contain a USER parameter in its JOB card, the submitted Postprocessor job runs under the authority of the user ID which has been assigned to the GPMSERVE started task, e.g. the user GPMSERVE. This is the case if you use the template GPMPPJCL which has been provided in pre-V2R3 releases of z/OS.

Consequently, a Postprocessor job which accesses SMF data sets or logstreams can only run successfully if the <code>GPMSERVE</code> user ID has read access to these SMF data sets. As it is unlikely that system environments will fulfill this strong requirement, we now support a USER parameter with the jobcard.

Example:

```
//GPMDDSPP JOB MSGCLASS=H, CLASS=A, MSGLEVEL=(1,1), REGION=256M, USER=BUID
```

This ensures that user ID BUID submits the Postprocessor job GPMDDSPP and the job is using the security authorities of BUID. Now the Postprocessor job may access any SMF data the user BUID is allowed to read.

In order for this mechanism to work, the <code>GPMSERVE</code> user ID needs permission to submit jobs on behalf of <code>BUID</code> and it needs UPDATE access to the job output on the JES spool. The following example shows RACF commands which allow these actions:

```
RDEFINE SURROGAT BUID.SUBMIT UACC(NONE) OWNER(BUID)
PERMIT BUID.SUBMIT CLASS(SURROGAT) ID(GPMSERVE) ACCESS(READ)
SETROPTS RACLIST(SURROGAT) REFRESH

RDEFINE JESSPOOL nodename.BUID.GPMSERVE.** UACC(NONE) OWNER(BUID)
PERMIT nodename.BUID.GPMSERVE.** CLASS(JESSPOOL) ID(GPMSERVE) ACCESS(UPDATE)
SETROPTS RACLIST(JESSPOOL) REFRESH
```

In order to use the job deletion functionality implemented with the new *joboutdel* parameter, a RACF profile in the JESJOBS class has to be defined like in the following example for the user BUID and the Postprocessor job GPMDDSPP started by GPMSERVE:

```
RDEFINE JESJOBS PURGE.nodename.BUID.GPMDDSPP UACC(NONE)
PERMIT PURGE.nodename.BUID.GPMDDSPP CLASS(JESJOBS) ID(BUID) ACC(ALTER)
```

5 Customizing GPMPPJV2 for variants of HTTP NOAUTH

Access to the RMF DDS may be restricted by means of the HTTP_NOAUTH option. Depending on your setting of this option in GPMSERVE, there are the following variants of customizing the JOB card in the PP JCL template:

5.1 DDS running with HTTP_NOAUTH(*)

You must provide a universal user ID gpmuid with the USER parameter of the JOB card:

```
//GPMDDSPP JOB MSGCLASS=H, CLASS=A, MSGLEVEL=(1,1), REGION=256M, //*UID USER=qpmuid
```

The user ID <code>gpmuid</code> which is used here has to be 'universal' in the sense that it can be used by all users of the DDS. The user ID <code>gpmuid</code> may be empty, in which case the Postprocessor job runs under the authority of the GPMSERVE started task user ID. When submitting a Postprocessor job, the DDS will expand this JCL to

```
//GPMDDSPP JOB MSGCLASS=H, CLASS=A, MSGLEVEL=(1,1), REGION=256M, // USER=qpmuid
```

5.2 DDS running with HTTP_NOAUTH()

This setting of the HTTP_NOAUTH option is also the default, if you do not specify it in your GPMSERVE PARMLIB member. Leave the //*UID line in GPMPPJV2 unchanged in this case:

```
//GPMDDSPP JOB MSGCLASS=H, CLASS=A, MSGLEVEL=(1,1), REGION=256M, //*UID USER=<UID>
```

Using this variant of HTTP_NOAUTH, every user of the DDS has to authorise himself with his own user ID userid. The DDS expands this template to

```
//GPMDDSPP JOB MSGCLASS=H,CLASS=A,MSGLEVEL=(1,1),REGION=256M,
// USER=userid
```

5.3 DDS running with HTTP_NOAUTH(<ip-addr>)

This setting of the HTTP_NOAUTH option allows users who access the RMF DDS with a matching IP address to use the DDS without authorisation, all other users must identify themselves with user ID and password. You must provide a universal user ID <code>gpmuid</code> with the USER parameter of the JOB card:

```
//GPMDDSPP JOB MSGCLASS=H, CLASS=A, MSGLEVEL=(1,1), REGION=256M, //*UID USER=gpmuid
```

• If a user with a matching IP address uses the DDS, then this case is equivalent to the HTTP_NOAUTH(*) case from section 5.1. The template is expanded by the DDS to

```
//GPMDDSPP JOB MSGCLASS=H,CLASS=A,MSGLEVEL=(1,1),REGION=256M,
// USER=qpmuid
```

• If a user with another IP address uses the DDS, then this case is equivalent to the HTTP_NOAUTH() case from section 5.2. The user has to authorise himself with user ID userID and the template is expanded by the DDS to

```
//GPMDDSPP JOB MSGCLASS=H,CLASS=A,MSGLEVEL=(1,1),REGION=256M,// USER=userid
```

6 New XML elements in the <ddsml> Schema

SMF-Input element

A <smf-input> tag provides information on the names of the SMF input data sets or logstreams used for the generated Postprocessor report.

Syntax: SMF-Input

Tag/Fragment	Description	Туре
file	name of a SMF data set or logstream	token

Example XML code:

```
<smf-input>
  <file> RMF.SMFDATA.SYSA </file>
  <file> RMF.SMFDATA.SYSB </file>
</smf-input>
```

RMF-MFP-Message element

A <rmf-mfpmsg> tag lists the messages which have been generated by RMF Postprocessor and are provided in the MFPMSGDS SYSOUT DD of the Postprocessor job run by the RMF Distributed Data Server.

Syntax: RMF-MFP-Message

Tag/Fragment	Description	Туре
mfpmsg	message text	token
id	Postprocessor message ID	token

Example XML code:

Message element


The <message> tag is now also available at the top level of the ddsml schema.

Example

```
<ddsml xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
       xsi:noNamespaceSchemaLocation="include/ddsml.xsd">
<server>
   <name>RMF-DDS-Server</name>
   <version>ZOSV2R3</version>
   <functionality>3211</functionality>
   <platform>z/OS</platform>
</server>
<smf-input>
   <file>IFASMF.PERF.SYSDPLEX</file>
</smf-input>
<message id="GPM0748W">
   <description>Incomplete action or Postprocessor data (Reason: Job could
   not be purged (probably a RACF problem))</description>
   <severity>2</severity>
</message>
<postprocessor>
   <metric id="CPU">
   <description>CPU Activity Report</description>
   <type>Interval</type>
   </metric>
   <version><smf-data>z/OS V2R2</smf-data><rmf-report>z/OS V2R3</rmf-</pre>
   report></version>
   <re>ource><resname>SYSE</resname><restype>SYSTEM</restype>
</postprocessor>
</ddsml>
```


7 Example screen shots from RMF Data Portal

Screen shot from RMF Data Portal showing input fields for the new parameters:



Screen shot with SMF data set information and ERB messages from RMF Postprocessor:

1. When sections are hidden



2. With sections expanded:

SMF Data

IFASMF.PERF.SYSDPLEX

RMF Postprocessor Messages

ERB103I PPS: OPTIONS IN EFFECT

ERB103I PPS: NODELTA -- DEFAULT

ERB103I PPS: NOEXITS -- DEFAULT

ERB103I PPS: ETOD(0000,2400) -- DEFAULT

ERB103I PPS: STOD(0000,2400) -- DEFAULT

ERB103I PPS: RTOD(0000,2400) -- DEFAULT

ERB103I PPS: SYSOUT(A) -- DEFAULT

ERB103I PPS: NOSUMMARY -- SYSIN

ERB103I PPS: REPORTS(CPU) -- SYSIN

ERB103I PPS: DATE(01011967,12312066) -- DEFAULT

8 New GPM messages

Together with the new SMF data set support, two new GPM messages are introduced to the RMF DDS:

GPM0748W Incomplete action or Postprocessor data (Reason: reason text).

Explanation: The Postprocessor job was successfully run, but the DDS did not return all output data or an action (e.g. deletion of job output) did not complete successfully.

System action: Either only a partial XML answer is produced for the request or the Postprocessor job output is not purged.

User response: Observe the *reason_text*, check the Postprocessor messages or the Postprocessor job directly. If job output could not be purged, examine your security definitions for the JESJOBS class.

GPM0749E The provided JCL is not valid for this Postprocessor HTTP request.

Explanation: The DDS uses a Postprocessor JCL template which is designed for the usage of SMF data sets and SMF logstream data, but this template does not contain the marker strings which are required for this functionality in the DDS.

System action: The HTTP Postprocessor request is rejected.

User response: Correct the Postprocessor JCL template which is used with the GPMPPJCL DD card of the GPMSERVE started task.

9 Bibliography

- z/OS RMF User's Guide, <u>https://www.ibm.com/support/knowledgecenter/SSLTBW_2.3.0/com.ibm.zos.v2r3.erbb200/t</u> oc.htm
- z/OS Security Server RACF Security Administrator's Guide, https://www.ibm.com/support/knowledgecenter/en/SSLTBW_2.3.0/com.ibm.zos.v2r3.icha70
 https://www.ibm.com/support/en/SSLTBW_2.3.0/com.ibm.zos.v2r3.icha70
 https://www.ibm.com/support/en/SSLTBW_2.3.0/com.ibm.zos.v2r3.icha70
 https://www.ibm.com/support/en/SSLTBW_2.3.0/com.ibm.zos.v2r3.icha70
 <a href="https://www.ibm.com/support/en/SSLTBW_2.3.0/com.ibm.zos.v2r3.icha70
 <a href="https://www.ibm.com/support/en/SSLTBW_2.3.0/com.ibm.zos.v2r3.ic