# Inferences in Regression and Correlation Analysis

## 2.1 Inference Concerning $\beta_1$

**Definition.** Inference concerning  $\beta_1$  Test concerning  $\beta_1$  is of the form

$$\begin{cases} \mathcal{H}_0 : \beta_1 = 0 \\ \mathcal{H}_\alpha : \beta_1 \neq 0 \end{cases}$$

 $\beta_1 = 0$  implies that there is no linear association between Y and X. On assumption of gaussian noise, there is also no relation of any type between Y and X, since probability of Y are identical for all levels of X

**Definition.** Linear estimators Least square estimator  $\hat{\beta}_1$  is a linear estimator

$$\hat{\beta}_1 = \sum_i k_i y_i$$
  $k_i = \frac{x_i - \overline{x}}{\sum_j (x_j - \overline{x})^2}$ 

with properties

$$\sum k_i = 0 \quad \sum k_i x_i = 1 \quad \sum k_i^2 = \frac{1}{S_{XX}}$$

Proof. Note

$$\sum (x_i - \overline{x})(y_i - \overline{y}) = \sum (x_i - \overline{x})y_i - \sum (x_i - \overline{x})\overline{y} = \sum (x_i - \overline{x})y_i \text{ by } \sum (x_i - \overline{x}) = 0$$

the result follows. Proof of properties are simple, i.e.

$$\sum k_i = \sum_i \left( \frac{x_i - \overline{x}}{\sum_j (x_j - \overline{x})^2} \right) = \frac{1}{\sum_j (x_j - \overline{x})^2} \sum_i (x_i - \overline{x}) = 0$$

For second property

$$\sum k_i x_i = \frac{1}{\sum_j (x_j - \overline{x})^2} \sum_i (x_i - \overline{x}) x_i = \frac{1}{S_{XX}} \sum_i x_i^2 - n \overline{x}^2 = \frac{1}{S_{XX}} S_{XX} = 1$$

**Definition.** Sampling distribution of  $\hat{\beta}_1$  The sampling distribution of  $\hat{\beta}_1$  refers to different values of the estimator obtained with repeated sampling when the levels of the predictor variable X are held constant from sample to sample. Given  $\hat{\beta}_1$ 

$$\hat{\beta}_1 = \frac{\sum (x_i - \overline{x})(y_i - \overline{y})}{\sum (x_i - \overline{x})^2}$$

The sampling distribution of  $\hat{\beta}_1$  is **normal** with mean and variance,

$$\mathbb{E}(\hat{\beta}_1|X) = \beta_1 \quad Var(\hat{\beta}_1|X) = \frac{\sigma^2}{\sum (x_i - \overline{x})^2} = \frac{\sigma^2}{S_{XX}}$$
$$\hat{\beta}_1 \sim \mathcal{N}(\beta_1, \frac{\sigma^2}{S_{XX}})$$

Proof.

#### 1. Mean and variance

$$\mathbb{E}(\hat{\beta}_1) = \mathbb{E}\{\sum k_i y_i\} \stackrel{ind}{=} \sum (k_i \mathbb{E}\{y_i\}) = \sum k_i (\beta_0 + \beta_1 x_i) = \beta_0 \sum k_i + \beta_1 \sum k_i x_i = \beta_1$$
$$Var(\hat{\beta}_1) = Var\left(\sum k_i y_i\right) = \sum k_i^2 Var(y_i) = \sum k_i^2 \sigma^2 = \sigma^2 \sum k_i^2 = \frac{\sigma^2}{S_{XX}}$$

with last step of both derivation given by properties of  $\hat{\beta}_1$  as a linear estimator.

- 2. Normality of sampling distribution given by the fact that  $\hat{\beta}_1$  is a linear combination of  $y_i$ s. Since  $y_i \stackrel{i.i.d}{\sim} \mathcal{N}(\beta_0 + \beta 1x_i, \sigma^2)$ , the estimator is normaly distributed because it is a linear combination of independent normal random variables
- 3. Estimated variance We can estimate the variance of  $\hat{\beta}_1$  by substituting  $\sigma^2$  (unknown) with its unbiased estimator MSE  $s^2$

$$s^2(\hat{\beta}_1) = \frac{MSE}{S_{XX}}$$
 where  $MSE = \frac{\sum e_i^2}{n-2}$ 

Note  $s^2$  carries a denominator of  $S_{XX}$ , this is from the variance of  $\hat{\beta}_1$ , we are simply substituting the unknown  $\sigma^2$  with MSE

# Definition. standardization of $\hat{\beta}_1$

Standardization of sampling distribution of  $\hat{\beta}_1$  gives

$$Z = \frac{\hat{\beta}_1 - \beta_1}{\sigma(\hat{\beta}_1)} = \mathcal{N}(0, 1) \quad wher \quad \sigma(\hat{\beta}_1) = \frac{\sigma}{\sqrt{S_{XX}}}$$

Usually, have to estimate standard error  $\sigma(\hat{\beta}_1)$  with  $s(\hat{\beta}_1)$ . Standardization where the denominator is an estimated standard error is called **studentized statistic**, given by

$$T = \frac{\hat{\beta}_1 - \beta_1}{s(\hat{\beta}_1)} \sim t_{n-2}$$
 where  $s^2(\hat{\beta}_1) = \frac{MSE}{S_{XX}}$ 

*Proof.* Assume proposition

$$\frac{\sum (\hat{e}_i)^2}{\sigma^2} \sim \chi_{n-2}^2$$

Then we have

$$\frac{\hat{\beta}_1 - \beta_1}{s(\hat{\beta}_1)} = \frac{\hat{\beta}_1 - \beta_1}{\sigma(\hat{\beta}_1)} / \frac{s(\hat{\beta}_1)}{\sigma(\hat{\beta}_1)} = \frac{\hat{\beta}_1 - \beta_1}{\sigma(\hat{\beta}_1)} / \sqrt{\frac{\sum e_i^2 S_{XX}}{(n-2)S_{XX}\sigma^2}} \sim \frac{Z}{\sqrt{\chi_{n-2}^2/(n-2)}} = t_{n-2}$$

### Definition. Confidence Interval and test for $\beta_1$

We use the previously derived distribution as a pivot

$$\Pr\left(t_{\alpha/2,n-2} \le \frac{\hat{\beta}_1 - \beta_1}{s(\hat{\beta}_1)} \le t_{1-\alpha/2,n-2}\right) = 1 - \alpha$$

$$\Pr\left(\hat{\beta}_{1} - s(\hat{\beta}_{1})t_{1-\alpha/2, n-2} \le \beta_{1} \le \hat{\beta}_{1} + s(\hat{\beta}_{1})t_{1-\alpha/2, n-2}\right) = 1 - \alpha$$

Hence the confidence interval is given by

$$\hat{\beta}_1 \pm s(\hat{\beta}_1)t_{1-\alpha/2,n-2}$$
 where  $s^2(\hat{\beta}_1) = \frac{MSE}{S_{XX}}$ 

For 2-sided tests

$$\begin{cases} \mathcal{H}_0 : \beta_1 = b \\ \mathcal{H}_\alpha : \beta_1 \neq b \end{cases}$$

We compute test statistics

$$t^* = \frac{\hat{\beta}_1 - b}{s(\hat{\beta}_1)}$$
 and reject  $\mathcal{H}_0$  if  $|t^*| > t_{1-\alpha/2, n-2}$ 

# 2.2 Inference Concerning of $\hat{\beta}_0$

# Definition. Sampling Distribution of $\hat{\beta}_0$

Given point estimator

$$\hat{\beta}_0 = \overline{y} - \beta_1 \overline{x}$$

 $\hat{\beta}_0$  refers to different values of  $\beta_0$  that would be obtained with repeated sampling when levels of predictor variable x are held constant from sample to sample. The **sampling distribution** of  $\hat{\beta}_0$  is **normal** with mean and variance

$$\mathbb{E}(\hat{\beta}_0) = \beta_0 \qquad Var(\hat{\beta}_0) = \sigma^2 \left[ \frac{1}{n} + \frac{\overline{x}^2}{\sum (x_i - \overline{x})^2} \right] = \sigma^2 \left[ \frac{1}{n} + \frac{\overline{x}^2}{S_{XX}} \right]$$

Proof.

$$\mathbb{E}(\hat{\beta}_0) = \mathbb{E}(\overline{y}) - \mathbb{E}(\hat{\beta}_1 \overline{x}) = \frac{1}{n} \sum \mathbb{E}(y_i) - \beta_1 \overline{x} = \beta_0 + \beta_1 \frac{1}{n} \sum x_i - \beta_1 \overline{x} = \beta_0$$

$$Var(\hat{\beta}_{0}) = Var(\overline{y} - \hat{\beta}_{1}\overline{x})$$

$$= Var(\overline{y}) + \overline{x}^{2}Var(\hat{\beta}_{1}) - 2\overline{x}Cov(\overline{y}, \hat{\beta}_{1})$$

$$= Var(\frac{1}{n}\sum y_{i}) + \frac{\sigma^{2}}{S_{XX}} - 2\overline{x}Cov(\frac{1}{n}\sum y_{i}, \sum_{i} k_{i}y_{i})$$

$$= \frac{\sigma^{2}}{n^{2}} + \frac{\sigma^{2}}{S_{XX}} - 2\overline{x}\frac{1}{n}\sum k_{i}Cov(y_{i}, y_{i})$$

$$= \frac{\sigma^{2}}{n^{2}} + \frac{\sigma^{2}}{S_{XX}} - 2\overline{x}\frac{\sigma^{2}}{n}\sum k_{i}$$

$$= \sigma^{2}\left(\frac{1}{n} + \frac{\overline{x}^{2}}{S_{XX}}\right)$$

The normality follows because  $\hat{\beta}_0$  is also a linear estimator of  $y_i$ s. We can estimate  $Var(\hat{\beta}_0)$  by replacing  $\sigma^2$  with MSE, as before

$$s^{2}(\hat{\beta}_{0}) = MSE\left[\frac{1}{n} + \frac{\overline{x}^{2}}{S_{XX}}\right]$$

Definition. Standardization of  $\hat{\beta}_0$ 

$$Z = \frac{\hat{\beta}_0 - \beta_0}{\sigma(\hat{\beta}_0)} \sim t_{n-2} \quad \text{where} \quad \sigma^2(\hat{\beta}_0) = \sigma^2 \left[ \frac{1}{n} + \frac{\overline{x}^2}{S_{XX}} \right]$$
$$T = \frac{\hat{\beta}_0 - \beta_0}{s(\hat{\beta}_0)} \sim t_{n-2} \quad \text{where} \quad s^2(\hat{\beta}_0) = MSE \left[ \frac{1}{n} + \frac{\overline{x}^2}{S_{XX}} \right]$$

Definition. Confidence Interval for  $\hat{\beta}_0$ 

$$\hat{\beta}_0 \pm s(\hat{\beta}_0) t_{1-\alpha/2,n-2} \quad \text{where} \quad s(\hat{\beta}_0) = \sqrt{\frac{\sum e_i^2}{n-2}} \sqrt{\frac{1}{n} + \frac{\overline{x}^2}{S_{XX}}}$$

Definition. Consideration about inference

- 1. **Spacing of** x **levels** Looking at variance of  $\hat{\beta}_0$  and  $\hat{\beta}_1$ , the larger the spread in x levels, the larger  $S_{XX}$  and smaller the variance.
- 2.4 Interval Estimation of  $\mathbb{E}(Y|X=x^*)$ , the population regression line

**Definition.** Mean estimation Often times want to estimate mean for one or more probability distribution of Y. (i.e. mean Y for low and high X levels). Let  $x^*$  be level of X for which we want to estimate the mean response  $\hat{y}^*$ . The mean response is given by

$$\mathbb{E}(Y|X = x^*) = E(y^*) = \beta_0 + \beta_1 x^*$$

The idea is that the expectation is a random variable because of the estimated correlation coefficients. We would want to do inference on the mean response. We have a point estimator of the the mean response

$$\hat{y}^* = \hat{\beta}_0 + \hat{\beta}_1 x^*$$

which is simply the estimated response from estimated correlation coefficients and regression function. Note  $X = x^*$  is a known constant

**Definition.** Sampling Distribution of mean response estimator  $\hat{y}^*$ The sampling distribution of  $\hat{y}^*$  is normal with mean and variance

$$\mathbb{E}(\hat{y}^*) = \mathbb{E}(\hat{y}|X = x^*) = \beta_0 + \beta_1 x^* \quad (= \mathbb{E}(y^*) \text{ so unbiased})$$

$$Var(\hat{y}^*) = Var(\hat{y}|X = x^*) = \sigma^2 \left[ \frac{1}{n} + \frac{(x^* - \overline{x})^2}{\sum (x_i - \overline{x})^2} \right] = \sigma^2 \left[ \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}} \right]$$


$$\hat{y}^* = (\hat{y}|X = x^*) \sim \mathcal{N}(\beta_0 + \beta_1 x^*, \sigma^2 \left[ \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}} \right])$$

Note when  $x^* = 0$ ,  $Var(\hat{y}^*)$  reduces to variance of  $\hat{\beta}_0$ .

Proof. 3 parts

- 1. Normality of  $\hat{y}^*$  follows from the fact that it is composed of  $\hat{\beta}_0$  and  $\hat{\beta}_1$ , both of which are linear estimators of  $y_i$
- 2. Mean

$$\mathbb{E}(\hat{y}^*) = \mathbb{E}\left(\hat{\beta}_0 + \hat{\beta}_1 x^*\right) = \mathbb{E}(\hat{\beta}_0) + x^* \mathbb{E}(\hat{\beta}_1) = \beta_0 + \beta_1 x^* = \mathbb{E}(y^*)$$



#### 3. Variance

$$Var(\hat{y}|X = x^*) = Var(\hat{\beta}_0 + \hat{\beta}_1 x | X = x^*)$$
  
=  $Var(\hat{\beta}_0 | X = x^*) + (x^*)^2 Var(\hat{\beta}_1 | X = x^*) + 2x^* Cov(\hat{\beta}_0, \hat{\beta}_1 | X = x^*)$ 

with

$$Cov(\hat{\beta}_0, \hat{\beta}_1 | X = x^*) = Cov(\overline{y} - \hat{\beta}_1 \overline{x} | X = x^*)$$

$$= Cov(\overline{y}, \hat{\beta}_1 | X = x^*) - \overline{x}Cov(\hat{\beta}_1, \hat{\beta}_1)$$

$$= 0 - \overline{x}Var(\hat{\beta}_1)$$

$$= \frac{-\overline{x}\sigma^2}{S_{XX}}$$

So

$$Var(\hat{y}|X = x^*) = \sigma^2 \left( \frac{1}{2} + \frac{\overline{x}^2}{S_{XX}} \right) + (x^*)^2 \frac{\sigma^2}{S_{XX}} - \frac{2x^* \overline{x} \sigma^2}{S_{XX}} = \sigma^2 \left( \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}} \right)$$

Idea is variability of  $\hat{y}^*$  is affected by how far  $x^*$  is from  $\overline{x}$ , via

$$(x^* - \overline{x})^2 = S_{XX}$$

The further  $x^*$  is from  $\overline{x}$ , the greater the variability. Note in plot,  $x_1$  near  $\overline{x}$ , the fitted value  $\hat{y}_1$  for two sample regression line (from 2 experiments) are close to each other; the fitted values  $\hat{y}_2$  differ substantially due to the fact that  $x_2$  is far from  $\overline{x}$ . In summary,

variation in  $\hat{y}^*$  value from sample to sample will be greater when  $x^*$  is far from mean than when  $x^*$  is near mean

We can substitute MSE for  $\sigma^2$  to obtain  $s^2(\hat{y}^*)$ . The estimated variance is given by

$$s^{2}(\hat{y}^{*}) = MSE\left[\frac{1}{n} + \frac{(x^{*} - \overline{x})^{2}}{S_{XX}}\right]$$

Definition. Standardization of mean response estimator  $\hat{y}^*$ 

$$Z = \frac{\hat{y}^* - (\beta_0 + \beta_1 x^*)}{\sigma(\hat{y}^*)} \sim \mathcal{N}(0, 1)$$

note  $\mathbb{E}(y^*) = \beta_0 + \beta_1 x^*$ 

$$T = \frac{\hat{y}^* - (\beta_0 + \beta_1 x^*)}{s(\hat{y}^*)} \sim t_{n-2}$$

Definition. Confidence Interval for  $\hat{y}^*$ 

The  $100(1-\alpha)\%$  confidence interval for  $\mathbb{E}(Y|X=x^*)=\beta_0+\beta_1x^*$  is given by

$$\hat{y}^* \pm s(\hat{y}^*) t_{1-\alpha/2, n-2} = (\hat{\beta}_0 + \hat{\beta}_1 x^*) \pm t_{1-\alpha/2, n-2} \sqrt{\frac{\sum e_i^2}{n-2}} \sqrt{\frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}}}$$

#### Definition. Obervations

- variance of ŷ\* is smallest when x\* = x̄. So in an experiment to estimate mean response at a particular level x\* of predictor variable, the precision of the estimate is greatest if (everything else remain equal) the observations on X are spaced so that x̄ = x\*
- 2. confidence interval for  $\hat{y}^*$  not sensitive to moderate departures from assumption of error being normally distributed. The robustness in estimating mean response is related to robustness of Confidence interval for  $\beta_0$  and  $\beta_1$

#### 2.5 Prediction of New Observations

#### Definition. Prediction of New Observations

- 1. Motivation Idea is that we have a model set up given a set of data, and we would want to extrapolate to new data points. The new observation Y is viewed as the result of a new trial, independent of trials on which the regression analysis is based. Let level of X be x\* and the new observation y\*<sub>new</sub> (which is unknown, and which we want to characterize), assuming that the underlying regression model is still appliable for basic sample data
- 2. Estimate of mean response  $\mathbb{E}(y^*)$  vs. Prediction of new response  $y_{new}^*$  In the former case, we estimate mean of distribution of Y. In latter case, we predict an individual outcome drown from the distribution of Y. Idea is we have to take into account of the fact that the majority of individual outcomes deviate from the mean response

Definition. Prediction Interval for  $y_{new}^*$  when parameter is known Assume all parameters are known, we have  $y^*$  follow a normal distribution


$$y_{new}^* \sim \mathcal{N}(\beta_0 + \beta_1 x^*, \sigma^2)$$

So we have confidence interval,

$$(\beta_0 + \beta_1 x^*) \pm \sigma z_{1-\alpha/2}$$

## Definition. Prediction Interval for $y_{new}^*$ when parameter is unknown

When parameter is unknown, we must estimate regression parameters. We might want to estimate mean distribution of Y with  $\hat{y^*}$  and variance of distribution of Y with MSE.



However, we cannot substitute these estimate into the previous distribution because  $\mathbb{E}(y^*)$  is a random variable. Since we do not know the mean  $\mathbb{E}(y^*)$ , and only estimate it by a confidence interval (shown previously), we cannot be certain of the distribution of Y. It could be anywhere along within its confidence intervals (for  $\mathbb{E}\{Y_h\}$ ). Hence **prediction** limit for  $y_{new}^*$  must take into account two elements

- 1. variation in possible location of distribution of Y (i.e. sampling distribution of  $\hat{y}^*$ )
- 2. variation within the probability distribution of Y (namely  $\sigma^2$ , same as that of error terms')

$$y_{new}^* - \hat{y}^* = \beta_0 + \beta_1 x^* + e^* - \hat{y}^* = \mathbb{E}(y_{new}|X = x^*) - \hat{y}^* + e^*$$

We can prove that

$$\mathbb{E}(y_{new}^* - \hat{y}^*) = \mathbb{E}(y_{new} - \hat{y}|X = x^*) = \beta_0 + \beta_1 x^* + \mathbb{E}(e^*) - \mathbb{E}(\hat{y}^*) = 0$$

$$Var(y_{new}^* - \hat{y}^*) = Var(\hat{\beta}_0 + \hat{\beta}_1 x^*) + Var(\hat{y}^*) - Cov(y_{new}^*, \hat{y}^*)$$
$$= \sigma^2 + \sigma^2 \left[ \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}} \right] = \sigma^2 \left[ 1 + \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}} \right]$$

Note  $Cov(y_{new}^*, \hat{y}^*) = 0$  by independence

$$y_{new}^* - \hat{y}^* \sim \mathcal{N}(0, \sigma^2 \left[ 1 + \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}} \right])$$

An unbiased estimtor of the variance is given by

$$s^{2}(y_{new}^{*} - \hat{y}^{*}) = MSE\left[1 + \frac{1}{n} + \frac{(x^{*} - \overline{x})^{2}}{S_{XX}}\right]$$

Standardization of  $y_{new}^*$  gives

$$T = \frac{y_{new}^* - \hat{y}^*}{s^2(y_{new}^* - \hat{y}^*)} \, \sim \, t_{n-2}$$

The  $(100 - \alpha)\%$  **Prediction limit** for  $y_{new}^*$  at  $X = x^*$  is thus given by,

$$(\hat{\beta}_0 + \hat{\beta}_1 x^*) \pm t_{1-\alpha/2, n-2} MSE \sqrt{1 + \frac{1}{n} + \frac{(x^* - \overline{x})^2}{S_{XX}}}$$

#### Definition. Comments

- 1. prediction limit is subject to departure from normality of error term distributions
- 2. A confidence interval represents an inference on a paramter and is an interval that is intended to cover the value of **parameter**. A prediction interval, is a statement about the value to be taken by a **random variable**, the new observation  $y_{new}^*$


## Confidence-band for Regression line

**Definition.** Confidence-band represents uncertainty in the estimate of regression line (i.e.  $\mathbb{E}(Y) = \beta_0 + \beta_1 X$ ). Used to determine appropriateness of a fitted regression function. The Working-Hotelling  $1 - \alpha$  confidence band for regression line has boundary values at any level  $x^*$ 

$$\hat{y}^* \pm Ws\{\hat{y}^*\}$$
 where  $W^2 = 2F_{1-\alpha,n-2}$ 

## Analysis of Variance Approach to Regression Analysis

**Definition.** Partitioning Total sum of Squares Idea is to partition sums of squares and degree of freedom associated with response variable Y



1. Total sum of squares (SST)

$$SST = \sum (y_i - \overline{y})^2$$

is a measure of uncertainty of Y, without taking X into account

2. Residual sum of squares (RSS, SSE)

$$RSS = \sum (y_i - \hat{y}_i)^2$$

is a measure of variation of Y, with X taken into account. The greater variation of Y around fitted regression line, the larger the RSS.

3. Regression sum of squares (SSR, SSreg)

$$SSreg = \sum (\hat{y}_i - \overline{y})^2$$

Alternatively we can expand and get to an equivalent expression

$$SSreg = \sum ((\hat{\beta}_0 - \hat{\beta}_1 x_i) - (\hat{\beta}_0 + \hat{\beta}_1 \overline{x}))^2 = \hat{\beta}_1^2 \sum (x_i - \overline{x})^2$$

SST can be broken down into 2 components, i.e. deviation of fitted value  $\hat{Y}_i$  around mean  $\overline{Y}$  and deviation of observed  $Y_i$  around fitted regression line

$$\underline{Y_i - \bar{Y}} = \underline{\hat{Y}_i - \bar{Y}} + \underline{Y_i - \hat{Y}_i}$$

Total Deviation Deviation deviation of fitted around regression value regression around mean line

The sum of these squared deviations have the same relationship!

$$\sum (Y_i - \hat{Y})^2 = \sum (\hat{Y}_i - \overline{Y})^2 + \sum (Y_i - \hat{Y}_i)^2$$
$$SST = RSS + SSreq$$

 $total\ variability = unexplained\ variability + variability\ explained\ by\ model$ 

Proof.

$$\sum (y_i - \overline{y})^2 = \sum [(\hat{y}_i - \overline{y}) + (y_i - \hat{y}_i)]^2$$

$$= \sum (\hat{y}_i - \overline{y})^2 + \sum (y_i - \hat{y}_i)^2 + 2\sum (\hat{y}_i - \overline{y})(y_i - \hat{y}_i)$$

$$= SSreg + RSS$$

where

$$2\sum_{i}(\hat{y}_{i} - \overline{y})(y_{i} - \hat{y}_{i}) = 2\sum_{i}\hat{y}_{i}(y_{i} - \hat{y}_{i}) - 2\overline{y}\sum_{i}(y_{i} - \hat{y}_{i})$$
$$= 2\sum_{i}\hat{y}_{i}e_{i} - 2\overline{y}\sum_{i}e_{i}$$
$$= 0$$

#### Definition. Break down of degress of freedom

- 1. SST has n-1 degrees of freedom (1 df is lost because sample mean  $\overline{y}$  is used to estimate population mean)
- 2. RSS has n-2 degrees of freedom (2 df lost because  $\beta_0$  and  $\beta_1$  are estimated)
- 3. SSreg has 1 degree of freedom.

$$n-1=1+(n-2)$$

**Definition.** Mean Squares A sum of squares divided by its associated degree of freedom is mean square

 $MSR = \frac{SSreg}{1} = SSreg \qquad MSE = \frac{RSS}{n-2}$ 

MSE of an estimator measures the average of the squares of the errors or deviations, i.e. the difference between the estimator and what is estimated. MSE is a measure of quality of estimator

**Definition.** Analysis of Variance Table displays breakdowns of total sum of squares and associated degrees of freedom

		1		
Source of Variation	SS	df	√M̂S	E{MS}
Regression	$SSR = \sum (\hat{Y}_i - \bar{Y})^2$ ,	1	$MSR = \frac{SSR}{1}$	$\sigma^2 + \beta_1^2 \sum (X_i - \bar{X})^2$
Error	$SSE = \sum (Y_i - \hat{Y}_i)^2$	n-2	$MSE = \frac{SSE}{n-2}$	$\sigma^2$
Total	$SSTO = \sum (Y_i - \bar{Y})^2$	n-1		

**Definition.** Expected Mean square Expected value of a mean square is the mean of its sampling distribution and tells us what is being estimated by the mean square.

$$\mathbb{E}(MSE) = \sigma^2$$

$$\mathbb{E}(MSR) = \sigma^2 + \beta_1^2 \sum_{i=1}^{\infty} (x_i - \overline{x})^2$$

Proof. Given

$$\frac{RSS}{\sigma^2} \sim \chi_{n-2}^2$$

We have

$$\mathbb{E}(\frac{RSS}{\sigma^2}) = n-2 \quad \to \quad \mathbb{E}(\frac{RSS}{n-2}) = \mathbb{E}(MSE) = \sigma^2$$

To prove  $\mathbb{E}(MSR)$ , we first note form of SSreg,

$$SSreg = \hat{\beta}_1^2 \sum (x_i - \overline{x})^2$$

to find its expected value, we first find

$$\mathbb{E}(\hat{\beta}_1^2) = Var\hat{\beta}_1 + (\mathbb{E}(\hat{\beta}_1))^2 = \frac{\sigma^2}{S_{XX}} + \beta_1^2$$

Then we have

$$\mathbb{E}(SSreg) = \mathbb{E}(\hat{\beta}_1^2) \sum_{i} (x_i - \overline{x})^2 = (\frac{\sigma^2}{S_{XX}} + \beta_1^2) S_{XX} = \sigma^2 + \beta_1^2 S_{XX}$$

Then we find mean squared regression

$$\mathbb{E}(MSR) = \mathbb{E}(\frac{SSreg}{1}) = \sigma^2 + \beta_1^2 S_{XX}$$

**Definition.** F test of  $\beta_1 = 0$  versus  $\beta_1 \neq 0$ 

To test for if there is a linear relationship between X and Y, We can test for this with t test

$$T = \frac{\hat{\beta}_1 - 0}{\sigma / \sqrt{S_{XX}}} \sim t_{n-2}$$

Alternatively, to generalize the test to multiple regression, we can use F test where test statistics is given by

$$F^* = \frac{MSR}{MSE} = \frac{SSreg}{RSS/(n-2)}$$

Intuitively, larger values of  $F^*$  (larger MSR) supports  $H_{\alpha}$  and values of  $F^*$  near 1 supports  $H_0$ . It can be shown that sampling distribution for  $F^*$  is given by

$$F^* \sim F_{1,n-2}$$

The test is then given by

**Reject** if 
$$F^* > F_{1-\alpha:1.n-2}$$

Proof.

$$F^* = \frac{MSR}{MSE} = \frac{MSR / \sigma^2}{MSE / \sigma^2} = \frac{\chi_1^2}{\chi_{n-2}^2} \sim F_{1,n-2}$$

Definition. Equivalence of F test and t test

Given  $\alpha$  confidence level, F test of  $\beta_1 = 0$  versus  $\beta_1 \neq 0$  is equivalent to two-sided t test

Proof.

$$F^* = \frac{SSreg/1}{RSS/(n-2)} = \frac{\hat{\beta}_1 \sum (x_i - \overline{x})^2}{MSE} = \frac{\hat{\beta}_1 S_{XX}}{MSE}$$

Note

$$s^2(\hat{\beta}_1) = \frac{MSE}{S_{XX}}$$

we have

$$F^* = \left(\frac{\hat{\beta}_1^2 - 0}{s(\hat{\beta}_1)}\right)^2 = (t^*)^2$$

where t is the t statistics

# 2.9 Descriptive Measures of Linear Association between X and Y Definition. Coefficient of Determination

- 1. SST measures variation in Y without taken into account of X
- 2. RSS is a measure of variation in Y when taken into account of X
- 3. A natural measure of effect of X in reducing variation in Y is in the difference between SST and RSS as a proportion of total variation

The coefficient of determination  $R^2$  is given by

$$R^2 = \frac{SST - RSS}{SST} = \frac{SSreg}{SST}$$

with

$$0 \le R^2 \le 1$$

 $\mathbb{R}^2$  can be interpreted as the proportionate reduction of total variation associated with use of X predictor variable

#### Definition. Coefficient of Correlation

A measure of linear association between Y and X when both Y and X are random is coefficient of correlation.

$$r = \pm \sqrt{R^2} = \frac{S_{XY}}{\sqrt{S_{XX}S_{YY}}}$$

Proof.

$$\sqrt{R^2} = \sqrt{\frac{SSReg}{SST}} = \sqrt{\frac{\hat{\beta}_1^2 S_{XX}}{S_{YY}}} = \sqrt{(\frac{S_{XY}}{S_{XX}})^2 \frac{S_{XX}}{S_{YY}}} = \frac{S_{XY}}{\sqrt{S_{XX}S_{YY}}}$$

# Dummy variable regression

**Definition.** 1. Dummy variable is one that takes the value 0 or 1 to indicate the absence or presence of some categorical effect that may expect to shift the outcome