

# IT Automation Online Installation

**\*** In this document, "Exastro IT Automation" is described as "ITA".

# **Exastro**

#### **Table of Contents**

- 1. Introduction
  - 1.1 About This Guide
- 2. System Organization
  - 2.1 Functions executed in conjunction with other tools
  - 2.2 System Requirements
- 3. IT Automation Configuration Procedure
  - 3.1 Online Installation
  - 3.2 Preparation (1/2)
  - 3.3 Preparation (2/2)
  - 3.4 Flow of IT Automation Configuration
  - 3.5 Configuration (1/7)
  - 3.6 Configuration (2/7)
  - 3.7 Configuration (3/7)
  - 3.8 Configuration (4/7)
  - 3.9 Configuration (5/7)
  - 3.10 Configuration (6/7)
  - 3.11 Configuration (7/7)
- 4. IT Automation Operation Check
  - 4.1 Operation Check (1/6)
  - 4.2 Operation Check (2/6)
  - 4.3 Operation Check (3/6)
  - 4.4 Operation Check (4/6)
  - 4.5 Operation Check (5/6)
  - 4.6 Operation Check (6/6)
  - 4.7 Reference

# 1. Introduction



#### 1.1 About This Guide

#### About this guide

• This guide describes how to set up IT Automation in an all-in-one configuration by using its installer and external repositories.



# 2. System Organization



# 2.1 Functions executed in conjunction with other tools

#### Functions executed in conjunction with other tools

• IT Automation supports the tools for the following functions:

Driver	Tool name (orchestrator)	Function name	Description	Installable with the IT Automation configuration tool	To be installed through this guide	
Material	Git	Management of configuration materials	This function allows you to "Check out" and "Check in" configuration materials registered in the standard configuration tools and to manage the versions of the materials via Git.	Yes	No	
Create_param	-	Creation of menus	This function allows you to create menus.	-	Yes	
Hostgroup	-	Host grouping	This function allows you to group hosts into logical units (functions and roles) and to manage the parameters to be applied.	-	Yes	
Ansible driver	Ansible	System construction	A Red Hat-provided OSS tool for setting up a platform. For a networked device, this tool allows you to install software, configure various settings, transfer files, and apply patches, based on an IaC called Playbook.	Yes	Yes	
	Ansible Tower	System construction	A management platform to enhance Ansible with such functions as access control, job scheduling, and task visualization.	No		
Cobbler driver	Cobbler	OS installation	An OSS tool for automating installation. For a networked device, this tool allows you to install an OS, based on a prepared template.	No	No	
OpenStack driver	OpenStack	Virtual system construction	An OSS tool for setting up a cloud environment. This tool allows you to set up virtual machines, storages, and networks.	No	No	
PowerShell DSC driver	PowerShell DSC	System construction	A Microsoft-provided tool for setting up a platform. For a Windows environment, this tool allows you to create server users and install software.	No	No	

## 2.2 System Requirements

- The followings are the system requirements to use IT Automation:
  - We are preparing a manual for Exastro-ITA system configuration and environment construction.


3. IT Automation Configuration Procedure



#### 3.1 Online Installation

#### Installation procedure

 When the IT Automation server has an internet-connection, install necessary libraries via the Internet and execute the IT Automation installer to perform configuration.



IT Automation server

Internet

# 3.2 Preparation (1/2)

#### Enabling repositories (only for online installation)

Depending on your OS version, enable the following repositories:

os	Repository			
	https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm			
RHEL7	https://downloads.mariadb.com/MariaDB/mariadb_repo_setup			
	http://rpms.remirepo.net/enterprise/remi-release-7.rpm			
	rhel-7-server-optional-rpms			
RHEL8	https://dl.fedoraproject.org/pub/epel/epel-release-latest-8.noarch.rpm			
KHEL8	codeready-builder-for-rhel-8-xxxxxx-rpms			
	epel-release			
CentOS7	https://downloads.mariadb.com/MariaDB/mariadb_repo_setup			
	http://rpms.remirepo.net/enterprise/remi-release-7.rpm			
CentOS8	epel-release			
Centoso	PowerTools			

xxxxxx:architecture

# 3.3 Preparation (2/2)

#### IT Automation configuration tools


• The following table lists tools for configuring IT Automation:

Description	File	Path location
Library collection script	ita_gather_library.sh	/(Extract path)/ita_install_package/install_scripts/
Configuration tool (for offline installation)	ita_builder_offline.sh	/(Extract path)/ita_install_package/install_scripts/
Configuration tool (for online installation)	ita_builder_online.sh	/(Extract path)/ita_install_package/install_scripts/
Setting file	ita_builder_setting.txt	/(Extract path)/ita_install_package/install_scripts/
IT Automation installer	ita_installer.sh	/(Extract path)/ita_install_package/install_scripts/
Answer file	ita_answers.txt	/(Extract path)/ita_install_package/install_scripts/

#### 3.4 Flow of IT Automation Configuration

#### Configuration flow (online)

• The configuration flow is as follows:



## 3.5 Configuration (1/7)

- \*Environment building users must be root users.
- Downloading the materials from Github
  - Download the materials with the following command:

```
# wget https://github.com/exastro-suite/it-automation/archive/vx.x.x.tar.gz
```

\*The wget command needs to be installed in advance.

\*Change the (x.x.x) for the version to be installed.

#### Changing the permission of the installation scripts

Unzip the .gz file and change the permission of the installation scripts.

```
# tar zxf vx.x.x.tar.gz
# find ./it-automation-x.x.x/ita_install_package/ -type f -name *.sh | xargs chmod 755
```

- Changing the directory
  - Move to the directory where the setting file and the shell are stored for configuration.

# cd it-automation-x.x.x/ita install package/install scripts

# 3.6 Configuration (2/7)

#### Editing the setting file


 The following table lists what to be edited in the setting file (ita\_builder\_setting.txt) for IT Automation configuration:

ltem	Required	Initial value	Description
linux_os	Yes (for all OS)	-	OS of the IT Automation server ("CentOS7","CentOS8","RHEL7","RHEL8", "RHEL7_AWS","RHEL8_AWS") *)RHEL7_AWS: RHEL7 on AWS RHEL8_AWS: RHEL8 on AWS
redhat_user_name		-	Username for the Red Hat account
redhat_user_password	For RHEL OS other than on AWS	-	Password for the Red Hat account
pool_id		-	Pool ID for the Red Hat account

#### 3.7 Configuration (3/7)

- Sample of the setting file (ita\_builder\_setting.txt)
  - The following shows an example of the setting file (ita\_builder\_setting.txt):

OS of the installation target server: RHEL 7



#### 3.8 Configuration (4/7)

#### Editing the answer file (ita\_answers.txt)

- Edit the answer file for IT Automation installation in advance.
- For ita\_base, ansible\_driver, create\_param, and Hostgroup, each of the initial values is set to yes. Change the value to no if the corresponding installation is not necessary.

ltem	Required	Default value	Description
install_mode	Yes	Install	Installation mode: Install or Uninstall
ita_directory	Yes	_	Specify the absolute path to the directory where IT Automation will be installed. If the directory does not exist, it will be newly created.
ita_language	Yes	en_US	IT Automation display language: ja_JP (Japanese) or en_US (English)
ita_os	Yes	RHEL7	OS for IT Automation: RHEL7 or RHEL8
db_root_password	Yes	-	Root password for MariaDB
db_name	Yes	-	Database name for MariaDB
db_username	Yes	-	Database username for MariaDB
db_password	Yes	_	Database password for MariaDB
ita_base	Yes	yes	Only <b>yes</b> can be specified to install IT Automation.
Material	Yes	no	Whether the Management of configuration materials function is to be installed
create_param	Yes	yes	Whether the <b>Creation of menus</b> function is to be installed
Hostgroup	Yes	yes	Whether the <b>Host grouping</b> function is to be installed
ansible_driver	Yes	yes	Whether the Ansible driver is to be installed
cobbler_driver	Yes	no	Whether the Cobbler driver is to be installed
openstack_driver	Yes	no	Whether the OpenStack driver is to be installed
dsc_driver	Yes	no	Whether the DSC driver is to be installed

#### 3.9 Configuration (5/7)

- Sample of the answer file (ita\_answers.txt)
  - The following shows an example of the answer file (ita\_answers.txt):

```
#Select install mode. ("Install" or "Uninstall")
# e.g) install mode:Install
install mode:Install
#Enter install directory.
# e.g) ita directory:/exastro
ita directory:/exastro
# Select language. ("en_US" or "ja_JP")
# e.g) ita language:en US
ita language:en US
# Select Operation System. ("RHEL7" or "RHEL8")
# e.g) ita os:RHEL8
ita os:RHEL7
# Enter the MariaDB root user's password
                                                                                 POINT
# e.g) db root password:sample root password
db root password: sample root password
                                                                                            With the answer file,
# Decide the database name, username, and password for ITA.
                                                                                        define the password for
# e.g) db name:sample db name
                                                                                                 MariaDB.
db name:sample db name
# e.g) db username:sample db username
db username:sample db username
# e.g) db password:sample db password
db password:sample db password
# Select the target you need to install.
# yes : need
# no : no need
ita base:yes
material:no
createparam:yes
hostgroup:yes
ansible driver:yes
cobbler driver:no
openstack driver:no
dsc driver:no
```

# 3.10 Configuration (6/7)

- Executing the configuration tool (for online installation)
  - Execute the configuration tool with the following command:

```
# sh ita_builder_online.sh
```

#### Checking the process

- Executing the configuration tool outputs the process details to ita\_builder.log and ita\_installer.log.
- Path to the logs

/(Extract path)/ita\_install\_package/install\_scripts/log/

# 3.11 Configuration (7/7)

#### Libraries installed through the configuration

• The following table lists the libraries installed through the execution of the configuration tool:

Installation driver	Library type	Library name	
ita_base	Installation tool	yum-utils(*), createrepo(*)	
ita_base	IT Automation common	zip, telnet, mailx, unzip	
ita_base	MariaDB MariaDB, MariaDB-server, expect		
ita_base	httpd	httpd, mod_ssl	
ita_base	php, php-bcmath, php-cli, php-ldap, php-mcrypt, php-mysqlnd, php-pear, pl php crypto, php-pecl-zip, php-process, php-snm xml, php-json, php-zip, php-gd, Python devel, libyaml, libyaml-devel, make		
ita_base	php plug-in php-yaml, HTML_AJAX-beta, PhpSpreadshee		
material	git	Git	
ansible_driver	Ansible ansible, sshpass, pexpect, pywinrm, boto3, nr ncat		

<sup>\*</sup> only RHEL7, CentOS7

4. IT Automation Operation Check



#### 4.1 Operation Check (1/6)

#### Checking the main menu

 After completing the installation, take the following steps with a Windows PC client to access the main menu of IT Automation and to check that the IT Automation and all the drivers are shown properly.

#### Accessing the login screen

- Access the login screen with the following URL:
- URL: http://(IP address)
- After installation, access from both HTTP and HTTPS are possible.
   Since HTTP is insecure, accessing from HTTPS is recommended.
   For the method to access from HTTPS, please refer to operation check (4/6).

#### Logging in

- When the IT Automation login screen appears, enter the given login ID and initial password and then click the **Login** button.
  - Login ID: administrator
  - Initial password: password
- If you have logged in for the first time after the installation, you will be prompted to change the password.
- Change the initial password.

# 4.2 Operation Check (2/6)

#### IT Automation login screen

 Having been successfully installed, IT Automation displays the following login screen:



# 4.3 Operation Check (3/6)

#### Checking the content by displaying the menus

• After logging in, check that the following menus are shown properly:

Function	Menu
	Management Console
IT Automation (main body)	Basic Console
	Export/Import
Creating menus	Create menu
Hostgroup	HostGroup management
	Ansible Common
Ansible driver	Ansible-Legacy
Alisible utiver	Ansible-Pioneer
	Ansible-LegacyRole

#### 4.4 Operation Check (4/6)

#### Preparation for accessing from HTTPS

- Specify the IP address and host name of the IT Automation server in the hosts file of the Windows client.
- For Windows 10, the hosts file is located at the following:

C:\forall C:\forall Windows\forall System32\forall drivers\forall etc\forall hosts

To the hosts file, add the following settings:

"ITA実装サーバのIPアドレス" exastro-it-automation 例) 192.168.0.3 exastro-it-automation

#### 4.5 Operation Check (5/6)

- Import the certificate into the operating device(Windows). The certificate is stored in the following directory of the IT Automation installation package.
- Use a tool (such as FFFTP and WinSCP) to download the client.

OS of the IT Automation server	File path	File name
RHEL 7, CentOS 7	/(extract path)/ita_install_package/ext_files_fo r_CentOS7.x/etc_pki_tls_certs/	exastro-it-automation.crt
RHEL 8, CentOS 8	/(extract path)/ita_install_package/ext_files_fo r_CentOS8.x/etc_pki_tls_certs/	exastro-it-automation.crt

- Import the certificate to a Web browser.
- For Google Chrome, import the certificate as follows.
  - 1. Start up Google Chrome. Then select **Settings button** in the upper right > **settings**.
  - 2. Select **Advanced** in the Lower part of browser > **Manage certificates**.
  - 3. In the **Trusted Root Certification Authorities** tab click the **Import** button in the lower left.
  - 4. When the certificate import wizard appears, click **Next**.
  - 5. Specify the name of the file to be imported. Then click **Next**.
  - 6. Make sure that the **Place all certificates in the following store** option is selected.

  - 8. Click Finish.

# 4.6 Operation Check (6/6)

- Accessing the login screen from HTTPS
  - Access the login screen with the following URL:
  - URL: https://exastro-it-automation

After connecting, follow the same procedure as from HTTP.



#### 4.7 Reference

#### Restrict HTTP or HTTPS access

Please perform the following procedure to resctrict HTTP or HTTPS access.

Edit file "/etc/httpd/conf.d/vhosts\_exastro-it-automation.conf".

 Restart Apache with the following command. systemctl restart httpd

