### Exastro-ITA\_(Reference) Configuration settings during installation

#### 1. MariaDB(server.cnf) modification list

The following setting is designed for operation on MariaDB10.4 and the minimum spec of ITA system server%1(CPU: 2 core/ Memory 4GB) %1 ITA system server ··· The basic ITA configuration that associated drivers such as Ansible driver are built in other servers.

			-	
No.	Required/ For reference	Default value	After ITA installation	Remarks
1	Required	OFF	explicit_defaults_for_timestamp = true	
2	Required	latin1	character-set-server = utf8	
4	Required	REPEATABLE -READ	transaction-isolation=READ-COMMITTED	Specify the transaction isolation level.  "READ-COMMITTED" is the default isolation level for many database systems(Oracle, PostgreSQL, SQL Server).  The default isolation level of MariaDB is "REPEATABLE-READ", which doesn't match the usage policy of ITA. So it is required to be changed.
3	For reference	128MB	innodb_buffer_pool_size = 512MB	Consider tuning depending on how to use ITA
5	For reference	16MB	innodb_log_buffer_size=64M	Consider tuning depending on how to use ITA
6	For reference	48MB	innodb_log_file_size=256M	Consider tuning depending on how to use ITA
7	For reference	0	min_examined_row_limit=100	Consider tuning depending on how to use ITA
8	For reference	256KB	join_buffer_size=128M	Consider tuning depending on how to use ITA
9	For reference	1M	query_cache_size=512M	Consider tuning depending on how to use ITA
10	For reference	OFF	query_cache_type=1	
11	For reference	16MB	max_heap_table_size=64M	Consider tuning depending on how to use ITA
12	For reference	16MB	tmp_table_size=64M	Consider tuning depending on how to use ITA
13	For reference	256KB	mrr_buffer_size=64M	Consider tuning depending on how to use ITA
14	For reference	151	max connections=256	Consider tuning depending on how to use ITA

### Exastro-ITA\_(Reference) Configuration settings during installation

#### 2. PHP(php.ini) modification list

The following setting is designed for operation on MariaDB10.4 and the minimum spec of ITA system server%1(CPU: 2 core/ Memory 4GB) %1 ITA system server ··· The basic ITA configuration that associated drivers such as Ansible driver are built in other servers.

No.	Required/ For reference	Default value	After ITA installation	Remarks
1	For reference	output_buffering = 4096	output_buffering = 8192	Consider tuning depending on how to use ITA
2	For reference	expose_php = On	expose_php = Off	Modify the setting to hide PHP version
3	For reference	max_execution_time = 30	max_execution_time = 600	Consider the tuning if timeout occurs when using ITA
4	For reference	max_input_time = 60	max_input_time = 600	Consider the tuning if timeout occurs when using ITA
5	For reference	memory_limit = 128M	memory_limit = 512M	Consider the tuning if memory allocation is not enough for PHP when using ITA
6	For reference	post_max_size = 8M	post_max_size = 4096M	Consider the tuning if large capacity registered/updated can't be performed when using ITA
7	For reference	upload_max_filesize = 2M	upload_max_filesize = 4096M	Consider the tuning according to the file size that users want to upload in ITA
8	For reference	default_socket_timeout = 60	default_socket_timeout = 600	Consider tuning depending on how to use ITA
9	Required	;date.timezone =	date.timezone = "Asia/Tokyo"	
10	For reference	pdo_mysql.cache_size = 2000	pdo_mysql.cache_size = 4000	Consider tuning depending on how to use ITA
11	Required	pdo_mysql.default_socket=	pdo_mysql.default_socket=/var/lib/mysql/mysql.sock	ITA uses PHP with PDO to connect to MySQL
12	For reference	mysql.cache_size = 2000	mysql.cache_size = 4000	Consider tuning depending on how to use ITA
13	For reference	mysql.connect_timeout = 60	mysql.connect_timeout = 600	Consider tuning depending on how to use ITA
14	Required	;session.save_path = "/tmp"	session.save_path = "/var/lib/php/session"	The directory mentioned in the modification is required to be created in advance.  The default directory(/tmp) is not recommended
15	Required	session.gc_divisor = 1000	session.gc_divisor = 1	Control garbage collection of PHP session file.  According to the setting on the left with the combination of the default value session.gc_probability = 1, the session file that passed 12 hours
16	Required	session.gc_maxlifetime = 1440	session.gc_maxlifetime = 43200	or more is in 100% probability to be performed garbage collection.
17	Required	;mbstring.language = Japanese	mbstring.language = Japanese	※Uncomment
18	Required	;mbstring.internal_encoding =	mbstring.internal_encoding = UTF-8	X Uncomment + Modify
19	Required	;mbstring.http_input =	mbstring.http_input = auto	X Uncomment + Modify
20	Required	;mbstring.http_output =	mbstring.http_output = UTF-8	
21	Required	;mbstring.encoding_translation = Off	mbstring.encoding_translation = Off	※Uncomment
22	Required	;mbstring.detect_order = auto	mbstring.detect_order = auto	**Uncomment
23	Required	;mbstring.substitute_character = none	mbstring.substitute_character = none	**Uncomment
24	Required	none	extension=yaml.so	※Add
-			I	ı

# Exastro-ITA\_(Reference) Configuration settings during installation 3. Ansible(ansible.ofg) modification list

٠.,	a loible(all	Sible.cig/ illoulification list		
No.	Required/ For reference	Default value	After ITA installation	Remarks
1		#inventory = /etc/ansible/hosts	inventory = /etc/ansible/hosts	*Uncomment
2	Required	#remote_tmp = ~/.ansible/tmp	remote_tmp = ~/.ansible/tmp	*Uncomment
3	Required	#forks = 5	forks = 5	※Uncomment
4	Required	#poll_interval = 15	poll_interval = 15	*Uncomment
5	Required	#sudo_user = root	sudo_user = root	*Uncomment
6	Required	#transport = smart	transport = smart	*Uncomment
7	Required	#module_lang = C	module_lang = C	*Uncomment
8	Required	#gathering = implicit	gathering = implicit	*Uncomment
9	Required	#host_key_checking = False	host_key_checking = False	*Uncomment
10	Required	#sudo_exe = sudo	sudo_exe = sudo	*Uncomment
11	Required	#timeout = 10	timeout = 60	
12	Required	#ansible_managed = Ansible managed	ansible_managed = Ansible managed	*Uncomment
13	Required	#deprecation_warnings = True	deprecation_warnings = False	
14	Required	#action_plugins = /usr/share/ansible/plugins/action	action_plugins = /usr/share/ansible/plugins/action	*Uncomment
15	Required	#callback_plugins = /usr/share/ansible/plugins/callback	callback_plugins = /usr/share/ansible/plugins/callback	*Uncomment
16	Required	#connection_plugins = /usr/share/ansible/plugins/connection	connection_plugins = /usr/share/ansible/plugins/connection	*Uncomment
17	Required	#lookup_plugins = /usr/share/ansible/plugins/lookup	lookup_plugins = /usr/share/ansible/plugins/lookup	*Uncomment
18	Required	#vars_plugins = /usr/share/ansible/plugins/vars	vars_plugins = /usr/share/ansible/plugins/vars	※Uncomment
19	Required	#filter_plugins = /usr/share/ansible/plugins/filter	filter_plugins = /usr/share/ansible/plugins/filter	*Uncomment
20	Required	#fact_caching = memory	fact_caching = memory	*Uncomment
21	Required	#ssh_args = -C -o ControlMaster=auto -o ControlPersist=60s	ssh_args = -o ControlMaster=auto -o ControlPersist=60s -o StrictHostKeyChecking=no -o UserKnownHostsFile=/dev/null	**Uncomment + Modify
22	Required	#accelerate_port = 5099	accelerate_port = 5099	*Uncomment
23	Required	#accelerate_timeout = 30	accelerate_timeout = 30	*Uncomment
24	Required	#accelerate_connect_timeout = 5.0	accelerate_connect_timeout = 5.0	*Uncomment
25	Required	#accelerate_daemon_timeout = 30	accelerate_daemon_timeout = 30	*Uncomment

## Exastro-ITA\_(Reference) Configuration settings during installation 4. ITA setting file description

No.	ITA-BASE	Inst	talled system Cobbler	/associated o	driver DSC	AnsibleTowe	Setting file name	Description
1	IIA DAGE	Alisible	CODDIE	Оренасаск	D30	Parisible I Owe	(ITA installed directory)/ita-root/confs/backyardconfs/cobbler_driver/path_DATA_RELAY_STRAGE_side_Cobbler	Define the root path of data relay storage in Cobbler server
			0					
2							(ITA installed directory)/ita-root/confs/backyardconfs/ita_base/data_portability_running_limit.txt	The execution time limit of data portability import process.  The process during execution will be determined as failed if the execution time passed the
	0							setting value.
								The unit is second.Default value is 300
3							(ITA installed directory)/ita-root/confs/backyardconfs/ita_base/hide_menu_column_list.txt	Describe the column to be excluded from the item display of substitution auto-registration setting
	0	0			0	0		The line starting with "#" is ignored.
4							(ITA installed directory)/ita-root/confs/backyardconfs/ita_env	Describe the log level of backyard function and the root directory(ita-root) of ITA
	0	0	0	0	0	0		
ш							(ITA installed directory)/ita-root/confs/backyardconfs/path_PHP_MODULE.txt	Describe the path of PHP module.
5	_						(11 A installed directory)/ita-root/conts/backyardconts/path_PHP_MODULE.bxt	Example: /bin/php
	0	0	0	0	0	0		
							(ITA installed directory)/ita-root/confs/backyardconfs/sysmail.list	Describe the setting when using system mail(ky mail).
0	_						(11 A installed directory)/ita-root/conis/backyaroconis/sysmali.list	Not required if the mail sending function(ky_mail) of ITA is not used.
	0							
7							(ITA installed directory)/ita-root/confs/commonconfs/ansible_vault_accesskey.bdt	The password of ansible-vault command.
,							(11A ilistalica dilectory)/ita-100y-collis/collillolicollis/alisible_vauit_accesskey.co.	The behavior of password changing is guaranteed only right after ITA is installed.
		0				0		Behavior is not guaranteed when changing password while system is operating or exporting/importing menus to environments whose password are the same.
		0						Example: The string encrypted from "ANSIBLE-VAULT-PASSWORD"
								Refer to %1 for the encryption specification
8							(ITA installed directory)/ita-root/confs/commonconfs/app_mail_from.txt	When using system mail (ky_mail) from WebDBCore, the file content becomes the sender's
	0						, , , , , , , , , , , , , , , , , , , ,	address. *In the case of sending mail to 00 loadtable.php when action occurs.
								*Not required if the mail sending function(ky_mail) of ITA is not used.
9							(ITA installed directory)/ita-root/confs/commonconfs/app_msg_language.txt	Define the language of ITA.
	0	0			0	0		
	_							
10							(ITA installed directory)/ita-root/confs/commonconfs/db_connection_string.txt	The string to connect to MySQL.
	0	0	0	0	0	0		Example: The string encrypted from "mysql:dbname=ITA_DB;host=localhost"
								Refer to %1 for the encryption specification
11							(ITA installed directory)/lta-root/confs/commonconfs/db_model_string.txt	Define the type of RDB
	0	0	0	0	0	0		0: OracleDB 1: MySQL/MariaDB
12							(ITA installed directory)/ita-root/confs/commonconfs/db_password.txt	The password to connect to MySQL.  Example: The string encrypted from "ITA_PASSWD"
	0	0	0	0	0	0		
								Refer to %1 for the encryption specification
13							(ITA installed directory)/ita-root/confs/commonconfs/db_username.txt	The user to connect to MySQL.  Example: The string encrypted from "ITA_USER"
	0	0	0	0	0	0		
								Refer to %1 for the encryption specification
14							(ITA installed directory)/ita-root/confs/commonconfs/path_ANSIBLE_MODULE.txt	Describe the path where ansible commands are installed(ansible-playbook/ansible-vault) This sample describes "/usr/local/bin"
	0	0				0		
						1		7
15		0					(ITA installed directory)/ita-root/confs/restapiconfs/ansible_driver/accesskey.txt	The access key used in the RestAPI of Ansible server.  Example: The string encrypted from "AccessKeyId"
								Refer to %1 for the encryption specification
16							(ITA installed directory)/ita-root/confs/restapiconfs/ansible_driver/secret_accesskey.txt	The secret key used in the RestAPI of Ansible server.
		0						Example: The string encrypted from "SecretAccessKey"
								Refer to %1 for the encryption specification
17							(ITA installed directory)/ita-root/confs/restapiconfs/ansible_driver/ansible_playbook_watch_time.txt	Describe the period for the RestAPI of Ansible server to check if ansible-playbook command is operating. (Unit: Millisecond)
		0						In this period, maximum operation check performed is 3 times.
18						1	(ITA installed directory)/ita-root/confs/commonconfs/admin_mail_addr.txt	Example: "10"  Describe the contact information (e-mail address) of the system administrator.
	0							If the file doesn'exist
			1	1	1			⇒The link of "Contact administrator" will disappear
19 20	0					1	(ITA installed directory)/ita-root/confs/webconfs/ExternalAuthSettings.ini (ITA installed directory)/ita-root/confs/webconfs/path_HTML_AJAX.bxt	Describe the information of the association target of ActiveDirectory.  Describe the path of HTML_AJAX.
20	0					1		Example: /usr/share/near/
21	0	0	0	0	0	0	(ITA installed directory)/ita-root/confs/webconfs/path_PhpSpreadsheet.txt	Describe the path of Phpspreadsheet. This sample: "/usr/share/php"
			_	_				*1 The value encoded by base64 then converted by rot13. Create it with the following com

This sample: "/usr/share/ohb"

% I The value encoded by base64 then converted by rot13. Create it with the following comments of the converts of the converts