## server.cnf modification list

The following setting is designed for operation with MariaDB10.4

No.	Required/ For	Default value	After ITA installation	Remarks
1	Required	OFF	explicit_defaults_for_timestamp = true	
2	Required	latin1	character-set-server = utf8	
4	Required	REPEATABLE -READ	transaction-isolation=READ-COMMITTED	Specify the transaction isolation level.  "READ-COMMITTED" is the default isolation level for many database systems(Oracle, PostgreSQL, SQL Server).  The default isolation level of MariaDB is "REPEATABLE-READ", which doesn't match the usage policy of ITA. So it is required to be changed.
3	For reference	128MB	innodb_buffer_pool_size = 256MB	Consider tuning depending on how to use ITA
5	For reference	16MB	innodb_log_buffer_size=32M	Consider tuning depending on how to use ITA
6	For reference	48MB	innodb_log_file_size=128M	Consider tuning depending on how to use ITA
7	For reference	0	min_examined_row_limit=100	Consider tuning depending on how to use ITA
8	For reference	256KB	join_buffer_size=64M	Consider tuning depending on how to use ITA
9	For reference	1M	query_cache_size=256M	Consider tuning depending on how to use ITA
10	For reference	OFF	query_cache_type=1	
11	For reference	16MB	max_heap_table_size=32M	Consider tuning depending on how to use ITA
12	For reference	16MB	tmp_table_size=32M	Consider tuning depending on how to use ITA
13	For reference	256KB	mrr_buffer_size=32M	Consider tuning depending on how to use ITA

## ansible.cfg modification list

arie	ansible.cfg modification list						
No.	Required/ For reference	Default value	After ITA installation	Remarks			
1	Required	#inventory = /etc/ansible/hosts	inventory = /etc/ansible/hosts	*Uncomment			
2	Required	#remote_tmp = ~/.ansible/tmp	remote_tmp = ~/_ansible/tmp				
3	Required	#forks = 5	forks = 5	*Uncomment			
4	Required	#poll_interval = 15	poll_interval = 15	*Uncomment			
5	Required	#sudo_user = root	sudo_user = root	*Uncomment			
6	Required	#transport = smart	transport = smart	*Uncomment			
7	Required	#module_lang = C	module_lang = C	*Uncomment			
8	Required	#gathering = implicit	gathering = implicit	*Uncomment			
8	Required	#host_key_checking = False	host_key_checking = False	*Uncomment			
9	Required	#sudo_exe = sudo	sudo_exe = sudo	*Uncomment			
10	Required	#timeout = 10	timeout = 10	*Uncomment			
11	Required	#ansible_managed = Ansible managed	ansible_managed = Ansible managed	*Uncomment			
23	Required	#deprecation_warnings = True	deprecation_warnings = False				
12	Required	#action_plugins = /usr/share/ansible/plugins/action	action_plugins = /usr/share/ansible/plugins/action	*Uncomment			
13	Required	#callback_plugins = /usr/share/ansible/plugins/callback	callback_plugins = /usr/share/ansible/plugins/callback	*Uncomment			
14	Required	#connection_plugins = /usr/share/ansible/plugins/connection	connection_plugins = /usr/share/ansible/plugins/connection	*Uncomment			
15	Required	#lookup_plugins = /usr/share/ansible/plugins/lookup	lookup_plugins = /usr/share/ansible/plugins/lookup	*Uncomment			
16	Required	#vars_plugins = /usr/share/ansible/plugins/vars	vars_plugins = /usr/share/ansible/plugins/vars	*Uncomment			
17	Required	#filter_plugins = /usr/share/ansible/plugins/filter	filter_plugins = /usr/share/ansible/plugins/filter	*Uncomment			
18	Required	#fact_caching = memory	fact_caching = memory	*Uncomment			
24	Required	#ssh_args = -C -o ControlMaster=auto -o ControlPersist=60s	ssh_args = -o ControlMaster=no -o ControlPersist=60s -o StrictHostKeyChecking=no -o UserKnownHostsFile=/dev/null				
19	Required	#accelerate_port = 5099	accelerate_port = 5099	*Uncomment			
20	Required	#accelerate_timeout = 30	accelerate_timeout = 30	*Uncomment			
21	Required	#accelerate_connect_timeout = 5.0	accelerate_connect_timeout = 5.0	*Uncomment			
22	Required	#accelerate_daemon_timeout = 30	accelerate_daemon_timeout = 30	*Uncomment			

## php.ini modification list

ph	php.ini modification list							
No.	Required/ For reference	Default value	After ITA installation	Remarks				
1		output_buffering = 4096	output_buffering = 8192	Consider tuning depending on how to use ITA				
2	For reference	expose_php = On	expose_php = Off	Modify the setting to hide PHP version				
		max_execution_time = 30	max_execution_time = 600	Consider the tuning if timeout occurs when using ITA				
		max_input_time = 60	max_input_time = 600	Consider the tuning if timeout occurs when using ITA				
		memory_limit = 128M	memory_limit = 512M	Consider the tuning if memory allocation is not enough for PHP when using ITA				
		post_max_size = 8M	post_max_size = 1024M	Consider the tuning if large capacity registered/updated can't be performed when using ITA				
		upload_max_filesize = 2M	upload_max_filesize = 1024M	Consider the tuning according to the file size that users want to upload in ITA				
		default_socket_timeout = 60	default_socket_timeout = 600	Consider tuning depending on how to use ITA				
9	Required	;date.timezone =	date.timezone = "Asia/Tokyo"					
		pdo_mysql.cache_size = 2000	pdo_mysql.cache_size = 4000	Consider tuning depending on how to use ITA				
11		pdo_mysql.default_socket=	pdo_mysql.default_socket=/var/lib/mysql/mysql.sock	ITA uses PHP with PDO to connect to MySQL				
		mysql.cache_size = 2000	mysql.cache_size = 4000	Consider tuning depending on how to use ITA				
13	For reference	mysql.connect_timeout = 60	mysql.connect_timeout = 600	Consider tuning depending on how to use ITA				
14	Required	;session.save_path = "/tmp"	session.save_path = "/var/lib/php/session"	The directory mentioned in the modification is required to be created in advance. The default directory(/tmp) is not recommended				
15	Required	session.gc_divisor = 1000	session.gc_divisor = 1	Control garbage collection of PHP session file.  According to the setting on the left with the combination of the default value session.gc.probability = 1, the session file that passed 12				
16	Required	session.gc_maxlifetime = 1440	session.gc_maxlifetime = 43200	hours or more is in 100% probability to be performed garbage collection.				
17	Required	;mbstring.language = Japanese	mbstring.language = Japanese	**Uncomment				
18	Required	;mbstring.internal_encoding =	mbstring.internal_encoding = UTF-8	※Uncomment + Modify				
19	Required	;mbstring.http_input =	mbstring.http_input = auto	※Uncomment + Modify				
20	Required	;mbstring.http_output =	mbstring.http_output = UTF-8	※Uncomment + Modify				
21		;mbstring.encoding_translation = Off	mbstring.encoding_translation = Off	**Uncomment				
22	Required	;mbstring.detect_order = auto	mbstring.detect_order = auto	<b>X</b> Uncomment				
23	Required	;mbstring.substitute_character = none	mbstring.substitute_character = none	※Uncomment				
24	Required	;openssl.cafile=	openssl.cafile=/etc/pki/tls/certs/exastro-it-automation-ja.crt					
25	Required	;openssl.capath=	openssl.capath=/etc/pki/tls/certs/exastro-it-automation-ja.crt					

## ITA setting file description

No.	ITA	Ansible	Cobbler	OpenStack	DSC	Ansible Towe		Description
1			0				(ITA installation directory)/it-automation=1.3.0/ita_install_package/ITA/backyardconfs/cobbler_driver/path_DATA_RELAY_STRAGE_side_Cobb	Define the root path of data relay storage in Cobbler server
2	0						ITA installation directory)/R-automation=1.3.0/8a_install_package/ITA/backyardconfs/8a_base/data_portability_running_limit.txt	The execution time limit of data portability import process. The process during execution will be determined as failed if the execution time passed the setting value. The unit is second Default value is 300
3	0	0			0	0	(TTA installation directory)/it-automation=1.3.0/ita_install_package/ITA/backyardconfs/ita_base/hide_menu_column.list.bst	Describe the column to be excluded from the item display of substitution auto- registration setting.  The line starting with "#" is ignored.
4	0	0	0	0	0	0	(ITA installation directory)/ita_install_package/ITA/backyardconfs/path.PHP.MODULE1st	Describe the path of PHP module. Example: /bin/php
5	0						(TTA installation directory)/it-automation=1.3.0/ita_install_package/TTA/backyardconfs/sysmallist	Describe the setting when using system malk(ky_mall).  **Not required if the mail sending function(ky_mall) of ITA is not used.
6	0						(TA installation directory)/it-automation=1.3.0/ita_install_package/TA/ita-confs/commonconfs/app_mail_from.txt	When using system mail (ky_mail) from WebDBCore, the file content becomes the sender's address. "All the case of sending mail to 00_loadtable_php when action occurs. %Not required if the mail sending function(ky_mail) of ITA is not used.
7	0	0			0	0	(ITA installation directory)/it-automation=1.3.0/ita, install_package/ITA/ita~confs/commonconfs/app,msg_language.txt	Define the language of ITA.
8	0	0	0	0	0	0	(ITA installation directory)/it-automation=1.3.0/ita, install_package/ITA/ita-confs/commonconfs/db,connection_string.txt	The string to connect to MySQL Example: The string encrypted from "mysqldbname=ITA_DB;host=localhost" Refer to %1 for the encryption specification
9	0	0	0	0	0	0	(ITA installation directory)/it-automation=1,3.0/ita, install_package/ITA/ita-confs/commonconfs/db,model_string.txt	Define the type of RDB 0: Oracle DB 1: MySQL/MarisDB
10	0	0	0	0	0	0	(ITA installation directory)/it-automation=1,3.0/ita, install_package/ITA/ita-confs/commonconfs/db,password.txt	The password to connect to MySQL.  Example: The string encrypted from "ITA PASSWD"  Refer to %1 for the encryption specification
11	0	0	0	0	0	0	(ITA installation directory)/it-automation=1,3.0/ita, install_package/ITA/ita-confs/commonconfs/db_usemame.txt	The user to connect to MySQL Example: The string encrypted from "ITA_USER" Refer to %1 for the encryption specification
12	0	0				0	(TA installation directory)/it-automation=1.3.0/fa, install_package/TTA/far-confs/commonconfs/path_PHPSpyc_Classes.txt	Describe the path of Spyc. This sample describes "/usr/share/php/spyc-master"
13		0					(TA installation directory)/it-automation=1.3.0/ita_install_package/TTA/ita-confis/restapiconfis/anable_driver/accesskey/st	The access key used in the RestAPI of Ansible server.  Example: The string encrypted from "AccessKeyId"  Refer to %1 for the encryption specification
14		0					(TTA installation directory)/it-automation=1.3.0/ita_install_package/ITA/ita-confs/restapiconfs/ansible_driver/secret_accesskey.txt	The secret key used in the RestAPI of Anable server.  Example: The string encrypted from "SecretAccessKey"  Refer to %1 for the encryption specification
15	0						(ITA installation directory)/it-automation=1.3.0/ita_install_package/ITA/ita-confs/admin_mail_addr.txt	Describe the contact information (e-mail address) of the system administrator.  If the file doesn'exist  ⇒The link of "Contact administrator" will disappear
16	0						(ITA installation directory)/it=automation=1.3.0/ita_install_package/ITA/ita=confs/webconfs/LTProtocol.txt	Used when the protocol of client →server is unknown, such as using HTTPS termination before TIA etc.  In the case that the file exists and the protocol(HTTP/HTTPS) is described.  The protocol (HTTP/HTTPS) described in the file is adopted.  Described the file of the file of the file is adopted.  Described the file of
17	0						(ITA installation directory)/it-automation=1.3.0/ita, install.package/ITA/ita-confs/webconfs/path.HTML_AJAX.txt	Describe the path of HTML/AJAX. Example: /usr/share/pear/

1 The value encoded by base64 then converted by rot13