

Skytree Admin Guide

Release 15.4.0

SKYTREE®

Notices

Copyright

Copyright 2014-2016 Skytree, Inc. All rights reserved.

Information in this document is furnished only under a Customer License Agreement or non-disclosure agreement and may be used or copied only in accordance with the terms of either such agreement. The software described in this document is owned by Skytree, Inc. and protected by U.S. copyright law and may not be copied on any medium except as specifically authorized in the Customer License Agreement or non-disclosure agreement.

Disclaimer

Skytree, Inc. reserves the right to revise this document and to make changes from time to time without any obligation of any kind to notify any person of such revisions or changes.

Trademarks

SKYTREE®, the Skytree logo, THE MACHINE LEARNING COMPANY®, THE DATA DRIVEN ENTERPRISE™, Skytree Infinity™, AutoModel™, and AutoDocumentation™ are trademarks or registered trademarks of Skytree, Inc. ORACLE®, JAVA®, and JDK™ are trademarks or registered trademarks of Oracle and/or its affiliates. HADOOP®, HIVE™, PIG™, HBASE™, SPARK™, TOMCAT™, and ZOOKEEPER™ are trademarks or registered trademarks of the Apache Software Foundation. MAPR® is a registered trademark of MapR Technologies, Inc. Python™ is a trademark of the Python Software Foundation. Third-party product names and related marks used in this document are trademarks or registered trademarks of their respective owners. Use of third-party product names and marks does not imply any affiliation or endorsement by such parties.

Company Information:

Skytree, Inc.
1731 Technology Drive, Suite 700
San Jose, CA 95110
408.392.9300
www.skytree.net

Customers with a support contact can contact support using any of the following methods:

- Log in to support.skytree.net.
- Send questions to support@skytree.net.
- Call 408.392.9300 and select option 3.
- You can also view additional Skytree documentation by logging on to support.skytree.net.

Freemium customers can send inquiries to the LinkedIn® Community Group for Skytree:

<https://www.linkedin.com/groups/4468542>

Revision Date: February 28, 2016

Contents

Chapter 1 Overview	1
Chapter 2 Administrative Workflow	3
Chapter 3 Administration through the REST API	5
Administrative APIs in the REST API	5
Administrative Parameters	6
Authenticate the Admin	6
Change the Admin Password	7
Users and Roles	7
Create Roles	8
Create a New User	8
Delete a Role	10
Change a User's Role	10
Add Another Role to a User	11
Retrieve Users	12
Change a User's Login Name	13
Change a User's Password	13
Reset a User's Password	14
Monitoring Activity	14
Activity Summary	14
Activity Detail	16
Chapter 4 Administration through the Python SDK	19
Installation and Import	19
Authenticate the Admin	19
Users and Roles	20
Create Roles	20
Create a New User	20
Delete a Role	21
Change a User's Role	21
Add Another Role to a User	21
Retrieve Users	21
Change a User's Login Name	21
Change Password	21
Reset a User's Password	22
Chapter 5 Administration through the GUI	23
Change the Admin Password	24

Users and Roles	25
Create a New User	25
Create a New User - without LDAP	25
Create a New User - with LDAP	26
Edit User Information	27
Usage	28
Index	31

Chapter 1 Overview

This document provides information about setup tasks performed by Admins. Admins should review the [Administrative Workflow](#) (page 3) section to get users up and running as well as for information regarding day-to-day tasks that Admins might encounter.

Note: Information regarding installing Skytree is found in the *Skytree Installation Guide*.

Admin tasks can be performed through REST API calls, Python SDK functions, or through the Skytree graphical user interface (GUI). Refer to any of the following sections to perform administrative tasks.

- [Administration through the REST API](#) (page 5)
- [Administration through the Python SDK](#) (page 19)
- [Administration through the GUI](#) (page 23)

Chapter 2 Administrative Workflow

After Skytree is installed, the remaining Admin tasks include creating the available roles ("admin" and "user"), and creating users. The required tasks are described below.

- **Create the Admin user**

An Admin must be authenticated before any additional actions can be performed.

- **Create roles**

Skytree ships with two roles: admin and user. These roles are not available until the Admin creates. They can then be assigned to users. A role must be specified when creating a new users.

- **Create users**

For each user, you must provide the user's name, an e-mail address, a default password, and a role of either admin or user.

- **Provide information to the users**

All users need to authenticate before using Skytree. In order to do this, you must provide each user the e-mail address and password that you used when the user was created.

In addition to an Admin's initial tasks, this manual also includes information for Admins to perform day-to-day Skytree tasks, including modifying users and monitoring activity.

Chapter 3 Administration through the REST API

Refer to the following topics for completing Admin tasks through the REST API:

- [Administrative APIs in the REST API](#) (page 5)
- [Authenticate the Admin](#) (page 6)
- [Change the Admin Password](#) (page 7)
- [Users and Roles](#) (page 7)

Administrative APIs in the REST API

Note: This section is applicable to Admins who will work with the REST APIs.

Two applications are installed as part of the Skytree installation process: adminv1 and v1. In addition, Skytree provides two default roles: admin and user. The admin role provides access to the adminv1 and v1 applications; the user role provides access to the v1 applications.

The adminv1 APIs allow administrators to authorize new users and review the activity of Skytree runs. Admins can specify to view a summary of all API activity broken down based on each user. This summary request can be appended to return information for only a single user. Admins can also specify to view detailed information about all runs made as well as those made from specific users. This metering information is available in an interactive graphical format.

Use the following base URLs to utilize the administrative APIs:

Note: Replace api.skytree.net with the correct URL.

```
'http://api.skytree.net:8080/v1/userPrefs/authenticate'  
'http://api.skytree.net:8080/v1/userPrefs/changePassword'  
'http://api.skytree.net:8080/adminv1/createRole'  
'http://api.skytree.net:8080/adminv1/users'  
'http://api.skytree.net:8080/adminv1/users/<user_id>/role'  
'http://api.skytree.net:8080/adminv1/users/resetPassword'  
'http://api.skytree.net:8080/adminv1/users/<user_id>/changeLogin'  
'http://api.skytree.net:8080/adminv1/activity/summary'  
'http://api.skytree.net:8080/adminv1/activity/detail'
```

Administrative Parameters

The following parameters are used in the Admin APIs in the REST API.

Table 1: Administrative Parameters

Parameter	Description	Used In
role	The name of a role	Create roles, Create a new user
description	A description of the role (for example, "Admin")	Create roles
name	The name of the role, user, or cluster	Create roles, Create a new user
userName	The user's login name (when using LDAP) or the user's e-mail address (when not using LDAP).	Create a new user, Change a password, Authenticate
password	The user's password	Create a new user
oldPassword	The user's last password	Change password
newPassword	The user's new password	Change password, Reset password
id	The ID of a role or user	Add user to another role, Retrieve a role

Authenticate the Admin

Admins, like users, must use the `authenticate` API to generate a token. This token is required when performing other `/v1` tasks, such as changing your password. When authenticating, Admins must provide `"admin@skytree.net"` as the `userName`, even if additional users will log in via LDAP authentication. In addition, Skytree ships with a default password of `"skytree"` (case sensitive) for the Admin.

Request

Use POST to authenticate the admin and return a new token.

```
curl -X POST -H "Content-type:application/json" \
-d '{"userName":"admin@skytree.net", "password":"skytree"}' \
'http://api.skytree.net:8080/v1/userPrefs/authenticate'
```

Response

The response returns the admin's email address and token. Be sure to retain this token because it is required in every request. In the event that you lose this token or the token expires, run the `authenticate` request again to generate a new token.

Warning: For security purposes, unused authentication tokens have a lifespan of 6 hours. This means that if you do not use this token, it will expire after 6 hours. When you do use this token, its expiry time will increment by another 6 hours. Run the `authenticate` request to generate a new token.

```
200 (OK)
"Content-type:application/json"
{
  "userName":"admin@skytree.net",
  "token":"YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ=="
}
```

Warning: Though it is not required, Admins should change their password immediately after receiving their authentication token. Refer to [Change the Admin Password \(page 7\)](#) for information on how to do this.

Change the Admin Password

After you generate a token, you can call the `changePassword` API to change the default password to something more memorable or meaningful. New passwords must be a minimum of eight characters and include at least one uppercase letter, one lowercase letter, and one number. Special characters are permitted.

Note: This REST API is not available for LDAP authentication users.

Request

Use POST to change the Admin password. The Admin e-mail address and the original (or most recent) password are required in this request.

```
curl -X POST -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
-d '{"userName":"admin@skytree.net", "oldPassword":"skytree",
  "newPassword":"^Sky3*zz!"}' \
'http://api.skytree.net:8080/v1/userPrefs/changePassword'
```

Response

Similar to when the user was created, the API returns the Admin's e-mail address, old password, and new password upon success. Otherwise, an error will display if any information was entered incorrectly.

```
200 (OK)
"Content-type:application/json"
{
  "userName":"admin@skytree.net",
  "oldPassword":"skytree",
  "newPassword":"^Sky3*zz!"
}
```

Users and Roles

Skytree ships with two available roles: `admin` and `user`. These roles define the APIs and functionality that a user can access. After the roles are created, new users can be created and added into one or both of these roles.

The sections that follow describe how to create roles and users. It also includes information on day-to-day tasks that the admin might encounter, such as changing roles, deleting users, changing or resetting a user's password, etc.

- [Create Roles](#) (page 8)
- [Create a New User](#) (page 8)
- [Delete a Role](#) (page 10)
- [Change a User's Role](#) (page 10)
- [Add Another Role to a User](#) (page 11)
- [Retrieve Users](#) (page 12)
- [Change a User's Password](#) (page 13)
- [Reset a User's Password](#) (page 14)

Create Roles

Use the `createRoles` API to make the Admin and User roles available in the REST API. Once available, a role is then assigned to users.

Request

The example below creates an admin role.

Note: A similar process must be followed to configure the "user" role.

```
curl -X POST -H "x-auth-token:YwRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
-d '{"name":"admin","description":"Skytree admin"}' \
'http://api.skytree.net:8080/adminv1/role'
```

Response

This API returns a unique ID for the role along with the request configuration information.

```
200 (OK)
"Content-type:application/json"
{
  "id":"8355312684",
  "role":"admin",
  "description":"Skytree admin"
}
```

Create a New User

When creating a new user, the user's full name, username (login name when using LDAP or e-mail address when not using LDAP), default password, login name, and the role are required. E-mail addresses can include all characters as permitted in [RFC 5322](#) with the exception of the following: ' | { }. Multibyte Character Encoded e-mail is not supported. Passwords must be a minimum of eight characters and include at least one uppercase letter, one lowercase letter, and one number.

Note: For those running Skytree in a Kerberos Hadoop environment, the `loginName` must track the primary part of the user's Kerberos principal. For example, if the Kerberos principal is `john@skytree.net` then the login name must be `john`. For those running Skytree in a non-Kerberos environment, the `loginName` field should contain the user's Linux username.

Note: If you are using LDAP authentication, we recommend using the Skytree GUI to create users. Refer to [Create a New User](#) (page 25).

Request

The example below describes how to authorize a new Skytree user named John Smith. In this example, John is given both user and admin roles.

```
curl -X POST -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
-d '{"userName":"johnsmith@skytree.net",
    "name":"John Smith",
    "password":"Password1",
    "loginName":"john",
    "roles":["admin","user"]}' \
'http://api.skytree.net:8080/adminv1/users'
```

Response

A response similar to below will be returned upon successful completion. At this time, Admins provide the user with this default password. Users will need this password to generate a token so that they can change their password to something more secure.

```
200 (OK)
"Content-type:application/json"
{
  "id":"148928663",
  "userName":"johnsmith@skytree.net",
  "name":"John Smith",
  "password":"Password1",
  "loginName":"john",
  "createdAt":1421262811001,
  "updatedAt":1421262811001,
  "roles":
  [
    {
      "id": 2799361016334148000,
      "description": "USER",
      "name": "user"
    },
    {
      "id": 4356158721640025000,
      "description": "Admin USER",
      "name": "admin"
    }
  ]
}
```

Delete a Role

Admins can delete an existing user's role using DELETE.

Request

The example below uses DELETE to remove a role from user John (user id = 148928663). When user John was previously created, he was created with both Admin and User roles. This example deletes his User role (role ID = 2799361016334148000). With this example, John will now only have the role of Admin. Note that the role ID is required in the request.

```
curl -X DELETE -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
-d '{"roles":["admin"]}' \
'http://api.skytree.net:8080/adminv1/users/148928663/role/2799361016334148000'
```

Response

A response similar to below will be returned upon successful completion. You can see that John's previous User role was removed, and now he is only an Admin. An error will result if the specified user and/or role does not exist.

```
200 (OK)
"Content-type:application/json"
{
  "id":"148928663",
  "userName":"johnsmith@skytree.net",
  "name":"John",
  "password":"password",
  "createdAt":1421262811001,
  "updatedAt":1421275938026,
  "roles":
  [
    {
      "id": 4356158721640025000,
      "description": "Admin USER",
      "name": "admin"
    }
  ]
}
```

Change a User's Role

Admins can change an existing user's role(s) using PUT.

Request

The example below uses PUT to change the role of John (user id = 148928663). When user John was originally created, he was created with both Admin and User roles. In the last example, we removed John's User role. With this example, John's current Admin role will be changed to User.

```
curl -X PUT -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" -d '{"roles":["user"]}' \
'http://api.skytree.net:8080/adminv1/users/148928663/role'
```

Response

A response similar to below will be returned upon successful completion. An error will result if the specified user and/or role does not exist.

```
200 (OK)
"Content-type:application/json"
{
  "id":"148928663",
  "userName":"johnsmith@skytree.net",
  "name":"John",
  "password":"password",
  "createdAt":1421262811001,
  "updatedAt":1421275938026,
  "roles":
  [
    {
      "id": 2799361016334148000,
      "description": "USER",
      "name": "user"
    }
  ]
}
```

Add Another Role to a User

Admins can give an additional role to a user using POST.

Request

The previous topic changed John's role (user id = 148928663) from Admin to User. The example below uses POST to once again make John an Admin as well as a User.

```
curl -X POST -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" -d '{"roles":"admin"}' \
'http://api.skytree.net:8080/adminv1/users/148928663/role'
```

Response

A response similar to below will be returned upon successful completion. An error will result if the specified user and/or role does not exist.

```
200 (OK)
"Content-type:application/json"
{
  "id":"148928663",
  "userName":"johnsmith@skytree.net",
  "name":"John",
  "password":"password",
  "createdAt":1421262811001,
  "updatedAt":1421275938026,
  "roles":
  [
    {
      "id": 4356158721640025000,
      "description": "Admin USER",
      "name": "admin"
    },
  ],
}
```

```
{
  "id": 2799361016334148000,
  "description": "USER",
  "name": "user"
}
]
```

Retrieve Users

Admins can retrieve a list of all users with GET.

Request

The example below uses GET to retrieve a list of all users.

```
curl -X GET -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
'http://api.skytree.net:8080/adminv1/users'
```

Response

A response similar to below will be returned upon successful completion. In the example response below, you can see that John has two roles: user and admin. A second user, Jane, has a single role: user.

```
[
  {
    "id": 3608087877748623400,
    "userName": "johnsmith@skytree.net",
    "name": "John Smith",
    "loginName": "john",
    "createdAt": 1428448388238,
    "updatedAt": 1428448388238,
    "roles":
    [
      {
        "id": 2799361016334148000,
        "description": "USER",
        "name": "user"
      },
      {
        "id": 4356158721640025000,
        "description": "Admin USER",
        "name": "admin"
      }
    ]
  },
  {
    "id": 622909745467753200,
    "userName": "janejones@skytree.net",
    "name": "Jane Jones",
    "loginName": "jane",
    "createdAt": 1428449229676,
    "updatedAt": 1428449229676,
    "roles":
    [
```



```
{
  "id": 2799361016334148000,
  "description": "USER",
  "name": "user"
}
],
},
]
```

Change a User's Login Name

It may be necessary for an Admin to change a user's loginName.

Note: This REST API is not available for LDAP authentication users.

Request

Use PUT to change the login name for a user. The user's ID is required in this request. In the example below, a user whose ID is 148928663 will now use jack as a login name.

```
curl -X PUT -H "x-auth-token:YwRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/x-www-form-urlencoded" -d login="jack" \
'http://api.skytree.net:8080/adminv1/users/148928663/changeLogin'
```

Response

The API returns the user ID, new login, and an e-mail address indicating who originated the request.

```
200 (OK)
"Content-type:application/json"
{
  "id":"148928663",
  "loginName":"jack",
  "modifier":"admin@skytree.net"
}
```

Change a User's Password

It may be necessary for an Admin to change a user's password. If you know the user's current password, then you can call the changePassword RSET API. Passwords must be a minimum of eight characters and include at least one uppercase letter, one lowercase letter, and one number.

Note: This REST API is not available for LDAP authentication users.

Request

Use PUT to change the password for a user. The user's e-mail address, the current password, and the new password are required in this request.

```
curl -X PUT -H "x-auth-token:YwRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
-d '{"userName":"user1@skytree.net", "oldPassword":"Password1",
```

```
"newPassword":"Password2"}' \
'http://api.skytree.net:8080/adminv1/userPrefs/changePassword'
```

Response

The API returns the user's e-mail address and password information upon successful completion. Otherwise, an error will display if any information was entered incorrectly.

```
200 (OK)
"Content-type:application/json"
{
  "userName":"user1@skytree.net",
  "oldPassword":"Password1",
  "newPassword":"Password2"
}
```

Reset a User's Password

It may be necessary for an admin to change a user's password.

If the admin has access to the user's current password, then the `changePassword` API should be used. If not (for example, if the user forgets his/her password), then the admin can reset a user's password by calling the `resetPassword` API. New passwords must be a minimum of 8 characters and include at least one uppercase letter, one lowercase letter, and one number.

Note: This REST API is not available for LDAP authentication users.

Request

Use PUT to reset a user's password. Unlike in the `changePassword` API, the original password is not used in this API request.

```
curl -X PUT -H "x-auth-token:YwRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
-d 'userName=user3@skytree.net&newPassword=Password2' \
'http://api.skytree.net:8080/adminv1/users/resetPassword'
```

Response

The API returns true upon successful completion. This new e-mail address should then be provided to the user.

Monitoring Activity

The monitoring APIs allow admins to review the activity of Skytree runs. Two API calls are available, allowing admins to view either summarized information or more detailed usage information. An Administration GUI is also available, which provides a graphical display of Skytree usage.

Activity Summary

Admins can specify to view a summary of all API activity broken down based on each user. This summary request can be appended to return information for only a single user.

Request

Use GET to run the Activity Summary API. Note that GET is the default method, so this keyword is not required.

```
curl -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
"Content-type:application/json" \
'http://api.skytree.net:8080/adminv1/activity/summary'
```

Response

This API returns summarized information similar to the following:

```
200 (OK)
"Content-type:application/json"
[
  {
    "userName":"demo@skytree.net",
    "count":79,
    "allocation":
    {
      "cores":78,
      "processes":78,
      "memoryMb":159744,
      "allocationDate":null
    }
  },
  {
    "userName":"test1@user.com",
    "count":13,
    "allocation":
    {
      "cores":13,
      "processes":13,
      "memoryMb":26624,
      "allocationDate":null
    }
  }
]
```

Summary Return Fields

A successfully generated summary output will have the following properties:

Table 2: Activity Summary Properties

Parameter	Description
userName	The unique login name (when using LDAP) or e-mail address (when not using LDAP) for each user who is making API calls
count	The total number of API calls made by the user
cores	The combined number of cores used in all calls
processes	The combined number of processes used in all calls
memoryMb	The combined amount of memory used in all calls

Table 2: Activity Summary Properties (continued)

Parameter	Description
allocationDate	This will always be NULL

Activity Detail

The Activity Detail API shows information about all API activity that has occurred across your system. You can optionally include a `userName` to view detailed activity for a specific user.

Request

Use GET to run the Activity Detail API. The example below shows a request for a specific user's detailed activity. Note that GET is the default method, so this keyword is not required.

```
curl -H "x-auth-token:YWRtaW5Ac2t5dHJIZS5uzXQ6c2t5dHJIZQ==" \
-H "Content-type:application/json" \
'http://api.skytree.net:8080/adminv1/activity/detail?userName=test1@user.com'
```

Response

This API returns detailed information similar to the following for the specified user.

```
200 (OK)
"Content-type:application/json"
[
  {
    "userName":"test1@user.com",
    "resourceId":"1986772683",
    "call":null,
    "code":"READY",
    "startDate":1402702340950,
    "endDate":1402702393610,
    "createdAt":1402702340950,
    "updatedAt":1402702393610,
    "allocation":
    {
      "cores":1,
      "processes":1,
      "memoryMb":2048,
      "allocationDate":1402702367088
    }
  },
  {
    "userName":"test1@user.com",
    "resourceId":"1525992726",
    "call":null,
    "code":"READY",
    "startDate":1402702492501,
    "endDate":1402702538989,
    "createdAt":1402702492501,
    "updatedAt":1402702538989,
    "allocation":
```

```

{
  "cores":1,
  "processes":1,
  "memoryMb":2048,
  "allocationDate":1402702517869
}
},
{
  "userName":"test1@user.com",
  "resourceId":"581112813",
  "call":null,
  "code":"INPROGRESS",
  "startDate":1402702982720,
  "endDate":null,
  "createdAt":1402702982720,
  "updatedAt":1402702987997,
  "allocation":
  {
    "cores":1,
    "processes":1,
    "memoryMb":2048,
    "allocationDate":1402702987992
  }
}
]

```

Detail Return Fields

A successfully generated detail output will have the following properties for each user.

Table 3: Activity Detail Properties

Parameter	Description
userName	The unique login name (when using LDAP) or e-mail address (when not using LDAP) for each user who is making API calls
resourceId	The unique ID for the API call. Detail responses are grouped first by userName and then by the resourceId.
call	The API call that was made
code	The current state of the call
startDate	The epoch time when the call was initially made
endDate	The epoch time when the call completed
createdAt	The epoch time when tracking of the call began
updatedAt	The last time when the call changed state (for example, from INPROGRESS to READY)
cores	The number of cores used by the call
processes	The number of processes used by the call
memoryMb	The amount of memory used by the call
allocationDate	The epoch time when allocation of resources was made

Chapter 4 Administration through the Python SDK

Refer to the following topics for completing Admin tasks through the Python SDK:

- [Installation and Import](#) (page 19)
- [Authenticate the Admin](#) (page 19)
- [Users and Roles](#) (page 20)
-

Installation and Import

This section describes how to set up your environment to use the Python SDK.

Note: This section is applicable to Admins who will work with the Python SDK.

Perform the following steps to install/upgrade Skytree:

```
$ cd <api_directory>
$ python setup.py install
```

Note that the above command assumes that you have sudo access on the machine. If you do not, then run the following instead:

```
$ python setup.py install --user
```

In Python, import the AdminAPI module.

```
$ python
>>> from skytree.admin_api import AdminAPI
```

Authenticate the Admin

An Admin user must exist before any additional users or roles can be created. After creating (or "authenticating") the Admin user, be sure to also change the default Admin user password.

Run the following command to authenticate using the Python SDK. New Admin users can be created after authenticating using the command below. Note that the initial admin e-mail and password are always `admin@skytree.net` and `skytree`, even if additional users will log in via LDAP authentication.

```
admin_api = AdminAPI("admin@skytree.net", "skytree", "http://path_to_url:port")
```

Users and Roles

Skytree ships with two available roles: `admin` and `user`. These roles define the functionality that a user can access. After the roles are created, new users can be created and added into one or both of these roles.

The sections that follow describe how to create roles and users. It also includes information on day-to-day tasks that the admin might encounter, such as changing roles, deleting users, changing or resetting a user's password, etc.

- [Create Roles](#) (page 20)
- [Create a New User](#) (page 20)
- [Delete a Role](#) (page 21)
- [Change a User's Role](#) (page 21)
- [Add Another Role to a User](#) (page 21)
- [Retrieve Users](#) (page 21)
- [Reset a User's Password](#) (page 22)

Create Roles

Run the following command in Python to create the admin role.

```
admin_api.add_role_for_user("admin@skytree.net", "admin")
```

Create a New User

When creating a new user, the user's full name, username (login name when using LDAP or e-mail address when not using LDAP), default password, login name, and the role are required. E-mail addresses can include all characters as permitted in [RFC 5322](#) with the exception of the following: ' | { }. Multibyte Character Encoded e-mail is not supported. Passwords must be a minimum of eight characters and include at least one uppercase letter, one lowercase letter, and one number.

Note: For those running Skytree in a Kerberos Hadoop environment, the `loginName` must track the primary part of the user's Kerberos principal. For example, if the Kerberos principal is `john@skytree.net` then the login name must be `john`. For those running Skytree in a non-Kerberos environment, the `loginName` field should contain the user's Linux username

Note: If you are using LDAP authentication, we recommend using the Skytree GUI to create users.

Run the following command to create a new user. The example below describes how to authorize a new Skytree user named John Smith. In this example, "John" is the username, and "jsmith" is either the user's Linux/Unix account username, which should be on all the cluster machines that are part of the Hadoop cluster. For Kerberos users, this should be the prefix part of the user's Kerberos principal. Finally, in the example below John is given both `user` and `admin` roles.


```
newuser = admin_api.create_user(  
    "John",  
    "Password1",  
    "john@skytree.net",  
    "jsmith",  
    ['user', 'admin']  
)
```

Delete a Role

Run the following command to delete John's user role. John's username is required in the command.

```
admin_api.remove_role_from_user("john@skytree.net", "user")
```

Change a User's Role

The Python SDK does not support changing a user's role with a single command. Instead, add the desired role to the user and then delete the undesired role.

Add Another Role to a User

In an earlier example, we used the Python SDK to delete John's user role. Simply run the `add_role_for_user()` function again to re-add the role.

```
admin_api.add_role_for_user("john@skytree.net", "user")
```

Retrieve Users

Run the following command to view a list of users:

```
allusers = admin_api.list_users()  
for user in allusers:  
    print user
```

Change a User's Login Name

It may be necessary for an Admin to change a user's login name. Run the following command to change John's user name (currently "john") to "jack".

Note: This function is not available for LDAP authentication users.

```
admin_api.change_login_name_for_user("john@skytree.net", "jack")
```

Change Password

It is currently not possible to change a password through the Python SDK. Use the REST API or GUI to change a password.

Reset a User's Password

It may be necessary for an admin to change a user's password. Run the following command to reset a user's password:


Note: This function is not available for LDAP authentication users.

```
admin_api.reset_password_for_user("john@skytree.net", "abc123DE")
```

Chapter 5 Administration through the GUI

Administrators who log in to the Skytree GUI have access to a separate menu for managing users and for monitoring usage. In a supported browser, navigate to your Skytree Web URL, and enter the current Admin username and password. Select the dropdown arrow beside your name and select **Administration**.

Note: Unless this was specifically changed during installation, the username and password for the initial Admin is always admin@skytree.net and skytree, even if users and admins will authenticate via LDAP.



This opens the **Administration > Users** page.

Administration > Users

ADMINISTRATION

USERS

USAGE

+ New User

Search

USERNAME	EMAIL	NAME	ROLES
admin@skytree.net	admin@skytree.net	admin	admin, user
anna@skytree.net	anna@skytree.net	Anna Smith	user
pete@skytree.net	pete@skytree.net	psdk1	user

You can switch from Admin mode to User mode by selecting the Skytree logo in the upper-left corner of the page. This takes you back to the Skytree Projects page.




Refer to the following topics for completing Admin tasks through the GUI:

- [Change the Admin Password](#) (page 24)
- [Users and Roles](#) (page 25)
- [Usage](#) (page 28)

Change the Admin Password

The Admin username and password default to "admin@skytree.net" and "skytree", but Admins are advised to change this. To change this password, navigate to MY ACCOUNT in the dropdown.



On the Admin account page, enter the current password, and enter the new password (twice). Note that the new password must be a minimum of eight characters and include at least one uppercase letter, one lowercase letter, and one number. Special characters are permitted.

admin

 Account

Email admin@skytree.net

Change password *****

Change password

Users and Roles

Skytree ships with two available roles: admin and user. These roles define the functionality that a user can access.

The sections that follow describe how to create users. It also includes information on day-to-day tasks that the admin might encounter, such as changing roles or changing a user's password.

- [Create a New User](#) (page 25)
- [Edit User Information](#) (page 27)

Create a New User

When creating a new user, the username (login name when using LDAP or e-mail address when not using LDAP), full name, default password, and role are required. E-mail addresses can include all characters as permitted in [RFC 5322](#) with the exception of the following: ' | { }. Multibyte Character Encoded e-mail is not supported. Passwords must be a minimum of eight characters and include at least one uppercase letter, one lowercase letter, and one number.

The process for creating a new user varies based on whether Skytree was configured to use LDAP authentication.

Create a New User - without LDAP

1. On the **Administration > Users** page, click the **+ New User** button to open the **NEW USER** entry form.
2. Enter the e-mail address, username (defaults to e-mail address), name, and password (twice), and then select the role or roles for this user.
3. Click **Create user** when you are finished. Note that this button is disabled until all of the user information is added correctly. This information should then be provided to the user.

Administration > Users > New User

NEW USER

Email:

Username:

Name:

Password:

Roles: ☐ admin ☒ user

[Create user](#)

Create a New User - with LDAP

1. On the **Administration > Users** page, click the **+ New User** button.
2. To start the New User process, enter the username of the user you want to add, and then click **Find user**. Note that only those usernames that exist in the active directory (AD) can be added.

Administration > Users > New User

NEW USER

[Find user](#)

Start by finding the user you'd like to add.

3. Skytree searches the AD for the specified user. Once found, the New User form populates with the users e-mail address, username, and full name. These fields are read only. Specify the role for this user, then click [Create user](#) when you are finished.

Administration > Users > New User

NEW USER

colin brown Find user

Email colin@test.net

Username Colin Brown

Full name Colin Brown

Roles ☐ admin ☒ user

Create user

Edit User Information

Admin's can change a user's password and assign a different role to a user through the GUI.

The **Administration > Users** page shows a list of current users along with each user's username, e-mail address, name, and role. Click anywhere in the row of the user that you want to edit.

Administration > Users

ADMINISTRATION

USERS USAGE

+ New User Search

USERNAME	EMAIL	NAME	ROLES
admin@skytree.net	admin@skytree.net	admin	admin, user
anna@skytree.net	anna@skytree.net	Anna Smith	user
pete@skytree.net	pete@skytree.net	psdk1	user

This opens the user's information page. From this page, you can specify a new password for the user. You can also add another role or change the user's current role. Click Update when you are finished.

Note: Only a user's role can be edited when Skytree is configured to use LDAP authentication.

Administration > Users > Anna Smith

ANNA SMITH

Username anna@skytree.net

Email anna@skytree.net

Name Anna Smith


New password

Roles ☒ admin ☒ user

[Update](#)

Usage

The **Administration > Usage** page shows a graph of the current Skytree usage information including the amount of memory used, the number of cores, and the number of processes. You can view usage information over the last day, week, or month by changing the range at the top of the graph. You can also select the forward and back arrows beside the date range to view previous day/week/month of usage.



The right side of this page shows the top five users. Select a user name to view detailed usage information for a specific user, or select the [Users](#) link to view statistics for all users. When viewing this information, the page by default shows all usage information for the current week. As with the previous page, you can change this to a specific day/week/month range.

Administration

RESOURCE MONITOR

SYSTEM [USERS](#)

DAY WEEK MONTH < Today, 12:00 AM to Today, 11:59 PM >

AGGREGATE STATS max@skytree.net

METRIC	MIN	MEDIAN	AVERAGE	MAX
⌚ Time (total: 42112.05 hours)	20.20 seconds	816.77 hours	752.00 hours	858.55 hours
🖨️ Cores	0	1	3.518	8
💾 Memory (MB)	0	4,096	17,298,429	96,000
🔄 Processes	0	1	1,268	2

USAGE max@skytree.net

EMAIL	API CALL	STATUS	START	DURATION	# CONTAINERS	TOTAL # CORES	TOTAL MEMORY (MB)
max@skytree.net	ETL	READY	5/6/2015 7:36:36 AM	20.20 seconds	1	2	4482
max@skytree.net	glbr-TRAIN	READY	5/6/2015 7:36:35 AM	1.33 minutes	1	1	4096
max@skytree.net	ETL	READY	5/6/2015 7:35:07 AM	24.68 seconds	1	2	4482

Index

A

- Activity Detail 16
- Activity Summary 14
- Add Another Role
 - Python SDK 21
 - REST API 11
- Administration
 - GUI 23
 - Python SDK 19
 - REST API 5
- Administrative
 - REST API Parameters 6
- Administrative APIs 5
- Administrative Workflow 3
- Authenticate the Admin
 - Python SDK 19
 - REST API 6

C

- Change a User's Password
 - GUI 27
 - Python SDK 21
 - REST API 13
- Change a User's Role
 - GUI 27
 - Python SDK 21
 - REST API 10
- Change Login Name
 - Python SDK 21
 - REST API 13
- Change the Admin Password
 - GUI 24
 - REST API 7
- Create a New User
 - GUI 25

Python SDK 20

Rest API 8

Create Roles

- Python SDK 20
- REST API 8

D

- Delete a Role
 - Python SDK 21
 - REST API 10

G

- GUI
 - Change a User's Password 27
 - Change a User's Role 27
 - Change the Admin Password 24
 - Create a New User 25
 - Switch to User Mode 24

L

- LDAP
 - Create User 26
 - Edit User 27

M

- Metering
 - Activity Detail 16
 - Activity Summary 14
- Monitoring
 - GUI 28
 - REST API 14

P

- Parameters
 - REST API Administration 6
- Python SDK
 - Add Another Role 21

- Authenticate the Admin 19
- Change a User's Password 21
- Change a User's Role 21
- Change Login Name 21
- Create a New User 20
- Create Roles 20
- Delete a Role 21
- Reset a User's Password 22
- Retrieve Users 21

R

- Reset a User's Password

 - Python SDK 22

 - REST API 14

- REST API

 - Add Another Role 11

 - Authenticate the Admin 6

 - Change a User's Password 13

 - Change a User's Role 10

 - Change Admin Password 7

 - Change Login Name 13

 - Create a New User 8

 - Create Roles 8

 - Delete a Role 10

 - Reset a User's Password 14

 - Retrieve Users 12

- REST API URLs 5

- Retrieve Users

 - Python SDK 21

 - REST API 12

U

- Usage

 - GUI 28

- User Mode

 - GUI 24

W

- Workflow 3