Title: Is Docker ARG allowed within CMD instruction

Post Body:

I have a Dockerfile where an ${\tt ARG}$ is used in the ${\tt CMD}$ instruction:

```
ARG MASTER_NAME CMD spark-submit --deploy-mode client --master ${MASTER_URL}
```

The arg is passed via docker-compose:

```
spark: build: context: spark args: - MASTER_URL=spark://master:7077
```

However, the ARG does not seem to get expanded for CMD. After I docker-compose up.

Here's what inspect shows:

```
docker inspect -f '{{.Name}} {{.Config.Cmd}}' $(docker ps -a -q) /spark {[/bin/sh -c spark-submit --deploy-mode client --mast
```

Accepted Answer:

The thing is that args only can be used at build time, and the CMD is executing at run time. I guess that the only approach now to achieve what you want is setting an environment variable in the Dockerfile with the MASTER_NAME value.

```
ARG MASTER_NAME ENV MASTER_NAME ${MASTER_NAME} CMD spark-submit --deploy-mode client --master ${MASTER_NAME}
```

Highest Rated Answer: None