Title: docker-compose for Detached mode

Post Body:

I have following docker command to run container

version: '2' services: hdinsight:

 $\verb|docker run -d --name test -v / etc/hadoop/conf:/etc/hadoop/conf -v / usr/lib/python 2.7/dist-packages/hdinsight_common:/usr/lib/python 2.7/dist-packages/hd$

container_name: ABC

volumes:

- /etc/hadoop/conf:/etc/had

This was to complicated so I was trying to create docker-compose file like this

But I am not sure where to pass -d, -i & -t flages from my original docker run command

image: hdinsight

I was running docker-compose like this

docker-compose -f docker-compose.yml run hdinsight

can anyone point me to right direction here?

UPDATE after first answer

I tried to run docker-compose up -d

root@abc-docker:~/ubuntu# docker-compose up -d Creating ABC root@sbd-docker:~/ubuntu# docker ps -a CONTAINER ID IMAGE

Dont know why its in Exited status

Any idea?

Thanks

Accepted Answer:

You should scour the Compose file docs.

Most docker run commands have a compose equivalent, and they should all be listed there.

The background flag -d goes after run or up.

The tty flag -t and interactive flag -i are not required as docker-compose run does this by default. You can add tty to individual containers in the compose file with -t, but you cannot use interactive mode since you may start multiple containers at once and you can't interact with them all.

In regard to your situation the command you're using should be working. If you add -d after the run command it will run in the background. But I recommend using up instead of run, as it will simply start all containers in the file rather than you having to specify hdinsight.

Highest Rated Answer:

As said by Anand Suthar, you have to use tty: true and stdin_open: true. Here is a minimal example:

version: '3' services: alpine1: image: alpine tty: true stdin_open: true

Start with:

docker-compose up -d

Attach to a container with:

docker attach 268bcfb650fb

and detach with $^P^Q$.