Jaya Logistics Driver Mobile App

Live workflow guide for Admin, dispatch team and drivers

Purpose
The Android app is only for delivery drivers. It shows the driver only their assigned Loading entries and trip actions. Admin and office users continue using the ERP website.

Simple end-to-end flow

Create VNN / Loading	Driver draft is created	Admin verifies driver	Trip is assigned	Driver starts & tracks	Delivery is completed

Important live rule
The app connects to **https://erp.jaya-groups.com** and uses the live ERP database. Do not use the old IP-address HTTP APK for driver rollout.

Who uses what

Person	Where they work	What they do
Admin / Dispatch	ERP website	Configure mobile, verify drivers, reset PINs, approve phones, assign trips and monitor tracking.
Driver	Jaya Logistics Driver Android app	Change temporary PIN, view assigned trip, allow location, start and update delivery.
Server / IT	Ubuntu server	Keeps HTTPS, database, PM2 and encryption configuration available.

Part 1 - One-time Admin setup

Complete these steps once before giving the app to drivers.

1. Enable the mobile service

- Login as Admin and open **Driver Mobile > Mobile settings**.
- Tick **Enable driver mobile access**.
- Select **Production** for live use. In Production, the Pilot mobile-number box is not used.
- Click **Generate strong secret**, then click **Save settings**. Do not share the secret.

2. Check staff permission

- Only Admin or users with **Driver Mobile Settings** permission can change mobile settings, verify drivers, reset PINs or enable mobile access.

3. Driver master

- Open **Driver Mobile > Driver Access Master**.
- Each driver has one master record: name, mobile number, licence number, record status and mobile-access status.
- A driver is not allowed into the app until an Admin enables mobile access.

Do not create duplicate drivers
Always search the Driver Access Master first. The same mobile number must belong to only one driver profile.

Part 2 - Office and dispatch workflow

A. VNN / vehicle placement

- When completing Vehicle Placement in VNN, enter **Driver Name**, **Driving Licence Number** and **Mobile Number** correctly.
- The system creates a draft driver record if the mobile number is new. It does not give app access automatically.

B. Loading Info

- Save Loading Info with the same driver mobile number, name and licence number.
- Loading Info updates the same draft driver record. It must not create a second driver with another spelling or number.

C. Verify and enable the driver

Open Driver Access Master	Review name/mobile/licence	Mark Registered	Reset temporary PIN	Enable mobile access

- Use **Review / edit** to check the draft details. Change record status from **Draft** to **Registered** only after verification.
- Use **Reset PIN** and give the temporary PIN privately to the driver.
- Click **Enable**. The driver must change the temporary PIN on first app login.

D. Assign work

- Open **Driver Mobile Setup**. Select the correct existing Loading Info and the correct enabled driver, then click **Assign trip**.
- The driver will see only Loading entries assigned to their own account.

If a mobile number changes
Edit it in Driver Access Master. For security, the system ends sessions, revokes the old phone and disables mobile access. Reset the PIN and enable access again only after verification.

Part 3 - Driver installation and first login

Give these steps directly to every driver.

1. Install

- Receive the official Jaya Logistics Driver APK from your office.
- Open the file on the Android phone. If Android asks, allow installation from this source.
- Open the app. It must show the **Jaya Logistics Driver** login screen, not the normal ERP website home page.

2. Login and create personal PIN

- Enter the mobile number registered by the office and the temporary PIN provided by dispatch.
- On first login, enter the temporary PIN again, choose a new private PIN and confirm it.
- Never share the new PIN with another driver.

3. Phone approval

- The app may show **waiting for dispatcher approval**. Inform dispatch that you have logged in.
- Dispatch approves the phone in Driver Mobile Setup. Tap **Refresh approval** in the app.
- After approval, assigned trips appear automatically.

New or replaced phone
Install the app again, login and ask dispatch to approve the new phone. The old phone should be revoked by dispatch.

Part 4 - Driver trip screens and actions

Screen	What the driver does
Login	Enter registered mobile number and personal PIN.
Set your own PIN	Shown only after a temporary PIN reset. Save a new private PIN before using the phone.
Waiting for approval	Wait for office approval, then tap Refresh approval.
My active trips	See only trips assigned to this driver. Select the correct trip.
Trip details	Read Loading reference, vehicle, pickup and destination information.
Trip action	Tap the available action: Start trip, At pickup, Start delivery, Arrived at stop, Confirm delivery or Complete.
Report an issue	Use this for breakdown, traffic, fuel or waiting problems.

Starting a trip

Open assigned trip	Tap Start trip	Allow permissions	Tracking notification appears	Continue delivery

- The app asks for location and notification permission. Choose **Precise location**.
- For tracked delivery, set Android location permission to **Allow all the time**. The trip will not start until required location permissions are ready.
- After start, confirm that the tracking notification remains visible.

During delivery

- Keep Location/GPS, mobile data or Wi-Fi and phone battery available.
- Do not force-close the app while the trip is active.
- Follow the trip action buttons in order. Contact dispatch if the wrong trip or stop is shown.

Part 5 - Android permissions and quick help

Driver phone checklist

Setting	What to do
Location	Turn Location on. Choose Precise location and Allow all the time for the Driver app.
Notifications	Allow notifications. A running tracking notification is expected during an active trip.
Battery	Set the app battery use to Unrestricted / Do not optimise if the phone has that option.
Data / Wi-Fi	Keep either mobile data or Wi-Fi connected. Android does not ask a separate permission for this.
Camera / files	Allow only when the app asks for a delivery photo or document upload.

Common issues

Problem	Driver / office action
Cannot login	Check registered mobile number. Ask Admin to reset PIN and confirm mobile access is enabled.
No trip shown	Office must assign the Loading entry to the correct driver and approve the phone.
App says waiting for approval	Ask office to approve the device, then tap Refresh approval.
Trip cannot start	Turn on Precise Location and Allow all the time in Android settings.
Tracking not updating	Keep GPS/data on, do not force-close app, allow notifications and remove battery restriction.
Changed phone / number	Tell Admin. The driver profile and device must be reviewed again.

Before every real delivery

Driver is Registered - mobile access Enabled - personal PIN works - phone Approved - correct Loading entry Assigned - location settings allowed - active trip tracking notification visible.

Support contact

For driver access, PIN, assignment or device approval, contact your Jaya Logistics dispatch / Admin team. Do not share passwords or signing secrets through WhatsApp.