

MEMSYST FINANCIAL INFRASTRUCTURE POLICY

Treasury, Wallet, Settlement & Withdrawal Architecture

This specification is a core platform policy and applies to all tenants, associations, regions, branches, executives, members, apprentices, and future modules built within the MemSyst ecosystem.

CORE FINANCIAL PRINCIPLE

MemSyst is not a bank.

MemSyst is not a money transfer platform.

MemSyst operates a controlled digital wallet infrastructure backed by verified Paystack transactions.

All financial activities must be:

Auditable

Traceable

Reconciliable

Permission Controlled

Tenant Aware

Ledger Driven

No financial activity may bypass the platform ledger.

DIGITAL WALLET MODEL

Unit Conversion Rule

Wallets do not store real cash.

Wallets store platform units.

Conversion:

Real Cash GH¢100

=

Wallet Units GH¢100

For user simplicity:

Units are displayed as GH¢

Example:

Paystack Payment:
GH¢500

Wallet Credit:
GH¢500 Units

Users see:

Wallet Balance:
GH¢500

Internally:

Real Cash Held = GH¢500
Wallet Units Issued = GH¢500

WALLET FUNDING

Allowed Funding Method

Only:

Paystack

may create wallet credits.

Funding Flow

User Initiates Funding

↓

Paystack Checkout

↓

Payment Verification

↓

Transaction Created

↓

Wallet Credited

↓

Receipt Generated

↓

Audit Logged

Prohibited Funding Methods

The following are forbidden:

- Manual Wallet Funding
- Admin Wallet Funding
- Cash Deposit Credits
- Executive Wallet Credits
- Member Wallet Credits
- Wallet Imports

No administrator may directly add funds to a wallet.

WALLET TRANSFERS

Disallowed

The platform does not support:

- Member → Member Transfers
- Member → Executive Transfers
- Executive → Member Transfers
- Wallet Gifts
- Wallet Sharing
- Peer-to-Peer Transfers

All spending must occur through approved platform transactions.

WALLET TYPES

The platform supports:

- Platform Wallet
- Tenant Wallet
- Region Wallet
- Branch Wallet
- Member Wallet
- Executive Wallet
- System Wallet
- Reserve Wallet

All wallets operate through a unified ledger engine.

LEDGER ARCHITECTURE

Every financial activity creates:

Transaction Record

Ledger Entry

Wallet Movement

Audit Log

Double-entry accounting principles must be enforced.

WITHDRAWAL ELIGIBILITY

Only approved executive accounts may request withdrawals.

Eligibility requires:

Executive Account

Active Status

Withdrawal Permission

Approved Organizational Role

Permissions are controlled through RBAC.

WHO CAN WITHDRAW

Members:

No

Apprentices:

No

Tenant Executives:

Yes

if granted permission.

BRANCH WITHDRAWAL CONFIGURATION

At branch creation:

Tenant Admin must configure:

Branch Withdrawal Enabled

Yes / No

If disabled:

Branch cannot request withdrawals

REGION WITHDRAWAL CONFIGURATION

At region creation:

Tenant Admin must configure:

Region Withdrawal Enabled

Yes / No

If disabled:

Region cannot request withdrawals

PAYOUT DESTINATION REQUIREMENT

A branch or region cannot be created without a payout destination.

Required:

Cash-Out Method

Options:

Bank Account

Mobile Money

Required fields must be completed during creation.

APPROVED PAYOUT DESTINATION RULE

Platform Administrators may only release funds to:

Registered Bank Account

or

Registered Mobile Money Account

stored on the account profile.

Ad-hoc payout destinations are prohibited.

WITHDRAWAL SOURCE RULE

Approved Architecture:

Option A

Withdrawals come directly from the requesting wallet.

Example:

Kumasi Branch Wallet

Balance = GH¢10,000

Withdrawal = GH¢2,000

New Balance = GH¢8,000

No other wallet is affected.

This preserves:

Financial Accountability

Regional Independence

Branch Accountability

Accurate Reporting

MONTHLY WITHDRAWAL RULE

Each eligible wallet may submit:

One Withdrawal Request Per Calendar Month

Examples:

National Wallet

1 Withdrawal

Ashanti Region Wallet

1 Withdrawal

Kumasi Branch Wallet

1 Withdrawal

Each wallet is evaluated independently.

WITHDRAWAL LIMIT RULE

Maximum withdrawal:

80%
of available wallet balance

Example:

Wallet Balance = GH¢10,000

Maximum Withdrawal = GH¢8,000

Reserved Balance = GH¢2,000

The reserve remains in the wallet.

WITHDRAWAL FEES

Withdrawal fee is mandatory.

Fee Type:

Percentage

Only.

Configuration Authority

Only:

Platform Super Admin

may configure:

Global Withdrawal Fee %

The fee applies platform-wide.

WITHDRAWAL WORKFLOW

Status Flow

Draft

Submitted

Under Review

Platform Review

Approved

Rejected

Cancelled
Processing
Completed

Step 1

Executive creates request.

Required:

Amount

Reason

Supporting Documents

Step 2

Request submitted.

System validates:

Permission

Monthly Limit

Available Balance

80% Rule

Step 3

Funds become locked.

Example:

Balance = GH¢10,000

Request = GH¢3,000

Available = GH¢7,000

Locked = GH¢3,000

Locked funds cannot be spent.

Step 4

Platform Review.

Authorized finance personnel verify:

Wallet History
Transaction Activity
Compliance
Eligibility

Step 5

Approval.

Status:

Approved

Funds remain locked.

Step 6

Manual Settlement.

Platform finance team manually transfers:

Bank
or
Mobile Money

to the registered payout destination.

Step 7

Completion.

Finance officer records:

Reference Number
Transfer ID
Proof of Payment
Settlement Date

System then:

Deducts Wallet Balance
Creates Ledger Entry

Generates Receipt
Creates Audit Record

REJECTION FLOW

If rejected:

Locked Funds Released
Balance Restored
Reason Recorded
Audit Created

SETTLEMENT CYCLE

Withdrawal processing operates on a settlement cycle.

Purpose:

Fraud Protection
Treasury Control
Reconciliation
Chargeback Protection

Only cleared funds become eligible for withdrawal.

FINANCIAL ADJUSTMENT ENGINE

Because manual wallet funding is prohibited:

Create a controlled adjustment system.

Only Platform Super Admin may create:

Correction
Refund
Charge Reversal
Migration Adjustment
Commission Reversal

Every adjustment requires:

Reason
Approval

Reference
Audit Record

TREASURY DASHBOARD

Platform Finance Dashboard must display:

Total Wallet Units Issued
Total Paystack Collections
Total Pending Withdrawals
Total Approved Withdrawals
Total Completed Withdrawals
Total Locked Funds
Total Withdrawal Fees
Total Platform Revenue
Outstanding Settlement Requests

AUDIT REQUIREMENTS

Every financial action must store:

Actor
Role
Date
Time
IP Address
Device
Action
Before Value
After Value
Reference
Comment

No financial records may be deleted.

MEMSYST FINANCIAL GOLDEN RULE

Money enters the platform only through verified Paystack transactions.

Money moves within the platform only through system-controlled transactions.

Money leaves the platform only through approved withdrawal workflows.

Every movement must be recorded in the ledger, auditable forever, and traceable to a responsible actor.

This should now be treated as the official financial governance specification for Stage 5 and all future MemSyst modules that interact with payments, wallets, fees, revenue distribution, grants, training payments, marketplace payments, events, and support services.