## 1. OVERVIEW

The following document outlines the steps and procedures in the Outbound Picking process.

## 2. EQUIPMENT, SUPPLIES AND CONSUMABLES

The following equipment, consumables, and supplies are necessary to perform the picking function:

Parts: Pallets with material, OEM-sealed cases, and loose (unpacked) items.

Tools and Materials: Powered Industrial Vehicle (PIV), RF scanner, LPN labels, box cutter, handheld counter, totes/pre-folded boxes, pallets, bags, and mobile printer.

## 3. PICKING PROCESS

1. Log into Oracle MWA on the RF gun and mobile printer, if applicable.
2. Enter the correct organization.
3. Grab the necessary supplies for the order: empty pallets, plastic totes, or pre-folded boxes.
   - ✓ No damaged pallets.
   - ✓ International Orders need Heat Treated (HT) Pallets
   - ✓ Brazil and China need Plastic pallets.
   - ✓ Customer: Ingram does not accept block pallets.
   - ➢ Reference the Packaging Guidelines Rev01.pdf for acceptable pallets.
   - ➢ Reference picking work instructions WI - Outbound - Discrete Picking v1.0.pdf
4. Proceed to the first location displayed on the RF gun.
5. Scan the sub-inventory and location from the physical location barcode on the racking.
6. If you cannot bypass the LPN, scan it or use the magnifying glass for the LPN to autofill. If you are allowed to bypass the LPN, proceed without scanning it.
7. Pick the item from the location and scan the SKU number from the packaging, not the location LPN.
8. If you pick the entire quantity in the location with an existing LPN, the system will default the quantity in the "Confirm" field to the required quantity. You must confirm the quantity needed for the pick before clicking submit on the RF scanner for tasks that are the rest of the LPN.
9. For non-serialized components, count the quantity of the material needed while placing it on the pallet/tote or box.
   - ✓ Do not "AIR" pick, meaning enter the quantity before verifying the part number and quantity.
10. For serialized components, count the material by placing it on the skid, and when prompted, scan the serial numbers using the 2D or 1D barcodes from the units on the skid.


*This document contains proprietary information which is the exclusive property of Zebra Technologies Corp.*

**The most recent version of this document is located on the ISO Library.**
**Verify revision number before use.**

- ✓ Do not scan the serial numbers while the freight is still in the location.
- ✓ If you pick the entire quantity in the location with an existing LPN, the system will default the quantity in the "Confirm" field to the required quantity and will not make you scan the serials if they are serialized.

**11.** Use handheld counters when counting large numbers of loose pick items, if necessary.

**12.** Use a calculator to perform complex math operations, if necessary.

**13.** Use precision count weight scales to count small TX5 items like pins, screws, etc.

- ✓ Ensure the scale is balanced before using it.

➢ Reference Scale Counting Rev01.pdf

**14.** When picking ESD items, follow the handling practices outlined in the ESD Sensitive Parts Handling Rev02.pdf

- ✓ Finger coats do not prevent ESD damage; finger coats are used to prevent bodily oils from transferring to the part.
- ✓ Must use the hand-wrist grounding before picking ESD items.

**15.** If possible, sensitive parts packed in separators must be picked with the separators.

**16.** Do not open the vacuum-sealed product; if the required quantity is less than what is in the vacuum-sealed package, inform the supervisor.

**17.** See your supervisor if the system prompts you to pick less than a full tray. Ideally, we want to pick full trays to minimize the handling of parts. The item must be individually bagged if you must pick less than the full tray quantity.

**18.** If picking full cases, do not "rack pick," meaning choose only from the front of the pallet, leaving the pallet in an uneven/unlevel location.

**19.** If you are picking on the floor levels and you are the first to cut the plastic wrap, you must take the entire plastic wrap and discard it.

**20.** When picking full pallets, while already having a partial pallet, transfer the material from an emptier pallet to a fuller pallet to reduce the handling.

*This document contains proprietary information which is the exclusive property of Zebra Technologies Corp.*

**The most recent version of this document is located on the ISO Library.**
**Verify revision number before use.**

✓ If possible, do not leave empty pallets in the locations.

21. Place the picked items on the LPN. In the Transfer (Xfer) LPN field, scan the pre-printed LPN where you want to place the picked items, or use the hotkeys on the RF gun, Control + G, to print the LPN on demand. Attach the LPN tag to the items, facing it outwards, and organize the items belonging to the LPN for clear identification.

22. If you pick the entire LPN, the Xfer LPN will default to the LPN you pick from. Pick to that LPN; whenever possible, remove the LPN tag from the location and attach it to the items.

    ✓ You can create a new LPN if needed.

23. If something has already been picked for that delivery, the pick will default to the previously selected LPN.

24. If the LPN has not been dropped, use that LPN as long as it does not exceed the size of the container (pallet/carton/tote); otherwise, override to a new LPN.

25. When picking a roll of product, the order needs to call for the entire roll quantity. If it does not, proceed to the office for further directions. Do not break down the roll.

26. Once you have completed assigned pick tasks or run out of space on the pallet, proceed to the drop zone based on the type of order you pick.

    ✓ Seek assistance from the Team Lead or Supervisor if unsure of the order type.

27. Remember, every product picked must have a part label, either from the manufacturer or from us printing the part label.

    ➢ Reference WI - Outbound - Label Printing v1.0.pdf

## 4. DROP ZONE

➢ **Reference** WI - Outbound - Drop LPN v1.0.pdf

**SINGLE LPN DROP**

1. For single-LPN Parcel orders, proceed to the intake conveyor belt.
2. For single-LPN orders, perform the drop transaction to the STL locator located in single line and drop the totes/cartons with material on one of the intake conveyors.
3. Keep the drop-off conveyors equally loaded.
4. Proceed until every single LPN is dropped.

    ✓ Every dropped LPN must have a Pick Drop Audit Label (PDAL).

5. For oversized cartons, bring the carton to the multi-LPN area.

*This document contains proprietary information which is the exclusive property of Zebra Technologies Corp.*

**The most recent version of this document is located on the ISO Library.**
**Verify revision number before use.**

**MULTI-LPN DROP**

6. For multi-LPN Parcel orders, proceed to the driving aisle for multi-LPN orders staging, navigating to the specific staging lane by scheduled ship date (SSD) or organization code.
7. If the shipment has been previously staged, a PCL locator will be recommended; find that locator, drop the LPN to the same pallet and complete the drop transaction.
   - ✓ If the shipment does not fit on one pallet, drop off the pallet next to the previously staged material and ensure all LPNs belonging to the delivery can be identified, or move all the product and its locator to a new pallet.
8. If the shipment wasn't staged before, drop material on a pallet within the staging lane by date and organization, pick a locator cone from the stand closest to that pallet, and complete the drop transaction to the corresponding cone.
9. Proceed until every LPN on the pallet is dropped.
10. Ensure that the product belonging to the locator is clearly identified and that LPNs are visible.
    - ✓ Every dropped LPN must have a Pick Drop Audit Label (PDAL).

**LTL LPN DROP**

11. For LTL orders, proceed to the LTL packing drop zone.
12. Scan the LPNs on the pallet. If the shipment has been staged before, move the product to the staging lane corresponding to the recommended fixed locator, stage the pallet in the drop zone, and perform a drop transaction.
13. If the shipment was not staged before, a default consolidation locator will be recommended; drop to a ghost locator and perform a stage move to the locator to which the delivery is assigned.
14. Proceed until every LPN on the pallet is dropped.
    - ✓ Every dropped LPN must have a Pick Drop Audit Label (PDAL).



## 5. HOUSEKEEPING

1. To promote a clean work environment, clean as you go.
2. Return to its location unused consumables and supplies, ESD bags, pre-folded boxes, totes, pallets, etc...
3. Do not leave any personal items on the PIVs.
4. Ensure your PIV is clean at the end of your shift.
5. Return the Mobil printer to the charging dock on the PIV. The Mobil printers must remain on the PIVs!
6. If the incorrect quantity or product was picked, please consult the SWI Mispick Process

## 6. REFERENCES

| Document # | Document Title |
|---|---|
| | Packaging Guidelines Rev01.pdf |
| | WI - Outbound - Discrete Picking v1.0.pdf |
| | ESD Sensitive Parts Handling Rev02.pdf |
| | Scale Counting Rev01.pdf |
| | WI - Outbound - Label Printing v1.0.pdf |
| | WI - Outbound - Drop LPN v1.0.pdf |
| | WI - Outbound - Stage Move v1.0 |
| | WI – Outbound – Mispick Process |

## 7. REVISION HISTORY

The following table lists all revisions (including the original document) to this procedure, the date, and the reason for the revision.

| Rev. | Rev. Date | Description of Change | Revised By |
|---|---|---|---|
| 01 | 04/23/24 | Original issue | A.Cabrera<br>P. Eroshenko |
| 02 | 01/09/25 | Revised sections 3 - 4. And added section 5 - Housekeeping. | A.Cabrera |
| 03 | 05/01/25 | Added a step for quantity verification before submitting the pick in the System.<br>Added steps for vacuum-sealed products and floor-level picking. | A.Cabrera |
| 04 | 6/11/2025 | Added section for Mispicks | V. Savic |


*This document contains proprietary information which is the exclusive property of Zebra Technologies Corp.*

**The most recent version of this document is located on the ISO Library.**
**Verify revision number before use.**