
## **Packet Tracer - Configuring Floating Static Routes**

### **Topology**



### **Objectives**

- Part 1: Configure an IPv4 Floating Static Route
- Part 2: Test Failover to the IPv4 Floating Static Route
- Part 3: Configure and Test Failover for an IPv6 Floating Static Route

### **Background**

In this activity, you will configure IPv4 and IPv6 floating static routes. These routes are manually configured with an administrative distance greater than that of the primary route and, therefore, would not be in the routing table until the primary route fails. You will test failover to the backup routes, and then restore connectivity to the primary route.

## Part 1: Configure an IPv4 Floating Static Route

### Step 1: Configure an IPv4 static default route.

a. Configure a directly connected static default route from **Edge\_Router** to the Internet. The primary default route should be through **ISP1**.

Answer: Edge\_Router(config)#ip route 0.0.0.0 0.0.0.0 s0/0/0

b. Display the contents of the routing table. Verify that the default route is visible in the routing table.

### Answer:

Edge\_Router#show ip route S\* 0.0.0.0/0 is directly connected, Serial0/0/0

c. What command is used to trace a path from a PC to a destination? 255.255.255.255

### **Answer:** #tracert 198.0.0.10

From **PC-A**, trace the route to the **Web Server**. The route should start at the default gateway 192.168.10.1 and go through the 10.10.10.1 address. If not, check your static default route configuration.

### Step 2: Configure an IPv4 floating static route.

- a. What is the administrative distance of a static route? 255.255.255.255. **Answer:** 0 for directly attached and 1 for hop to hop.
- b. Configure a directly connected floating static default route with an administrative distance of 5. The route should point to **ISP2**.

Answer: Edge\_Router(config)#ip route 0.0.0.0 0.0.0.0 s0/0/1 5

c. View the running configuration and verify that the IPv4 floating static default route is there, as well as the IPv4 static default route.

### Answer:

Edge\_Router#show run ip route 0.0.0.0 0.0.0.0 Serial0/0/0 ip route 0.0.0.0 0.0.0.0 Serial0/0/1 5 d. Display the contents of the routing table. Is the IPv4 floating static route visible in the routing table? Explain

255.255.255.255

#### **Answer:**

### Edge\_Router#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

### Gateway of last resort is 0.0.0.0 to network 0.0.0.0

10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks

C 10.10.10.0/30 is directly connected, Serial0/0/0

L 10.10.10.2/32 is directly connected, Serial0/0/0

C 10.10.10.4/30 is directly connected, Serial0/0/1

L 10.10.10.6/32 is directly connected, Serial0/0/1

192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.10.0/24 is directly connected, GigabitEthernet0/0

L 192.168.10.1/32 is directly connected, GigabitEthernet0/0

192.168.11.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.11.0/24 is directly connected, GigabitEthernet0/1

L 192.168.11.1/32 is directly connected, GigabitEthernet0/1

S\* 0.0.0.0/0 is directly connected, Serial0/0/0

### Edge\_Router#

**Explanation:** No, it is not visible because it is not the primary route. Routers will only place the best path in the routing table and because this is the backup route, it will only be visible in the routing table when the primary route goes down.

## Part 2: Test Failover to the IPv4 Floating Static Route

### **Packet Tracer - Configuring Floating Static Routes**

a. On Edge\_Router, administratively disable the exit interface of the primary route.

### **Answer:**

Edge\_Router(config)#int s0/0/0 Edge\_Router(config-if)#shutdown

b. Verify that the IPv4 floating static route is now in the routing table.

### Answer:

Edge\_Router#show ip route

S\* 0.0.0.0/0 is directly connected, Serial0/0/1

c. Trace the route from PC-A to the Web Server.

Answer: PC>tracert 198.0.0.10

Did the backup route work? If not, wait a few more seconds for convergence and then re-test. If the backup route is still not working, investigate your floating static route configuration.

d. Restore connectivity to the primary route.

### Answer:

Edge\_Router(config)#int s0/0/0

Edge\_Router(config-if)#no shutdown

e. Trace the route from **PC-A** to the **Web Server** to verify that the primary route is restored.

Answer: PC>tracert 198.0.0.10

## Part 3: Configure and Test Failover to an IPv6 Floating Static Route

### Step 1: Configure an IPv6 floating static route.

- a. The IPv6 static default route to **ISP1** is already configured. Configure an IPv6 floating static default route with an administrative distance of 5. The route should point to IPv6 address (2001:DB8:A:2::1) of ISP2.
- b. View the running configuration to verify that the IPv6 floating static default route is now listed under the IPv6 static default route.

### Step 2: Test Failover to the IPv6 Floating Static Route.

a. On Edge\_Router, administratively disable the exit interface of the primary route.

Answer: Edge Router(config)# ipv6 route ::/0 2001:DB8:A:2::1 5

b. Verify that the IPv6 floating static route is now in the routing table.

### **Answer:**

Edge Router#show run

ipv6 route ::/0 2001:DB8:A:1::1

ipv6 route ::/0 2001:DB8:A:2::1 5

c. Trace the route from PC-A to the Web Server.

Answer: PC>tracert 2001:db8:f:f::10

Did the backup route work? If not, wait a few more seconds for convergence and then re-test. If the backup route is still not working, investigate your floating static route configuration.

d. Restore connectivity to the primary route.

### Answer:

Edge\_Router(config)#int s0/0/0

Edge\_Router(config-if)#no shutdown

e. Trace the route from **PC-A** to the **Web Server** to verify that the primary route is restored.

Answer:PC>tracert 2001:db8:f:f::10

# **Suggested Scoring Rubric**

Activity Section	Question Location	Possible Points	Earned Points
Part 1: Configuring a Floating Static Route	Step 1c	2	
	Step 2a	3	
	Step 2d	5	
Part 1 Total		10	
Packet Tracer Score		90	
Total Score		100	