AMICI

Generated by Doxygen 1.8.15

1 About AMICI 2

2 License Conditions 2

3 How to contribute 3

4 Installation 3

5 Python Interface 6

6 MATLAB Interface 8

7 C++ Interface 13

8 FAQ 14

9 Namespace Documentation 14

9.1 amici Namespace Reference . . . 14
9.2 amici.ode_export Namespace Reference . . . 77
9.3 amici.plotting Namespace Reference . . . 85
9.4 amici.sbml_import Namespace Reference . . . 86

10 Class Documentation 90

10.1 AmiException Class Reference . . . 90
10.2 AmiVector Class Reference . . . 93
10.3 AmiVectorArray Class Reference . . . 104
10.4 BackwardProblem Class Reference . . . 111
10.5 CvodeException Class Reference . . . 116
10.6 ExpData Class Reference . . . 117
10.7 ForwardProblem Class Reference . . . 147
10.8 IDAException Class Reference . . . 154
10.9 IntegrationFailure Class Reference . . . 155
10.10 IntegrationFailureB Class Reference . . . 157
10.11 Model Class Reference . . . 159
10.12 Model_DAE Class Reference . . . 300
10.13 Model_ODE Class Reference . . . 332
10.14 NewtonFailure Class Reference . . . 362
10.15 NewtonSolver Class Reference . . . 363
10.16 NewtonSolverDense Class Reference . . . 370
10.17 NewtonSolverIterative Class Reference . . . 373
10.18 NewtonSolverSparse Class Reference . . . 376
10.19 ConservationLaw Class Reference . . . 379
10.20 Constant Class Reference . . . 380
10.21 Expression Class Reference . . . 382
10.22 LogLikelihood Class Reference . . . 383
10.23 ModelQuantity Class Reference . . . 384

10.24 Observable Class Reference . . . 387
10.25 ODEExporter Class Reference . . . 388
10.26 ODEModel Class Reference . . . 392
10.27 Parameter Class Reference . . . 409
10.28 SigmaY Class Reference . . . 411
10.29 State Class Reference . . . 412
10.30 TemplateAmici Class Reference . . . 415
10.31 ReturnData Class Reference . . . 416
10.32 SBMLException Class Reference . . . 434
10.33 SbmlImporter Class Reference . . . 434
10.34 SetupFailure Class Reference . . . 447
10.35 Solver Class Reference . . . 448
10.36 SteadystateProblem Class Reference . . . 517
10.37 amidata Class Reference . . . 524
10.38 amievent Class Reference . . . 529
10.39 amifun Class Reference . . . 532
10.40 amimodel Class Reference . . . 539
10.41 amioption Class Reference . . . 563
10.42 amised Class Reference . . . 572
10.43 optsym Class Reference . . . 575

11 File Documentation **576**

11.1 am_and.m File Reference . . . 576
11.2 am_eq.m File Reference . . . 577
11.3 am_ge.m File Reference . . . 578
11.4 am_gt.m File Reference . . . 579
11.5 am_if.m File Reference . . . 580
11.6 am_le.m File Reference . . . 581
11.7 am_lt.m File Reference . . . 582
11.8 am_max.m File Reference . . . 583
11.9 am_min.m File Reference . . . 584
11.10 am_or.m File Reference . . . 585
11.11 am_piecewise.m File Reference . . . 586
11.12 am_stepfun.m File Reference . . . 587
11.13 am_xor.m File Reference . . . 588
11.14 amici.cpp File Reference . . . 589
11.15 amiwrap.m File Reference . . . 590
11.16 cblas.cpp File Reference . . . 590
11.17 interface_matlab.cpp File Reference . . . 591
11.18 SBML2AMICI.m File Reference . . . 593
11.19 spline.cpp File Reference . . . 594
11.20 symbolic_functions.cpp File Reference . . . 595

Index 597

1 About AMICI

AMICI provides a multilanguage (Python, C++, Matlab) interface for the SUNDIALS solvers CVODES (for ordinary differential equations) and IDAS (for algebraic differential equations). AMICI allows the user to read differential equation models specified as SBML and automatically compiles such models as .mex simulation files, C++ executables or python modules. In contrast to the SUNDIALSTB interface, all necessary functions are transformed into native C++ code, which allows for a significantly faster simulation. Beyond forward integration, the compiled simulation file also allows for forward sensitivity analysis, steady state sensitivity analysis and adjoint sensitivity analysis for likelihood based output functions.

The interface was designed to provide routines for efficient gradient computation in parameter estimation of biochemical reaction models but is also applicable to a wider range of differential equation constrained optimization problems.

Online documentation is available as `github-pages`.

Publications

Fröhlich, F., Kaltenbacher, B., Theis, F. J., & Hasenauer, J. (2017). Scalable Parameter Estimation for Genome-Scale Biochemical Reaction Networks. Plos Computational Biology, 13(1), e1005331. doi: 10.1371/journal.pcbi.1005331

Fröhlich, F., Theis, F. J., Rädler, J. O., & Hasenauer, J. (2017). Parameter estimation for dynamical systems with discrete events and logical operations. Bioinformatics, 33(7), 1049-1056. doi: 10.1093/bioinformatics/btw764

Current build status

2 License Conditions

Copyright (c) 2015-2018, Fabian Fröhlich, Jan Hasenauer, Daniel Weindl and Paul Stapor All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SP↩ECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTI↩ON) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

3 How to contribute

We are happy about contributions to AMICI in any form (new functionality, documentation, bug reports, ...).

Making code changes

When making code changes:

- Check if you agree to release your contribution under the conditions provided in `LICENSE`
- Start a new branch from `develop`
- Implement your changes
- Submit a pull request to the `develop` branch
- Make sure your code is documented appropriately
  - Run `mtoc/makeDocumentation.m` to check completeness of your documentation
- Make sure your code is compatible with C++11, `gcc` and `clang`
- when adding new functionality, please also provide test cases (see `tests/cpputest/`)
- Write meaningful commit messages
- Run all tests to ensure nothing was broken
  - Run `tests/cpputest/wrapTestModels.m` followed by CI tests `scripts/buildAll.sh && scripts/run-cpputest.sh`
  - Run `tests/testModels.m`
  - Run `make python-tests` in `build`
- When all tests are passing and you think your code is ready to merge, request a code review

Adding/Updating tests

To add new tests add a new corresponding python script (see, e.g., `tests/example_dirac.py`) and add it to and run `tests/generateTestConfigurationForExamples.sh` To update test results replace `tests/cpputest/expectedResults.h5` by `tests/cpputest/writeResults.h5.bak` [ONLY DO THIS AFTER TRIPLE CHECKING CORRECTNESS OF RESULTS] Before replacing the test results, confirm that only expected datasets have changed, e.g. using `h5diff -v -r 1e-8 tests/cpputest/expectedResults.h5 tests/cpputest/writeResults.h5.bak | less`

4 Installation

Availability

The sources for AMICI are accessible as

- Source `tarball`
- Source `zip`
- GIT repository on `github`

Obtaining AMICI via the GIT versioning system

In order to always stay up-to-date with the latest AMICI versions, simply pull it from our GIT repository and recompile it when a new release is available. For more information about GIT checkout their website

The GIT repository can currently be found at https://github.com/ICB-DCM/AMICI and a direct clone is possible via

```
git clone https://github.com/ICB-DCM/AMICI.git AMICI
```

Installation

If AMICI was downloaded as a zip, it needs to be unpacked in a convenient directory. If AMICI was obtained via cloning of the git repository, no further unpacking is necessary.

Dependencies

The MATLAB interface only depends on the symbolic toolbox, which is needed for model compilation, but not simulation.

Symbolic Engine

The MATLAB interface requires the symbolic toolbox for model compilation. The symbolic toolbox is not required for model simulation.

Math Kernel Library (MKL)

The python and C++ interfaces require a system installation of BLAS. AMICI has been tested with various native and general purpose MKL implementations such as Accelerate, Intel MKL, cblas, openblas, atlas. The matlab interface uses the MATLAB MKL, which requires no prior installation.

HDF5

The python and C++ interfaces provide routines to read and write options and results in hdf5 format. For the python interface, the installation of hdf5 is optional, but for the C++ interace it is required. HDF can be installed using package managers such as brew or apt:

```
brew install hdf5
```

or

```
apt-get install libhdf5-serial-dev
```

SWIG

The python interface requires SWIG, which has to be installed by the user. Swig can be installed using package managers such as brew or apt:

```
brew install swig
```

or

```
apt-get install swig3.0
```

We note here that some linux package managers may provide swig executables as swig3.0, but installation as swig is required. This can be fixed using, e.g., symbolic links:

```
mkdir -p ~/bin/ && ln -s $(which swig3.0) ~/bin/swig && export PATH=~/bin/:$PATH
```

python packages

The python interface requires the python packages `pkgconfig` and `numpy` to be installed before AMICI can be installed. These can be installed via `pip`:

```
pip3 install pkgconfig numpy
```

MATLAB

To use AMICI from MATLAB, start MATLAB and add the AMICI/matlab direcory to the MATLAB path. To add all toolbox directories to the MATLAB path, execute the matlab script

```
installAMICI.m
```

To store the installation for further MATLAB session, the path can be saved via

```
savepath
```

For the compilation of .mex files, MATLAB needs to be configured with a working C compiler. The C compiler needs to be installed and configured via:

```
mex -setup c
```

For a list of supported compilers we refer to the mathworks documentation: mathworks.com Note that Microsoft Visual Studio compilers are currently not supported.

python

To use AMICI from python, install the module and all other requirements using pip

```
pip3 install amici
```

You can now import it as python module:

```
import amici
```

C++

To use AMICI from C++, run the

```
./scripts/buildSundials.sh
./scripts/buildSuitesparse.sh
./scripts/buildAmici.sh
```

script to compile amici libary. The static library file can then be linked from

```
./build/libamici.a
```

In CMake-based packages, amici can be linked via

```
find_package(Amici)
```

Dependencies

The MATLAB interface requires the Mathworks Symbolic Toolbox for model generation via `amiwrap(...)`, but not for execution of precompiled models. Currently MATLAB R2018a or newer is not supported (see https://github.com/ICB-DCM/AMICI/issues/307)

The python interface requires python 3.6 or newer and `cblas` library to be installed. Windows installations via pip are currently not supported, but users may try to install amici using the build scripts provided for the C++ interface (these will by default automatically install the python module).

The C++ interface requires `cmake` and `cblas` to be installed.

The tools SUNDIALS and SuiteSparse shipped with AMICI do **not** require explicit installation.

AMICI uses the following packages from SUNDIALS:

CVODES: the sensitivity-enabled ODE solver in SUNDIALS. Radu Serban and Alan C. Hindmarsh. *ASME 2005 International Design Engineering Technical Conferences and Computers and Information in Engineering Conference.* American Society of Mechanical Engineers, 2005. PDF

IDAS

AMICI uses the following packages from SuiteSparse:

Algorithm 907: KLU, A Direct Sparse Solver for Circuit Simulation Problems. Timothy A. Davis, Ekanathan Palamadai Natarajan, *ACM Transactions on Mathematical Software*, Vol 37, Issue 6, 2010, pp 36:1 - 36:17. PDF

Algorithm 837: AMD, an approximate minimum degree ordering algorithm, Patrick R. Amestoy, Timothy A. Davis, Iain S. Duff, *ACM Transactions on Mathematical Software*, Vol 30, Issue 3, 2004, pp 381 - 388. PDF

Algorithm 836: COLAMD, a column approximate minimum degree ordering algorithm, Timothy A. Davis, John R. Gilbert, Stefan I. Larimore, Esmond G. Ng *ACM Transactions on Mathematical Software*, Vol 30, Issue 3, 2004, pp 377 - 380. PDF

5 Python Interface

In the following we will give a detailed overview how to specify models in Python and how to call the generated simulation files.

Model Definition

This guide will guide the user on how to specify models in Python using SBML. For example implementations see the examples in the python/examples directory.

SBML input

First, import an sbml file using the `amici.sbml_import.SbmlImporter` class:

```
import amici
sbmlImporter = amici.SbmlImporter('model_steadystate_scaled.sbml')
```

the sbml document as imported by `libSBML` is available as

```
sbml = sbmlImporter.sbml
```

Constants

parameters that should be considered constants can be specified in a list of strings specifying the respective SbmlId of a parameter.

```
constantParameters=['k4']
```

Observables

assignment rules that should be considered as observables can extracted using the `amici.assignment↩Rules2observables` function

```
observables = amici.assignmentRules2observables(sbml, filter=lambda variableId:
                                                variableId.startswith('observable_') and not variableId.endswi
```

Standard Deviations

standard deviations can be specified as dictionaries ...

```
sigmas = {'observable_x1withsigma': 'observable_x1withsigma_sigma'}
```

Model Compilation

to compile the sbml as python module, the user has to call the method `amici.sbml_import.SbmlImporter.sbml2amici`, passing all the previously defined model specifications

```
sbmlImporter.sbml2amici('test', 'test',
                        observables=observables,
                        constantParameters=constantParameters,
                        sigmas=sigma)
```

Note: To build AMICI with OpenMP support, which allows to parallelize model simulations of multiple experimental conditions, set the environment variables `AMICI_CXXFLAGS` and `AMICI_LDFLAGS` to the correct OpenMP flags of your compiler and linker, respectively. This has to be done for both AMICI package installation *and* model compilation. When using `gcc` on Linux, use:

```
# on your shell:
AMICI_CXXFLAGS=-fopenmp AMICI_LDFLAGS=-fopenmp pip3 install amici

# in python, before model compilation:
import os
os.environ['AMICI_CXXFLAGS'] = '-fopenmp'
os.environ['AMICI_LDFLAGS'] = '-fopenmp'
```

Model Simulation

currently the model folder has to be manually added to the python path

```
import sys
sys.path.insert(0, 'test')
```

the compiled model can now be imported as python module

```
import test as modelModule
```

to obtain a model instance call the `getModel()` method. This model instance will be instantiated using the defautl parameter values specified in the sbml.

```
model = modelModule.getModel()
```

then pass the simulation timepoints to `amici.Model.setTimepoints`

```
model.setTimepoints(np.linspace(0, 60, 60))
```

for simulation we need to generate a solver instance

```
solver = model.getSolver()
```

the model simulation can now be carried out using `amici.runAmiciSimulation`

```
rdata = amici.runAmiciSimulation(model, solver)
```

6 MATLAB Interface

In the following we will give a detailed overview how to specify models in MATLAB and how to call the generated simulation files.

Model Definition

This guide will guide the user on how to specify models in MATLAB. For example implementations see the examples in the matlab/examples directory.

Header

The model definition needs to be defined as a function which returns a struct with all symbolic definitions and options.

```
function [model] = example_model_syms()
```

Options

Set the options by specifying the respective field of the modelstruct

```
model.(fieldname) = value
```

The options specify default options for simulation, parametrisation and compilation. All of these options are optional.

field	description	default
.param	default parametrisation 'log'/'log10'/'lin'	'lin'
.debug	flag to compile with debug symbols	false
.forward	flag to activate forward sensitivities	true
.adjoint	flag to activate adjoint sensitivities	true

When set to false, the fields 'forward' and 'adjoint' will speed up the time required to compile the model but also disable the respective sensitivity computation.

States

Create the respective symbolic variables. The name of the symbolic variable can be chosen arbitrarily.

```
syms state1 state2 state3
```

Create the state vector containing all states:

```
model.sym.x = [ state1 state2 state3 ];
```

Parameters

Create the respective symbolic variables. The name of the symbolic variable can be chosen arbitrarily. Sensitivities **will be derived** for all paramaters.

```
syms param1 param2 param3 param4 param5 param6
```

Create the parameters vector

```
model.sym.p = [ param1 param2 param3 param4 param5 param6 ];
```

Constants

Create the respective symbolic variables. The name of the symbolic variable can be chosen arbitrarily. Sensitivities with respect to constants **will not be derived**.

```
syms const1 const2
```

Create the parameters vector

```
model.sym.k = [ const1 const2 ];
```

Differential Equation

For time-dependent differential equations you can specify a symbolic variable for time. This **needs** to be denoted by `t`.

```
syms t
```

Specify the right hand side of the differential equation `f` or `xdot`

```
model.sym.xdot(1) = [ const1 - param1*state1 ];
model.sym.xdot(2) = [ +param2*state1 + dirac(t-param3) - const2*state2 ];
model.sym.xdot(3) = [ param4*state2 ];
```

or

```
model.sym.f(1) = [ const1 - param1*state1 ];
model.sym.f(2) = [ +param2*state1 + dirac(t-param3) - const2*state2 ];
model.sym.f(3) = [ param4*state2 ];
```

The specification of `f` or `xdot` may depend on states, parameters and constants.

For DAEs also specify the mass matrix.

```
model.sym.M = [1, 0, 0;...
               0, 1, 0;...
               0, 0, 0];
```

The specification of M may depend on parameters and constants.

For ODEs the integrator will solve the equation $\dot{x} = f$ and for DAEs the equations $M \cdot \dot{x} = f$. AMICI will decide whether to use CVODES (for ODEs) or IDAS (for DAEs) based on whether the mass matrix is defined or not.

In the definition of the differential equation you can use certain symbolic functions. For a full list of available functions see `src/symbolic_functions.cpp`.

Dirac functions can be used to cause a jump in the respective states at the specified time-point. This is typically used to model injections, or other external stimuli. Spline functions can be used to model time/state dependent response with unkown time/state dependence.

Initial Conditions

Specify the initial conditions. These may depend on parameters on constants and must have the same size as `x`.

```
model.sym.x0 = [ param4, 0, 0 ];
```

Observables

Specify the observables. These may depend on parameters and constants.

```
model.sym.y(1) = state1 + state2;
model.sym.y(2) = state3 - state2;
```

In the definition of the observable you can use certain symbolic functions. For a full list of available functions see `src/symbolic_functions.cpp`. Dirac functions in observables will have no effect.

Events

Specifying events is optional. Events are specified in terms of a trigger function, a bolus fuction and an output function. The roots of the trigger function defines the occurences of the event. The bolus function defines the change in the state on event occurences. The output function defines the expression which is evaluated and reported by the simulation routine on every event occurence. The user can create events by constructing a vector of objects of the class amievent.

```
model.sym.event(1) = amievent(state1 - state2,0,[]);
```

Events may depend on states, parameters and constants but **not** on observables.

For more details about event support see https://doi.org/10.1093/bioinformatics/btw764

Standard Deviation

Specifying standard deviations is optional. It only has an effect when computing adjoint sensitivities. It allows the user to specify standard deviations of experimental data for observables and events.

Standard deviaton for observable data is denoted by sigma_y

```
model.sym.sigma_y(1) = param5;
```

Standard deviaton for event data is denoted by sigma_t

```
model.sym.sigma_t(1) = param6;
```

Both `sigma_y` and `sigma_t` can either be a scalar or of the same dimension as the observables / events function. They can depend on time and parameters but must not depend on the states or observables. The values provided in `sigma_y` and `sigma_t` will only be used if the value in `D.Sigma_Y` or `D.Sigma_T` in the user-provided data struct is `NaN`. See simulation for details.

Objective Function

By default, AMICI assumes a normal noise model and uses the corresponding negative log-likelihood

```
J = 1/2*sum(((y_i(t)-my_ti)/sigma_y_i)^2 + log(2*pi*sigma_y^2)
```

as objective function. A user provided objective function can be specified in

```
model.sym.Jy
```

As reference see the default specification of `this.sym.Jy` in `amimodel.makeSyms`.

SBML

AMICI can also import SBML models using the command `SBML2AMICI`. This will generate a model specification as described above, which may be edited by the user to apply further changes.

Model Compilation

The model can then be compiled by calling `amiwrap.m`:

```
amiwrap(modelname,'example_model_syms',dir,o2flag)
```

Here `modelname` should be a string defining the name of the model, `dir` should be a string containing the path to the directory in which simulation files should be placed and `o2flag` is a flag indicating whether second order sensitivities should also be compiled. The user should make sure that the previously defined function ''example_model_syms'`is in the user path. Alternatively, the user can also call the function`'example_model_syms''

```
[model] = example_model_syms()
```

and subsequently provide the generated struct to `amiwrap(...)`, instead of providing the symbolic function:

```
amiwrap(modelname,model,dir,o2flag)
```

In a similar fashion, the user could also generate multiple models and pass them directly to `amiwrap(...)` without generating respective model definition scripts.

Model Simulation

After the call to `amiwrap(...)` two files will be placed in the specified directory. One is a *modelname*.mex and the other is simulate_ *modelname*.m. The mex file should never be called directly. Instead the MATLAB script, which acts as a wrapper around the .mex simulation file should be used.

The simulate_ *modelname*.m itself carries extensive documentation on how to call the function, what it returns and what additional options can be specified. In the following we will give a short overview of possible function calls.

Integration

Define a time vector:

```
t = linspace(0,10,100)
```

Generate a parameter vector:

```
theta = ones(6,1);
```

Generate a constants vector:

```
kappa = ones(2,1);
```

Integrate:

```
sol = simulate_modelname(t,theta,kappa,[],options)
```

The integration status will be indicated by the `sol.status` flag. Negative values indicated failed integration. The states will then be available as sol.x. The observables will then be available as `sol.y`. The event outputs will then be available as `sol.z`. If no event occured there will be an event at the end of the considered interval with the final value of the root function is stored in `sol.rz`.

Alternatively the integration can also be called via

```
[status,t,x,y] = simulate_modelname(t,theta,kappa,[],options)
```

The integration status will be indicated by the flag `status` . Negative values indicated failed integration. The states will then be available as `x`. The observables will then be available as `y`. No event output will be given.

Forward Sensitivities

Set the sensitivity computation to forward sensitivities and integrate:

```
options.sensi = 1;
options.sensi_meth = 'forward;
sol = simulate_modelname(t,theta,kappa,[],options)
```

The integration status will be indicated by the `sol.status` flag. Negative values indicate failed integration. The states will be available as `sol.x`, with the derivative with respect to the parameters in `sol.sx`. The observables will be available as `sol.y`, with the derivative with respect to the parameters in `sol.sy`. The event outputs will be available as `sol.z`, with the derivative with respect to the parameters in `sol.sz`. If no event occured there will be an event at the end of the considered interval with the final value of the root function stored in `sol.rz`, with the derivative with respect to the parameters in `sol.srz`.

Alternatively the integration can also be called via

```
[status,t,x,y,sx,sy] = simulate_modelname(t,theta,kappa,[],options)
```

The integration status will be indicated by the status flag. Negative values indicate failed integration. The states will then be available as `x`, with derivative with respect to the parameters in `sx`. The observables will then be available as `y`, with derivative with respect to the parameters in `sy`. No event output will be given.

Adjoint Sensitivities

Set the sensitivity computation to adjoint sensitivities:

```
options.sensi = 1;
options.sensi_meth = 'adjoint';
```

Define Experimental Data:

```
D.Y = [NaN(1,2)],ones(length(t)-1,2)];
D.Sigma_Y = [0.1*ones(length(t)-1,2),NaN(1,2)];
D.T = ones(1,1);
D.Sigma_T = NaN;
```

The `NaN` values in `Sigma_Y` and `Sigma_T` will be replaced by the specification in `model.sym.sigma_y` and `model.sym.sigma_t`. Data points with `NaN` value will be completely ignored.

Integrate:

```
sol = simulate_modelname(t,theta,kappa,D,options)
```

The integration status will be indicated by the sol.status flag. Negative values indicate failed integration. The log-likelihood will then be available as `sol.llh` and the derivative with respect to the parameters in `sol.sllh`. Notice that for adjoint sensitivities no state, observable and event sensitivities will be available. Yet this approach can be expected to be significantly faster for systems with a large number of parameters.

Steady State Sensitivities

This will compute state sensitivities according to the formula $s_k^x = -\left(\frac{\partial f}{\partial x}\right)^{-1} \frac{\partial f}{\partial \theta_k}$

In the current implementation this formulation does not allow for conservation laws as this would result in a singular Jacobian.

Set the final timepoint as infinity, this will indicate the solver to compute the steadystate:

```
t = Inf;
```

Set the sensitivity computation to steady state sensitivities:

```
options.sensi = 1;
```

Integrate:

```
sol = simulate_modelname(t,theta,kappa,D,options)
```

The states will be available as `sol.x`, with the derivative with respect to the parameters in `sol.sx`. The observables will be available as `sol.y`, with the derivative with respect to the parameters in `sol.sy`. Notice that for steady state sensitivities no event sensitivities will be available. For the accuracy of the computed derivatives it is essential that the system is sufficiently close to a steady state. This can be checked by examining the right hand side of the system at the final time-point via `sol.diagnosis.xdot`.

7 C++ Interface

The Python Interface and MATLAB Interface can translate the model definition into C++ code, which is then compiled into a .mex file or a python module. Advanced users can also use this code within stand-alone C/C++ application for use in other environments (e.g. on high performance computing systems). This section will give a short overview over the generated files and provide a brief introduction of how this code can be included in other applications.

Generated model files

`amiwrap.m` and `amici.SbmlImporter.sbml2amici` write the model source files to ${AMICI_ROOT_↩DIR}/models/${MODEL_NAME} by default. The content of a model source directory might look something like this (given `MODEL_NAME=model_steadystate`):

```
CMakeLists.txt
hashes.mat
main.cpp
model_steadystate_deltaqB.cpp
model_steadystate_deltaqB.h
[... many more files model_steadystate_*.(cpp|h|md5|o) ]
wrapfunctions.cpp
wrapfunctions.h
model_steadystate.h
```

Running a simulation

The entry function for running an AMICI simulation is `runAmiciSimulation(...)`, declared in amici.h. This function requires (i) a `Model` instance. For the example `model_steadystate` the respective class is provided as `Model_model_steadystate` in `model_steadystate.h`. For convenience, the header `wrapfunctions.h` defines a function `getModel()`, that returns an instance of that class. (ii) a `Solver` instance. This solver instance needs to match the requirements of the model and can be generated using `model->getSolver()`. (iii) optionally an `ExpData` instance, which contains any experimental data.

A scaffold for a standalone simulation program is generated in `main.cpp` in the model source directory. This programm shows how to initialize the above-mentioned structs and how to obtain the simulation results.

Compiling and linking

The complete AMICI API is available through `amici.h`; this is the only header file that needs to be included. `hdf5.h` provides some functions for reading and writing `HDF5` files).

You need to compile and link `${AMICI_ROOT_DIR}/models/${MODEL_NAME}/*.cpp`, `${AMICI_ROOT_DIR}/src/*.cpp`, the SUNDIALS and the SUITESPARSE library, or use the CMake package configuration from the build directory which tells CMake about all AMICI dependencies.

Along with `main.cpp`, a `CMake` file (`CMakeLists.txt`) will be generated automatically. The CMake file shows the abovementioned library dependencies. These files provide a scaffold for a standalone simulation program. The required numerical libraries are shipped with AMICI. To compile them, run `${AMICI_ROOT_DIR}/scripts/run-tests.sh` once. HDF5 libraries and header files need to be installed separately. More information on how to run the compiled program is provided in `main.cpp`.

8 FAQ

Q: My model fails to build.

A: Remove the corresponding model directory located in AMICI/models/∗yourmodelname∗ and compile again.

Q: It still does not compile.

A: Make an `issue` and we will have a look.

Q: I get an out of memory error while compiling my model on a Windows machine.

A: This may be due to an old compiler version. See `issue #161` for instructions on how to install a new compiler.

Q: The simulation/sensitivities I get are incorrect.

A: There are some known issues, especially with adjoint sensitivities, events and DAEs. If your particular problem is not featured in the `issues` list, please add it!

9 Namespace Documentation

9.1 amici Namespace Reference

The AMICI Python module (in doxygen this will also contain documentation about the C++ library)

Namespaces

- ode_export

  The C++ ODE export module for python.
- plotting

  Plotting related functions.
- sbml_import

  The python sbml import module for python.

Classes

- class AmiException

  amici exception handler class
- class AmiVector
- class AmiVectorArray
- class BackwardProblem

  class to solve backwards problems.
- class CvodeException

  cvode exception handler class
- class ExpData

  ExpData carries all information about experimental or condition-specific data.
- class ForwardProblem

  The ForwardProblem class groups all functions for solving the backwards problem. Has only static members.
- class IDAException

  ida exception handler class
- class IntegrationFailure

  integration failure exception for the forward problem this exception should be thrown when an integration failure occured for this exception we can assume that we can recover from the exception and return a solution struct to the user
- class IntegrationFailureB

  integration failure exception for the backward problem this exception should be thrown when an integration failure occured for this exception we can assume that we can recover from the exception and return a solution struct to the user
- class Model

  The Model class represents an AMICI ODE model. The model can compute various model related quantities based on symbolically generated code.
- class Model_DAE

  The Model class represents an AMICI DAE model. The model does not contain any data, but represents the state of the model at a specific time t. The states must not always be in sync, but may be updated asynchroneously.
- class Model_ODE

  The Model class represents an AMICI ODE model. The model does not contain any data, but represents the state of the model at a specific time t. The states must not always be in sync, but may be updated asynchroneously.
- class NewtonFailure

  newton failure exception this exception should be thrown when the steady state computation failed to converge for this exception we can assume that we can recover from the exception and return a solution struct to the user
- class NewtonSolver

  The NewtonSolver class sets up the linear solver for the Newton method.
- class NewtonSolverDense

  The NewtonSolverDense provides access to the dense linear solver for the Newton method.
- class NewtonSolverIterative

  The NewtonSolverIterative provides access to the iterative linear solver for the Newton method.
- class NewtonSolverSparse

The NewtonSolverSparse provides access to the sparse linear solver for the Newton method.

- class ReturnData

  class that stores all data which is later returned by the mex function

- class SetupFailure

  setup failure exception this exception should be thrown when the solver setup failed for this exception we can assume that we cannot recover from the exception and an error will be thrown

- class Solver
- class SteadystateProblem

  The SteadystateProblem class solves a steady-state problem using Newton's method and falls back to integration on failure.

Typedefs

- typedef double realtype
- typedef void(∗ msgIdAndTxtFp) (const char ∗identifier, const char ∗format,...)

  msgIdAndTxtFp

Enumerations

- enum BLASLayout { **rowMajor** = 101, **colMajor** = 102 }
- enum BLASTranspose { **noTrans** = 111, **trans** = 112, **conjTrans** = 113 }
- enum ParameterScaling { **none**, **ln**, **log10** }
- enum SecondOrderMode { **none**, **full**, **directional** }
- enum SensitivityOrder { **none**, **first**, **second** }
- enum SensitivityMethod { **none**, **forward**, **adjoint** }
- enum LinearSolver {
  dense = 1, **band** = 2, **LAPACKDense** = 3, **LAPACKBand** = 4,
  diag = 5, **SPGMR** = 6, **SPBCG** = 7, **SPTFQMR** = 8,
  KLU = 9 }
- enum InternalSensitivityMethod { **simultaneous** = 1, **staggered** = 2, **staggered1** = 3 }
- enum InterpolationType { **hermite** = 1, **polynomial** = 2 }
- enum LinearMultistepMethod { **adams** = 1, **BDF** = 2 }
- enum NonlinearSolverIteration { **functional** = 1, **newton** = 2 }
- enum StateOrdering { **AMD**, **COLAMD**, **natural** }
- enum SteadyStateSensitivityMode { **newtonOnly**, **simulationFSA** }
- enum NewtonStatus { **failed** =-1, **newt** =1, **newt_sim** =2, **newt_sim_newt** =3 }
- enum mexRhsArguments {
  RHS_TIMEPOINTS, **RHS_PARAMETERS**, **RHS_CONSTANTS**, **RHS_OPTIONS**,
  RHS_PLIST, **RHS_XSCALE_UNUSED**, **RHS_INITIALIZATION**, **RHS_DATA**,
  RHS_NUMARGS_REQUIRED = RHS_DATA, **RHS_NUMARGS** }

  The mexFunctionArguments enum takes care of the ordering of mex file arguments (indexing in prhs)

Functions

- void printErrMsgIdAndTxt (const char ∗identifier, const char ∗format,...)
- void printWarnMsgIdAndTxt (const char ∗identifier, const char ∗format,...)
- std::unique_ptr< ReturnData > runAmiciSimulation (Solver &solver, const ExpData ∗edata, Model &model)
- std::vector< std::unique_ptr< ReturnData > > runAmiciSimulations (Solver const &solver, const std↩ ::vector< ExpData ∗ > &edatas, Model const &model, int num_threads)
- void amici_dgemv (BLASLayout layout, BLASTranspose TransA, const int M, const int N, const double alpha, const double ∗A, const int lda, const double ∗X, const int incX, const double beta, double ∗Y, const int incY)

- void amici_dgemm (BLASLayout layout, BLASTranspose TransA, BLASTranspose TransB, const int M, const int N, const int K, const double alpha, const double ∗A, const int lda, const double ∗B, const int ldb, const double beta, double ∗C, const int ldc)
- void amici_daxpy (int n, double alpha, const double ∗x, const int incx, double ∗y, int incy)

  Compute y = a∗x + y.
- void checkSigmaPositivity (std::vector< realtype > const &sigmaVector, const char ∗vectorName)
- void checkSigmaPositivity (const realtype sigma, const char ∗sigmaName)
- void setModelData (const mxArray ∗prhs[ ], int nrhs, Model &model)

  setModelData sets data from the matlab call to the model object
- void setSolverOptions (const mxArray ∗prhs[ ], int nrhs, Solver &solver)

  setSolverOptions solver options from the matlab call to a solver object
- ReturnDataMatlab ∗ setupReturnData (mxArray ∗plhs[ ], int nlhs)
- std::unique_ptr< ExpData > expDataFromMatlabCall (const mxArray ∗prhs[ ], const Model &model)
- int checkFinite (const int N, const realtype ∗array, const char ∗fun)
- void unscaleParameters (const double ∗bufferScaled, const ParameterScaling ∗pscale, int n, double ∗buffer↩ Unscaled)

  Remove parameter scaling according to the parameter scaling in pscale.
- void unscaleParameters (std::vector< double > const &bufferScaled, std::vector< ParameterScaling > const &pscale, std::vector< double > &bufferUnscaled)

  Remove parameter scaling according to the parameter scaling in pscale.
- double getUnscaledParameter (double scaledParameter, ParameterScaling scaling)

  Remove parameter scaling according to `scaling`
- double getScaledParameter (double unscaledParameter, ParameterScaling scaling)

  Apply parameter scaling according to `scaling`
- void scaleParameters (const std::vector< double > &bufferUnscaled, const std::vector< ParameterScaling > &pscale, std::vector< double > &bufferScaled)

  Apply parameter scaling according to `scaling`
- bool operator== (const Model &a, const Model &b)
- mxArray ∗ getReturnDataMatlabFromAmiciCall (ReturnData const ∗rdata)
- mxArray ∗ initMatlabReturnFields (ReturnData const ∗rdata)
- mxArray ∗ initMatlabDiagnosisFields (ReturnData const ∗rdata)
- template<typename T >
  void writeMatlabField0 (mxArray ∗matlabStruct, const char ∗fieldName, T fieldData)
- template<typename T >
  void writeMatlabField1 (mxArray ∗matlabStruct, const char ∗fieldName, std::vector< T > const &fieldData, const int dim0)
- template<typename T >
  void writeMatlabField2 (mxArray ∗matlabStruct, const char ∗fieldName, std::vector< T > const &fieldData, int dim0, int dim1, std::vector< int > perm)
- template<typename T >
  void writeMatlabField3 (mxArray ∗matlabStruct, const char ∗fieldName, std::vector< T > const &fieldData, int dim0, int dim1, int dim2, std::vector< int > perm)
- template<typename T >
  void writeMatlabField4 (mxArray ∗matlabStruct, const char ∗fieldName, std::vector< T > const &fieldData, int dim0, int dim1, int dim2, int dim3, std::vector< int > perm)
- double ∗ initAndAttachArray (mxArray ∗matlabStruct, const char ∗fieldName, std::vector< mwSize > dim)
- void checkFieldNames (const char ∗∗fieldNames, const int fieldCount)
- template<typename T >
  std::vector< T > reorder (std::vector< T > const &input, std::vector< int > const &order)
- template<typename T >
  char ∗ serializeToChar (T const &data, int ∗size)
- template<typename T >
  T deserializeFromChar (const char ∗buffer, int size)
- template<typename T >
  std::string serializeToString (T const &data)

- template<typename T >
  std::vector< char > serializeToStdVec (T const &data)
- template<typename T >
  T deserializeFromString (std::string const &serialized)
- bool operator== (const Solver &a, const Solver &b)
- int spline (int n, int end1, int end2, double slope1, double slope2, double x[ ], double y[ ], double b[ ], double c[ ], double d[ ])
- double seval (int n, double u, double x[ ], double y[ ], double b[ ], double c[ ], double d[ ])

  Evaluate the cubic spline function.
- double sinteg (int n, double u, double x[ ], double y[ ], double b[ ], double c[ ], double d[ ])
- double log (double x)
- double dirac (double x)
- double heaviside (double x)
- double min (double a, double b, double c)
- double Dmin (int id, double a, double b, double c)
- double max (double a, double b, double c)
- double Dmax (int id, double a, double b, double c)
- double pos_pow (double base, double exponent)
- int isNaN (double what)
- int isInf (double what)
- double getNaN ()
- double sign (double x)
- double spline (double t, int num,...)
- double spline_pos (double t, int num,...)
- double Dspline (int id, double t, int num,...)
- double Dspline_pos (int id, double t, int num,...)
- double DDspline (int id1, int id2, double t, int num,...)
- double DDspline_pos (int id1, int id2, double t, int num,...)
- def runAmiciSimulation (model, solver, edata=None)

  Convenience wrapper around amici.runAmiciSimulation (generated by swig)
- def ExpData (∗args)

  Convenience wrapper for ExpData constructors.
- def runAmiciSimulations (model, solver, edata_list, num_threads=1)

  Convenience wrapper for loops of amici.runAmiciSimulation.
- int dbl2int (const double x)
- char amici_blasCBlasTransToBlasTrans (BLASTranspose trans)
- std::vector< realtype > mxArrayToVector (const mxArray ∗array, int length)
- realtype getValueById (std::vector< std::string > const &ids, std::vector< realtype > const &values, std↩ ::string const &id, const char ∗variable_name, const char ∗id_name)

  local helper function to get parameters
- void setValueById (std::vector< std::string > const &ids, std::vector< realtype > &values, realtype value, std::string const &id, const char ∗variable_name, const char ∗id_name)

  local helper function to set parameters
- int setValueByIdRegex (std::vector< std::string > const &ids, std::vector< realtype > &values, realtype value, std::string const &regex, const char ∗variable_name, const char ∗id_name)

  local helper function to set parameters via regex

Variables

- msgIdAndTxtFp errMsgIdAndTxt = &printErrMsgIdAndTxt
- msgIdAndTxtFp warnMsgIdAndTxt = &printWarnMsgIdAndTxt
- constexpr double pi = 3.14159265358979323846
- bool hdf5_enabled = False

  boolean indicating if amici was compiled with hdf5 support
- bool has_clibs = False

  boolean indicating if this is the full package with swig interface or the raw package without
- amici_path

  absolute root path of the amici repository
- amiciSwigPath = os.path.join(amici_path, 'swig')

  absolute path of the amici swig directory
- amiciSrcPath = os.path.join(amici_path, 'src')

  absolute path of the amici source directory
- amiciModulePath = os.path.dirname(__file__)

  absolute root path of the amici module

9.1.1 Detailed Description

The AMICI Python module provides functionality for importing SBML models and turning them into C++ Python extensions.

Getting started:

```
 creating a extension module for an SBML model:
import amici
amiSbml = amici.SbmlImporter('mymodel.sbml')
amiSbml.sbml2amici('modelName', 'outputDirectory')
 using the created module (set python path)
import modelName
help(modelName)
```

9.1.2 Typedef Documentation

9.1.2.1 realtype

```
typedef double realtype
```

defines variable type for simulation variables (determines numerical accuracy)

Definition at line 51 of file defines.h.

9.1.2.2 msgIdAndTxtFp

```
typedef void(* msgIdAndTxtFp) (const char *identifier, const char *format,...)
```

Parameters

identifier	string with error message identifier
format	string with error message printf-style format
...	arguments to be formatted

Definition at line 159 of file defines.h.

9.1.3 Enumeration Type Documentation

9.1.3.1 BLASLayout

`enum BLASLayout [strong]`

BLAS Matrix Layout, affects dgemm and gemv calls

Definition at line 54 of file defines.h.

9.1.3.2 BLASTranspose

`enum BLASTranspose [strong]`

BLAS Matrix Transposition, affects dgemm and gemv calls

Definition at line 60 of file defines.h.

9.1.3.3 ParameterScaling

`enum ParameterScaling [strong]`

modes for parameter transformations

Definition at line 67 of file defines.h.

9.1.3.4 SecondOrderMode

`enum SecondOrderMode [strong]`

modes for second order sensitivity analysis

Definition at line 74 of file defines.h.

9.1.3.5 SensitivityOrder

`enum SensitivityOrder [strong]`

orders of sensitivity analysis

Definition at line 81 of file defines.h.

9.1.3.6 SensitivityMethod

```
enum SensitivityMethod [strong]
```

methods for sensitivity computation

Definition at line 88 of file defines.h.

9.1.3.7 LinearSolver

```
enum LinearSolver [strong]
```

linear solvers for CVODES/IDAS

Definition at line 95 of file defines.h.

9.1.3.8 InternalSensitivityMethod

```
enum InternalSensitivityMethod [strong]
```

CVODES/IDAS forward sensitivity computation method

Definition at line 108 of file defines.h.

9.1.3.9 InterpolationType

```
enum InterpolationType [strong]
```

CVODES/IDAS state interpolation for adjoint sensitivity analysis

Definition at line 115 of file defines.h.

9.1.3.10 LinearMultistepMethod

```
enum LinearMultistepMethod [strong]
```

CVODES/IDAS linear multistep method

Definition at line 121 of file defines.h.

9.1.3.11 NonlinearSolverIteration

```
enum NonlinearSolverIteration [strong]
```

CVODES/IDAS Nonlinear Iteration method

Definition at line 127 of file defines.h.

9.1.3.12 StateOrdering

```
enum StateOrdering [strong]
```

KLU state reordering

Definition at line 133 of file defines.h.

9.1.3.13 SteadyStateSensitivityMode

```
enum SteadyStateSensitivityMode [strong]
```

Sensitivity computation mode in steadyStateProblem

Definition at line 140 of file defines.h.

9.1.3.14 NewtonStatus

```
enum NewtonStatus [strong]
```

State in which the steady state computionat finished

Definition at line 146 of file defines.h.

9.1.4 Function Documentation

9.1.4.1 printErrMsgIdAndTxt()

```
void printErrMsgIdAndTxt (
            const char * identifier,
            const char * format,
             ...  )
```

printErrMsgIdAndTxt prints a specified error message associated to the specified identifier

Parameters

in	*identifier*	error identifier **Type**: char
in	*format*	string with error message printf-style format
	...	arguments to be formatted

Returns

void

Definition at line 113 of file amici.cpp.

9.1.4.2 printWarnMsgIdAndTxt()

```
void printWarnMsgIdAndTxt (
            const char * identifier,
            const char * format,
             ...  )
```

printErrMsgIdAndTxt prints a specified warning message associated to the specified identifier

Parameters

in	*identifier*	warning identifier **Type**: char
in	*format*	string with error message printf-style format
	...	arguments to be formatted

Returns

void

Definition at line 134 of file amici.cpp.

9.1.4.3 runAmiciSimulation() [1/2]

```
std::unique_ptr< ReturnData > runAmiciSimulation (
            Solver & solver,
            const ExpData * edata,
            Model & model )
```

runAmiciSimulation is the core integration routine. It initializes the solver and runs the forward and backward problem.

Parameters

solver	Solver instance
edata	pointer to experimental data object
model	Model specification object

Returns

rdata pointer to return data object

Definition at line 42 of file amici.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.4 runAmiciSimulations() [1/2]

```
std::vector< std::unique_ptr< ReturnData > > runAmiciSimulations (
            Solver const & solver,
            const std::vector< ExpData * > & edatas,
            Model const & model,
            int num_threads )
```

runAmiciSimulations does the same as runAmiciSimulation, but for multiple ExpData instances.

Parameters

solver	Solver instance
edatas	experimental data objects
model	model specification object
num_threads	number of threads for parallel execution

Returns

vector of pointers to return data objects

Definition at line 146 of file amici.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.5 amici_dgemv()

```
void amici_dgemv (
            BLASLayout layout,
            BLASTranspose TransA,
            const int M,
            const int N,
            const double alpha,
            const double * A,
            const int lda,
            const double * X,
            const int incX,
            const double beta,
            double * Y,
            const int incY )
```

amici_dgemm provides an interface to the blas matrix vector multiplication routine dgemv. This routines computes y = alpha∗A∗x + beta∗y with A: [MxK] B:[KxN] C:[MxN]

Parameters

in	*layout*	can be AMICI_BLAS_ColMajor or AMICI_BLAS_RowMajor.
in	*TransA*	flag indicating whether A should be transposed before multiplication
in	*M*	number of rows in A
in	*N*	number of columns in A
in	*alpha*	coefficient alpha
in	*A*	matrix A
in	*lda*	leading dimension of A (m or n)
in	*X*	vector X
in	*incX*	increment for entries of X
in	*beta*	coefficient beta
in,out	*Y*	vector Y
in	*incY*	increment for entries of Y

amici_dgemm provides an interface to the CBlas matrix vector multiplication routine dgemv. This routines computes y = alpha∗A∗x + beta∗y with A: [MxN] x:[Nx1] y:[Mx1]

Parameters

layout	always needs to be AMICI_BLAS_ColMajor.
TransA	flag indicating whether A should be transposed before multiplication
M	number of rows in A
N	number of columns in A
alpha	coefficient alpha
A	matrix A
lda	leading dimension of A (m or n)
X	vector X
incX	increment for entries of X
beta	coefficient beta
Y	vector Y
incY	increment for entries of Y

Returns

void

Definition at line 73 of file cblas.cpp.

9.1.4.6 amici_dgemm()

```
void amici_dgemm (
            BLASLayout layout,
            BLASTranspose TransA,
            BLASTranspose TransB,
            const int M,
            const int N,
            const int K,
            const double alpha,
```

```
const double * A,
const int lda,
const double * B,
const int ldb,
const double beta,
double * C,
const int ldc )
```

amici_dgemm provides an interface to the blas matrix matrix multiplication routine dgemm. This routines computes C = alpha∗A∗B + beta∗C with A: [MxK] B:[KxN] C:[MxN]

Parameters

in	*layout*	can be AMICI_BLAS_ColMajor or AMICI_BLAS_RowMajor.
in	*TransA*	flag indicating whether A should be transposed before multiplication
in	*TransB*	flag indicating whether B should be transposed before multiplication
in	*M*	number of rows in A/C
in	*N*	number of columns in B/C
in	*K*	number of rows in B, number of columns in A
in	*alpha*	coefficient alpha
in	*A*	matrix A
in	*lda*	leading dimension of A (m or k)
in	*B*	matrix B
in	*ldb*	leading dimension of B (k or n)
in	*beta*	coefficient beta
in,out	*C*	matrix C
in	*ldc*	leading dimension of C (m or n)

amici_dgemm provides an interface to the CBlas matrix matrix multiplication routine dgemm. This routines computes C = alpha∗A∗B + beta∗C with A: [MxK] B:[KxN] C:[MxN]

Parameters

layout	memory layout.
TransA	flag indicating whether A should be transposed before multiplication
TransB	flag indicating whether B should be transposed before multiplication
M	number of rows in A/C
N	number of columns in B/C
K	number of rows in B, number of columns in A
alpha	coefficient alpha
A	matrix A
lda	leading dimension of A (m or k)
B	matrix B
ldb	leading dimension of B (k or n)
beta	coefficient beta
C	matrix C
ldc	leading dimension of C (m or n)

Returns

void

Definition at line 44 of file cblas.cpp.

Here is the caller graph for this function:

9.1.4.7 amici_daxpy()

```
void amici_daxpy (
            int n,
            double alpha,
            const double * x,
            const int incx,
            double * y,
            int incy )
```

Parameters

n	number of elements in y
alpha	scalar coefficient of x
x	vector of length n∗incx
incx	x stride
y	vector of length n∗incy
incy	y stride

Definition at line 90 of file cblas.cpp.

9.1.4.8 checkSigmaPositivity() [1/2]

```
void checkSigmaPositivity (
            std::vector< realtype > const & sigmaVector,
            const char * vectorName )
```

checks input vector of sigmas for not strictly positive values

Parameters

sigmaVector	vector input to be checked
vectorName	name of the input

Definition at line 300 of file edata.cpp.

Here is the caller graph for this function:

9.1.4.9 checkSigmaPositivity() [2/2]

```
void checkSigmaPositivity (
            const realtype sigma,
            const char * sigmaName )
```

checks input scalar sigma for not strictly positive value

Parameters

sigma	input to be checked
sigmaName	name of the input

Definition at line 305 of file edata.cpp.

9.1.4.10 setModelData()

```
void setModelData (
            const mxArray * prhs[],
            int nrhs,
            Model & model )
```

Parameters

in	*prhs*	pointer to the array of input arguments **Type**: mxArray
in	*nrhs*	number of elements in prhs
in,out	*model*	model to update

Definition at line 389 of file interface_matlab.cpp.

Here is the call graph for this function:

9.1.4.11 setSolverOptions()

```
void setSolverOptions (
            const mxArray * prhs[],
            int nrhs,
            Solver & solver )
```

Parameters

in	*prhs*	pointer to the array of input arguments **Type**: mxArray
in	*nrhs*	number of elements in prhs
in,out	*solver*	solver to update

Definition at line 304 of file interface_matlab.cpp.

Here is the call graph for this function:

9.1.4.12 setupReturnData()

```
ReturnDataMatlab* amici::setupReturnData (
            mxArray * plhs[],
            int nlhs )
```

setupReturnData initialises the return data struct

Parameters

in	*plhs*	user input **Type**: mxArray
in	*nlhs*	number of elements in plhs **Type**: mxArray

Returns

rdata: return data struct
Type: ∗ReturnData

9.1.4.13 expDataFromMatlabCall()

```
std::unique_ptr< ExpData > expDataFromMatlabCall (
            const mxArray * prhs[],
            const Model & model )
```

expDataFromMatlabCall initialises the experimental data struct

Parameters

in	*prhs*	user input **Type**: ∗mxArray

Returns

edata: experimental data struct
Type: ∗ExpData

expDataFromMatlabCall parses the experimental data from the matlab call and writes it to an ExpData class object

Parameters

prhs	pointer to the array of input arguments
model	pointer to the model object, this is necessary to perform dimension checks

Returns

edata pointer to experimental data object

Definition at line 179 of file interface_matlab.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.14 checkFinite()

```
int checkFinite (
            const int N,
            const realtype * array,
            const char * fun )
```

Checks the values in an array for NaNs and Infs

Parameters

N	number of elements in array
array	array
fun	name of calling function

Returns

AMICI_RECOVERABLE_ERROR if a NaN/Inf value was found, AMICI_SUCCESS otherwise

Definition at line 17 of file misc.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.15 unscaleParameters() [1/2]

```
void unscaleParameters (
            const double * bufferScaled,
            const ParameterScaling * pscale,
            int n,
            double * bufferUnscaled )
```

Parameters

bufferScaled	scaled parameters
pscale	parameter scaling
n	number of elements in bufferScaled, pscale and bufferUnscaled
bufferUnscaled	unscaled parameters are written to the array

Returns

status flag indicating success of execution
Type: int

Definition at line 46 of file misc.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.16 unscaleParameters() [2/2]

```
void unscaleParameters (
            std::vector< double > const & bufferScaled,
            std::vector< ParameterScaling > const & pscale,
            std::vector< double > & bufferUnscaled )
```

All vectors must be of same length

Parameters

bufferScaled	scaled parameters
pscale	parameter scaling
bufferUnscaled	unscaled parameters are written to the array

Definition at line 54 of file misc.cpp.

Here is the call graph for this function:

9.1.4.17 getUnscaledParameter()

```
double getUnscaledParameter (
            double scaledParameter,
            ParameterScaling scaling )
```

Parameters

scaledParameter	scaled parameter
scaling	parameter scaling

Returns

Unscaled parameter

Definition at line 32 of file misc.cpp.

Here is the caller graph for this function:

9.1.4.18 getScaledParameter()

```
double getScaledParameter (
            double unscaledParameter,
            ParameterScaling scaling )
```

Parameters

unscaledParameter	
scaling	parameter scaling

Returns

Scaled parameter

Definition at line 61 of file misc.cpp.

Here is the caller graph for this function:

9.1.4.19 scaleParameters()

```
void scaleParameters (
            const std::vector< double > & bufferUnscaled,
            const std::vector< ParameterScaling > & pscale,
            std::vector< double > & bufferScaled )
```

Parameters

bufferUnscaled	
pscale	parameter scaling
bufferScaled	destination

Definition at line 76 of file misc.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.20 operator==() [1/2]

```
bool operator== (
            const Model & a,
            const Model & b )
```

Parameters

a	first model instance
b	second model instance

Returns

equality

Definition at line 1432 of file model.cpp.

9.1.4.21 getReturnDataMatlabFromAmiciCall()

```
mxArray * getReturnDataMatlabFromAmiciCall (
            ReturnData const * rdata )
```

generates matlab mxArray from a ReturnData object

Parameters

rdata	ReturnDataObject

Returns

rdatamatlab ReturnDataObject stored as matlab compatible data

generates matlab mxArray from a ReturnData object

Parameters

rdata	ReturnDataObject

Returns

rdatamatlab ReturnDataObject stored as matlab compatible data

Definition at line 7 of file returndata_matlab.cpp.

Here is the call graph for this function:

9.1.4.22 initMatlabReturnFields()

```
mxArray * initMatlabReturnFields (
            ReturnData const * rdata )
```

allocates and initialises solution mxArray with the corresponding fields

Parameters

rdata	ReturnDataObject

Returns

Solution mxArray

allocates and initialises solution mxArray with the corresponding fields

Parameters

rdata	ReturnDataObject

Returns

Solution mxArray

Definition at line 18 of file returndata_matlab.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.23 initMatlabDiagnosisFields()

```
mxArray * initMatlabDiagnosisFields (
            ReturnData const * rdata )
```

allocates and initialises diagnosis mxArray with the corresponding fields

Parameters

rdata	ReturnDataObject

Returns

Diagnosis mxArray

allocates and initialises diagnosis mxArray with the corresponding fields

Parameters

rdata	ReturnDataObject

Returns

Diagnosis mxArray

Definition at line 116 of file returndata_matlab.cpp.

Here is the call graph for this function:

9.1.4.24 writeMatlabField0()

```
void writeMatlabField0 (
            mxArray * matlabStruct,
            const char * fieldName,
            T fieldData )
```

initialise vector and attach to the field

Parameters

matlabStruct	pointer of the field to which the vector will be attached
fieldName	Name of the field to which the vector will be attached
fieldData	Data wich will be stored in the field

initialise vector and attach to the field

Parameters

matlabStruct	pointer of the field to which the vector will be attached
fieldName	Name of the field to which the vector will be attached
fieldData	Data wich will be stored in the field

Definition at line 181 of file returndata_matlab.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.25 writeMatlabField1()

```
void writeMatlabField1 (
            mxArray * matlabStruct,
            const char * fieldName,
            std::vector< T > const & fieldData,
            const int dim0 )
```

initialise vector and attach to the field

Parameters

matlabStruct	pointer of the field to which the vector will be attached
fieldName	Name of the field to which the vector will be attached
fieldData	Data wich will be stored in the field
dim0	Number of elements in the vector

initialise vector and attach to the field

Parameters

matlabStruct	pointer of the field to which the vector will be attached
fieldName	Name of the field to which the vector will be attached
fieldData	Data wich will be stored in the field
dim0	Number of elements in the vector

Definition at line 199 of file returndata_matlab.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.26 writeMatlabField2()

```
void writeMatlabField2 (
            mxArray * matlabStruct,
            const char * fieldName,
            std::vector< T > const & fieldData,
            int dim0,
            int dim1,
            std::vector< int > perm )
```

initialise matrix, attach to the field and write data

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
fieldData	Data wich will be stored in the field
dim0	Number of rows in the tensor
dim1	Number of columns in the tensor
perm	reordering of dimensions (i.e., transposition)

initialise matrix, attach to the field and write data

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
fieldData	Data wich will be stored in the field

Parameters

dim0	Number of rows in the tensor
dim1	Number of columns in the tensor
perm	reordering of dimensions (i.e., transposition)

Definition at line 221 of file returndata_matlab.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.27 writeMatlabField3()

```
void writeMatlabField3 (
            mxArray * matlabStruct,
            const char * fieldName,
            std::vector< T > const & fieldData,
            int dim0,
            int dim1,
            int dim2,
            std::vector< int > perm )
```

initialise 3D tensor, attach to the field and write data

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
fieldData	Data wich will be stored in the field
dim0	number of rows in the tensor
dim1	number of columns in the tensor
dim2	number of elements in the third dimension of the tensor
perm	reordering of dimensions

initialise 3D tensor, attach to the field and write data

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
fieldData	Data wich will be stored in the field
dim0	number of rows in the tensor
dim1	number of columns in the tensor
dim2	number of elements in the third dimension of the tensor
perm	reordering of dimensions

Definition at line 254 of file returndata_matlab.cpp.

Here is the call graph for this function:

9.1.4.28 writeMatlabField4()

```
void writeMatlabField4 (
            mxArray * matlabStruct,
            const char * fieldName,
            std::vector< T > const & fieldData,
            int dim0,
            int dim1,
            int dim2,
            int dim3,
            std::vector< int > perm )
```

initialise 4D tensor, attach to the field and write data

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
fieldData	Data wich will be stored in the field
dim0	number of rows in the tensor
dim1	number of columns in the tensor
dim2	number of elements in the third dimension of the tensor
dim3	number of elements in the fourth dimension of the tensor
perm	reordering of dimensions

initialise 4D tensor, attach to the field and write data

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
fieldData	Data wich will be stored in the field
dim0	number of rows in the tensor
dim1	number of columns in the tensor
dim2	number of elements in the third dimension of the tensor
dim3	number of elements in the fourth dimension of the tensor
perm	reordering of dimensions

Definition at line 290 of file returndata_matlab.cpp.

Here is the call graph for this function:

9.1.4.29 initAndAttachArray()

```
double * initAndAttachArray (
            mxArray * matlabStruct,
            const char * fieldName,
            std::vector< mwSize > dim )
```

initialises the field fieldName in matlabStruct with dimension dim

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
dim	vector of field dimensions

Returns

Pointer to field data

initialises the field fieldName in matlabStruct with dimension dim

Parameters

matlabStruct	Pointer to the matlab structure
fieldName	Name of the field to which the tensor will be attached
dim	vector of field dimensions

Returns

Pointer to field data

Definition at line 328 of file returndata_matlab.cpp.

Here is the caller graph for this function:

9.1.4.30 checkFieldNames()

```
void checkFieldNames (
            const char ** fieldNames,
            const int fieldCount )
```

checks whether fieldNames was properly allocated

Parameters

fieldNames	array of field names
fieldCount	expected number of fields in fieldNames

checks whether fieldNames was properly allocated

Parameters

fieldNames	array of field names
fieldCount	expected number of fields in fieldNames

Definition at line 349 of file returndata_matlab.cpp.

Here is the caller graph for this function:

9.1.4.31 reorder()

```
std::vector< T > reorder (
            std::vector< T > const & input,
            std::vector< int > const & order )
```

template function that reorders elements in a std::vector

Parameters

input	unordered vector
order	dimension permutation

Returns

Reordered vector

template function that reorders elements in a std::vector

Parameters

input	unordered vector
order	dimension permutation

Returns

Reordered vector

Definition at line 362 of file returndata_matlab.cpp.

Here is the caller graph for this function:

9.1.4.32 serializeToChar()

```
char* amici::serializeToChar (
            T const & data,
            int * size )
```

Serialize object to char array

Parameters

data	input object
size	maximum char length

Returns

The object serialized as char

Definition at line 177 of file serialization.h.

9.1.4.33 deserializeFromChar()

```
T amici::deserializeFromChar (
            const char * buffer,
            int size )
```

Deserialize object that has been serialized using serializeToChar

Parameters

buffer	serialized object
size	length of buffer

Returns

The deserialized object

Definition at line 210 of file serialization.h.

9.1.4.34 serializeToString()

```
std::string amici::serializeToString (
            T const & data )
```

Serialize object to string

Parameters

data	input object

Returns

The object serialized as string

Definition at line 235 of file serialization.h.

9.1.4.35 serializeToStdVec()

```
std::vector<char> amici::serializeToStdVec (
            T const & data )
```

Serialize object to std::vector<char>

Parameters

data	input object

Returns

The object serialized as std::vector<char>

Definition at line 261 of file serialization.h.

9.1.4.36 deserializeFromString()

```
T amici::deserializeFromString (
            std::string const & serialized )
```

Deserialize object that has been serialized using serializeToString

Parameters

serialized	serialized object

Returns

The deserialized object

Definition at line 288 of file serialization.h.

9.1.4.37 operator==() [2/2]

```
bool operator== (
            const Solver & a,
            const Solver & b )
```

Parameters

a	
b	

Returns

Definition at line 365 of file solver.cpp.

Here is the call graph for this function:

9.1.4.38 spline() [1/2]

```
int spline (
            int n,
            int end1,
            int end2,
            double slope1,
            double slope2,
            double x[],
            double y[],
            double b[],
            double c[],
            double d[] )
```

Evaluate the coefficients b[i], c[i], d[i], i = 0, 1, .. n-1 for a cubic interpolating spline

S(xx) = Y[i] + b[i] ∗ w + c[i] ∗ w∗∗2 + d[i] ∗ w∗∗3 where w = xx - x[i] and x[i] <= xx <= x[i+1]

The n supplied data points are x[i], y[i], i = 0 ... n-1.

Parameters

in	*n*	The number of data points or knots (n >= 2)
in	*end1*	0: default condition 1: specify the slopes at x[0]
in	*end2*	0: default condition 1: specify the slopes at x[n-1]
in	*slope1*	slope at x[0]
in	*slope2*	slope at x[n-1]
in	*x[]*	the abscissas of the knots in strictly increasing order
in	*y[]*	the ordinates of the knots
out	*b[]*	array of spline coefficients
out	*c[]*	array of spline coefficients
out	*d[]*	array of spline coefficients

Return values

0	normal return
1	less than two data points; cannot interpolate
2	x[] are not in ascending order

Notes

- The accompanying function seval() may be used to evaluate the spline while deriv will provide the first derivative.
- Using p to denote differentiation y[i] = S(X[i]) b[i] = Sp(X[i]) c[i] = Spp(X[i])/2 d[i] = Sppp(X[i])/6 (Derivative from the right)
- Since the zero elements of the arrays ARE NOW used here, all arrays to be passed from the main program should be dimensioned at least [n]. These routines will use elements [0 .. n-1].
- Adapted from the text Forsythe, G.E., Malcolm, M.A. and Moler, C.B. (1977) "Computer Methods for Mathematical Computations" Prentice Hall
- Note that although there are only n-1 polynomial segments, n elements are requird in b, c, d. The elements b[n-1], c[n-1] and d[n-1] are set to continue the last segment past x[n-1].

Definition at line 16 of file spline.cpp.

Here is the caller graph for this function:

9.1.4.39 seval()

```
double seval (
            int n,
            double u,
            double x[],
            double y[],
            double b[],
            double c[],
            double d[] )
```

S(xx) = y[i] + b[i] ∗ w + c[i] ∗ w∗∗2 + d[i] ∗ w∗∗3 where w = u - x[i] and x[i] <= u <= x[i+1] Note that Horner's rule is used. If u < x[0] then i = 0 is used. If u > x[n-1] then i = n-1 is used.

Parameters

in	*n*	The number of data points or knots (n >= 2)
in	*u*	the abscissa at which the spline is to be evaluated
in	*x[]*	the abscissas of the knots in strictly increasing order
in	*y[]*	the ordinates of the knots
in	*b*	array of spline coefficients computed by spline().
in	*c*	array of spline coefficients computed by spline().
in	*d*	array of spline coefficients computed by spline().

Returns

the value of the spline function at u

Notes

- If u is not in the same interval as the previous call then a binary search is performed to determine the proper interval.

Definition at line 195 of file spline.cpp.

Here is the caller graph for this function:

9.1.4.40 sinteg()

```
double sinteg (
            int n,
            double u,
            double x[],
            double y[],
            double b[],
            double c[],
            double d[] )
```

Integrate the cubic spline function

S(xx) = y[i] + b[i] ∗ w + c[i] ∗ w∗∗2 + d[i] ∗ w∗∗3 where w = u - x[i] and x[i] <= u <= x[i+1]

The integral is zero at u = x[0].

If u < x[0] then i = 0 segment is extrapolated. If u > x[n-1] then i = n-1 segment is extrapolated.

Parameters

in	*n*	the number of data points or knots (n >= 2)
in	*u*	the abscissa at which the spline is to be evaluated
in	*x[]*	the abscissas of the knots in strictly increasing order
in	*y[]*	the ordinates of the knots
in	*b*	array of spline coefficients computed by spline().
in	*c*	array of spline coefficients computed by spline().
in	*d*	array of spline coefficients computed by spline().

Returns

the value of the spline function at u

Notes

- If u is not in the same interval as the previous call then a binary search is performed to determine the proper interval.

Definition at line 256 of file spline.cpp.

9.1.4.41 log()

```
double log (
            double x )
```

c implementation of log function, this prevents returning NaN values for negative values

Parameters

x	argument

Returns

if(x>0) then log(x) else -Inf

Definition at line 62 of file symbolic_functions.cpp.

Here is the caller graph for this function:

9.1.4.42 dirac()

```
double dirac (
            double x )
```

c implementation of matlab function dirac

Parameters

x	argument

Returns

if(x==0) then INF else 0

Definition at line 77 of file symbolic_functions.cpp.

9.1.4.43 heaviside()

```
double heaviside (
            double x )
```

c implementation of matlab function heaviside

Parameters

x	argument

Returns

if(x>0) then 1 else 0

Definition at line 92 of file symbolic_functions.cpp.

9.1.4.44 min()

```
double min (
            double a,
            double b,
            double c )
```

c implementation of matlab function min

Parameters

a	value1
b	value2
c	bogus parameter to ensure correct parsing as a function

Returns

if(a < b) then a else b

Definition at line 149 of file symbolic_functions.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.45 Dmin()

```
double Dmin (
            int id,
            double a,
            double b,
            double c )
```

parameter derivative of c implementation of matlab function max

Parameters

id	argument index for differentiation
a	value1
b	value2
c	bogus parameter to ensure correct parsing as a function

Returns

id == 1: if(a > b) then 1 else 0
id == 2: if(a > b) then 0 else 1

Definition at line 191 of file symbolic_functions.cpp.

Here is the call graph for this function:

9.1.4.46 max()

```
double max (
            double a,
            double b,
            double c )
```

c implementation of matlab function max

Parameters

a	value1
b	value2
c	bogus parameter to ensure correct parsing as a function

Returns

if(a > b) then a else b

Definition at line 128 of file symbolic_functions.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.47 Dmax()

```
double Dmax (
            int id,
            double a,
            double b,
            double c )
```

parameter derivative of c implementation of matlab function max

Parameters

id	argument index for differentiation
a	value1
b	value2
c	bogus parameter to ensure correct parsing as a function

Returns

id == 1: if(a > b) then 1 else 0
id == 2: if(a > b) then 0 else 1

Definition at line 164 of file symbolic_functions.cpp.

Here is the caller graph for this function:

9.1.4.48 pos_pow()

```
double pos_pow (
            double base,
            double exponent )
```

specialized pow functions that assumes positivity of the first argument

Parameters

base	base
exponent	exponent

Returns

pow(max(base,0.0),exponen)

Definition at line 203 of file symbolic_functions.cpp.

9.1.4.49 isNaN()

```
int isNaN (
            double what )
```

c++ interface to the isNaN function

Parameters

what	argument

Returns

isnan(what)

Definition at line 35 of file symbolic_functions.cpp.

Here is the caller graph for this function:

9.1.4.50 isInf()

```
int isInf (
            double what )
```

c++ interface to the isinf function

Parameters

what	argument

Returns

isnan(what)

Definition at line 44 of file symbolic_functions.cpp.

Here is the caller graph for this function:

9.1.4.51 getNaN()

```
double getNaN ( )
```

function returning nan

Returns

NaN

Definition at line 52 of file symbolic_functions.cpp.

Here is the caller graph for this function:

9.1.4.52 sign()

```
double sign (
            double x )
```

c implementation of matlab function sign

Parameters

x	argument

Returns

0

Definition at line 107 of file symbolic_functions.cpp.

9.1.4.53 spline() [2/2]

```
double spline (
            double t,
            int num,
             ...  )
```

spline function, takes variable argument pairs (ti,pi) with `ti`: location of node i and `pi`: spline value at node i. the last two arguments are always `ss`: flag indicating whether slope at first node should be user defined and `dudt` user defined slope at first node. All arguments must be of type double.

Parameters

t	point at which the spline should be evaluated
num	number of spline nodes

Returns

spline(t)

Definition at line 222 of file symbolic_functions.cpp.

Here is the call graph for this function:

9.1.4.54 spline_pos()

```
double spline_pos (
            double t,
            int num,
             ...  )
```

exponentiated spline function, takes variable argument pairs (ti,pi) with `ti`: location of node i and `pi`: spline value at node i. the last two arguments are always `ss`: flag indicating whether slope at first node should be user defined and `dudt` user defined slope at first node. All arguments must be of type double.

Parameters

t	point at which the spline should be evaluated
num	number of spline nodes

Returns

spline(t)

Definition at line 273 of file symbolic_functions.cpp.

Here is the call graph for this function:

9.1.4.55 Dspline()

```
double Dspline (
            int id,
            double t,
            int num,
             ...  )
```

derivation of a spline function, takes variable argument pairs (ti,pi) with `ti`: location of node i and `pi`: spline value at node i. the last two arguments are always `ss`: flag indicating whether slope at first node should be user defined and `dudt` user defined slope at first node. All arguments but id must be of type double.

Parameters

id	index of node to which the derivative of the corresponding spline coefficient should be computed
t	point at which the spline should be evaluated
num	number of spline nodes

Returns

dsplinedp(t)

Definition at line 326 of file symbolic_functions.cpp.

Here is the call graph for this function:

9.1.4.56 Dspline_pos()

```
double Dspline_pos (
            int id,
            double t,
            int num,
             ...  )
```

derivation of an exponentiated spline function, takes variable argument pairs (ti,pi) with `ti`: location of node i and `pi`: spline value at node i. the last two arguments are always `ss`: flag indicating whether slope at first node should be user defined and `dudt` user defined slope at first node. All arguments but id must be of type double.

Parameters

id	index of node to which the derivative of the corresponding spline coefficient should be computed
t	point at which the spline should be evaluated
num	number of spline nodes

Returns

dsplinedp(t)

Definition at line 382 of file symbolic_functions.cpp.

Here is the call graph for this function:

9.1.4.57 DDspline()

```
double DDspline (
            int id1,
            int id2,
            double t,
            int num,
             ...  )
```

second derivation of a spline function, takes variable argument pairs (ti,pi) with `ti`: location of node i and `pi`: spline value at node i. the last two arguments are always `ss`: flag indicating whether slope at first node should be user defined and `dudt` user defined slope at first node. All arguments but id1 and id2 must be of type double.

Parameters

id1	index of node to which the first derivative of the corresponding spline coefficient should be computed
id2	index of node to which the second derivative of the corresponding spline coefficient should be computed
t	point at which the spline should be evaluated
num	number of spline nodes

Returns

ddspline(t)

Definition at line 448 of file symbolic_functions.cpp.

9.1.4.58 DDspline_pos()

```
double DDspline_pos (
            int id1,
```

```
            int id2,
            double t,
            int num,
             ...  )
```

derivation of an exponentiated spline function, takes variable argument pairs (ti,pi) with `ti`: location of node i and `pi`: spline value at node i. the last two arguments are always `ss`: flag indicating whether slope at first node should be user defined and `dudt` user defined slope at first node. All arguments but id1 and id2 must be of type double.

Parameters

id1	index of node to which the first derivative of the corresponding spline coefficient should be computed
id2	index of node to which the second derivative of the corresponding spline coefficient should be computed
t	point at which the spline should be evaluated
num	number of spline nodes

Returns

ddspline(t)

Definition at line 468 of file symbolic_functions.cpp.

Here is the call graph for this function:

9.1.4.59 runAmiciSimulation() [2/2]

```
def amici.runAmiciSimulation (
              model,
              solver,
              edata = None )
```

Parameters

model	Model instance
solver	Solver instance, must be generated from Model.getSolver()
edata	ExpData instance (optional)

Returns

ReturnData object with simulation results

Definition at line 116 of file __init__.py.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.60 ExpData()

```
def amici.ExpData (
            * args )
```

Parameters

args	arguments

Returns

ExpData Instance

Definition at line 135 of file __init__.py.

Here is the caller graph for this function:

9.1.4.61 runAmiciSimulations() [2/2]

```
def amici.runAmiciSimulations (
              model,
              solver,
              edata_list,
              num_threads = 1 )
```

Parameters

model	Model instance
solver	Solver instance, must be generated from Model.getSolver()
edata_list	list of ExpData instances
num_threads	number of threads to use (only used if compiled with openmp)

Returns

list of ReturnData objects with simulation results

Definition at line 163 of file __init__.py.

Here is the call graph for this function:

Here is the caller graph for this function:

9.1.4.62 dbl2int()

```
int dbl2int (
            const double x )
```

conversion from double to int with checking for loss of data

Parameters

x	input

Returns

int_x casted value

Definition at line 298 of file interface_matlab.cpp.

Here is the caller graph for this function:

9.1.4.63 amici_blasCBlasTransToBlasTrans()

```
char amici::amici_blasCBlasTransToBlasTrans (
            BLASTranspose trans )
```

amici_blasCBlasTransToBlasTrans translates AMICI_BLAS_TRANSPOSE values to CBlas readable strings

Parameters

trans	flag indicating transposition and complex conjugation

Returns

cblastrans CBlas readable CHAR indicating transposition and complex conjugation

Definition at line 52 of file interface_matlab.cpp.

9.1.4.64 mxArrayToVector()

```
std::vector<realtype> amici::mxArrayToVector (
            const mxArray * array,
            int length )
```

conversion from mxArray to vector<realtype>

Parameters

array	Matlab array to create vector from
length	Number of elements in array

Returns

std::vector with data from array

Definition at line 166 of file interface_matlab.cpp.

Here is the caller graph for this function:

9.1.4.65 getValueById()

```
realtype amici::getValueById (
            std::vector< std::string > const & ids,
            std::vector< realtype > const & values,
            std::string const & id,
            const char * variable_name,
            const char * id_name )
```

Parameters

ids	vector of name/ids of (fixed)Parameters
values	values of the (fixed)Parameters
id	name/id to look for in the vector
variable_name	string indicating what variable we are lookin at
id_name	string indicating whether name or id was specified

Returns

value of the selected parameter

Definition at line 347 of file model.cpp.

Here is the caller graph for this function:

9.1.4.66 setValueById()

```
void amici::setValueById (
            std::vector< std::string > const & ids,
            std::vector< realtype > & values,
            realtype value,
            std::string const & id,
            const char * variable_name,
            const char * id_name )
```

Parameters

ids	vector of names/ids of (fixed)Parameters
values	values of the (fixed)Parameters
value	for the selected parameter
id	name/id to look for in the vector
variable_name	string indicating what variable we are lookin at
id_name	string indicating whether name or id was specified

Definition at line 365 of file model.cpp.

Here is the caller graph for this function:

9.1.4.67 setValueByIdRegex()

```
int amici::setValueByIdRegex (
            std::vector< std::string > const & ids,
            std::vector< realtype > & values,
            realtype value,
            std::string const & regex,
            const char * variable_name,
            const char * id_name )
```

Parameters

ids	vector of names/ids of (fixed)Parameters
values	values of the (fixed)Parameters
value	for the selected parameter
regex	string according to which names/ids are to be matched
variable_name	string indicating what variable we are lookin at
id_name	string indicating whether name or id was specified

Returns

number of matched names/ids

Definition at line 384 of file model.cpp.

Here is the caller graph for this function:

9.1.5 Variable Documentation

9.1.5.1 errMsgIdAndTxt

```
msgIdAndTxtFp errMsgIdAndTxt = &printErrMsgIdAndTxt
```

errMsgIdAndTxt is a function pointer for printErrMsgIdAndTxt

Definition at line 37 of file amici.cpp.

9.1.5.2 warnMsgIdAndTxt

```
msgIdAndTxtFp warnMsgIdAndTxt = &printWarnMsgIdAndTxt
```

warnMsgIdAndTxt is a function pointer for printWarnMsgIdAndTxt

Definition at line 13 of file model_dae.h.

9.1.5.3 pi

```
constexpr double pi = 3.14159265358979323846
```

MS definition of PI and other constants

Definition at line 13 of file defines.h.

9.1.5.4 amici_path

```
amici_path
```

Initial value:

```
os.path.abspath(os.path.join(
        os.path.dirname(__file__), '..', '..'))
```

Definition at line 56 of file __init__.py.

9.2 amici.ode_export Namespace Reference

The C++ ODE export module for python.

Classes

- class ConservationLaw

  A conservation law defines the absolute the total amount of a (weighted) sum of states.
- class Constant

  A Constant is a fixed variable in the model with respect to which sensitivites cannot be computed, abbreviated by k
- class Expression

  An Expressions is a recurring elements in symbolic formulas.
- class LogLikelihood

  A LogLikelihood defines the distance between measurements and experiments for a particular observable.
- class ModelQuantity

  Base class for model components.
- class Observable

  An Observable links model simulations to experimental measurements, abbreviated by y
- class ODEExporter

  The ODEExporter class generates AMICI C++ files for ODE model as defined in symbolic expressions.
- class ODEModel

  An ODEModel defines an Ordinay Differential Equation as set of ModelQuantities.
- class Parameter

  A Parameter is a free variable in the model with respect to which sensitivites may be computed, abbreviated by p
- class SigmaY

  A Standard Deviation SigmaY rescales the distance between simulations and measurements when computing residuals, abbreviated by `sigmay`
- class State

  A State variable defines an entity that evolves with time according to the provided time derivative, abbreviated by x
- class TemplateAmici

  Template format used in AMICI (see string.template for more details).

Functions

- def var_in_function_signature (name, varname)

  Checks if the values for a symbolic variable is passed in the signature of a function.
- def getSymbolicDiagonal (matrix)

  Get symbolic matrix with diagonal of matrix `matrix`*.*
- def applyTemplate (sourceFile, targetFile, templateData)

  Load source file, apply template substitution as provided in templateData and save as targetFile.
- def sanitize_basic_sympy (basic)

  Strips pysb info from the sympy.Basic object.
- def get_function_definition (fun, name)

  Constructs the function definition for a given function.
- def get_function_implementation (fun, name)

  Constructs the function implementation for a given function.
- def remove_typedefs (signature)

  Strips typedef info from a function signature.

Variables

- pysb = None

  pysb import dummy
- dictionary functions

  prototype for generated C++ functions, keys are the names of functions
- list sparse_functions

  list of sparse functions
- list sensi_functions

  list of sensitivity functions
- list multiobs_functions

  list of multiobs functions
- dictionary symbol_to_type

  indicates which type some attributes in ODEModel should have

9.2.1 Detailed Description

!/usr/bin/env python3

9.2.2 Function Documentation

9.2.2.1 var_in_function_signature()

```
def amici.ode_export.var_in_function_signature (
            name,
            varname )
```

Parameters

name	name of the function **Type**: str
varname	name of the symbolic variable **Type**: str

Returns

Definition at line 290 of file ode_export.py.

Here is the caller graph for this function:

9.2.2.2 getSymbolicDiagonal()

```
def amici.ode_export.getSymbolicDiagonal (
              matrix )
```

Parameters

matrix	Matrix from which to return the diagonal **Type**: symengine.DenseMatrix

Returns

A Symbolic matrix with the diagonal of `matrix`.

Exceptions

Exception	The provided matrix was not square

Definition at line 2639 of file ode_export.py.

Here is the caller graph for this function:

9.2.2.3 applyTemplate()

```
def amici.ode_export.applyTemplate (
            sourceFile,
            targetFile,
            templateData )
```

Parameters

sourceFile	relative or absolute path to template file **Type**: str
targetFile	relative or absolute path to output file **Type**: str
templateData	template keywords to substitute (key is template variable without TemplateAmici.delimiter) **Type**: dict

Returns

Definition at line 2675 of file ode_export.py.

Here is the caller graph for this function:

9.2.2.4 sanitize_basic_sympy()

```
def amici.ode_export.sanitize_basic_sympy (
            basic )
```

Parameters

basic	symbolic expression **Type**: sympy.Basic

Returns

sanitized sympy.Basic

Definition at line 2694 of file ode_export.py.

Here is the caller graph for this function:

9.2.2.5 get_function_definition()

```
def amici.ode_export.get_function_definition (
            fun,
            name )
```

Parameters

fun	function name **Type**: str
name	model name **Type**: str

Returns

c++ function definition string

Definition at line 2731 of file ode_export.py.

Here is the caller graph for this function:

9.2.2.6 get_function_implementation()

```
def amici.ode_export.get_function_implementation (
              fun,
              name )
```

Parameters

fun	function name **Type**: str
name	model name **Type**: str

Returns

c++ function implementation string

Definition at line 2748 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

9.2.2.7 remove_typedefs()

```
def amici.ode_export.remove_typedefs (
              signature )
```

Parameters

signature	function signature **Type**: str

Returns

string that can be used to construct function calls with the same variable names and ordering as in the function signature

Definition at line 2774 of file ode_export.py.

Here is the caller graph for this function:

9.2.3 Variable Documentation

9.2.3.1 functions

```
dictionary functions
```

signature: defines the argument part of the function signature, input variables should have a const flag

assume_pow_positivity: identifies the functions on which assume_pow_positivity will have an effect when specified during model generation. generally these are functions that are used for solving the ODE, where negative values may negatively affect convergence of the integration algorithm

sparse: specifies whether the result of this function will be stored in sparse format. sparse format means that the function will only return an array of nonzero values and not a full matrix.

Definition at line 43 of file ode_export.py.

9.2.3.2 sparse_functions

```
list sparse_functions
```

Initial value:

```
1 =  [
2     function for function in functions
3     if 'sparse' in functions[function]
4     and functions[function]['sparse']
5 ]
```

Definition at line 259 of file ode_export.py.

9.2.3.3 sensi_functions

```
list sensi_functions
```

Initial value:

```
1 =  [
2     function for function in functions
3     if 'const int ip' in functions[function]['signature']
4     and function is not 'sxdot'
5 ]
```

Definition at line 265 of file ode_export.py.

9.2.3.4 multiobs_functions

```
list multiobs_functions
```

Initial value:

```
1 =  [
2     function for function in functions
3     if 'const int iy' in functions[function]['signature']
4 ]
```

Definition at line 271 of file ode_export.py.

9.2.3.5 symbol_to_type

```
dictionary symbol_to_type
```

Initial value:

```
1 =  {
2     'species': State,
3     'parameter': Parameter,
4     'fixed_parameter': Constant,
5     'observable': Observable,
6     'sigmay': SigmaY,
7     'llhy': LogLikelihood,
8     'expression': Expression,
9 }
```

Definition at line 689 of file ode_export.py.

9.3 amici.plotting Namespace Reference

Plotting related functions.

Functions

- def plotStateTrajectories (rdata, state_indices=None, ax=None)

  Plot state trajectories.
- def plotObservableTrajectories (rdata, observable_indices=None, ax=None)

  Plot observable trajectories.

9.3.1 Function Documentation

9.3.1.1 plotStateTrajectories()

```
def amici.plotting.plotStateTrajectories (
            rdata,
            state_indices = None,
            ax = None )
```

Parameters

rdata	AMICI simulation results as returned by amici.getSimulationResults()
state_indices	Indices of states for which trajectories are to be plotted
ax	matplotlib.axes.Axes instance to plot into

Returns

Definition at line 17 of file plotting.py.

9.3.1.2 plotObservableTrajectories()

```
def amici.plotting.plotObservableTrajectories (
            rdata,
            observable_indices = None,
            ax = None )
```

Parameters

rdata	AMICI simulation results as returned by amici.getSimulationResults()
observable_indices	Indices of observables for which trajectories are to be plotted
ax	matplotlib.axes.Axes instance to plot into

Returns

Definition at line 42 of file plotting.py.

9.4 amici.sbml_import Namespace Reference

The python sbml import module for python.

Classes

- class SBMLException
- class SbmlImporter

  The SbmlImporter class generates AMICI C++ files for a model provided in the Systems Biology Markup Language (SBML).

Functions

- def getRuleVars (rules)

  Extract free symbols in SBML rule formulas.
- def assignmentRules2observables (sbml_model, filter_function=lambda ∗_:True)

  Turn assignment rules into observables.
- def constantSpeciesToParameters (sbml_model)

  Convert constant species in the SBML model to constant parameters.
- def replaceLogAB (x)

  Replace log(a, b) in the given string by ln(b)/ln(a)
- def l2s (inputs)

  transforms an list into list of strings
- def checkLibSBMLErrors (sbml_doc, show_warnings=False)

  Checks the error log in the current self.sbml_doc.

Variables

- dictionary default_symbols

  default dict for symbols

9.4.1 Function Documentation

9.4.1.1 getRuleVars()

```
def amici.sbml_import.getRuleVars (
            rules )
```

Parameters

rules	sbml definitions of rules **Type**: list

Returns

Tuple of free symbolic variables in the formulas all provided rules

Definition at line 977 of file sbml_import.py.

Here is the caller graph for this function:

9.4.1.2 assignmentRules2observables()

```
def amici.sbml_import.assignmentRules2observables (
            sbml_model,
            filter_function = lambda *_: True )
```

Parameters

sbml_model	an sbml Model instance
filter_function	callback function taking assignment variable as input and returning True/False to indicate if the respective rule should be turned into an observable

Returns

A dictionary(observableId:{ 'name': observableName, 'formula': formulaString })

Definition at line 1002 of file sbml_import.py.

9.4.1.3 constantSpeciesToParameters()

```
def amici.sbml_import.constantSpeciesToParameters (
            sbml_model )
```

Parameters

sbml_model	libsbml model instance

Returns

species IDs that have been turned into constants

Definition at line 1034 of file sbml_import.py.

9.4.1.4 replaceLogAB()

```
def amici.sbml_import.replaceLogAB (
              x )
```

Works for nested parentheses and nested 'log's. This can be used to circumvent the incompatible argument order between symengine (log(x, basis)) and libsbml (log(basis, x)).

Parameters

x	string to replace **Type**: str

Returns

string with replaced 'log's

Definition at line 1082 of file sbml_import.py.

Here is the caller graph for this function:

9.4.1.5 l2s()

```
def amici.sbml_import.l2s (
              inputs )
```

Parameters

inputs	objects **Type**: list

Returns

list of str(object)

Definition at line 1128 of file sbml_import.py.

Here is the caller graph for this function:

9.4.1.6 checkLibSBMLErrors()

```
def amici.sbml_import.checkLibSBMLErrors (
              sbml_doc,
              show_warnings = False )
```

Parameters

sbml_doc	SBML document **Type**: libsbml.SBMLDocument
show_warnings	display SBML warnings **Type**: bool

Returns

```
raises SBMLException if errors with severity ERROR or FATAL have
```

Exceptions

occurred	

Definition at line 1144 of file sbml_import.py.

9.4.2 Variable Documentation

9.4.2.1 default_symbols

```
dictionary default_symbols
```

Initial value:

```
1 =  {
2     'species': {},
3     'parameter': {},
```

```
    'fixed_parameter': {},
    'observable': {},
    'expression': {},
    'sigmay': {},
    'my': {},
    'llhy': {},
}
```

Definition at line 17 of file sbml_import.py.

10 Class Documentation

10.1 AmiException Class Reference

amici exception handler class

`#include <exception.h>`

Inheritance diagram for AmiException:

Public Member Functions

- AmiException (char const ∗fmt,...)
- AmiException (const AmiException &old)
- const char ∗ what () const throw ()
- const char ∗ getBacktrace () const
- void storeBacktrace (const int nMaxFrames)

10.1.1 Detailed Description

has a printf style interface to allow easy generation of error messages

Definition at line 29 of file exception.h.

10.1.2 Constructor & Destructor Documentation

10.1.2.1 AmiException() [1/2]

```
AmiException (
            char const * fmt,
             ...  )
```

constructor with printf style interface

Parameters

fmt	error message with printf format
...	printf formating variables

Definition at line 31 of file exception.h.

Here is the call graph for this function:

10.1.2.2 AmiException() [2/2]

```
AmiException (
            const AmiException & old )
```

copy constructor

Parameters

old	object to copy from

Definition at line 43 of file exception.h.

10.1.3 Member Function Documentation

10.1.3.1 what()

```
const char* what ( ) const throw ( )
```

override of default error message function

Returns

msg error message

Definition at line 54 of file exception.h.

Here is the caller graph for this function:

10.1.3.2 getBacktrace()

```
const char* getBacktrace ( ) const
```

returns the stored backtrace

Returns

trace backtrace

Definition at line 61 of file exception.h.

Here is the caller graph for this function:

10.1.3.3 storeBacktrace()

```
void storeBacktrace (
            const int nMaxFrames )
```

stores the current backtrace

Parameters

nMaxFrames	number of frams to go back in stacktrace

Definition at line 68 of file exception.h.

Here is the caller graph for this function:

10.2 AmiVector Class Reference

```
#include <vector.h>
```

Public Member Functions

- AmiVector (const long int length)
- AmiVector (std::vector< realtype > rvec)
- AmiVector (const AmiVector &vold)
- AmiVector & operator= (AmiVector const &other)
- realtype * data ()
- const realtype * data () const
- N_Vector getNVector () const
- std::vector< realtype > const & getVector () const
- int getLength () const
- void reset ()
- void minus ()
- void set (realtype val)
- realtype & operator[ ] (int pos)
- realtype & at (int pos)
- const realtype & at (int pos) const

10.2.1 Detailed Description

AmiVector class provides a generic interface to the NVector_Serial struct

Definition at line 12 of file vector.h.

10.2.2 Constructor & Destructor Documentation

10.2.2.1 AmiVector() [1/3]

```
AmiVector (
            const long int length ) [explicit]
```

Creates an std::vector<realtype> and attaches the data pointer to a newly created N_Vector_Serial. Using N↩_VMake_Serial ensures that the N_Vector module does not try to deallocate the data vector when calling N_V↩Destroy_Serial

Parameters

length	number of elements in vector

Returns

new AmiVector instance

Definition at line 24 of file vector.h.

10.2.2.2 AmiVector() [2/3]

```
AmiVector (
            std::vector< realtype > rvec )  [explicit]
```

constructor from std::vector, copies data from std::vector and constructs an nvec that points to the data

Parameters

rvec	vector from which the data will be copied

Returns

new AmiVector instance

Definition at line 35 of file vector.h.

10.2.2.3 AmiVector() [3/3]

```
AmiVector (
            const AmiVector & vold )
```

copy constructor

Parameters

vold	vector from which the data will be copied

Definition at line 44 of file vector.h.

10.2.3 Member Function Documentation

10.2.3.1 operator=()

```
AmiVector& operator= (
            AmiVector const & other )
```

copy-move assignment operator

Parameters

other	right hand side

Returns

left hand side

Definition at line 52 of file vector.h.

10.2.3.2 data() [1/2]

```
realtype* data ( )
```

data accessor

Returns

pointer to data array

Definition at line 63 of file vector.h.

Here is the caller graph for this function:

10.2.3.3 data() [2/2]

```
const realtype* data ( ) const
```

const data accessor

Returns

const pointer to data array

Definition at line 70 of file vector.h.

10.2.3.4 getNVector()

```
N_Vector getNVector ( ) const
```

N_Vector accessor

Returns

N_Vector

Definition at line 77 of file vector.h.

Here is the caller graph for this function:

10.2.3.5 getVector()

```
std::vector<realtype> const& getVector ( ) const
```

Vector accessor

Returns

Vector

Definition at line 84 of file vector.h.

10.2.3.6 getLength()

```
int getLength ( ) const
```

returns the length of the vector

Returns

length

Definition at line 91 of file vector.h.

Here is the caller graph for this function:

10.2.3.7 reset()

```
void reset ( )
```

resets the Vector by filling with zero values

Definition at line 97 of file vector.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.2.3.8 minus()

```
void minus ( )
```

changes the sign of data elements

Definition at line 103 of file vector.h.

Here is the caller graph for this function:

10.2.3.9 set()

```
void set (
            realtype val )
```

sets all data elements to a specific value

Parameters

val	value for data elements

Definition at line 112 of file vector.h.

Here is the caller graph for this function:

10.2.3.10 operator[]()

```
realtype& operator[] (
            int pos )
```

accessor to data elements of the vector

Parameters

pos	index of element

Returns

element

Definition at line 120 of file vector.h.

10.2.3.11 at() [1/2]

```
realtype& at (
            int pos )
```

accessor to data elements of the vector

Parameters

pos	index of element

Returns

element

Definition at line 128 of file vector.h.

Here is the caller graph for this function:

10.2.3.12 at() [2/2]

```
const realtype& at (
            int pos ) const
```

accessor to data elements of the vector

Parameters

pos	index of element

Returns

element

Definition at line 136 of file vector.h.

10.3 AmiVectorArray Class Reference

```
#include <vector.h>
```

Public Member Functions

- AmiVectorArray (long int length_inner, long int length_outer)
- AmiVectorArray (const AmiVectorArray &vaold)
- realtype ∗ data (int pos)
- const realtype ∗ data (int pos) const
- realtype & at (int ipos, int jpos)
- const realtype & at (int ipos, int jpos) const
- N_Vector ∗ getNVectorArray ()
- N_Vector getNVector (int pos)
- AmiVector & operator[ ] (int pos)
- const AmiVector & operator[ ] (int pos) const
- int getLength () const
- void reset ()
- void flatten_to_vector (std::vector< realtype > &vec) const

10.3.1 Detailed Description

AmiVectorArray class. provides a generic interface to arrays of NVector_Serial structs

Definition at line 156 of file vector.h.

10.3.2 Constructor & Destructor Documentation

10.3.2.1 AmiVectorArray() [1/2]

```
AmiVectorArray (
            long int length_inner,
            long int length_outer )
```

creates an std::vector<realype> and attaches the data pointer to a newly created N_VectorArray using Clone↩ VectorArrayEmpty ensures that the N_Vector module does not try to deallocate the data vector when calling N_V↩ DestroyVectorArray_Serial

Parameters

length_inner	length of vectors
length_outer	number of vectors

Returns

New AmiVectorArray instance

Definition at line 167 of file vector.h.

10.3.2.2 AmiVectorArray() [2/2]

```
AmiVectorArray (
            const AmiVectorArray & vaold )
```

copy constructor

Parameters

vaold	object to copy from

Returns

new AmiVectorArray instance

Definition at line 181 of file vector.h.

Here is the call graph for this function:

10.3.3 Member Function Documentation

10.3.3.1 data() [1/2]

```
realtype* data (
            int pos )
```

accessor to data of AmiVector elements

Parameters

pos	index of AmiVector

Returns

pointer to data array

Definition at line 192 of file vector.h.

Here is the caller graph for this function:

10.3.3.2 data() [2/2]

```
const realtype* data (
            int pos ) const
```

const accessor to data of AmiVector elements

Parameters

pos	index of AmiVector

Returns

const pointer to data array

Definition at line 200 of file vector.h.

10.3.3.3 at() [1/2]

```
realtype& at (
            int ipos,
            int jpos )
```

accessor to elements of AmiVector elements

Parameters

ipos	inner index in AmiVector
jpos	outer index in AmiVectorArray

Returns

element

Definition at line 209 of file vector.h.

Here is the caller graph for this function:

10.3.3.4 at() [2/2]

```
const realtype& at (
            int ipos,
            int jpos ) const
```

accessor to elements of AmiVector elements

Parameters

ipos	inner index in AmiVector
jpos	outer index in AmiVectorArray

Returns

element

Definition at line 218 of file vector.h.

10.3.3.5 getNVectorArray()

```
N_Vector* getNVectorArray ( )
```

accessor to NVectorArray

Returns

N_VectorArray

Definition at line 225 of file vector.h.

10.3.3.6 getNVector()

```
N_Vector getNVector (
            int pos )
```

accessor to NVector element

Parameters

pos	index of corresponding AmiVector

Returns

N_Vector

Definition at line 233 of file vector.h.

10.3.3.7 operator[]() [1/2]

```
AmiVector& operator[] (
            int pos )
```

accessor to AmiVector elements

Parameters

pos	index of AmiVector

Returns

AmiVector

Definition at line 241 of file vector.h.

10.3.3.8 operator[]() [2/2]

```
const AmiVector& operator[] (
            int pos ) const
```

const accessor to AmiVector elements

Parameters

pos	index of AmiVector

Returns

const AmiVector

Definition at line 249 of file vector.h.

10.3.3.9 getLength()

```
int getLength ( ) const
```

length of AmiVectorArray

Returns

length

Definition at line 256 of file vector.h.

Here is the caller graph for this function:

10.3.3.10 reset()

```
void reset ( )
```

resets every AmiVector in AmiVectorArray

Definition at line 261 of file vector.h.

10.3.3.11 flatten_to_vector()

```
void flatten_to_vector (
            std::vector< realtype > & vec ) const
```

flattens the AmiVectorArray to a vector in row-major format

Parameters

vec	vector into which the AmiVectorArray will be flattened. Must have length equal to number of elements.

Definition at line 270 of file vector.h.

Here is the call graph for this function:

10.4 BackwardProblem Class Reference

class to solve backwards problems.

```
#include <backwardproblem.h>
```

Public Member Functions

- void workBackwardProblem ()
- BackwardProblem (const ForwardProblem *fwd)
- realtype gett () const
- int getwhich () const
- int * getwhichptr ()
- AmiVector * getxBptr ()
- AmiVector * getxQBptr ()
- AmiVector * getdxBptr ()
- std::vector< realtype > const & getdJydx () const

10.4.1 Detailed Description

solves the backwards problem for adjoint sensitivity analysis and handles events and data-points

Definition at line 23 of file backwardproblem.h.

10.4.2 Constructor & Destructor Documentation

10.4.2.1 BackwardProblem()

```
BackwardProblem (
            const ForwardProblem * fwd )  [explicit]
```

Construct backward problem from forward problem

Parameters

fwd	pointer to corresponding forward problem

Returns

new BackwardProblem instance

Definition at line 18 of file backwardproblem.cpp.

Here is the call graph for this function:

10.4.3 Member Function Documentation

10.4.3.1 workBackwardProblem()

```
void workBackwardProblem ( )
```

workBackwardProblem solves the backward problem. if adjoint sensitivities are enabled this will also compute sensitivies workForwardProblem should be called before this is function is called

Definition at line 42 of file backwardproblem.cpp.

Here is the call graph for this function:

10.4.3.2 gett()

```
realtype gett ( ) const
```

accessor for t

Returns

t

Definition at line 32 of file backwardproblem.h.

Here is the caller graph for this function:

10.4.3.3 getwhich()

```
int getwhich ( ) const
```

accessor for which

Returns

which

Definition at line 39 of file backwardproblem.h.

Here is the caller graph for this function:

10.4.3.4 getwhichptr()

```
int* getwhichptr ( )
```

accessor for pointer to which

Returns

which

Definition at line 46 of file backwardproblem.h.

Here is the caller graph for this function:

10.4.3.5 getxBptr()

```
AmiVector* getxBptr ( )
```

accessor for pointer to xB

Returns

&xB

Definition at line 53 of file backwardproblem.h.

Here is the caller graph for this function:

10.4.3.6 getxQBptr()

```
AmiVector* getxQBptr ( )
```

accessor for pointer to xQB

Returns

&xQB

Definition at line 60 of file backwardproblem.h.

Here is the caller graph for this function:

10.4.3.7 getdxBptr()

```
AmiVector* getdxBptr ( )
```

accessor for pointer to dxB

Returns

&dxB

Definition at line 67 of file backwardproblem.h.

Here is the caller graph for this function:

10.4.3.8 getdJydx()

```
std::vector<realtype> const& getdJydx ( ) const
```

accessor for dJydx

Returns

dJydx

Definition at line 74 of file backwardproblem.h.

Here is the caller graph for this function:

10.5 CvodeException Class Reference

cvode exception handler class

```
#include <exception.h>
```

Inheritance diagram for CvodeException:

Public Member Functions

- CvodeException (const int error_code, const char *function)

10.5.1 Detailed Description

Definition at line 123 of file exception.h.

10.5.2 Constructor & Destructor Documentation

10.5.2.1 CvodeException()

```
CvodeException (
            const int error_code,
            const char * function )
```

constructor

Parameters

error_code	error code returned by cvode function
function	cvode function name

Definition at line 129 of file exception.h.

10.6 ExpData Class Reference

ExpData carries all information about experimental or condition-specific data.

```
#include <edata.h>
```

Public Member Functions

- ExpData ()
- ExpData (const ExpData &)=default
- ExpData (int nytrue, int nztrue, int nmaxevent)
- ExpData (int nytrue, int nztrue, int nmaxevent, std::vector< realtype > const &ts)
- ExpData (int nytrue, int nztrue, int nmaxevent, std::vector< realtype > const &ts, std::vector< realtype > const &fixedParameters)
- ExpData (int nytrue, int nztrue, int nmaxevent, std::vector< realtype > const &ts, std::vector< realtype > const &observedData, std::vector< realtype > const &observedDataStdDev, std::vector< realtype > const &observedEvents, std::vector< realtype > const &observedEventsStdDev)
- ExpData (const Model &model)
- ExpData (const ReturnData &rdata, realtype sigma_y, realtype sigma_z)
- ExpData (const ReturnData &rdata, std::vector< realtype > sigma_y, std::vector< realtype > sigma_z)
- int nytrue () const
- int nztrue () const
- int nmaxevent () const
- int nt () const
- void setTimepoints (const std::vector< realtype > &ts)
- std::vector< realtype > const & getTimepoints () const

- realtype getTimepoint (int it) const
- void setObservedData (const std::vector< realtype > &observedData)
- void setObservedData (const std::vector< realtype > &observedData, int iy)
- bool isSetObservedData (int it, int iy) const
- std::vector< realtype > const & getObservedData () const
- const realtype * getObservedDataPtr (int it) const
- void setObservedDataStdDev (const std::vector< realtype > &observedDataStdDev)
- void setObservedDataStdDev (const realtype stdDev)
- void setObservedDataStdDev (const std::vector< realtype > &observedDataStdDev, int iy)
- void setObservedDataStdDev (const realtype stdDev, int iy)
- bool isSetObservedDataStdDev (int it, int iy) const
- std::vector< realtype > const & getObservedDataStdDev () const
- const realtype * getObservedDataStdDevPtr (int it) const
- void setObservedEvents (const std::vector< realtype > &observedEvents)
- void setObservedEvents (const std::vector< realtype > &observedEvents, int iz)
- bool isSetObservedEvents (int ie, int iz) const
- std::vector< realtype > const & getObservedEvents () const
- const realtype * getObservedEventsPtr (int ie) const
- void setObservedEventsStdDev (const std::vector< realtype > &observedEventsStdDev)
- void setObservedEventsStdDev (const realtype stdDev)
- void setObservedEventsStdDev (const std::vector< realtype > &observedEventsStdDev, int iz)
- void setObservedEventsStdDev (const realtype stdDev, int iz)
- bool isSetObservedEventsStdDev (int ie, int iz) const
- std::vector< realtype > const & getObservedEventsStdDev () const
- const realtype * getObservedEventsStdDevPtr (int ie) const

Public Attributes

- std::vector< realtype > fixedParameters
- std::vector< realtype > fixedParametersPreequilibration
- std::vector< realtype > fixedParametersPresimulation
- realtype t_presim = 0

  duration of pre-simulation if this is > 0, presimualation will be performed from (model->t0 - t_presim) to model->t0 using the fixedParameters in fixedParametersPresimulation

Protected Member Functions

- void applyDimensions ()
- void applyDataDimension ()
- void applyEventDimension ()
- void checkDataDimension (std::vector< realtype > input, const char *fieldname) const
- void checkEventsDimension (std::vector< realtype > input, const char *fieldname) const

Protected Attributes

- int nytrue_
- int nztrue_
- int nmaxevent_
- std::vector< realtype > ts
- std::vector< realtype > observedData
- std::vector< realtype > observedDataStdDev
- std::vector< realtype > observedEvents
- std::vector< realtype > observedEventsStdDev

10.6.1 Detailed Description

Definition at line 14 of file edata.h.

10.6.2 Constructor & Destructor Documentation

10.6.2.1 ExpData() [1/9]

```
ExpData ( )
```

default constructor

Definition at line 14 of file edata.cpp.

10.6.2.2 ExpData() [2/9]

```
ExpData (
            const ExpData &  )  [default]
```

default copy constructor, needs to be declared to be generated in swig

10.6.2.3 ExpData() [3/9]

```
ExpData (
            int nytrue,
            int nztrue,
            int nmaxevent )
```

constructor that only initializes dimensions

Parameters

nytrue	
nztrue	
nmaxevent	

Definition at line 16 of file edata.cpp.

Here is the call graph for this function:

10.6.2.4 ExpData() [4/9]

```
ExpData (
            int nytrue,
            int nztrue,
            int nmaxevent,
            std::vector< realtype > const & ts )
```

constructor that initializes timepoints from vectors

Parameters

nytrue	(dimension: scalar)
nztrue	(dimension: scalar)
nmaxevent	(dimension: scalar)
ts	(dimension: nt)

Definition at line 22 of file edata.cpp.

Here is the call graph for this function:

10.6.2.5 ExpData() [5/9]

```
ExpData (
            int nytrue,
            int nztrue,
            int nmaxevent,
            std::vector< realtype > const & ts,
            std::vector< realtype > const & fixedParameters )
```

constructor that initializes timepoints and fixed parameters from vectors

Parameters

nytrue	(dimension: scalar)
nztrue	(dimension: scalar)
nmaxevent	(dimension: scalar)
ts	(dimension: nt)
fixedParameters	(dimension: nk)

Definition at line 29 of file edata.cpp.

Here is the call graph for this function:

10.6.2.6 ExpData() [6/9]

```
ExpData (
            int nytrue,
            int nztrue,
            int nmaxevent,
            std::vector< realtype > const & ts,
            std::vector< realtype > const & observedData,
            std::vector< realtype > const & observedDataStdDev,
            std::vector< realtype > const & observedEvents,
            std::vector< realtype > const & observedEventsStdDev )
```

constructor that initializes timepoints and data from vectors

Parameters

nytrue	(dimension: scalar)
nztrue	(dimension: scalar)
nmaxevent	(dimension: scalar)
ts	(dimension: nt)
observedData	(dimension: nt x nytrue, row-major)
observedDataStdDev	(dimension: nt x nytrue, row-major)
observedEvents	(dimension: nmaxevent x nztrue, row-major)
observedEventsStdDev	(dimension: nmaxevent x nztrue, row-major)

Definition at line 38 of file edata.cpp.

Here is the call graph for this function:

10.6.2.7 ExpData() [7/9]

```
ExpData (
            const Model & model )  [explicit]
```

constructor that initializes with Model

Parameters

model	pointer to model specification object

Definition at line 53 of file edata.cpp.

10.6.2.8 ExpData() [8/9]

```
ExpData (
            const ReturnData & rdata,
            realtype sigma_y,
            realtype sigma_z )
```

constructor that initializes with returnData, adds

Parameters

rdata	return data pointer with stored simulation results
sigma↩ _y	scalar standard deviations for all observables
sigma↩ _z	scalar standard deviations for all event observables

Definition at line 57 of file edata.cpp.

10.6.2.9 ExpData() [9/9]

```
ExpData (
            const ReturnData & rdata,
            std::vector< realtype > sigma_y,
            std::vector< realtype > sigma_z )
```

constructor that initializes with returnData, adds

Parameters

rdata	return data pointer with stored simulation results
sigma↩ _y	vector of standard deviations for observables (dimension: nytrue or nt x nytrue, row-major)
sigma↩ _z	vector of standard deviations for event observables (dimension: nztrue or nmaxevent x nztrue, row-major)

Definition at line 60 of file edata.cpp.

Here is the call graph for this function:

10.6.3 Member Function Documentation

10.6.3.1 nytrue()

```
int nytrue ( ) const
```

number of observables of the non-augmented model

Returns

number of observables of the non-augmented model

Definition at line 310 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.2 nztrue()

```
int nztrue ( ) const
```

number of event observables of the non-augmented model

Returns

number of event observables of the non-augmented model

Definition at line 315 of file edata.cpp.

10.6.3.3 nmaxevent()

```
int nmaxevent ( ) const
```

maximal number of events to track

Returns

maximal number of events to track

Definition at line 320 of file edata.cpp.

10.6.3.4 nt()

```
int nt ( ) const
```

number of timepoints

Returns

number of timepoints

Definition at line 108 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.5 setTimepoints()

```
void setTimepoints (
            const std::vector< realtype > & ts )
```

set function that copies data from input to ExpData::ts

Parameters

ts	timepoints

Definition at line 97 of file edata.cpp.

Here is the call graph for this function:

10.6.3.6 getTimepoints()

```
std::vector< realtype > const & getTimepoints ( ) const
```

get function that copies data from ExpData::ts to output

Returns

ExpData::ts

Definition at line 104 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.7 getTimepoint()

```
realtype getTimepoint (
            int it ) const
```

get function that returns timepoint at index

Parameters

it	timepoint index

Returns

timepoint timepoint at index

Definition at line 112 of file edata.cpp.

10.6.3.8 setObservedData() [1/2]

```
void setObservedData (
            const std::vector< realtype > & observedData )
```

set function that copies data from input to ExpData::my

Parameters

observedData	observed data (dimension: nt x nytrue, row-major)

Definition at line 116 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.9 setObservedData() [2/2]

```
void setObservedData (
            const std::vector< realtype > & observedData,
            int iy )
```

set function that copies observed data for specific observable

Parameters

observedData	observed data (dimension: nt)
iy	oberved data index

Definition at line 125 of file edata.cpp.

Here is the call graph for this function:

10.6.3.10 isSetObservedData()

```
bool isSetObservedData (
            int it,
            int iy ) const
```

get function that checks whether data at specified indices has been set

Parameters

it	time index
iy	observable index

Returns

boolean specifying if data was set

Definition at line 133 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.11 getObservedData()

```
std::vector< realtype > const & getObservedData ( ) const
```

get function that copies data from ExpData::observedData to output

Returns

observed data (dimension: nt x nytrue, row-major)

Definition at line 137 of file edata.cpp.

10.6.3.12 getObservedDataPtr()

```
const realtype * getObservedDataPtr (
            int it ) const
```

get function that returns a pointer to observed data at index

Parameters

it	timepoint index

Returns

pointer to observed data at index (dimension: nytrue)

Definition at line 141 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.13 setObservedDataStdDev() [1/4]

```
void setObservedDataStdDev (
            const std::vector< realtype > & observedDataStdDev )
```

set function that copies data from input to ExpData::observedDataStdDev

Parameters

observedDataStdDev	standard deviation of observed data (dimension: nt x nytrue, row-major)

Definition at line 148 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.14 setObservedDataStdDev() [2/4]

```
void setObservedDataStdDev (
            const realtype stdDev )
```

set function that sets all ExpData::observedDataStdDev to the input value

Parameters

stdDev	standard deviation (dimension: scalar)

Definition at line 158 of file edata.cpp.

Here is the call graph for this function:

10.6.3.15 setObservedDataStdDev() [3/4]

```
void setObservedDataStdDev (
            const std::vector< realtype > & observedDataStdDev,
            int iy )
```

set function that copies standard deviation of observed data for specific observable

Parameters

observedDataStdDev	standard deviation of observed data (dimension: nt)
iy	observed data index

Definition at line 163 of file edata.cpp.

Here is the call graph for this function:

10.6.3.16 setObservedDataStdDev() [4/4]

```
void setObservedDataStdDev (
            const realtype stdDev,
            int iy )
```

set function that sets all standard deviation of a specific observable to the input value

Parameters

stdDev	standard deviation (dimension: scalar)
iy	observed data index

Definition at line 172 of file edata.cpp.

Here is the call graph for this function:

10.6.3.17 isSetObservedDataStdDev()

```
bool isSetObservedDataStdDev (
            int it,
            int iy ) const
```

get function that checks whether standard deviation of data at specified indices has been set

Parameters

it	time index
iy	observable index

Returns

boolean specifying if standard deviation of data was set

Definition at line 178 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.18 getObservedDataStdDev()

```
std::vector< realtype > const & getObservedDataStdDev ( ) const
```

get function that copies data from ExpData::observedDataStdDev to output

Returns

standard deviation of observed data

Definition at line 182 of file edata.cpp.

10.6.3.19 getObservedDataStdDevPtr()

```
const realtype * getObservedDataStdDevPtr (
            int it ) const
```

get function that returns a pointer to standard deviation of observed data at index

Parameters

it	timepoint index

Returns

pointer to standard deviation of observed data at index

Definition at line 186 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.20 setObservedEvents() [1/2]

```
void setObservedEvents (
            const std::vector< realtype > & observedEvents )
```

set function that copies observed event data from input to ExpData::observedEvents

Parameters

observedEvents	observed data (dimension: nmaxevent x nztrue, row-major)

Definition at line 193 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.21 setObservedEvents() [2/2]

```
void setObservedEvents (
            const std::vector< realtype > & observedEvents,
            int iz )
```

set function that copies observed event data for specific event observable

Parameters

observedEvents	observed data (dimension: nmaxevent)
iz	observed event data index

Definition at line 202 of file edata.cpp.

10.6.3.22 isSetObservedEvents()

```
bool isSetObservedEvents (
            int ie,
            int iz ) const
```

get function that checks whether event data at specified indices has been set

Parameters

ie	event index
iz	event observable index

Returns

boolean specifying if data was set

Definition at line 211 of file edata.cpp.

Here is the call graph for this function:

10.6.3.23 getObservedEvents()

```
std::vector< realtype > const & getObservedEvents ( ) const
```

get function that copies data from ExpData::mz to output

Returns

observed event data

Definition at line 215 of file edata.cpp.

10.6.3.24 getObservedEventsPtr()

```
const realtype * getObservedEventsPtr (
            int ie ) const
```

get function that returns a pointer to observed data at ieth occurence

Parameters

ie	event occurence

Returns

pointer to observed event data at ieth occurence

Definition at line 219 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.25 setObservedEventsStdDev() [1/4]

```
void setObservedEventsStdDev (
            const std::vector< realtype > & observedEventsStdDev )
```

set function that copies data from input to ExpData::observedEventsStdDev

Parameters

observedEventsStdDev	standard deviation of observed event data

Definition at line 226 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.26 setObservedEventsStdDev() [2/4]

```
void setObservedEventsStdDev (
            const realtype stdDev )
```

set function that sets all ExpData::observedDataStdDev to the input value

Parameters

stdDev	standard deviation (dimension: scalar)

Definition at line 236 of file edata.cpp.

Here is the call graph for this function:

10.6.3.27 setObservedEventsStdDev() [3/4]

```
void setObservedEventsStdDev (
            const std::vector< realtype > & observedEventsStdDev,
            int iz )
```

set function that copies standard deviation of observed data for specific observable

Parameters

observedEventsStdDev	standard deviation of observed data (dimension: nmaxevent)
iz	observed data index

Definition at line 241 of file edata.cpp.

Here is the call graph for this function:

10.6.3.28 setObservedEventsStdDev() [4/4]

```
void setObservedEventsStdDev (
            const realtype stdDev,
            int iz )
```

set function that sets all standard deviation of a specific observable to the input value

Parameters

stdDev	standard deviation (dimension: scalar)
iz	observed data index

Definition at line 250 of file edata.cpp.

Here is the call graph for this function:

10.6.3.29 isSetObservedEventsStdDev()

```
bool isSetObservedEventsStdDev (
            int ie,
            int iz ) const
```

get function that checks whether standard deviation of even data at specified indices has been set

Parameters

ie	event index
iz	event observable index

Returns

boolean specifying if standard deviation of event data was set

Definition at line 257 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.30 getObservedEventsStdDev()

```
std::vector< realtype > const & getObservedEventsStdDev ( ) const
```

get function that copies data from ExpData::observedEventsStdDev to output

Returns

standard deviation of observed event data

Definition at line 264 of file edata.cpp.

10.6.3.31 getObservedEventsStdDevPtr()

```
const realtype * getObservedEventsStdDevPtr (
            int ie ) const
```

get function that returns a pointer to standard deviation of observed event data at ieth occurence

Parameters

ie	event occurence

Returns

pointer to standard deviation of observed event data at ieth occurence

Definition at line 268 of file edata.cpp.

Here is the caller graph for this function:

10.6.3.32 applyDimensions()

```
void applyDimensions ( ) [protected]
```

resizes observedData, observedDataStdDev, observedEvents and observedEventsStdDev

Definition at line 275 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.33 applyDataDimension()

```
void applyDataDimension ( ) [protected]
```

resizes observedData and observedDataStdDev

Definition at line 280 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.34 applyEventDimension()

```
void applyEventDimension ( ) [protected]
```

resizes observedEvents and observedEventsStdDev

Definition at line 285 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.35 checkDataDimension()

```
void checkDataDimension (
            std::vector< realtype > input,
            const char * fieldname ) const  [protected]
```

checker for dimensions of input observedData or observedDataStdDev

Parameters

input	vector input to be checked
fieldname	name of the input

Definition at line 290 of file edata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.6.3.36 checkEventsDimension()

```
void checkEventsDimension (
            std::vector< realtype > input,
            const char * fieldname ) const  [protected]
```

checker for dimensions of input observedEvents or observedEventsStdDev

Parameters

input	vector input to be checkedjupyter_contrib_nbextensions
fieldname	name of the input

Definition at line 295 of file edata.cpp.

Here is the caller graph for this function:

10.6.4 Member Data Documentation

10.6.4.1 fixedParameters

```
std::vector<realtype> fixedParameters
```

condition-specific parameters of size Model::nk() or empty

Definition at line 340 of file edata.h.

10.6.4.2 fixedParametersPreequilibration

```
std::vector<realtype> fixedParametersPreequilibration
```

condition-specific parameters for pre-equilibration of size Model::nk() or empty. Overrides Solver::newton_preeq

Definition at line 343 of file edata.h.

10.6.4.3 fixedParametersPresimulation

```
std::vector<realtype> fixedParametersPresimulation
```

condition-specific parameters for pre-simulation of size Model::nk() or empty.

Definition at line 345 of file edata.h.

10.6.4.4 nytrue_

```
int nytrue_ [protected]
```

number of observables

Definition at line 388 of file edata.h.

10.6.4.5 nztrue_

```
int nztrue_ [protected]
```

number of event observables

Definition at line 391 of file edata.h.

10.6.4.6 nmaxevent_

```
int nmaxevent_ [protected]
```

maximal number of event occurences

Definition at line 394 of file edata.h.

10.6.4.7 ts

```
std::vector<realtype> ts [protected]
```

observation timepoints (dimension: nt)

Definition at line 397 of file edata.h.

10.6.4.8 observedData

```
std::vector<realtype> observedData [protected]
```

observed data (dimension: nt x nytrue, row-major)

Definition at line 400 of file edata.h.

10.6.4.9 observedDataStdDev

```
std::vector<realtype> observedDataStdDev [protected]
```

standard deviation of observed data (dimension: nt x nytrue, row-major)

Definition at line 402 of file edata.h.

10.6.4.10 observedEvents

```
std::vector<realtype> observedEvents [protected]
```

observed events (dimension: nmaxevents x nztrue, row-major)

Definition at line 405 of file edata.h.

10.6.4.11 observedEventsStdDev

```
std::vector<realtype> observedEventsStdDev [protected]
```

standard deviation of observed events/roots (dimension: nmaxevents x nztrue, row-major)

Definition at line 408 of file edata.h.

10.7 ForwardProblem Class Reference

The ForwardProblem class groups all functions for solving the backwards problem. Has only static members.

```
#include <forwardproblem.h>
```

Public Member Functions

- ForwardProblem (ReturnData *rdata, const ExpData *edata, Model *model, Solver *solver)
- void workForwardProblem ()
- realtype getTime () const
- AmiVectorArray const & getStateSensitivity () const
- AmiVectorArray const & getStatesAtDiscontinuities () const
- AmiVectorArray const & getRHSAtDiscontinuities () const
- AmiVectorArray const & getRHSBeforeDiscontinuities () const
- std::vector< int > const & getNumberOfRoots () const
- std::vector< realtype > const & getDiscontinuities () const
- std::vector< int > const & getRootIndexes () const
- std::vector< realtype > const & getDJydx () const
- std::vector< realtype > const & getDJzdx () const
- int getRootCounter () const
- AmiVector * getStatePointer ()
- AmiVector * getStateDerivativePointer ()
- AmiVectorArray * getStateSensitivityPointer ()
- AmiVectorArray * getStateDerivativeSensitivityPointer ()

Public Attributes

- Model * model
- ReturnData * rdata
- Solver * solver
- const ExpData * edata

10.7.1 Detailed Description

Definition at line 23 of file forwardproblem.h.

10.7.2 Constructor & Destructor Documentation

10.7.2.1 ForwardProblem()

```
ForwardProblem (
            ReturnData * rdata,
            const ExpData * edata,
            Model * model,
            Solver * solver )
```

Constructor

Parameters

rdata	pointer to ReturnData instance
edata	pointer to ExpData instance
model	pointer to Model instance
solver	pointer to Solver instance

Definition at line 42 of file forwardproblem.cpp.

10.7.3 Member Function Documentation

10.7.3.1 workForwardProblem()

```
void workForwardProblem ( )
```

workForwardProblem solves the forward problem. if forward sensitivities are enabled this will also compute sensitivies

Definition at line 79 of file forwardproblem.cpp.

Here is the call graph for this function:

10.7.3.2 getTime()

```
realtype getTime ( ) const
```

accessor for t

Returns

t

Definition at line 37 of file forwardproblem.h.

Here is the caller graph for this function:

10.7.3.3 getStateSensitivity()

```
AmiVectorArray const& getStateSensitivity ( ) const
```

accessor for sx

Returns

sx

Definition at line 44 of file forwardproblem.h.

10.7.3.4 getStatesAtDiscontinuities()

```
AmiVectorArray const& getStatesAtDiscontinuities ( ) const
```

accessor for x_disc

Returns

x_disc

Definition at line 51 of file forwardproblem.h.

10.7.3.5 getRHSAtDiscontinuities()

```
AmiVectorArray const& getRHSAtDiscontinuities ( ) const
```

accessor for xdot_disc

Returns

xdot_disc

Definition at line 58 of file forwardproblem.h.

10.7.3.6 getRHSBeforeDiscontinuities()

```
AmiVectorArray const& getRHSBeforeDiscontinuities ( ) const
```

accessor for xdot_old_disc

Returns

xdot_old_disc

Definition at line 65 of file forwardproblem.h.

10.7.3.7 getNumberOfRoots()

```
std::vector<int> const& getNumberOfRoots ( ) const
```

accessor for nroots

Returns

nroots

Definition at line 72 of file forwardproblem.h.

10.7.3.8 getDiscontinuities()

```
std::vector<realtype> const& getDiscontinuities ( ) const
```

accessor for discs

Returns

discs

Definition at line 79 of file forwardproblem.h.

10.7.3.9 getRootIndexes()

```
std::vector<int> const& getRootIndexes ( ) const
```

accessor for rootidx

Returns

rootidx

Definition at line 86 of file forwardproblem.h.

10.7.3.10 getDJydx()

```
std::vector<realtype> const& getDJydx ( ) const
```

accessor for dJydx

Returns

dJydx

Definition at line 93 of file forwardproblem.h.

10.7.3.11 getDJzdx()

```
std::vector<realtype> const& getDJzdx ( ) const
```

accessor for dJzdx

Returns

dJzdx

Definition at line 100 of file forwardproblem.h.

10.7.3.12 getRootCounter()

```
int getRootCounter ( ) const
```

accessor for iroot

Returns

iroot

Definition at line 107 of file forwardproblem.h.

Here is the caller graph for this function:

10.7.3.13 getStatePointer()

```
AmiVector* getStatePointer ( )
```

accessor for pointer to x

Returns

&x

Definition at line 114 of file forwardproblem.h.

10.7.3.14 getStateDerivativePointer()

```
AmiVector* getStateDerivativePointer ( )
```

accessor for pointer to dx

Returns

&dx

Definition at line 121 of file forwardproblem.h.

10.7.3.15 getStateSensitivityPointer()

```
AmiVectorArray* getStateSensitivityPointer ( )
```

accessor for pointer to sx

Returns

&sx

Definition at line 128 of file forwardproblem.h.

10.7.3.16 getStateDerivativeSensitivityPointer()

```
AmiVectorArray* getStateDerivativeSensitivityPointer ( )
```

accessor for pointer to sdx

Returns

&sdx

Definition at line 135 of file forwardproblem.h.

10.7.4 Member Data Documentation

10.7.4.1 model

```
Model* model
```

pointer to model instance

Definition at line 140 of file forwardproblem.h.

10.7.4.2 rdata

```
ReturnData* rdata
```

pointer to return data instance

Definition at line 142 of file forwardproblem.h.

10.7.4.3 solver

```
Solver* solver
```

pointer to solver instance

Definition at line 144 of file forwardproblem.h.

10.7.4.4 edata

```
const ExpData* edata
```

pointer to experimental data instance

Definition at line 146 of file forwardproblem.h.

10.8 IDAException Class Reference

ida exception handler class

```
#include <exception.h>
```

Inheritance diagram for IDAException:

Public Member Functions

- IDAException (const int error_code, const char *function)

10.8.1 Detailed Description

Definition at line 135 of file exception.h.

10.8.2 Constructor & Destructor Documentation

10.8.2.1 IDAException()

```
IDAException (
            const int error_code,
            const char * function )
```

constructor

Parameters

error_code	error code returned by ida function
function	ida function name

Definition at line 141 of file exception.h.

10.9 IntegrationFailure Class Reference

integration failure exception for the forward problem this exception should be thrown when an integration failure occured for this exception we can assume that we can recover from the exception and return a solution struct to the user

```
#include <exception.h>
```

Inheritance diagram for IntegrationFailure:

Public Member Functions

- IntegrationFailure (int code, realtype t)

Public Attributes

- int error_code
- realtype time

10.9.1 Detailed Description

Definition at line 150 of file exception.h.

10.9.2 Constructor & Destructor Documentation

10.9.2.1 IntegrationFailure()

```
IntegrationFailure (
            int code,
            realtype t )
```

constructor

Parameters

code	error code returned by cvode/ida
t	time of integration failure

Definition at line 160 of file exception.h.

10.9.3 Member Data Documentation

10.9.3.1 error_code

```
int error_code
```

error code returned by cvode/ida

Definition at line 153 of file exception.h.

10.9.3.2 time

```
realtype time
```

time of integration failure

Definition at line 155 of file exception.h.

10.10 IntegrationFailureB Class Reference

integration failure exception for the backward problem this exception should be thrown when an integration failure occured for this exception we can assume that we can recover from the exception and return a solution struct to the user

```
#include <exception.h>
```

Inheritance diagram for IntegrationFailureB:

Public Member Functions

- IntegrationFailureB (int code, realtype t)

Public Attributes

- int error_code
- realtype time

10.10.1 Detailed Description

Definition at line 170 of file exception.h.

10.10.2 Constructor & Destructor Documentation

10.10.2.1 IntegrationFailureB()

```
IntegrationFailureB (
            int code,
            realtype t )
```

constructor

Parameters

code	error code returned by cvode/ida
t	time of integration failure

Definition at line 180 of file exception.h.

10.10.3 Member Data Documentation

10.10.3.1 error_code

```
int error_code
```

error code returned by cvode/ida

Definition at line 173 of file exception.h.

10.10.3.2 time

```
realtype time
```

time of integration failure

Definition at line 175 of file exception.h.

10.11 Model Class Reference

The Model class represents an AMICI ODE model. The model can compute various model related quantities based on symbolically generated code.

```
#include <model.h>
```

Inheritance diagram for Model:

Public Member Functions

- Model ()
- Model (const int nx_rdata, const int nxtrue_rdata, const int nx_solver, const int nxtrue_solver, const int ny, const int nytrue, const int nz, const int nztrue, const int ne, const int nJ, const int nw, const int ndwdx, const int ndwdp, const int nnz, const int ubw, const int lbw, amici::SecondOrderMode o2mode, const std↩::vector< amici::realtype > &p, std::vector< amici::realtype > k, const std::vector< int > &plist, std::vector< amici::realtype > idlist, std::vector< int > z2event)
- Model (Model const &other)
- virtual ~Model ()
- Model & operator= (Model const &other)=delete
- virtual Model * clone () const =0

  Clone this instance.
- virtual std::unique_ptr< Solver > getSolver ()=0
- virtual void froot (realtype t, AmiVector *x, AmiVector *dx, realtype *root)=0
- virtual void fxdot (realtype t, AmiVector *x, AmiVector *dx, AmiVector *xdot)=0
- virtual void fsxdot (realtype t, AmiVector *x, AmiVector *dx, int ip, AmiVector *sx, AmiVector *sdx, AmiVector *sxdot)=0
- virtual void fJ (realtype t, realtype cj, AmiVector *x, AmiVector *dx, AmiVector *xdot, DlsMat J)=0
- virtual void fJSparse (realtype t, realtype cj, AmiVector *x, AmiVector *dx, AmiVector *xdot, SlsMat J)=0
- virtual void fJDiag (realtype t, AmiVector *Jdiag, realtype cj, AmiVector *x, AmiVector *dx)=0
- virtual void fdxdotdp (realtype t, AmiVector *x, AmiVector *dx)=0

- virtual void fJv (realtype t, AmiVector *x, AmiVector *dx, AmiVector *xdot, AmiVector *v, AmiVector *nJv, realtype cj)=0
- void fx_rdata (AmiVector *x_rdata, const AmiVector *x_solver)
- void fsx_rdata (AmiVectorArray *sx_rdata, const AmiVectorArray *sx_solver)
- void fx0 (AmiVector *x)
- void fx0_fixedParameters (AmiVector *x)
- virtual void fdx0 (AmiVector *x0, AmiVector *dx0)
- void fsx0 (AmiVectorArray *sx, const AmiVector *x)
- void fsx0_fixedParameters (AmiVectorArray *sx, const AmiVector *x)
- virtual void fsdx0 ()
- void fstau (const realtype t, const int ie, const AmiVector *x, const AmiVectorArray *sx)
- void fy (const realtype t, const int it, const AmiVector *x, ReturnData *rdata)
- void fdydp (const realtype t, const AmiVector *x)
- void fdydx (const realtype t, const AmiVector *x)
- void fz (const int nroots, const int ie, const realtype t, const AmiVector *x, ReturnData *rdata)
- void fsz (const int nroots, const int ie, const realtype t, const AmiVector *x, const AmiVectorArray *sx, ReturnData *rdata)
- void frz (const int nroots, const int ie, const realtype t, const AmiVector *x, ReturnData *rdata)
- void fsrz (const int nroots, const int ie, const realtype t, const AmiVector *x, const AmiVectorArray *sx, ReturnData *rdata)
- void fdzdp (const realtype t, const int ie, const AmiVector *x)
- void fdzdx (const realtype t, const int ie, const AmiVector *x)
- void fdrzdp (const realtype t, const int ie, const AmiVector *x)
- void fdrzdx (const realtype t, const int ie, const AmiVector *x)
- void fdeltax (const int ie, const realtype t, const AmiVector *x, const AmiVector *xdot, const AmiVector *xdot↩_old)
- void fdeltasx (const int ie, const realtype t, const AmiVector *x, const AmiVectorArray *sx, const AmiVector *xdot, const AmiVector *xdot_old)
- void fdeltaxB (const int ie, const realtype t, const AmiVector *x, const AmiVector *xB, const AmiVector *xdot, const AmiVector *xdot_old)
- void fdeltaqB (const int ie, const realtype t, const AmiVector *x, const AmiVector *xB, const AmiVector *xdot, const AmiVector *xdot_old)
- void fsigmay (const int it, ReturnData *rdata, const ExpData *edata)
- void fdsigmaydp (const int it, ReturnData *rdata, const ExpData *edata)
- void fsigmaz (const realtype t, const int ie, const int *nroots, ReturnData *rdata, const ExpData *edata)
- void fdsigmazdp (const realtype t, const int ie, const int *nroots, ReturnData *rdata, const ExpData *edata)
- void fJy (const int it, ReturnData *rdata, const ExpData *edata)
- void fJz (const int nroots, ReturnData *rdata, const ExpData *edata)
- void fJrz (const int nroots, ReturnData *rdata, const ExpData *edata)
- void fdJydy (const int it, const ReturnData *rdata, const ExpData *edata)
- void fdJydsigma (const int it, const ReturnData *rdata, const ExpData *edata)
- void fdJzdz (const int nroots, const ReturnData *rdata, const ExpData *edata)
- void fdJzdsigma (const int nroots, const ReturnData *rdata, const ExpData *edata)
- void fdJrzdz (const int nroots, const ReturnData *rdata, const ExpData *edata)
- void fdJrzdsigma (const int nroots, const ReturnData *rdata, const ExpData *edata)
- void fsy (const int it, const AmiVectorArray *sx, ReturnData *rdata)
- void fsz_tf (const int *nroots, const int ie, ReturnData *rdata)
- void fsJy (const int it, const std::vector< realtype > &dJydx, const AmiVectorArray *sx, ReturnData *rdata)
- void fdJydp (const int it, ReturnData *rdata, const ExpData *edata)
- void fdJydx (std::vector< realtype > *dJydx, const int it, const ReturnData *rdata, const ExpData *edata)
- void fsJz (const int nroots, const std::vector< realtype > &dJzdx, const AmiVectorArray *sx, ReturnData *rdata)
- void fdJzdp (const int nroots, realtype t, const ExpData *edata, const ReturnData *rdata)
- void fdJzdx (std::vector< realtype > *dJzdx, const int nroots, realtype t, const ExpData *edata, const ReturnData *rdata)

- void initialize (AmiVector *x, AmiVector *dx, AmiVectorArray *sx, AmiVectorArray *sdx, bool compute↩ Sensitivities)
- void initializeStates (AmiVector *x)
- void initializeStateSensitivities (AmiVectorArray *sx, AmiVector *x)
- void initHeaviside (AmiVector *x, AmiVector *dx)
- int nplist () const

  number of paramaeters wrt to which sensitivities are computed
- int np () const

  total number of model parameters
- int nk () const

  number of constants
- int ncl () const

  number of conservation laws
- const double * k () const

  fixed parameters
- int nMaxEvent () const

  Get nmaxevent.
- void setNMaxEvent (int nmaxevent)

  Set nmaxevent.
- int nt () const

  Get number of timepoints.
- std::vector< ParameterScaling > const & getParameterScale () const

  Get ParameterScale for each parameter.
- void setParameterScale (ParameterScaling pscale)

  Set ParameterScale for each parameter, resets initial state sensitivities.
- void setParameterScale (const std::vector< ParameterScaling > &pscaleVec)

  Set ParameterScale for each parameter, resets initial state sensitivities.
- std::vector< realtype > const & getParameters () const

  Get the parameter vector.
- void setParameters (std::vector< realtype > const &p)

  Sets the parameter vector.
- std::vector< realtype > const & getUnscaledParameters () const

  Gets parameters with transformation according to ParameterScale applied.
- std::vector< realtype > const & getFixedParameters () const

  Gets the fixedParameter member.
- void setFixedParameters (std::vector< realtype > const &k)

  Sets the fixedParameter member.
- realtype getFixedParameterById (std::string const &par_id) const

  Get value of fixed parameter with the specified Id.
- realtype getFixedParameterByName (std::string const &par_name) const

  Get value of fixed parameter with the specified name, if multiple parameters have the same name, the first parameter with matching name is returned.
- void setFixedParameterById (std::string const &par_id, realtype value)

  Set value of first fixed parameter with the specified id.
- int setFixedParametersByIdRegex (std::string const &par_id_regex, realtype value)

  Set values of all fixed parameters with the id matching the specified regex.
- void setFixedParameterByName (std::string const &par_name, realtype value)

  Set value of first fixed parameter with the specified name,.
- int setFixedParametersByNameRegex (std::string const &par_name_regex, realtype value)

  Set value of all fixed parameters with name matching the specified regex,.
- std::vector< realtype > const & getTimepoints () const

Get the timepoint vector.

- void setTimepoints (std::vector< realtype > const &ts)

  Set the timepoint vector.
- std::vector< bool > const & getStateIsNonNegative () const

  gets flags indicating whether states should be treated as non-negative
- void setStateIsNonNegative (std::vector< bool > const &stateIsNonNegative)

  sets flags indicating whether states should be treated as non-negative
- double t (int idx) const

  Get timepoint for given index.
- std::vector< int > const & getParameterList () const

  Get the list of parameters for which sensitivities are computed.
- void setParameterList (std::vector< int > const &plist)

  Set the list of parameters for which sensitivities are computed, resets initial state sensitivities.
- std::vector< realtype > const & getInitialStates () const

  Get the initial states.
- void setInitialStates (std::vector< realtype > const &x0)

  Set the initial states.
- std::vector< realtype > const & getInitialStateSensitivities () const

  Get the initial states sensitivities.
- void setInitialStateSensitivities (std::vector< realtype > const &sx0)

  Set the initial state sensitivities.
- void setUnscaledInitialStateSensitivities (std::vector< realtype > const &sx0)

  Set the initial state sensitivities.
- double t0 () const

  get simulation start time
- void setT0 (double t0)

  set simulation start time
- int plist (int pos) const

  entry in parameter list
- void requireSensitivitiesForAllParameters ()

  Require computation of sensitivities for all parameters p [0..np[in natural order, resets initial state sensitivities.
- void fw (const realtype t, const realtype *x)

  Recurring terms in xdot.
- void fdwdp (const realtype t, const realtype *x)

  Recurring terms in xdot, parameter derivative.
- void fdwdx (const realtype t, const realtype *x)

  Recurring terms in xdot, state derivative.
- void fres (const int it, ReturnData *rdata, const ExpData *edata)
- void fchi2 (const int it, ReturnData *rdata)
- void fsres (const int it, ReturnData *rdata, const ExpData *edata)
- void fFIM (const int it, ReturnData *rdata)
- void updateHeaviside (const std::vector< int > &rootsfound)
- void updateHeavisideB (const int *rootsfound)
- realtype gett (const int it, const ReturnData *rdata) const
- int checkFinite (const int N, const realtype *array, const char *fun) const

  Check if the given array has only finite elements. If not try to give hints by which other fields this could be caused.
- virtual const std::string getAmiciVersion () const

  Returns the amici version that was used to generate the model.
- virtual const std::string getAmiciCommit () const

  Returns the amici commit that was used to generate the model.
- virtual bool hasParameterNames () const

Reports whether the model has parameter names set.

- virtual std::vector< std::string > getParameterNames () const

  Get names of the model parameters.
- virtual bool hasStateNames () const

  Reports whether the model has state names set.
- virtual std::vector< std::string > getStateNames () const

  Get names of the model states.
- virtual bool hasFixedParameterNames () const

  Reports whether the model has fixed parameter names set.
- virtual std::vector< std::string > getFixedParameterNames () const

  Get names of the fixed model parameters.
- virtual bool hasObservableNames () const

  Reports whether the model has observable names set.
- virtual std::vector< std::string > getObservableNames () const

  Get names of the observables.
- virtual bool hasParameterIds () const

  Reports whether the model has parameter ids set.
- virtual std::vector< std::string > getParameterIds () const

  Get ids of the model parameters.
- realtype getParameterById (std::string const &par_id) const

  Get value of first model parameter with the specified id.
- realtype getParameterByName (std::string const &par_name) const

  Get value of first model parameter with the specified name,.
- void setParameterById (std::string const &par_id, realtype value)

  Set value of first model parameter with the specified id.
- int setParametersByIdRegex (std::string const &par_id_regex, realtype value)

  Set all values of model parameters with ids matching the specified regex.
- void setParameterByName (std::string const &par_name, realtype value)

  Set value of first model parameter with the specified name.
- int setParametersByNameRegex (std::string const &par_name_regex, realtype value)

  Set all values of all model parameters with names matching the specified regex.
- virtual bool hasStateIds () const

  Reports whether the model has state ids set.
- virtual std::vector< std::string > getStateIds () const

  Get ids of the model states.
- virtual bool hasFixedParameterIds () const

  Reports whether the model has fixed parameter ids set.
- virtual std::vector< std::string > getFixedParameterIds () const

  Get ids of the fixed model parameters.
- virtual bool hasObservableIds () const

  Reports whether the model has observable ids set.
- virtual std::vector< std::string > getObservableIds () const

  Get ids of the observables.
- void setSteadyStateSensitivityMode (const SteadyStateSensitivityMode mode)

  sets the mode how sensitivities are computed in the steadystate simulation
- SteadyStateSensitivityMode getSteadyStateSensitivityMode () const

  gets the mode how sensitivities are computed in the steadystate simulation
- void setReinitializeFixedParameterInitialStates (bool flag)

  set whether initial states depending on fixedParmeters are to be reinitialized after preequilibration and presimulation
- bool getReinitializeFixedParameterInitialStates () const

  get whether initial states depending on fixedParmeters are to be reinitialized after preequilibration and presimulation

Public Attributes

- const int nx_rdata
- const int nxtrue_rdata
- const int nx_solver
- const int nxtrue_solver
- const int ny
- const int nytrue
- const int nz
- const int nztrue
- const int ne
- const int nw
- const int ndwdx
- const int ndwdp
- const int nnz
- const int nJ
- const int ubw
- const int lbw
- const SecondOrderMode o2mode
- const std::vector< int > z2event
- const std::vector< realtype > idlist
- std::vector< realtype > sigmay
- std::vector< realtype > dsigmaydp
- std::vector< realtype > sigmaz
- std::vector< realtype > dsigmazdp
- std::vector< realtype > dJydp
- std::vector< realtype > dJzdp
- std::vector< realtype > deltax
- std::vector< realtype > deltasx
- std::vector< realtype > deltaxB
- std::vector< realtype > deltaqB
- std::vector< realtype > dxdotdp

Protected Member Functions

- void initializeVectors ()

  Set the nplist-dependent vectors to their proper sizes.
- virtual void fx_rdata (realtype *x_rdata, const realtype *x_solver, const realtype *tcl)
- virtual void fsx_rdata (realtype *sx_rdata, const realtype *sx_solver, const realtype *stcl, const int ip)
- virtual void fx_solver (realtype *x_solver, const realtype *x_rdata)
- virtual void fsx_solver (realtype *sx_solver, const realtype *sx_rdata)
- virtual void ftotal_cl (realtype *total_cl, const realtype *x_rdata)
- virtual void fstotal_cl (realtype *stotal_cl, const realtype *sx_rdata, const int ip)
- virtual void fx0 (realtype *x0, const realtype t, const realtype *p, const realtype *k)
- virtual void fx0_fixedParameters (realtype *x0, const realtype t, const realtype *p, const realtype *k)
- virtual void fsx0_fixedParameters (realtype *sx0, const realtype t, const realtype *x0, const realtype *p, const realtype *k, const int ip)
- virtual void fsx0 (realtype *sx0, const realtype t, const realtype *x0, const realtype *p, const realtype *k, const int ip)
- virtual void fstau (realtype *stau, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *sx, const int ip, const int ie)
- virtual void fy (realtype *y, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w)

- virtual void fdydp (realtype *dydp, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ip, const realtype *w, const realtype *dwdp)
- virtual void fdydx (realtype *dydx, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const realtype *dwdx)
- virtual void fz (realtype *z, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h)
- virtual void fsz (realtype *sz, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *sx, const int ip)
- virtual void frz (realtype *rz, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h)
- virtual void fsrz (realtype *srz, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *sx, const int ip)
- virtual void fdzdp (realtype *dzdp, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ip)
- virtual void fdzdx (realtype *dzdx, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h)
- virtual void fdrzdp (realtype *drzdp, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ip)
- virtual void fdrzdx (realtype *drzdx, const int ie, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h)
- virtual void fdeltax (realtype *deltax, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ie, const realtype *xdot, const realtype *xdot_old)
- virtual void fdeltasx (realtype *deltasx, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const int ip, const int ie, const realtype *xdot, const realtype *xdot_old, const realtype *sx, const realtype *stau)
- virtual void fdeltaxB (realtype *deltaxB, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ie, const realtype *xdot, const realtype *xdot_old, const realtype *xB)
- virtual void fdeltaqB (realtype *deltaqB, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ip, const int ie, const realtype *xdot, const realtype *xdot_old, const realtype *xB)
- virtual void fsigmay (realtype *sigmay, const realtype t, const realtype *p, const realtype *k)
- virtual void fdsigmaydp (realtype *dsigmaydp, const realtype t, const realtype *p, const realtype *k, const int ip)
- virtual void fsigmaz (realtype *sigmaz, const realtype t, const realtype *p, const realtype *k)
- virtual void fdsigmazdp (realtype *dsigmazdp, const realtype t, const realtype *p, const realtype *k, const int ip)
- virtual void fJy (realtype *nllh, const int iy, const realtype *p, const realtype *k, const realtype *y, const realtype *sigmay, const realtype *my)
- virtual void fJz (realtype *nllh, const int iz, const realtype *p, const realtype *k, const realtype *z, const realtype *sigmaz, const realtype *mz)
- virtual void fJrz (realtype *nllh, const int iz, const realtype *p, const realtype *k, const realtype *z, const realtype *sigmaz)
- virtual void fdJydy (realtype *dJydy, const int iy, const realtype *p, const realtype *k, const realtype *y, const realtype *sigmay, const realtype *my)
- virtual void fdJydsigma (realtype *dJydsigma, const int iy, const realtype *p, const realtype *k, const realtype *y, const realtype *sigmay, const realtype *my)
- virtual void fdJzdz (realtype *dJzdz, const int iz, const realtype *p, const realtype *k, const realtype *z, const realtype *sigmaz, const realtype *mz)
- virtual void fdJzdsigma (realtype *dJzdsigma, const int iz, const realtype *p, const realtype *k, const realtype *z, const realtype *sigmaz, const realtype *mz)
- virtual void fdJrzdz (realtype *dJrzdz, const int iz, const realtype *p, const realtype *k, const realtype *rz, const realtype *sigmaz)
- virtual void fdJrzdsigma (realtype *dJrzdsigma, const int iz, const realtype *p, const realtype *k, const realtype *rz, const realtype *sigmaz)
- virtual void fw (realtype *w, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *tcl)

- virtual void fdwdp (realtype *dwdp, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const realtype *tcl, const realtype *stcl)
- virtual void fdwdx (realtype *dwdx, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const realtype *tcl)
- void getmy (const int it, const ExpData *edata)
- void getmz (const int nroots, const ExpData *edata)
- const realtype * gety (const int it, const ReturnData *rdata) const
- const realtype * getz (const int nroots, const ReturnData *rdata) const
- const realtype * getrz (const int nroots, const ReturnData *rdata) const
- const realtype * getsz (const int nroots, const int ip, const ReturnData *rdata) const
- const realtype * getsrz (const int nroots, const int ip, const ReturnData *rdata) const
- virtual bool isFixedParameterStateReinitializationAllowed () const
- N_Vector computeX_pos (N_Vector x)

  computes nonnegative state vector according to stateIsNonNegative if anyStateNonNegative is set to false, i.e., all entries in stateIsNonNegative are false, this function directly returns x, otherwise all entries of x are copied in to x_pos_tmp and negative values are replaced by 0 where applicable

Protected Attributes

- SlsMat J = nullptr
- std::vector< realtype > my
- std::vector< realtype > mz
- std::vector< realtype > dJydy
- std::vector< realtype > dJydsigma
- std::vector< realtype > dJzdz
- std::vector< realtype > dJzdsigma
- std::vector< realtype > dJrzdz
- std::vector< realtype > dJrzdsigma
- std::vector< realtype > dzdx
- std::vector< realtype > dzdp
- std::vector< realtype > drzdx
- std::vector< realtype > drzdp
- std::vector< realtype > dydp
- std::vector< realtype > dydx
- std::vector< realtype > w
- std::vector< realtype > dwdx
- std::vector< realtype > dwdp
- std::vector< realtype > M
- std::vector< realtype > stau
- std::vector< realtype > sx
- std::vector< realtype > x_rdata
- std::vector< realtype > sx_rdata
- std::vector< realtype > h
- std::vector< realtype > unscaledParameters
- std::vector< realtype > originalParameters
- std::vector< realtype > fixedParameters
- std::vector< realtype > total_cl
- std::vector< realtype > stotal_cl
- std::vector< int > plist_
- std::vector< double > x0data
- std::vector< realtype > sx0data
- std::vector< realtype > ts
- std::vector< bool > stateIsNonNegative
- bool anyStateNonNegative = false

- AmiVector x_pos_tmp
- int nmaxevent = 10
- std::vector< ParameterScaling > pscale
- double tstart = 0.0
- SteadyStateSensitivityMode steadyStateSensitivityMode = SteadyStateSensitivityMode::newtonOnly
- bool reinitializeFixedParameterInitialStates = false

Friends

- template<class Archive >
  void boost::serialization::serialize (Archive &ar, Model &r, const unsigned int version)

  Serialize Model (see boost::serialization::serialize)
- bool operator== (const Model &a, const Model &b)

  Check equality of data members.

10.11.1 Detailed Description

Definition at line 41 of file model.h.

10.11.2 Constructor & Destructor Documentation

10.11.2.1 Model() [1/3]

```
Model ( )
```

default constructor

Definition at line 44 of file model.h.

10.11.2.2 Model() [2/3]

```
Model (
            const int nx_rdata,
            const int nxtrue_rdata,
            const int nx_solver,
            const int nxtrue_solver,
            const int ny,
            const int nytrue,
            const int nz,
            const int nztrue,
            const int ne,
            const int nJ,
            const int nw,
            const int ndwdx,
            const int ndwdp,
            const int nnz,
            const int ubw,
            const int lbw,
            amici::SecondOrderMode o2mode,
            const std::vector< amici::realtype > & p,
            std::vector< amici::realtype > k,
            const std::vector< int > & plist,
            std::vector< amici::realtype > idlist,
            std::vector< int > z2event )
```

constructor with model dimensions

Parameters

nx_rdata	number of state variables
nxtrue_rdata	number of state variables of the non-augmented model
nx_solver	number of state variables with conservation laws applied
nxtrue_solver	number of state variables of the non-augmented model with conservation laws applied
ny	number of observables
nytrue	number of observables of the non-augmented model
nz	number of event observables
nztrue	number of event observables of the non-augmented model
ne	number of events
nJ	number of objective functions
nw	number of repeating elements
ndwdx	number of nonzero elements in the x derivative of the repeating elements
ndwdp	number of nonzero elements in the p derivative of the repeating elements
nnz	number of nonzero elements in Jacobian
ubw	upper matrix bandwidth in the Jacobian
lbw	lower matrix bandwidth in the Jacobian
o2mode	second order sensitivity mode
p	parameters
k	constants
plist	indexes wrt to which sensitivities are to be computed
idlist	indexes indicating algebraic components (DAE only)
z2event	mapping of event outputs to events

Definition at line 704 of file model.cpp.

Here is the call graph for this function:

10.11.2.3 Model() [3/3]

```
Model (
            Model const & other )
```

Copy constructor

Parameters

other	object to copy from

Returns

Definition at line 789 of file model.cpp.

10.11.2.4 ~Model()

```
~Model ( ) [virtual]
```

destructor

Definition at line 856 of file model.cpp.

10.11.3 Member Function Documentation

10.11.3.1 operator=()

```
Model& operator= (
            Model const & other ) [delete]
```

Copy assignment is disabled until const members are removed

Parameters

other	object to copy from

Returns

10.11.3.2 clone()

```
virtual Model* clone ( ) const [pure virtual]
```

Returns

The clone

10.11.3.3 getSolver()

```
virtual std::unique_ptr<Solver> getSolver ( )  [pure virtual]
```

Retrieves the solver object

Returns

The Solver instance

Implemented in Model_DAE, and Model_ODE.

10.11.3.4 froot()

```
virtual void froot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            realtype * root )  [pure virtual]
```

Root function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
root	array to which values of the root function will be written

Implemented in Model_DAE, and Model_ODE.

Here is the caller graph for this function:

10.11.3.5 fxdot()

```
virtual void fxdot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot )  [pure virtual]
```

Residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
xdot	array to which values of the residual function will be written

Implemented in Model_ODE, and Model_DAE.

10.11.3.6 fsxdot()

```
virtual void fsxdot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            int ip,
            AmiVector * sx,
            AmiVector * sdx,
            AmiVector * sxdot )  [pure virtual]
```

Sensitivity Residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
ip	parameter index
sx	sensitivity state
sdx	time derivative of sensitivity state (DAE only)
sxdot	array to which values of the sensitivity residual function will be written

Implemented in Model_ODE, and Model_DAE.

10.11.3.7 fJ()

```
virtual void fJ (
            realtype t,
            realtype cj,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            DlsMat J )  [pure virtual]
```

Dense Jacobian function

Parameters

t	time

Parameters

cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
J	dense matrix to which values of the jacobian will be written

Implemented in Model_DAE, and Model_ODE.

Here is the caller graph for this function:

10.11.3.8 fJSparse()

```
virtual void fJSparse (
            realtype t,
            realtype cj,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            SlsMat J )  [pure virtual]
```

Sparse Jacobian function

Parameters

t	time
cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
J	sparse matrix to which values of the Jacobian will be written

Implemented in Model_DAE, and Model_ODE.

Here is the caller graph for this function:

10.11.3.9 fJDiag()

```
virtual void fJDiag (
            realtype t,
            AmiVector * Jdiag,
            realtype cj,
            AmiVector * x,
            AmiVector * dx )  [pure virtual]
```

Diagonal Jacobian function

Parameters

t	time
Jdiag	array to which the diagonal of the Jacobian will be written
cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)

Returns

flag indicating successful evaluation

Implemented in Model_ODE, and Model_DAE.

Here is the caller graph for this function:

10.11.3.10 fdxdotdp()

```
virtual void fdxdotdp (
            realtype t,
            AmiVector * x,
            AmiVector * dx )  [pure virtual]
```

parameter derivative of residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)

Returns

flag indicating successful evaluation

Implemented in Model_ODE, and Model_DAE.

Here is the caller graph for this function:

10.11.3.11 fJv()

```
virtual void fJv (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            AmiVector * v,
            AmiVector * nJv,
            realtype cj )  [pure virtual]
```

Jacobian multiply function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
v	multiplication vector (unused)
nJv	array to which result of multiplication will be written
cj	scaling factor (inverse of timestep, DAE only)

Implemented in Model_ODE, and Model_DAE.

Here is the caller graph for this function:

10.11.3.12 fx_rdata() [1/2]

```
void fx_rdata (
            AmiVector * x_rdata,
            const AmiVector * x_solver )
```

Expands conservation law for states

Parameters

x_rdata	pointer to state variables with conservation laws expanded (stored in rdata)
x_solver	pointer to state variables with conservation laws applied (solver returns this)

Definition at line 878 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.13 fsx_rdata() [1/2]

```
void fsx_rdata (
            AmiVectorArray * sx_rdata,
            const AmiVectorArray * sx_solver )
```

Expands conservation law for state sensitivities

Parameters

sx_rdata	pointer to state variable sensitivities with conservation laws expanded (stored in rdata)
sx_solver	pointer to state variable sensitivities with conservation laws applied (solver returns this)

Definition at line 908 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.14 fx0() [1/2]

```
void fx0 (
            AmiVector * x )
```

Initial states

Parameters

x	pointer to state variables

Definition at line 882 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.15 fx0_fixedParameters() [1/2]

```
void fx0_fixedParameters (
            AmiVector * x )
```

Sets only those initial states that are specified via fixedParmeters

Parameters

x	pointer to state variables

Definition at line 891 of file model.cpp.

Here is the call graph for this function:

10.11.3.16 fdx0()

```
void fdx0 (
            AmiVector * x0,
            AmiVector * dx0 )  [virtual]
```

Initial value for time derivative of states (only necessary for DAEs)

Parameters

x0	Vector with the initial states
dx0	Vector to which the initial derivative states will be written (only DAE)

Definition at line 906 of file model.cpp.

Here is the caller graph for this function:

10.11.3.17 fsx0() [1/2]

```
void fsx0 (
            AmiVectorArray * sx,
            const AmiVector * x )
```

Initial value for initial state sensitivities

Parameters

sx	pointer to state sensitivity variables
x	pointer to state variables

Definition at line 917 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.18 fsx0_fixedParameters() [1/2]

```
void fsx0_fixedParameters (
            AmiVectorArray * sx,
            const AmiVector * x )
```

Sets only those initial states sensitivities that are affected from fx0 fixedParmeters

Parameters

sx	pointer to state sensitivity variables
x	pointer to state variables

Definition at line 931 of file model.cpp.

Here is the call graph for this function:

10.11.3.19 fsdx0()

```
void fsdx0 ( ) [virtual]
```

Sensitivity of derivative initial states sensitivities sdx0 (only necessary for DAEs)

Definition at line 947 of file model.cpp.

Here is the caller graph for this function:

10.11.3.20 fstau() [1/2]

```
void fstau (
            const realtype t,
            const int ie,
            const AmiVector * x,
            const AmiVectorArray * sx )
```

Sensitivity of event timepoint, total derivative

Parameters

t	current timepoint
ie	event index
x	pointer to state variables
sx	pointer to state sensitivity variables

Definition at line 949 of file model.cpp.

Here is the call graph for this function:

10.11.3.21 fy() [1/2]

```
void fy (
            const realtype t,
            const int it,
            const AmiVector * x,
            ReturnData * rdata )
```

Observables / measurements

Parameters

t	current timepoint
it	timepoint index
x	current state
rdata	pointer to return data instance

Definition at line 956 of file model.cpp.

Here is the call graph for this function:

10.11.3.22 fdydp() [1/2]

```
void fdydp (
            const realtype t,
            const AmiVector * x )
```

partial derivative of observables y w.r.t. model parameters p

Parameters

t	current timepoint
x	current state

Definition at line 963 of file model.cpp.

Here is the call graph for this function:

10.11.3.23 fdydx() [1/2]

```
void fdydx (
            const realtype t,
            const AmiVector * x )
```

partial derivative of observables y w.r.t. state variables x

Parameters

t	current timepoint
x	current state

Definition at line 984 of file model.cpp.

Here is the call graph for this function:

10.11.3.24 fz() [1/2]

```
void fz (
            const int nroots,
            const int ie,
            const realtype t,
            const AmiVector * x,
            ReturnData * rdata )
```

Event-resolved output

Parameters

nroots	number of events for event index
ie	event index
t	current timepoint
x	current state
rdata	pointer to return data instance

Definition at line 994 of file model.cpp.

Here is the call graph for this function:

10.11.3.25 fsz() [1/2]

```
void fsz (
            const int nroots,
            const int ie,
            const realtype t,
            const AmiVector * x,
            const AmiVectorArray * sx,
            ReturnData * rdata )
```

Sensitivity of z, total derivative

Parameters

nroots	number of events for event index
ie	event index
t	current timepoint
x	current state
sx	current state sensitivities
rdata	pointer to return data instance

Definition at line 998 of file model.cpp.

Here is the call graph for this function:

10.11.3.26 frz() [1/2]

```
void frz (
            const int nroots,
            const int ie,
            const realtype t,
            const AmiVector * x,
            ReturnData * rdata )
```

Event root function of events (equal to froot but does not include non-output events)

Parameters

nroots	number of events for event index
ie	event index
t	current timepoint
x	current state
rdata	pointer to return data instance

Definition at line 1004 of file model.cpp.

Here is the call graph for this function:

10.11.3.27 fsrz() [1/2]

```
void fsrz (
            const int nroots,
            const int ie,
            const realtype t,
            const AmiVector * x,
            const AmiVectorArray * sx,
            ReturnData * rdata )
```

Sensitivity of rz, total derivative

Parameters

nroots	number of events for event index
ie	event index
t	current timepoint
x	current state
sx	current state sensitivities
rdata	pointer to return data instance

Definition at line 1008 of file model.cpp.

Here is the call graph for this function:

10.11.3.28 fdzdp() [1/2]

```
void fdzdp (
            const realtype t,
            const int ie,
            const AmiVector * x )
```

partial derivative of event-resolved output z w.r.t. to model parameters p

Parameters

ie	event index
t	current timepoint
x	current state

Definition at line 1014 of file model.cpp.

Here is the call graph for this function:

10.11.3.29 fdzdx() [1/2]

```
void fdzdx (
            const realtype t,
            const int ie,
            const AmiVector * x )
```

partial derivative of event-resolved output z w.r.t. to model states x

Parameters

ie	event index
t	current timepoint
x	current state

Definition at line 1021 of file model.cpp.

Here is the call graph for this function:

10.11.3.30 fdrzdp() [1/2]

```
void fdrzdp (
            const realtype t,
            const int ie,
            const AmiVector * x )
```

Sensitivity of event-resolved root output w.r.t. to model parameters p

Parameters

ie	event index
t	current timepoint
x	current state

Definition at line 1026 of file model.cpp.

Here is the call graph for this function:

10.11.3.31 fdrzdx() [1/2]

```
void fdrzdx (
            const realtype t,
            const int ie,
            const AmiVector * x )
```

Sensitivity of event-resolved measurements rz w.r.t. to model states x

Parameters

ie	event index
t	current timepoint
x	current state

Definition at line 1034 of file model.cpp.

Here is the call graph for this function:

10.11.3.32 fdeltax() [1/2]

```
void fdeltax (
            const int ie,
            const realtype t,
            const AmiVector * x,
            const AmiVector * xdot,
            const AmiVector * xdot_old )
```

State update functions for events

Parameters

ie	event index
t	current timepoint
x	current state
xdot	current residual function values
xdot_old	value of residual function before event

Definition at line 1039 of file model.cpp.

Here is the call graph for this function:

10.11.3.33 fdeltasx() [1/2]

```
void fdeltasx (
            const int ie,
            const realtype t,
            const AmiVector * x,
            const AmiVectorArray * sx,
            const AmiVector * xdot,
            const AmiVector * xdot_old )
```

Sensitivity update functions for events, total derivative

Parameters

ie	event index
t	current timepoint
x	current state
sx	current state sensitivity
xdot	current residual function values
xdot_old	value of residual function before event

Definition at line 1045 of file model.cpp.

Here is the call graph for this function:

10.11.3.34 fdeltaxB() [1/2]

```
void fdeltaxB (
            const int ie,
            const realtype t,
            const AmiVector * x,
            const AmiVector * xB,
            const AmiVector * xdot,
            const AmiVector * xdot_old )
```

Adjoint state update functions for events

Parameters

ie	event index
t	current timepoint
x	current state
xB	current adjoint state
xdot	current residual function values
xdot_old	value of residual function before event

Definition at line 1054 of file model.cpp.

Here is the call graph for this function:

10.11.3.35 fdeltaqB() [1/2]

```
void fdeltaqB (
            const int ie,
            const realtype t,
            const AmiVector * x,
            const AmiVector * xB,
            const AmiVector * xdot,
            const AmiVector * xdot_old )
```

Quadrature state update functions for events

Parameters

ie	event index
t	current timepoint
x	current state
xB	current adjoint state
xdot	current residual function values
xdot_old	value of residual function before event

Definition at line 1060 of file model.cpp.

Here is the call graph for this function:

10.11.3.36 fsigmay() [1/2]

```
void fsigmay (
            const int it,
            ReturnData * rdata,
            const ExpData * edata )
```

Standard deviation of measurements

Parameters

it	timepoint index
edata	pointer to experimental data instance
rdata	pointer to return data instance

Definition at line 1068 of file model.cpp.

Here is the call graph for this function:

10.11.3.37 fdsigmaydp() [1/2]

```
void fdsigmaydp (
            const int it,
            ReturnData * rdata,
            const ExpData * edata )
```

partial derivative of standard deviation of measurements w.r.t. model

Parameters

it	timepoint index
rdata	pointer to return data instance
edata	pointer to ExpData data instance holding sigma values

Definition at line 1093 of file model.cpp.

Here is the call graph for this function:

10.11.3.38 fsigmaz() [1/2]

```
void fsigmaz (
            const realtype t,
            const int ie,
            const int * nroots,
            ReturnData * rdata,
            const ExpData * edata )
```

Standard deviation of events

Parameters

t	current timepoint
ie	event index
nroots	array with event numbers
edata	pointer to experimental data instance
rdata	pointer to return data instance

Definition at line 1122 of file model.cpp.

Here is the call graph for this function:

10.11.3.39 fdsigmazdp() [1/2]

```
void fdsigmazdp (
            const realtype t,
            const int ie,
            const int * nroots,
            ReturnData * rdata,
            const ExpData * edata )
```

Sensitivity of standard deviation of events measurements w.r.t. model parameters p

Parameters

t	current timepoint
ie	event index
nroots	array with event numbers
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1141 of file model.cpp.

Here is the call graph for this function:

10.11.3.40 fJy() [1/2]

```
void fJy (
            const int it,
            ReturnData * rdata,
            const ExpData * edata )
```

negative log-likelihood of measurements y

Parameters

it	timepoint index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1166 of file model.cpp.

Here is the call graph for this function:

10.11.3.41 fJz() [1/2]

```
void fJz (
            const int nroots,
            ReturnData * rdata,
            const ExpData * edata )
```

negative log-likelihood of event-resolved measurements z

Parameters

nroots	event index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1178 of file model.cpp.

Here is the call graph for this function:

10.11.3.42 fJrz() [1/2]

```
void fJrz (
            const int nroots,
            ReturnData * rdata,
            const ExpData * edata )
```

regularization of negative log-likelihood with roots of event-resolved measurements rz

Parameters

nroots	event index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1190 of file model.cpp.

Here is the call graph for this function:

10.11.3.43 fdJydy() [1/2]

```
void fdJydy (
            const int it,
            const ReturnData * rdata,
            const ExpData * edata )
```

partial derivative of time-resolved measurement negative log-likelihood Jy

Parameters

it	timepoint index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1202 of file model.cpp.

Here is the call graph for this function:

10.11.3.44 fdJydsigma() [1/2]

```
void fdJydsigma (
            const int it,
            const ReturnData * rdata,
            const ExpData * edata )
```

Sensitivity of time-resolved measurement negative log-likelihood Jy w.r.t. standard deviation sigma

Parameters

it	timepoint index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1222 of file model.cpp.

Here is the call graph for this function:

10.11.3.45 fdJzdz() [1/2]

```
void fdJzdz (
            const int nroots,
            const ReturnData * rdata,
            const ExpData * edata )
```

partial derivative of event measurement negative log-likelihood Jz

Parameters

nroots	event index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1242 of file model.cpp.

Here is the call graph for this function:

10.11.3.46 fdJzdsigma() [1/2]

```
void fdJzdsigma (
            const int nroots,
            const ReturnData * rdata,
            const ExpData * edata )
```

Sensitivity of event measurement negative log-likelihood Jz w.r.t. standard deviation sigmaz

Parameters

nroots	event index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1253 of file model.cpp.

Here is the call graph for this function:

10.11.3.47 fdJrzdz() [1/2]

```
void fdJrzdz (
            const int nroots,
            const ReturnData * rdata,
            const ExpData * edata )
```

partial derivative of event measurement negative log-likelihood Jz

Parameters

nroots	event index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1264 of file model.cpp.

Here is the call graph for this function:

10.11.3.48 fdJrzdsigma() [1/2]

```
void fdJrzdsigma (
            const int nroots,
            const ReturnData * rdata,
            const ExpData * edata )
```

Sensitivity of event measurement negative log-likelihood Jz w.r.t. standard deviation sigmaz

Parameters

nroots	event index
rdata	pointer to return data instance
edata	pointer to experimental data instance

Definition at line 1275 of file model.cpp.

Here is the call graph for this function:

10.11.3.49 fsy()

```
void fsy (
            const int it,
            const AmiVectorArray * sx,
            ReturnData * rdata )
```

Sensitivity of measurements y, total derivative sy = dydx $*$ sx + dydp

Parameters

it	timepoint index
sx	pointer to state sensitivities
rdata	pointer to return data instance

Definition at line 13 of file model.cpp.

Here is the call graph for this function:

10.11.3.50 fsz_tf()

```
void fsz_tf (
            const int * nroots,
            const int ie,
            ReturnData * rdata )
```

Sensitivity of z at final timepoint (ignores sensitivity of timepoint), total derivative

Parameters

nroots	number of events for event index
ie	event index
rdata	pointer to return data instance

Definition at line 31 of file model.cpp.

Here is the call graph for this function:

10.11.3.51 fsJy()

```
void fsJy (
            const int it,
```

```
            const std::vector< realtype > & dJydx,
            const AmiVectorArray * sx,
            ReturnData * rdata )
```

Sensitivity of time-resolved measurement negative log-likelihood Jy, total derivative

Parameters

it	timepoint index
sx	pointer to state sensitivities
dJydx	vector with values of state derivative of Jy
rdata	pointer to return data instance

Definition at line 38 of file model.cpp.

Here is the call graph for this function:

10.11.3.52 fdJydp()

```
void fdJydp (
            const int it,
            ReturnData * rdata,
            const ExpData * edata )
```

Compute sensitivity of time-resolved measurement negative log-likelihood Jy w.r.t. parameters for the given timepoint. Add result to respective fields in rdata.

Parameters

it	timepoint index
edata	pointer to experimental data instance
rdata	pointer to return data instance

Definition at line 68 of file model.cpp.

Here is the call graph for this function:

10.11.3.53 fdJydx()

```
void fdJydx (
            std::vector< realtype > * dJydx,
            const int it,
            const ReturnData * rdata,
            const ExpData * edata )
```

Sensitivity of time-resolved measurement negative log-likelihood Jy w.r.t. state variables

Parameters

dJydx	pointer to vector with values of state derivative of Jy
it	timepoint index
edata	pointer to experimental data instance
rdata	pointer to return data instance

Definition at line 115 of file model.cpp.

Here is the call graph for this function:

10.11.3.54 fsJz()

```
void fsJz (
            const int nroots,
            const std::vector< realtype > & dJzdx,
            const AmiVectorArray * sx,
            ReturnData * rdata )
```

Sensitivity of event-resolved measurement negative log-likelihood Jz, total derivative

Parameters

nroots	event index
dJzdx	vector with values of state derivative of Jz
sx	pointer to state sensitivities
rdata	pointer to return data instance

Definition at line 134 of file model.cpp.

Here is the call graph for this function:

10.11.3.55 fdJzdp()

```
void fdJzdp (
            const int nroots,
            realtype t,
            const ExpData * edata,
            const ReturnData * rdata )
```

Sensitivity of event-resolved measurement negative log-likelihood Jz w.r.t. parameters

Parameters

nroots	event index
t	current timepoint
edata	pointer to experimental data instance
rdata	pointer to return data instance

Definition at line 164 of file model.cpp.

Here is the call graph for this function:

10.11.3.56 fdJzdx()

```
void fdJzdx (
            std::vector< realtype > * dJzdx,
            const int nroots,
            realtype t,
            const ExpData * edata,
            const ReturnData * rdata )
```

Sensitivity of event-resolved measurement negative log-likelihood Jz w.r.t. state variables

Parameters

dJzdx	pointer to vector with values of state derivative of Jz
nroots	event index
t	current timepoint
edata	pointer to experimental data instance
rdata	pointer to return data instance

Definition at line 200 of file model.cpp.

Here is the call graph for this function:

10.11.3.57 initialize()

```
void initialize (
            AmiVector * x,
            AmiVector * dx,
            AmiVectorArray * sx,
            AmiVectorArray * sdx,
            bool computeSensitivities )
```

initialization of model properties

Parameters

x	pointer to state variables
dx	pointer to time derivative of states (DAE only)
sx	pointer to state variable sensititivies
sdx	pointer to time derivative of state sensitivities (DAE only)
computeSensitivities	flag indicating whether sensitivities are to be computed

Definition at line 223 of file model.cpp.

Here is the call graph for this function:

10.11.3.58 initializeStates()

```
void initializeStates (
            AmiVector * x )
```

initialization of initial states

Parameters

x	pointer to state variables

Definition at line 240 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.59 initializeStateSensitivities()

```
void initializeStateSensitivities (
            AmiVectorArray * sx,
            AmiVector * x )
```

initialization of initial state sensitivities

Parameters

sx	pointer to state variable sensititivies
x	pointer to state variables

Definition at line 253 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.60 initHeaviside()

```
void initHeaviside (
            AmiVector * x,
            AmiVector * dx )
```

initHeaviside initialises the heaviside variables h at the intial time t0 heaviside variables activate/deactivate on event occurences

Parameters

x	pointer to state variables
dx	pointer to time derivative of states (DAE only)

Definition at line 271 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.61 nplist()

```
int nplist ( ) const
```

Returns

length of sensitivity index vector

Definition at line 288 of file model.cpp.

Here is the caller graph for this function:

10.11.3.62 np()

```
int np ( ) const
```

Returns

length of parameter vector

Definition at line 292 of file model.cpp.

Here is the caller graph for this function:

10.11.3.63 nk()

```
int nk ( ) const
```

Returns

length of constant vector

Definition at line 296 of file model.cpp.

Here is the caller graph for this function:

10.11.3.64 ncl()

```
int ncl ( ) const
```

Returns

difference between nx_rdata and nx_solver

Definition at line 605 of file model.h.

Here is the caller graph for this function:

10.11.3.65 k()

```
const double * k ( ) const
```

Returns

pointer to constants array

Definition at line 300 of file model.cpp.

Here is the caller graph for this function:

10.11.3.66 nMaxEvent()

```
int nMaxEvent ( ) const
```

Returns

maximum number of events that may occur for each type

Definition at line 304 of file model.cpp.

10.11.3.67 setNMaxEvent()

```
void setNMaxEvent (
            int nmaxevent )
```

Parameters

nmaxevent	maximum number of events that may occur for each type

Definition at line 308 of file model.cpp.

10.11.3.68 nt()

```
int nt ( ) const
```

Returns

number of timepoints

Definition at line 312 of file model.cpp.

10.11.3.69 getParameterScale()

```
const std::vector< ParameterScaling > & getParameterScale ( ) const
```

Returns

vector of parameter scale

Definition at line 316 of file model.cpp.

10.11.3.70 setParameterScale() [1/2]

```
void setParameterScale (
            ParameterScaling pscale )
```

Parameters

pscale	scalar parameter scale for all parameters

Definition at line 320 of file model.cpp.

Here is the call graph for this function:

10.11.3.71 setParameterScale() [2/2]

```
void setParameterScale (
            const std::vector< ParameterScaling > & pscaleVec )
```

Parameters

pscaleVec	vector of parameter scales

Definition at line 326 of file model.cpp.

Here is the call graph for this function:

10.11.3.72 getParameters()

```
std::vector< realtype > const & getParameters ( ) const
```

Returns

The user-set parameters (see also getUnscaledParameters)

Definition at line 334 of file model.cpp.

10.11.3.73 setParameters()

```
void setParameters (
            std::vector< realtype > const & p )
```

Parameters

p	vector of parameters

Definition at line 421 of file model.cpp.

Here is the call graph for this function:

10.11.3.74 getUnscaledParameters()

```
const std::vector< realtype > & getUnscaledParameters ( ) const
```

Returns

unscaled parameters

Definition at line 483 of file model.cpp.

10.11.3.75 getFixedParameters()

```
const std::vector< realtype > & getFixedParameters ( ) const
```

Returns

vector of fixed parameters

Definition at line 487 of file model.cpp.

10.11.3.76 setFixedParameters()

```
void setFixedParameters (
            std::vector< realtype > const & k )
```

Parameters

k	vector of fixed parameters

Definition at line 513 of file model.cpp.

Here is the call graph for this function:

10.11.3.77 getFixedParameterById()

```
realtype getFixedParameterById (
            std::string const & par_id ) const
```

Parameters

par_id	parameter id

Returns

parameter value

Definition at line 491 of file model.cpp.

Here is the call graph for this function:

10.11.3.78 getFixedParameterByName()

```
realtype getFixedParameterByName (
            std::string const & par_name ) const
```

Parameters

par_name	parameter name

Returns

parameter value

Definition at line 502 of file model.cpp.

Here is the call graph for this function:

10.11.3.79 setFixedParameterById()

```
void setFixedParameterById (
            std::string const & par_id,
            realtype value )
```

Parameters

par_id	fixed parameter id
value	fixed parameter value

Definition at line 519 of file model.cpp.

Here is the call graph for this function:

10.11.3.80 setFixedParametersByIdRegex()

```
int setFixedParametersByIdRegex (
            std::string const & par_id_regex,
            realtype value )
```

Parameters

par_id_regex	fixed parameter name regex
value	fixed parameter value

Returns

number of fixed parameter ids that matched the regex

Definition at line 531 of file model.cpp.

Here is the call graph for this function:

10.11.3.81 setFixedParameterByName()

```
void setFixedParameterByName (
            std::string const & par_name,
            realtype value )
```

Parameters

par_name	fixed parameter id
value	fixed parameter value

Definition at line 543 of file model.cpp.

Here is the call graph for this function:

10.11.3.82 setFixedParametersByNameRegex()

```
int setFixedParametersByNameRegex (
            std::string const & par_name_regex,
            realtype value )
```

Parameters

par_name_regex	fixed parameter name regex
value	fixed parameter value

Returns

number of fixed parameter names that matched the regex

Definition at line 555 of file model.cpp.

Here is the call graph for this function:

10.11.3.83 getTimepoints()

```
std::vector< realtype > const & getTimepoints ( ) const
```

Returns

timepoint vector

Definition at line 567 of file model.cpp.

10.11.3.84 setTimepoints()

```
void setTimepoints (
            std::vector< realtype > const & ts )
```

Parameters

ts	timepoint vector

Definition at line 571 of file model.cpp.

10.11.3.85 getStateIsNonNegative()

```
std::vector< bool > const & getStateIsNonNegative ( ) const
```

Returns

vector of flags

Definition at line 579 of file model.cpp.

10.11.3.86 setStateIsNonNegative()

```
void setStateIsNonNegative (
            std::vector< bool > const & stateIsNonNegative )
```

Parameters

stateIsNonNegative	vector of flags

Definition at line 583 of file model.cpp.

10.11.3.87 t()

```
double t (
            int idx ) const
```

Parameters

idx	timepoint index

Returns

timepoint

Definition at line 599 of file model.cpp.

Here is the caller graph for this function:

10.11.3.88 getParameterList()

```
const std::vector< int > & getParameterList ( ) const
```

Returns

list of parameter indices

Definition at line 603 of file model.cpp.

10.11.3.89 setParameterList()

```
void setParameterList (
            std::vector< int > const & plist )
```

Parameters

plist	list of parameter indices

Definition at line 607 of file model.cpp.

Here is the call graph for this function:

10.11.3.90 getInitialStates()

```
std::vector< realtype > const & getInitialStates ( ) const
```

Returns

initial state vector

Definition at line 618 of file model.cpp.

10.11.3.91 setInitialStates()

```
void setInitialStates (
            std::vector< realtype > const & x0 )
```

Parameters

x0	initial state vector

Definition at line 622 of file model.cpp.

10.11.3.92 getInitialStateSensitivities()

```
const std::vector< realtype > & getInitialStateSensitivities ( ) const
```

Returns

vector of initial state sensitivities

Definition at line 635 of file model.cpp.

10.11.3.93 setInitialStateSensitivities()

```
void setInitialStateSensitivities (
            std::vector< realtype > const & sx0 )
```

Parameters

sx0	vector of initial state sensitivities with chainrule applied. This could be a slice of ReturnData::sx or ReturnData::sx0

Definition at line 639 of file model.cpp.

Here is the call graph for this function:

10.11.3.94 setUnscaledInitialStateSensitivities()

```
void setUnscaledInitialStateSensitivities (
            std::vector< realtype > const & sx0 )
```

Parameters

sx0	vector of initial state sensitivities without chainrule applied. This could be the readin from a model.sx0data saved to hdf5.

Definition at line 676 of file model.cpp.

Here is the call graph for this function:

10.11.3.95 t0()

```
double t0 ( ) const
```

Returns

simulation start time

Definition at line 691 of file model.cpp.

Here is the caller graph for this function:

10.11.3.96 setT0()

```
void setT0 (
            double t0 )
```

Parameters

t0	simulation start time

Definition at line 695 of file model.cpp.

Here is the call graph for this function:

10.11.3.97 plist()

```
int plist (
            int pos ) const
```

Parameters

pos	index

Returns

entry

Definition at line 699 of file model.cpp.

Here is the caller graph for this function:

10.11.3.98 fw() [1/2]

```
void fw (
            const realtype t,
            const realtype * x )
```

Parameters

t	timepoint
x	array with the states

Definition at line 1285 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.99 fdwdp() [1/2]

```
void fdwdp (
            const realtype t,
            const realtype * x )
```

Parameters

t	timepoint
x	array with the states

Definition at line 1290 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.100 fdwdx() [1/2]

```
void fdwdx (
            const realtype t,
            const realtype * x )
```

Parameters

t	timepoint
x	array with the states

Definition at line 1296 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.101 fres()

```
void fres (
            const int it,
            ReturnData * rdata,
            const ExpData * edata )
```

residual function

Parameters

it	time index
rdata	ReturnData instance to which result will be written
edata	ExpData instance containing observable data

Definition at line 1302 of file model.cpp.

Here is the call graph for this function:

10.11.3.102 fchi2()

```
void fchi2 (
            const int it,
            ReturnData * rdata )
```

chi-squared function

Parameters

it	time index
rdata	ReturnData instance to which result will be written

Definition at line 1317 of file model.cpp.

10.11.3.103 fsres()

```
void fsres (
            const int it,
            ReturnData * rdata,
            const ExpData * edata )
```

residual sensitivity function

Parameters

it	time index
rdata	ReturnData instance to which result will be written
edata	ExpData instance containing observable data

Definition at line 1327 of file model.cpp.

Here is the call graph for this function:

10.11.3.104 fFIM()

```
void fFIM (
            const int it,
            ReturnData * rdata )
```

fisher information matrix function

Parameters

it	time index
rdata	ReturnData instance to which result will be written

Definition at line 1343 of file model.cpp.

Here is the call graph for this function:

10.11.3.105 updateHeaviside()

```
void updateHeaviside (
            const std::vector< int > & rootsfound )
```

updateHeaviside updates the heaviside variables h on event occurences

Parameters

rootsfound	provides the direction of the zero-crossing, so adding it will give the right update to the heaviside variables (zero if no root was found)

Definition at line 1359 of file model.cpp.

10.11.3.106 updateHeavisideB()

```
void updateHeavisideB (
            const int * rootsfound )
```

updateHeavisideB updates the heaviside variables h on event occurences in the backward problem

Parameters

rootsfound	provides the direction of the zero-crossing, so adding it will give the right update to the heaviside variables (zero if no root was found)

Definition at line 1365 of file model.cpp.

10.11.3.107 gett()

```
realtype gett (
            const int it,
            const ReturnData * rdata ) const
```

get current timepoint from index

Parameters

it	timepoint index
rdata	pointer to return data instance

Returns

current timepoint

Definition at line 1384 of file model.cpp.

10.11.3.108 checkFinite()

```
int checkFinite (
            const int N,
            const realtype * array,
            const char * fun ) const
```

Parameters

N	number of datapoints in array
array	arrays of values
fun	name of the fucntion that generated the values

Returns

AMICI_RECOVERABLE_ERROR if a NaN/Inf value was found, AMICI_SUCCESS otherwise

Definition at line 1412 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.109 getAmiciVersion()

```
virtual const std::string getAmiciVersion ( ) const  [virtual]
```

Returns

ver amici version string

Definition at line 935 of file model.h.

10.11.3.110 getAmiciCommit()

```
virtual const std::string getAmiciCommit ( ) const  [virtual]
```

Returns

ver amici commit string

Definition at line 943 of file model.h.

10.11.3.111 hasParameterNames()

```
virtual bool hasParameterNames ( ) const  [virtual]
```

Returns

boolean indicating whether parameter names were set

Definition at line 951 of file model.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.112 getParameterNames()

```
virtual std::vector<std::string> getParameterNames ( ) const  [virtual]
```

Returns

the names

Definition at line 957 of file model.h.

Here is the caller graph for this function:

10.11.3.113 hasStateNames()

```
virtual bool hasStateNames ( ) const  [virtual]
```

Returns

boolean indicating whether state names were set

Definition at line 963 of file model.h.

Here is the call graph for this function:

10.11.3.114 getStateNames()

```
virtual std::vector<std::string> getStateNames ( ) const  [virtual]
```

Returns

the names

Definition at line 969 of file model.h.

Here is the caller graph for this function:

10.11.3.115 hasFixedParameterNames()

```
virtual bool hasFixedParameterNames ( ) const  [virtual]
```

Returns

boolean indicating whether fixed parameter names were set

Definition at line 975 of file model.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.116 getFixedParameterNames()

```
virtual std::vector<std::string> getFixedParameterNames ( ) const  [virtual]
```

Returns

the names

Definition at line 981 of file model.h.

Here is the caller graph for this function:

10.11.3.117 hasObservableNames()

```
virtual bool hasObservableNames ( ) const  [virtual]
```

Returns

boolean indicating whether observabke names were set

Definition at line 987 of file model.h.

Here is the call graph for this function:

10.11.3.118 getObservableNames()

```
virtual std::vector<std::string> getObservableNames ( ) const  [virtual]
```

Returns

the names

Definition at line 993 of file model.h.

Here is the caller graph for this function:

10.11.3.119 hasParameterIds()

```
virtual bool hasParameterIds ( ) const  [virtual]
```

Returns

boolean indicating whether parameter ids were set

Definition at line 999 of file model.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.120 getParameterIds()

```
virtual std::vector<std::string> getParameterIds ( ) const  [virtual]
```

Returns

the ids

Definition at line 1005 of file model.h.

Here is the caller graph for this function:

10.11.3.121 getParameterById()

```
realtype getParameterById (
            std::string const & par_id ) const
```

Parameters

par↩ _id	parameter id

Returns

parameter value

Definition at line 405 of file model.cpp.

Here is the call graph for this function:

10.11.3.122 getParameterByName()

```
realtype getParameterByName (
            std::string const & par_name ) const
```

Parameters

par_name	parameter name

Returns

parameter value

Definition at line 411 of file model.cpp.

Here is the call graph for this function:

10.11.3.123 setParameterById()

```
void setParameterById (
            std::string const & par_id,
            realtype value )
```

Parameters

par_id	parameter id
value	parameter value

Definition at line 429 of file model.cpp.

Here is the call graph for this function:

10.11.3.124 setParametersByIdRegex()

```
int setParametersByIdRegex (
            std::string const & par_id_regex,
            realtype value )
```

Parameters

par_id_regex	parameter id regex
value	parameter value

Returns

number of parameter ids that matched the regex

Definition at line 442 of file model.cpp.

Here is the call graph for this function:

10.11.3.125 setParameterByName()

```
void setParameterByName (
            std::string const & par_name,
            realtype value )
```

Parameters

par_name	parameter name
value	parameter value

Definition at line 455 of file model.cpp.

Here is the call graph for this function:

10.11.3.126 setParametersByNameRegex()

```
int setParametersByNameRegex (
            std::string const & par_name_regex,
            realtype value )
```

Parameters

par_name_regex	parameter name regex
value	parameter value

Returns

number of fixed parameter names that matched the regex

Definition at line 468 of file model.cpp.

Here is the call graph for this function:

10.11.3.127 hasStateIds()

```
virtual bool hasStateIds ( ) const  [virtual]
```

Returns

Definition at line 1057 of file model.h.

Here is the call graph for this function:

10.11.3.128 getStateIds()

```
virtual std::vector<std::string> getStateIds ( ) const  [virtual]
```

Returns

the ids

Definition at line 1063 of file model.h.

Here is the caller graph for this function:

10.11.3.129 hasFixedParameterIds()

```
virtual bool hasFixedParameterIds ( ) const  [virtual]
```

Returns

boolean indicating whether fixed parameter ids were set

Definition at line 1071 of file model.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.130 getFixedParameterIds()

```
virtual std::vector<std::string> getFixedParameterIds ( ) const  [virtual]
```

Returns

the ids

Definition at line 1077 of file model.h.

Here is the caller graph for this function:

10.11.3.131 hasObservableIds()

```
virtual bool hasObservableIds ( ) const  [virtual]
```

Returns

boolean indicating whether observale ids were set

Definition at line 1085 of file model.h.

Here is the call graph for this function:

10.11.3.132 getObservableIds()

```
virtual std::vector<std::string> getObservableIds ( ) const  [virtual]
```

Returns

the ids

Definition at line 1091 of file model.h.

Here is the caller graph for this function:

10.11.3.133 setSteadyStateSensitivityMode()

```
void setSteadyStateSensitivityMode (
            const SteadyStateSensitivityMode mode )
```

Parameters

mode	steadyStateSensitivityMode

Definition at line 1099 of file model.h.

10.11.3.134 getSteadyStateSensitivityMode()

```
SteadyStateSensitivityMode getSteadyStateSensitivityMode ( ) const
```

Returns

flag value

Definition at line 1107 of file model.h.

10.11.3.135 setReinitializeFixedParameterInitialStates()

```
void setReinitializeFixedParameterInitialStates (
            bool flag )
```

Parameters

flag	true/false

Definition at line 1116 of file model.h.

Here is the call graph for this function:

10.11.3.136 getReinitializeFixedParameterInitialStates()

```
bool getReinitializeFixedParameterInitialStates ( ) const
```

Returns

flag true/false

Definition at line 1130 of file model.h.

Here is the caller graph for this function:

10.11.3.137 fx_rdata() [2/2]

```
virtual void fx_rdata (
            realtype * x_rdata,
            const realtype * x_solver,
            const realtype * tcl )  [protected], [virtual]
```

model specific implementation of fx_rdata

Parameters

x_rdata	state variables with conservation laws expanded
x_solver	state variables with conservation laws applied
tcl	total abundances for conservation laws

Definition at line 1212 of file model.h.

10.11.3.138 fsx_rdata() [2/2]

```
virtual void fsx_rdata (
            realtype * sx_rdata,
            const realtype * sx_solver,
            const realtype * stcl,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsx_solver

Parameters

sx_rdata	state sensitivity variables with conservation laws expanded
sx_solver	state sensitivity variables with conservation laws applied
stcl	sensitivities of total abundances for conservation laws
ip	sensitivity index

Definition at line 1229 of file model.h.

Here is the call graph for this function:

10.11.3.139 fx_solver()

```
virtual void fx_solver (
            realtype * x_solver,
            const realtype * x_rdata )  [protected], [virtual]
```

model specific implementation of fx_solver

Parameters

x_solver	state variables with conservation laws applied
x_rdata	state variables with conservation laws expanded

Definition at line 1238 of file model.h.

Here is the caller graph for this function:

10.11.3.140 fsx_solver()

```
virtual void fsx_solver (
            realtype * sx_solver,
            const realtype * sx_rdata )  [protected], [virtual]
```

model specific implementation of fsx_solver

Parameters

sx_rdata	state sensitivity variables with conservation laws expanded
sx_solver	state sensitivity variables with conservation laws applied

Definition at line 1251 of file model.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.141 ftotal_cl()

```
virtual void ftotal_cl (
            realtype * total_cl,
            const realtype * x_rdata )  [protected], [virtual]
```

model specific implementation of ftotal_cl

Parameters

total_cl	total abundances of conservation laws
x_rdata	state variables with conservation laws expanded

Definition at line 1262 of file model.h.

Here is the caller graph for this function:

10.11.3.142 fstotal_cl()

```
virtual void fstotal_cl (
            realtype * stotal_cl,
            const realtype * sx_rdata,
            const int ip )  [protected], [virtual]
```

model specific implementation of fstotal_cl

Parameters

stotal↩ _cl	sensitivites for the total abundances of conservation laws
sx_rdata	state sensitivity variables with conservation laws expanded
ip	sensitivity index

Definition at line 1276 of file model.h.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.143 fx0() [2/2]

```
virtual void fx0 (
            realtype * x0,
            const realtype t,
            const realtype * p,
            const realtype * k )  [protected], [virtual]
```

model specific implementation of fx0

Parameters

x0	initial state
t	initial time
p	parameter vector
k	constant vector

Definition at line 1290 of file model.h.

10.11.3.144 fx0_fixedParameters() [2/2]

```
virtual void fx0_fixedParameters (
            realtype * x0,
            const realtype t,
            const realtype * p,
            const realtype * k )  [protected], [virtual]
```

model specific implementation of fx0_fixedParameters

Parameters

x0	initial state
t	initial time
p	parameter vector
k	constant vector

Definition at line 1300 of file model.h.

10.11.3.145 fsx0_fixedParameters() [2/2]

```
virtual void fsx0_fixedParameters (
            realtype * sx0,
            const realtype t,
            const realtype * x0,
            const realtype * p,
            const realtype * k,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsx0_fixedParameters

Parameters

sx0	initial state sensitivities
t	initial time
x0	initial state
p	parameter vector
k	constant vector
ip	sensitivity index

Definition at line 1311 of file model.h.

10.11.3.146 fsx0() [2/2]

```
virtual void fsx0 (
            realtype * sx0,
```

```
            const realtype t,
            const realtype * x0,
            const realtype * p,
            const realtype * k,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsx0

Parameters

sx0	initial state sensitivities
t	initial time
x0	initial state
p	parameter vector
k	constant vector
ip	sensitivity index

Definition at line 1322 of file model.h.

10.11.3.147 fstau() [2/2]

```
virtual void fstau (
            realtype * stau,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * sx,
            const int ip,
            const int ie )  [protected], [virtual]
```

model specific implementation of fstau

Parameters

stau	total derivative of event timepoint
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
sx	current state sensitivity
ip	sensitivity index
ie	event index

Definition at line 1337 of file model.h.

10.11.3.148 fy() [2/2]

```
virtual void fy (
            realtype * y,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w )  [protected], [virtual]
```

model specific implementation of fy

Parameters

y	model output at current timepoint
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
w	repeating elements vector

Definition at line 1350 of file model.h.

10.11.3.149 fdydp() [2/2]

```
virtual void fdydp (
            realtype * dydp,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip,
            const realtype * w,
            const realtype * dwdp )  [protected], [virtual]
```

model specific implementation of fdydp

Parameters

dydp	partial derivative of observables y w.r.t. model parameters p
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
ip	parameter index w.r.t. which the derivative is requested
w	repeating elements vector
dwdp	Recurring terms in xdot, parameter derivative

Definition at line 1365 of file model.h.

10.11.3.150 fdydx() [2/2]

```
virtual void fdydx (
            realtype * dydx,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation of fdydx

Parameters

dydx	partial derivative of observables y w.r.t. model states x
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
w	repeating elements vector
dwdx	Recurring terms in xdot, state derivative

Definition at line 1379 of file model.h.

10.11.3.151 fz() [2/2]

```
virtual void fz (
            realtype * z,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h )  [protected], [virtual]
```

model specific implementation of fz

Parameters

z	value of event output
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector

Definition at line 1392 of file model.h.

10.11.3.152 fsz() [2/2]

```
virtual void fsz (
            realtype * sz,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * sx,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsz

Parameters

sz	Sensitivity of rz, total derivative
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
sx	current state sensitivity
ip	sensitivity index

Definition at line 1407 of file model.h.

10.11.3.153 frz() [2/2]

```
virtual void frz (
            realtype * rz,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h )  [protected], [virtual]
```

model specific implementation of frz

Parameters

rz	value of root function at current timepoint (non-output events not included)
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector

Definition at line 1420 of file model.h.

10.11.3.154 fsrz() [2/2]

```
virtual void fsrz (
            realtype * srz,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * sx,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsrz

Parameters

srz	Sensitivity of rz, total derivative
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
sx	current state sensitivity
h	heavyside vector
ip	sensitivity index

Definition at line 1435 of file model.h.

10.11.3.155 fdzdp() [2/2]

```
virtual void fdzdp (
            realtype * dzdp,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip )  [protected], [virtual]
```

model specific implementation of fdzdp

Parameters

dzdp	partial derivative of event-resolved output z w.r.t. model parameters p
ie	event index
t	current time

Parameters

x	current state
p	parameter vector
k	constant vector
h	heavyside vector
ip	parameter index w.r.t. which the derivative is requested

Definition at line 1449 of file model.h.

10.11.3.156 fdzdx() [2/2]

```
virtual void fdzdx (
            realtype * dzdx,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h )  [protected], [virtual]
```

model specific implementation of fdzdx

Parameters

dzdx	partial derivative of event-resolved output z w.r.t. model states x
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector

Definition at line 1462 of file model.h.

10.11.3.157 fdrzdp() [2/2]

```
virtual void fdrzdp (
            realtype * drzdp,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip )  [protected], [virtual]
```

model specific implementation of fdrzdp

Parameters

drzdp	partial derivative of root output rz w.r.t. model parameters p
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
ip	parameter index w.r.t. which the derivative is requested

Definition at line 1476 of file model.h.

10.11.3.158 fdrzdx() [2/2]

```
virtual void fdrzdx (
            realtype * drzdx,
            const int ie,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h )  [protected], [virtual]
```

model specific implementation of fdrzdx

Parameters

drzdx	partial derivative of root output rz w.r.t. model states x
ie	event index
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector

Definition at line 1489 of file model.h.

10.11.3.159 fdeltax() [2/2]

```
virtual void fdeltax (
            realtype * deltax,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ie,
```

```
            const realtype * xdot,
            const realtype * xdot_old )  [protected], [virtual]
```

model specific implementation of fdeltax

Parameters

deltax	state update
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
ie	event index
xdot	new model right hand side
xdot_old	previous model right hand side

Definition at line 1504 of file model.h.

10.11.3.160 fdeltasx() [2/2]

```
virtual void fdeltasx (
            realtype * deltasx,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w,
            const int ip,
            const int ie,
            const realtype * xdot,
            const realtype * xdot_old,
            const realtype * sx,
            const realtype * stau )  [protected], [virtual]
```

model specific implementation of fdeltasx

Parameters

deltasx	sensitivity update
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
w	repeating elements vector
ip	sensitivity index
ie	event index
xdot	new model right hand side
xdot_old	previous model right hand side
sx	state sensitivity
stau	event-time sensitivity

Definition at line 1524 of file model.h.

10.11.3.161 fdeltaxB() [2/2]

```
virtual void fdeltaxB (
            realtype * deltaxB,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ie,
            const realtype * xdot,
            const realtype * xdot_old,
            const realtype * xB )  [protected], [virtual]
```

model specific implementation of fdeltaxB

Parameters

deltaxB	adjoint state update
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
ie	event index
xdot	new model right hand side
xdot_old	previous model right hand side
xB	current adjoint state

Definition at line 1542 of file model.h.

10.11.3.162 fdeltaqB() [2/2]

```
virtual void fdeltaqB (
            realtype * deltaqB,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip,
            const int ie,
            const realtype * xdot,
            const realtype * xdot_old,
            const realtype * xB )  [protected], [virtual]
```

model specific implementation of fdeltaqB

Parameters

deltaqB	sensitivity update
t	current time
x	current state
p	parameter vector
k	constant vector
h	heavyside vector
ip	sensitivity index
ie	event index
xdot	new model right hand side
xdot_old	previous model right hand side
xB	adjoint state

Definition at line 1560 of file model.h.

10.11.3.163 fsigmay() [2/2]

```
virtual void fsigmay (
            realtype * sigmay,
            const realtype t,
            const realtype * p,
            const realtype * k )  [protected], [virtual]
```

model specific implementation of fsigmay

Parameters

sigmay	standard deviation of measurements
t	current time
p	parameter vector
k	constant vector

Definition at line 1571 of file model.h.

10.11.3.164 fdsigmaydp() [2/2]

```
virtual void fdsigmaydp (
            realtype * dsigmaydp,
            const realtype t,
            const realtype * p,
            const realtype * k,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsigmay

Parameters

dsigmaydp	partial derivative of standard deviation of measurements
t	current time
p	parameter vector
k	constant vector
ip	sensitivity index

Definition at line 1582 of file model.h.

10.11.3.165 fsigmaz() [2/2]

```
virtual void fsigmaz (
            realtype * sigmaz,
            const realtype t,
            const realtype * p,
            const realtype * k )  [protected], [virtual]
```

model specific implementation of fsigmaz

Parameters

sigmaz	standard deviation of event measurements
t	current time
p	parameter vector
k	constant vector

Definition at line 1592 of file model.h.

10.11.3.166 fdsigmazdp() [2/2]

```
virtual void fdsigmazdp (
            realtype * dsigmazdp,
            const realtype t,
            const realtype * p,
            const realtype * k,
            const int ip )  [protected], [virtual]
```

model specific implementation of fsigmaz

Parameters

dsigmazdp	partial derivative of standard deviation of event measurements
t	current time
p	parameter vector
k	constant vector
ip	sensitivity index

Definition at line 1603 of file model.h.

10.11.3.167 fJy() [2/2]

```
virtual void fJy (
            realtype * nllh,
            const int iy,
            const realtype * p,
            const realtype * k,
            const realtype * y,
            const realtype * sigmay,
            const realtype * my )  [protected], [virtual]
```

model specific implementation of fJy

Parameters

nllh	negative log-likelihood for measurements y
iy	output index
p	parameter vector
k	constant vector
y	model output at timepoint
sigmay	measurement standard deviation at timepoint
my	measurements at timepoint

Definition at line 1616 of file model.h.

10.11.3.168 fJz() [2/2]

```
virtual void fJz (
            realtype * nllh,
            const int iz,
            const realtype * p,
            const realtype * k,
            const realtype * z,
            const realtype * sigmaz,
            const realtype * mz )  [protected], [virtual]
```

model specific implementation of fJz

Parameters

nllh	negative log-likelihood for event measurements z
iz	event output index
p	parameter vector
k	constant vector
z	model event output at timepoint
sigmaz	event measurement standard deviation at timepoint
mz	event measurements at timepoint

Definition at line 1628 of file model.h.

10.11.3.169 fJrz() [2/2]

```
virtual void fJrz (
            realtype * nllh,
            const int iz,
            const realtype * p,
            const realtype * k,
            const realtype * z,
            const realtype * sigmaz )  [protected], [virtual]
```

model specific implementation of fJrz

Parameters

nllh	regularization for event measurements z
iz	event output index
p	parameter vector
k	constant vector
z	model event output at timepoint
sigmaz	event measurement standard deviation at timepoint

Definition at line 1640 of file model.h.

10.11.3.170 fdJydy() [2/2]

```
virtual void fdJydy (
            realtype * dJydy,
            const int iy,
            const realtype * p,
            const realtype * k,
            const realtype * y,
            const realtype * sigmay,
            const realtype * my )  [protected], [virtual]
```

model specific implementation of fdJydy

Parameters

dJydy	partial derivative of time-resolved measurement negative log-likelihood Jy
iy	output index
p	parameter vector
k	constant vector
y	model output at timepoint
sigmay	measurement standard deviation at timepoint
my	measurement at timepoint

Definition at line 1653 of file model.h.

10.11.3.171 fdJydsigma() [2/2]

```
virtual void fdJydsigma (
            realtype * dJydsigma,
            const int iy,
            const realtype * p,
            const realtype * k,
            const realtype * y,
            const realtype * sigmay,
            const realtype * my )  [protected], [virtual]
```

model specific implementation of fdJydsigma

Parameters

dJydsigma	Sensitivity of time-resolved measurement negative log-likelihood Jy w.r.t. standard deviation sigmay
iy	output index
p	parameter vector
k	constant vector
y	model output at timepoint
sigmay	measurement standard deviation at timepoint
my	measurement at timepoint

Definition at line 1668 of file model.h.

10.11.3.172 fdJzdz() [2/2]

```
virtual void fdJzdz (
            realtype * dJzdz,
            const int iz,
            const realtype * p,
            const realtype * k,
            const realtype * z,
            const realtype * sigmaz,
            const realtype * mz )  [protected], [virtual]
```

model specific implementation of fdJzdz

Parameters

dJzdz	partial derivative of event measurement negative log-likelihood Jz
iz	event output index
p	parameter vector
k	constant vector
z	model event output at timepoint
sigmaz	event measurement standard deviation at timepoint
mz	event measurement at timepoint

Definition at line 1682 of file model.h.

10.11.3.173 fdJzdsigma() [2/2]

```
virtual void fdJzdsigma (
            realtype * dJzdsigma,
            const int iz,
            const realtype * p,
            const realtype * k,
            const realtype * z,
            const realtype * sigmaz,
            const realtype * mz )  [protected], [virtual]
```

model specific implementation of fdJzdsigma

Parameters

dJzdsigma	Sensitivity of event measurement negative log-likelihood Jz w.r.t. standard deviation sigmaz
iz	event output index
p	parameter vector
k	constant vector
z	model event output at timepoint
sigmaz	event measurement standard deviation at timepoint
mz	event measurement at timepoint

Definition at line 1697 of file model.h.

10.11.3.174 fdJrzdz() [2/2]

```
virtual void fdJrzdz (
            realtype * dJrzdz,
            const int iz,
            const realtype * p,
            const realtype * k,
            const realtype * rz,
            const realtype * sigmaz )  [protected], [virtual]
```

model specific implementation of fdJrzdz

Parameters

dJrzdz	partial derivative of event penalization Jrz
iz	event output index
p	parameter vector
k	constant vector
rz	model root output at timepoint
sigmaz	event measurement standard deviation at timepoint

Definition at line 1710 of file model.h.

10.11.3.175 fdJrzdsigma() [2/2]

```
virtual void fdJrzdsigma (
            realtype * dJrzdsigma,
            const int iz,
            const realtype * p,
            const realtype * k,
            const realtype * rz,
            const realtype * sigmaz )  [protected], [virtual]
```

model specific implementation of fdJrzdsigma

Parameters

dJrzdsigma	Sensitivity of event penalization Jrz w.r.t. standard deviation sigmaz
iz	event output index
p	parameter vector
k	constant vector
rz	model root output at timepoint
sigmaz	event measurement standard deviation at timepoint

Definition at line 1724 of file model.h.

10.11.3.176 fw() [2/2]

```
virtual void fw (
            realtype * w,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * tcl )  [protected], [virtual]
```

model specific implementation of fw

Parameters

w	Recurring terms in xdot
t	timepoint
x	vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
tcl	total abundances for conservations laws

Definition at line 1738 of file model.h.

10.11.3.177 fdwdp() [2/2]

```
virtual void fdwdp (
            realtype * dwdp,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w,
            const realtype * tcl,
            const realtype * stcl )  [protected], [virtual]
```

model specific implementation of dwdp

Parameters

dwdp	Recurring terms in xdot, parameter derivative
t	timepoint
x	vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables
tcl	total abundances for conservations laws
stcl	sensitivities of total abundances for conservations laws

Definition at line 1752 of file model.h.

10.11.3.178 fdwdx() [2/2]

```
virtual void fdwdx (
            realtype * dwdx,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w,
            const realtype * tcl )  [protected], [virtual]
```

model specific implementation of dwdx

Parameters

dwdx	Recurring terms in xdot, state derivative
t	timepoint
x	vector with the states

Parameters

p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables
tcl	total abundances for conservations laws

Definition at line 1766 of file model.h.

10.11.3.179 getmy()

```
void getmy (
            const int it,
            const ExpData * edata )  [protected]
```

create my slice at timepoint

Parameters

it	timepoint index
edata	pointer to experimental data instance

Definition at line 1372 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.180 getmz()

```
void getmz (
            const int nroots,
            const ExpData * edata )  [protected]
```

create mz slice at event

Parameters

nroots	event occurence
edata	pointer to experimental data instance

Definition at line 1388 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.3.181 gety()

```
const realtype * gety (
            const int it,
            const ReturnData * rdata ) const  [protected]
```

create y slice at timepoint

Parameters

it	timepoint index
rdata	pointer to return data instance

Returns

y y-slice from rdata instance

Definition at line 1380 of file model.cpp.

Here is the caller graph for this function:

10.11.3.182 getz()

```
const realtype * getz (
            const int nroots,
            const ReturnData * rdata ) const  [protected]
```

create z slice at event

Parameters

nroots	event occurence
rdata	pointer to return data instance

Returns

z slice

Definition at line 1396 of file model.cpp.

Here is the caller graph for this function:

10.11.3.183 getrz()

```
const realtype * getrz (
            const int nroots,
            const ReturnData * rdata ) const  [protected]
```

create rz slice at event

Parameters

nroots	event occurence
rdata	pointer to return data instance

Returns

rz slice

Definition at line 1400 of file model.cpp.

Here is the caller graph for this function:

10.11.3.184 getsz()

```
const realtype * getsz (
            const int nroots,
            const int ip,
            const ReturnData * rdata ) const  [protected]
```

create sz slice at event

Parameters

nroots	event occurence
ip	sensitivity index
rdata	pointer to return data instance

Returns

z slice

Definition at line 1404 of file model.cpp.

Here is the call graph for this function:

10.11.3.185 getsrz()

```
const realtype * getsrz (
            const int nroots,
            const int ip,
            const ReturnData * rdata ) const  [protected]
```

create srz slice at event

Parameters

nroots	event occurence
ip	sensitivity index
rdata	pointer to return data instance

Returns

rz slice

Definition at line 1408 of file model.cpp.

Here is the call graph for this function:

10.11.3.186 isFixedParameterStateReinitializationAllowed()

```
virtual bool isFixedParameterStateReinitializationAllowed ( ) const  [protected], [virtual]
```

function indicating whether reinitialization of states depending on fixed parameters is permissible

Returns

flag inidication whether reinitialization of states depending on fixed parameters is permissible

Definition at line 1823 of file model.h.

Here is the caller graph for this function:

10.11.3.187 computeX_pos()

```
N_Vector computeX_pos (
            N_Vector x )  [protected]
```

Parameters

x	state vector possibly containing negative values

Returns

state vector with negative values replaced by 0 according to stateIsNonNegative

Definition at line 1470 of file model.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.11.4 Friends And Related Function Documentation

10.11.4.1 boost::serialization::serialize

```
void boost::serialization::serialize (
            Archive & ar,
```

```
            Model & r,
            const unsigned int version )  [friend]
```

Parameters

ar	Archive to serialize to
r	Data to serialize
version	Version number

10.11.4.2 operator==

```
bool operator== (
            const Model & a,
            const Model & b )  [friend]
```

Parameters

a	first model instance
b	second model instance

Returns

equality

Definition at line 1432 of file model.cpp.

10.11.5 Member Data Documentation

10.11.5.1 nx_rdata

```
const int nx_rdata
```

number of states

Definition at line 1135 of file model.h.

10.11.5.2 nxtrue_rdata

```
const int nxtrue_rdata
```

number of states in the unaugmented system

Definition at line 1137 of file model.h.

10.11.5.3 nx_solver

```
const int nx_solver
```

number of states with conservation laws applied

Definition at line 1139 of file model.h.

10.11.5.4 nxtrue_solver

```
const int nxtrue_solver
```

number of states in the unaugmented system with conservation laws applied

Definition at line 1141 of file model.h.

10.11.5.5 ny

```
const int ny
```

number of observables

Definition at line 1143 of file model.h.

10.11.5.6 nytrue

```
const int nytrue
```

number of observables in the unaugmented system

Definition at line 1145 of file model.h.

10.11.5.7 nz

```
const int nz
```

number of event outputs

Definition at line 1147 of file model.h.

10.11.5.8 nztrue

```
const int nztrue
```

number of event outputs in the unaugmented system

Definition at line 1149 of file model.h.

10.11.5.9 ne

```
const int ne
```

number of events

Definition at line 1151 of file model.h.

10.11.5.10 nw

```
const int nw
```

number of common expressions

Definition at line 1153 of file model.h.

10.11.5.11 ndwdx

```
const int ndwdx
```

number of derivatives of common expressions wrt x

Definition at line 1155 of file model.h.

10.11.5.12 ndwdp

```
const int ndwdp
```

number of derivatives of common expressions wrt p

Definition at line 1157 of file model.h.

10.11.5.13 nnz

```
const int nnz
```

number of nonzero entries in jacobian

Definition at line 1159 of file model.h.

10.11.5.14 nJ

```
const int nJ
```

dimension of the augmented objective function for 2nd order ASA

Definition at line 1161 of file model.h.

10.11.5.15 ubw

```
const int ubw
```

upper bandwith of the jacobian

Definition at line 1163 of file model.h.

10.11.5.16 lbw

```
const int lbw
```

lower bandwith of the jacobian

Definition at line 1165 of file model.h.

10.11.5.17 o2mode

```
const SecondOrderMode o2mode
```

flag indicating whether for sensi == AMICI_SENSI_ORDER_SECOND directional or full second order derivative will be computed

Definition at line 1168 of file model.h.

10.11.5.18 z2event

```
const std::vector<int> z2event
```

index indicating to which event an event output belongs

Definition at line 1170 of file model.h.

10.11.5.19 idlist

```
const std::vector<realtype> idlist
```

flag array for DAE equations

Definition at line 1172 of file model.h.

10.11.5.20 sigmay

```
std::vector<realtype> sigmay
```

data standard deviation for current timepoint (dimension: ny)

Definition at line 1175 of file model.h.

10.11.5.21 dsigmaydp

```
std::vector<realtype> dsigmaydp
```

parameter derivative of data standard deviation for current timepoint (dimension: nplist x ny, row-major)

Definition at line 1177 of file model.h.

10.11.5.22 sigmaz

```
std::vector<realtype> sigmaz
```

event standard deviation for current timepoint (dimension: nz)

Definition at line 1179 of file model.h.

10.11.5.23 dsigmazdp

```
std::vector<realtype> dsigmazdp
```

parameter derivative of event standard deviation for current timepoint (dimension: nplist x nz, row-major)

Definition at line 1181 of file model.h.

10.11.5.24 dJydp

```
std::vector<realtype> dJydp
```

parameter derivative of data likelihood for current timepoint (dimension: nplist x nJ, row-major)

Definition at line 1183 of file model.h.

10.11.5.25 dJzdp

```
std::vector<realtype> dJzdp
```

parameter derivative of event likelihood for current timepoint (dimension: nplist x nJ, row-major)

Definition at line 1185 of file model.h.

10.11.5.26 deltax

```
std::vector<realtype> deltax
```

change in x at current timepoint (dimension: nx_solver)

Definition at line 1188 of file model.h.

10.11.5.27 deltasx

```
std::vector<realtype> deltasx
```

change in sx at current timepoint (dimension: nplist x nx_solver, row-major)

Definition at line 1190 of file model.h.

10.11.5.28 deltaxB

```
std::vector<realtype> deltaxB
```

change in xB at current timepoint (dimension: nJ x nxtrue_cl, row-major)

Definition at line 1192 of file model.h.

10.11.5.29 deltaqB

```
std::vector<realtype> deltaqB
```

change in qB at current timepoint (dimension: nJ x nplist, row-major)

Definition at line 1194 of file model.h.

10.11.5.30 dxdotdp

```
std::vector<realtype> dxdotdp
```

tempory storage of dxdotdp data across functions (dimension: nplist x nx_solver, row-major)

Definition at line 1197 of file model.h.

10.11.5.31 J

```
SlsMat J = nullptr  [protected]
```

Sparse Jacobian (dimension: nnz)

Definition at line 1829 of file model.h.

10.11.5.32 my

```
std::vector<realtype> my  [protected]
```

current observable (dimension: nytrue)

Definition at line 1832 of file model.h.

10.11.5.33 mz

```
std::vector<realtype> mz  [protected]
```

current event measurement (dimension: nztrue)

Definition at line 1834 of file model.h.

10.11.5.34 dJydy

```
std::vector<realtype> dJydy  [protected]
```

observable derivative of data likelihood (dimension nJ x nytrue x ny, ordering = ?)

Definition at line 1836 of file model.h.

10.11.5.35 dJydsigma

```
std::vector<realtype> dJydsigma  [protected]
```

observable sigma derivative of data likelihood (dimension nJ x nytrue x ny, ordering = ?)

Definition at line 1838 of file model.h.

10.11.5.36 dJzdz

```
std::vector<realtype> dJzdz  [protected]
```

event ouput derivative of event likelihood (dimension nJ x nztrue x nz, ordering = ?)

Definition at line 1841 of file model.h.

10.11.5.37 dJzdsigma

```
std::vector<realtype> dJzdsigma  [protected]
```

event sigma derivative of event likelihood (dimension nJ x nztrue x nz, ordering = ?)

Definition at line 1843 of file model.h.

10.11.5.38 dJrzdz

```
std::vector<realtype> dJrzdz  [protected]
```

event ouput derivative of event likelihood at final timepoint (dimension nJ x nztrue x nz, ordering = ?)

Definition at line 1845 of file model.h.

10.11.5.39 dJrzdsigma

```
std::vector<realtype> dJrzdsigma  [protected]
```

event sigma derivative of event likelihood at final timepoint (dimension nJ x nztrue x nz, ordering = ?)

Definition at line 1847 of file model.h.

10.11.5.40 dzdx

```
std::vector<realtype> dzdx  [protected]
```

state derivative of event output (dimension: nz x nx_solver, ordering = ?)

Definition at line 1849 of file model.h.

10.11.5.41 dzdp

```
std::vector<realtype> dzdp  [protected]
```

parameter derivative of event output (dimension: nz x nplist, ordering = ?)

Definition at line 1851 of file model.h.

10.11.5.42 drzdx

```
std::vector<realtype> drzdx  [protected]
```

state derivative of event timepoint (dimension: nz x nx_solver, ordering = ?)

Definition at line 1853 of file model.h.

10.11.5.43 drzdp

```
std::vector<realtype> drzdp [protected]
```

parameter derivative of event timepoint (dimension: nz x nplist, ordering = ?)

Definition at line 1855 of file model.h.

10.11.5.44 dydp

```
std::vector<realtype> dydp [protected]
```

parameter derivative of observable (dimension: nplist x ny, row-major)

Definition at line 1857 of file model.h.

10.11.5.45 dydx

```
std::vector<realtype> dydx [protected]
```

state derivative of observable (dimension: ny x nx_solver, ordering = ?)

Definition at line 1860 of file model.h.

10.11.5.46 w

```
std::vector<realtype> w [protected]
```

tempory storage of w data across functions (dimension: nw)

Definition at line 1862 of file model.h.

10.11.5.47 dwdx

```
std::vector<realtype> dwdx [protected]
```

tempory storage of sparse dwdx data across functions (dimension: ndwdx)

Definition at line 1864 of file model.h.

10.11.5.48 dwdp

```
std::vector<realtype> dwdp  [protected]
```

tempory storage of sparse dwdp data across functions (dimension: ndwdp)

Definition at line 1866 of file model.h.

10.11.5.49 M

```
std::vector<realtype> M  [protected]
```

tempory storage of mass matrix data across functions (dimension: nx_solver)

Definition at line 1868 of file model.h.

10.11.5.50 stau

```
std::vector<realtype> stau  [protected]
```

tempory storage of stau data across functions (dimension: nplist)

Definition at line 1870 of file model.h.

10.11.5.51 sx

```
std::vector<realtype> sx  [protected]
```

tempory storage of sx data for flattening (dimension: nx_solver x nplist, ordering = row-major)

Definition at line 1874 of file model.h.

10.11.5.52 x_rdata

```
std::vector<realtype> x_rdata  [protected]
```

tempory storage x_rdata (dimension: nx_rdata)

Definition at line 1877 of file model.h.

10.11.5.53 sx_rdata

```
std::vector<realtype> sx_rdata [protected]
```

tempory storage sx_rdata slice (dimension: nx_rdata)

Definition at line 1879 of file model.h.

10.11.5.54 h

```
std::vector<realtype> h [protected]
```

flag indicating whether a certain heaviside function should be active or not (dimension: ne)

Definition at line 1883 of file model.h.

10.11.5.55 unscaledParameters

```
std::vector<realtype> unscaledParameters [protected]
```

unscaled parameters (dimension: np)

Definition at line 1886 of file model.h.

10.11.5.56 originalParameters

```
std::vector<realtype> originalParameters [protected]
```

orignal user-provided, possibly scaled parameter array (size np)

Definition at line 1889 of file model.h.

10.11.5.57 fixedParameters

```
std::vector<realtype> fixedParameters [protected]
```

constants (dimension: nk)

Definition at line 1892 of file model.h.

10.11.5.58 total_cl

```
std::vector<realtype> total_cl  [protected]
```

total abundances for conservation laws (dimension: nx_rdata-nx_solver)

Definition at line 1896 of file model.h.

10.11.5.59 stotal_cl

```
std::vector<realtype> stotal_cl  [protected]
```

sensitivities of total abundances for conservation laws (dimension: (nx_rdata-nx_solver) $*$ np, ordering = row-major)

Definition at line 1900 of file model.h.

10.11.5.60 plist_

```
std::vector<int> plist_  [protected]
```

indexes of parameters wrt to which sensitivities are computed (dimension nplist)

Definition at line 1903 of file model.h.

10.11.5.61 x0data

```
std::vector<double> x0data  [protected]
```

state initialisation (size nx_solver)

Definition at line 1906 of file model.h.

10.11.5.62 sx0data

```
std::vector<realtype> sx0data  [protected]
```

sensitivity initialisation (size nx_rdata $*$ nplist, ordering = row-major)

Definition at line 1909 of file model.h.

10.11.5.63 ts

```
std::vector<realtype> ts  [protected]
```

timepoints (size nt)

Definition at line 1912 of file model.h.

10.11.5.64 stateIsNonNegative

```
std::vector<bool> stateIsNonNegative  [protected]
```

vector of bools indicating whether state variables are to be assumed to be positive

Definition at line 1915 of file model.h.

10.11.5.65 anyStateNonNegative

```
bool anyStateNonNegative = false  [protected]
```

boolean indicating whether any entry in stateIsNonNegative is `true`

Definition at line 1918 of file model.h.

10.11.5.66 x_pos_tmp

```
AmiVector x_pos_tmp  [protected]
```

temporary storage of positified state variables according to stateIsNonNegative

Definition at line 1921 of file model.h.

10.11.5.67 nmaxevent

```
int nmaxevent = 10  [protected]
```

maximal number of events to track

Definition at line 1924 of file model.h.

10.11.5.68 pscale

```
std::vector<ParameterScaling> pscale  [protected]
```

parameter transformation of `originalParameters` (dimension np)

Definition at line 1927 of file model.h.

10.11.5.69 tstart

```
double tstart = 0.0  [protected]
```

starting time

Definition at line 1930 of file model.h.

10.11.5.70 steadyStateSensitivityMode

```
SteadyStateSensitivityMode steadyStateSensitivityMode = SteadyStateSensitivityMode::newtonOnly
[protected]
```

flag indicating whether steadystate sensivities are to be computed via FSA when steadyStateSimulation is used

Definition at line 1934 of file model.h.

10.11.5.71 reinitializeFixedParameterInitialStates

```
bool reinitializeFixedParameterInitialStates = false  [protected]
```

flag indicating whether reinitialization of states depending on fixed parameters is activated

Definition at line 1939 of file model.h.

10.12 Model_DAE Class Reference

The Model class represents an AMICI DAE model. The model does not contain any data, but represents the state of the model at a specific time t. The states must not always be in sync, but may be updated asynchroneously.

```
#include <model_dae.h>
```

Inheritance diagram for Model_DAE:

Public Member Functions

- Model_DAE ()
- Model_DAE (const int nx_rdata, const int nxtrue_rdata, const int nx_solver, const int nxtrue_solver, const int ny, const int nytrue, const int nz, const int nztrue, const int ne, const int nJ, const int nw, const int ndwdx, const int ndwdp, const int nnz, const int ubw, const int lbw, const SecondOrderMode o2mode, std::vector< realtype > const &p, std::vector< realtype > const &k, std::vector< int > const &plist, std::vector< realtype > const &idlist, std::vector< int > const &z2event)
- virtual void fJ (realtype t, realtype cj, AmiVector *x, AmiVector *dx, AmiVector *xdot, DlsMat J) override
- void fJ (realtype t, realtype cj, N_Vector x, N_Vector dx, N_Vector xdot, DlsMat J)
- void fJB (realtype t, realtype cj, N_Vector x, N_Vector dx, N_Vector xB, N_Vector dxB, DlsMat JB)
- virtual void fJSparse (realtype t, realtype cj, AmiVector *x, AmiVector *dx, AmiVector *xdot, SlsMat J) override
- void fJSparse (realtype t, realtype cj, N_Vector x, N_Vector dx, SlsMat J)
- void fJSparseB (realtype t, realtype cj, N_Vector x, N_Vector dx, N_Vector xB, N_Vector dxB, SlsMat JB)
- virtual void fJDiag (realtype t, AmiVector *JDiag, realtype cj, AmiVector *x, AmiVector *dx) override
- virtual void fJv (realtype t, AmiVector *x, AmiVector *dx, AmiVector *xdot, AmiVector *v, AmiVector *nJv, realtype cj) override
- void fJv (realtype t, N_Vector x, N_Vector dx, N_Vector v, N_Vector Jv, realtype cj)
- void fJvB (realtype t, N_Vector x, N_Vector dx, N_Vector xB, N_Vector dxB, N_Vector vB, N_Vector JvB, realtype cj)
- virtual void froot (realtype t, AmiVector *x, AmiVector *dx, realtype *root) override
- void froot (realtype t, N_Vector x, N_Vector dx, realtype *root)
- virtual void fxdot (realtype t, AmiVector *x, AmiVector *dx, AmiVector *xdot) override
- void fxdot (realtype t, N_Vector x, N_Vector dx, N_Vector xdot)
- void fxBdot (realtype t, N_Vector x, N_Vector dx, N_Vector xB, N_Vector dxB, N_Vector xBdot)
- void fqBdot (realtype t, N_Vector x, N_Vector dx, N_Vector xB, N_Vector dxB, N_Vector qBdot)
- void fdxdotdp (const realtype t, const N_Vector x, const N_Vector dx)
- virtual void fdxdotdp (realtype t, AmiVector *x, AmiVector *dx) override
- void fsxdot (realtype t, AmiVector *x, AmiVector *dx, int ip, AmiVector *sx, AmiVector *sdx, AmiVector *sxdot) override
- void fsxdot (realtype t, N_Vector x, N_Vector dx, int ip, N_Vector sx, N_Vector sdx, N_Vector sxdot)
- void fM (realtype t, const N_Vector x)

  Mass matrix for DAE systems.
- virtual std::unique_ptr< Solver > getSolver () override

Protected Member Functions

- virtual void fJ (realtype *J, const realtype t, const realtype *x, const double *p, const double *k, const realtype *h, const realtype cj, const realtype *dx, const realtype *w, const realtype *dwdx)=0
- virtual void fJB (realtype *JB, const realtype t, const realtype *x, const double *p, const double *k, const realtype *h, const realtype cj, const realtype *xB, const realtype *dx, const realtype *dxB, const realtype *w, const realtype *dwdx)
- virtual void fJSparse (SlsMat JSparse, const realtype t, const realtype *x, const double *p, const double *k, const realtype *h, const realtype cj, const realtype *dx, const realtype *w, const realtype *dwdx)=0
- virtual void fJSparseB (SlsMat JSparseB, const realtype t, const realtype *x, const double *p, const double *k, const realtype *h, const realtype cj, const realtype *xB, const realtype *dx, const realtype *dxB, const realtype *w, const realtype *dwdx)
- virtual void fJDiag (realtype *JDiag, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype cj, const realtype *dx, const realtype *w, const realtype *dwdx)
- virtual void fJv (realtype *Jv, const realtype t, const realtype *x, const double *p, const double *k, const realtype *h, const realtype cj, const realtype *dx, const realtype *v, const realtype *w, const realtype *dwdx)
- virtual void fJvB (realtype *JvB, const realtype t, const realtype *x, const double *p, const double *k, const realtype *h, const realtype cj, const realtype *xB, const realtype *dx, const realtype *dxB, const realtype *vB, const realtype *w, const realtype *dwdx)

- virtual void froot (realtype ∗root, const realtype t, const realtype ∗x, const double ∗p, const double ∗k, const realtype ∗h, const realtype ∗dx)
- virtual void fxdot (realtype ∗xdot, const realtype t, const realtype ∗x, const double ∗p, const double ∗k, const realtype ∗h, const realtype ∗dx, const realtype ∗w)=0
- virtual void fxBdot (realtype ∗xBdot, const realtype t, const realtype ∗x, const double ∗p, const double ∗k, const realtype ∗h, const realtype ∗xB, const realtype ∗dx, const realtype ∗dxB, const realtype ∗w, const realtype ∗dwdx)
- virtual void fqBdot (realtype ∗qBdot, const int ip, const realtype t, const realtype ∗x, const double ∗p, const double ∗k, const realtype ∗h, const realtype ∗xB, const realtype ∗dx, const realtype ∗dxB, const realtype ∗w, const realtype ∗dwdp)
- virtual void fdxdotdp (realtype ∗dxdotdp, const realtype t, const realtype ∗x, const realtype ∗p, const realtype ∗k, const realtype ∗h, const int ip, const realtype ∗dx, const realtype ∗w, const realtype ∗dwdp)
- virtual void fsxdot (realtype ∗sxdot, const realtype t, const realtype ∗x, const realtype ∗p, const realtype ∗k, const realtype ∗h, const int ip, const realtype ∗dx, const realtype ∗sx, const realtype ∗sdx, const realtype ∗w, const realtype ∗dwdx, const realtype ∗M, const realtype ∗J, const realtype ∗dxdotdp)
- virtual void fM (realtype ∗M, const realtype t, const realtype ∗x, const realtype ∗p, const realtype ∗k)

Additional Inherited Members

10.12.1 Detailed Description

Definition at line 24 of file model_dae.h.

10.12.2 Constructor & Destructor Documentation

10.12.2.1 Model_DAE() [1/2]

```
Model_DAE ( )
```

default constructor

Definition at line 27 of file model_dae.h.

10.12.2.2 Model_DAE() [2/2]

```
Model_DAE (
            const int nx_rdata,
            const int nxtrue_rdata,
            const int nx_solver,
            const int nxtrue_solver,
            const int ny,
            const int nytrue,
            const int nz,
            const int nztrue,
            const int ne,
            const int nJ,
            const int nw,
            const int ndwdx,
            const int ndwdp,
```

```
            const int nnz,
            const int ubw,
            const int lbw,
            const SecondOrderMode o2mode,
            std::vector< realtype > const & p,
            std::vector< realtype > const & k,
            std::vector< int > const & plist,
            std::vector< realtype > const & idlist,
            std::vector< int > const & z2event )
```

constructor with model dimensions

Parameters

nx_rdata	number of state variables
nxtrue_rdata	number of state variables of the non-augmented model
nx_solver	number of state variables with conservation laws applied
nxtrue_solver	number of state variables of the non-augmented model with conservation laws applied
ny	number of observables
nytrue	number of observables of the non-augmented model
nz	number of event observables
nztrue	number of event observables of the non-augmented model
ne	number of events
nJ	number of objective functions
nw	number of repeating elements
ndwdx	number of nonzero elements in the x derivative of the repeating elements
ndwdp	number of nonzero elements in the p derivative of the repeating elements
nnz	number of nonzero elements in Jacobian
ubw	upper matrix bandwidth in the Jacobian
lbw	lower matrix bandwidth in the Jacobian
o2mode	second order sensitivity mode
p	parameters
k	constants
plist	indexes wrt to which sensitivities are to be computed
idlist	indexes indicating algebraic components (DAE only)
z2event	mapping of event outputs to events

Definition at line 56 of file model_dae.h.

10.12.3 Member Function Documentation

10.12.3.1 fJ() [1/3]

```
void fJ (
            realtype t,
            realtype cj,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            DlsMat J )  [override], [virtual]
```

Dense Jacobian function

Parameters

t	time
cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
J	dense matrix to which values of the jacobian will be written

Implements Model.

Definition at line 6 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.2 fJ() [2/3]

```
void fJ (
            realtype t,
            realtype cj,
            N_Vector x,
            N_Vector dx,
            N_Vector xdot,
            DlsMat J )
```

Jacobian of xdot with respect to states x

Parameters

t	timepoint
cj	scaling factor, inverse of the step size
x	Vector with the states
dx	Vector with the derivative states
xdot	Vector with the right hand side
J	Matrix to which the Jacobian will be written

Definition at line 20 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.3 fJB() [1/2]

```
void fJB (
            realtype t,
            realtype cj,
            N_Vector x,
            N_Vector dx,
            N_Vector xB,
            N_Vector dxB,
            DlsMat JB )
```

Jacobian of xBdot with respect to adjoint state xB

Parameters

t	timepoint
cj	scaling factor, inverse of the step size
x	Vector with the states
dx	Vector with the derivative states
xB	Vector with the adjoint states
dxB	Vector with the adjoint derivative states
JB	Matrix to which the Jacobian will be written

Definition at line 166 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.4 fJSparse() [1/3]

```
void fJSparse (
            realtype t,
            realtype cj,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            SlsMat J )  [override], [virtual]
```

Sparse Jacobian function

Parameters

t	time
cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
J	sparse matrix to which values of the Jacobian will be written

Implements Model.

Definition at line 29 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.5 fJSparse() [2/3]

```
void fJSparse (
            realtype t,
            realtype cj,
            N_Vector x,
            N_Vector dx,
            SlsMat J )
```

J in sparse form (for sparse solvers from the SuiteSparse Package)

Parameters

t	timepoint
cj	scalar in Jacobian (inverse stepsize)
x	Vector with the states
dx	Vector with the derivative states
J	Matrix to which the Jacobian will be written

Definition at line 41 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.6 fJSparseB() [1/2]

```
void fJSparseB (
            realtype t,
            realtype cj,
            N_Vector x,
            N_Vector dx,
            N_Vector xB,
            N_Vector dxB,
            SlsMat JB )
```

JB in sparse form (for sparse solvers from the SuiteSparse Package)

Parameters

t	timepoint
cj	scalar in Jacobian
x	Vector with the states
dx	Vector with the derivative states
xB	Vector with the adjoint states
dxB	Vector with the adjoint derivative states
JB	Matrix to which the Jacobian will be written

Definition at line 184 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.7 fJDiag() [1/2]

```
void fJDiag (
            realtype t,
            AmiVector * JDiag,
            realtype cj,
            AmiVector * x,
            AmiVector * dx )  [override], [virtual]
```

diagonalized Jacobian (for preconditioning)

Parameters

t	timepoint
JDiag	Vector to which the Jacobian diagonal will be written
cj	scaling factor, inverse of the step size
x	Vector with the states
dx	Vector with the derivative states

Returns

status flag indicating successful execution

Implements Model.

Definition at line 116 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.8 fJv() [1/3]

```
void fJv (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            AmiVector * v,
            AmiVector * nJv,
            realtype cj )  [override], [virtual]
```

Jacobian multiply function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
v	multiplication vector (unused)
nJv	array to which result of multiplication will be written
cj	scaling factor (inverse of timestep, DAE only)

Implements Model.

Definition at line 49 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.9 fJv() [2/3]

```
void fJv (
            realtype t,
            N_Vector x,
            N_Vector dx,
            N_Vector v,
            N_Vector Jv,
            realtype cj )
```

Matrix vector product of J with a vector v (for iterative solvers)

Parameters

t	timepoint **Type**: realtype
cj	scaling factor, inverse of the step size
x	Vector with the states
dx	Vector with the derivative states
v	Vector with which the Jacobian is multiplied
Jv	Vector to which the Jacobian vector product will be written

Definition at line 64 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.10 fJvB() [1/2]

```
void fJvB (
            realtype t,
            N_Vector x,
            N_Vector dx,
            N_Vector xB,
            N_Vector dxB,
            N_Vector vB,
            N_Vector JvB,
            realtype cj )
```

Matrix vector product of JB with a vector v (for iterative solvers)

Parameters

t	timepoint
x	Vector with the states
dx	Vector with the derivative states
xB	Vector with the adjoint states
dxB	Vector with the adjoint derivative states
vB	Vector with which the Jacobian is multiplied
JvB	Vector to which the Jacobian vector product will be written
cj	scalar in Jacobian (inverse stepsize)

Definition at line 204 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.11 froot() [1/3]

```
void froot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            realtype * root )  [override], [virtual]
```

Root function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
root	array to which values of the root function will be written

Implements Model.

Definition at line 73 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.12 froot() [2/3]

```
void froot (
            realtype t,
            N_Vector x,
            N_Vector dx,
            realtype * root )
```

Event trigger function for events

Parameters

t	timepoint
x	Vector with the states
dx	Vector with the derivative states
root	array with root function values

Definition at line 83 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.13 fxdot() [1/3]

```
void fxdot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot )  [override], [virtual]
```

Residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
xdot	array to which values of the residual function will be written

Implements Model.

Definition at line 90 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.14 fxdot() [2/3]

```
void fxdot (
            realtype t,
            N_Vector x,
            N_Vector dx,
            N_Vector xdot )
```

residual function of the DAE

Parameters

t	timepoint
x	Vector with the states
dx	Vector with the derivative states
xdot	Vector with the right hand side

Definition at line 100 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.15 fxBdot() [1/2]

```
void fxBdot (
            realtype t,
            N_Vector x,
            N_Vector dx,
            N_Vector xB,
            N_Vector dxB,
            N_Vector xBdot )
```

Right hand side of differential equation for adjoint state xB

Parameters

t	timepoint

Parameters

x	Vector with the states
dx	Vector with the derivative states
xB	Vector with the adjoint states
dxB	Vector with the adjoint derivative states
xBdot	Vector with the adjoint right hand side

Definition at line 222 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.16 fqBdot() [1/2]

```
void fqBdot (
            realtype t,
            N_Vector x,
            N_Vector dx,
            N_Vector xB,
            N_Vector dxB,
            N_Vector qBdot )
```

Right hand side of integral equation for quadrature states qB

Parameters

t	timepoint
x	Vector with the states
dx	Vector with the derivative states
xB	Vector with the adjoint states
dxB	Vector with the adjoint derivative states
qBdot	Vector with the adjoint quadrature right hand side

Definition at line 240 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.17 fdxdotdp() [1/3]

```
void fdxdotdp (
            const realtype t,
            const N_Vector x,
            const N_Vector dx )
```

Sensitivity of dx/dt wrt model parameters p

Parameters

t	timepoint
x	Vector with the states
dx	Vector with the derivative states

Returns

status flag indicating successful execution

Definition at line 133 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.18 fdxdotdp() [2/3]

```
virtual void fdxdotdp (
            realtype t,
            AmiVector * x,
            AmiVector * dx )  [override], [virtual]
```

parameter derivative of residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)

Returns

flag indicating successful evaluation

Implements Model.

Definition at line 102 of file model_dae.h.

Here is the call graph for this function:

10.12.3.19 fsxdot() [1/3]

```
void fsxdot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            int ip,
            AmiVector * sx,
            AmiVector * sdx,
            AmiVector * sxdot )  [override], [virtual]
```

Sensitivity Residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
ip	parameter index
sx	sensitivity state
sdx	time derivative of sensitivity state (DAE only)
sxdot	array to which values of the sensitivity residual function will be written

Implements Model.

Definition at line 250 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.20 fsxdot() [2/3]

```
void fsxdot (
            realtype t,
            N_Vector x,
            N_Vector dx,
            int ip,
            N_Vector sx,
            N_Vector sdx,
            N_Vector sxdot )
```

Right hand side of differential equation for state sensitivities sx

Parameters

t	timepoint
x	Vector with the states
dx	Vector with the derivative states
ip	parameter index
sx	Vector with the state sensitivities
sdx	Vector with the derivative state sensitivities
sxdot	Vector with the sensitivity right hand side

Definition at line 266 of file model_dae.cpp.

Here is the call graph for this function:

10.12.3.21 fM() [1/2]

```
void fM (
            realtype t,
            const N_Vector x )
```

Parameters

t	timepoint
x	Vector with the states

Definition at line 147 of file model_dae.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.12.3.22 getSolver()

```
std::unique_ptr< Solver > getSolver ( ) [override], [virtual]
```

Retrieves the solver object

Returns

The Solver instance

Implements Model.

Definition at line 153 of file model_dae.cpp.

10.12.3.23 fJ() [3/3]

```
virtual void fJ (
            realtype * J,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype cj,
            const realtype * dx,
            const realtype * w,
            const realtype * dwdx ) [protected], [pure virtual]
```

model specific implementation for fJ

Parameters

J	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
dx	Vector with the derivative states
w	vector with helper variables
dwdx	derivative of w wrt x

10.12.3.24 fJB() [2/2]

```
virtual void fJB (
            realtype * JB,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype cj,
            const realtype * xB,
            const realtype * dx,
            const realtype * dxB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJB

Parameters

JB	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
xB	Vector with the adjoint states
dx	Vector with the derivative states
dxB	Vector with the adjoint derivative states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 146 of file model_dae.h.

10.12.3.25 fJSparse() [3/3]

```
virtual void fJSparse (
            SlsMat JSparse,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype cj,
            const realtype * dx,
            const realtype * w,
            const realtype * dwdx )  [protected], [pure virtual]
```

model specific implementation for fJSparse

Parameters

JSparse	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
dx	Vector with the derivative states
w	vector with helper variables
dwdx	derivative of w wrt x

10.12.3.26 fJSparseB() [2/2]

```
virtual void fJSparseB (
            SlsMat JSparseB,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype cj,
            const realtype * xB,
            const realtype * dx,
            const realtype * dxB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJSparseB

Parameters

JSparseB	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
xB	Vector with the adjoint states
dx	Vector with the derivative states
dxB	Vector with the adjoint derivative states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 181 of file model_dae.h.

10.12.3.27 fJDiag() [2/2]

```
virtual void fJDiag (
            realtype * JDiag,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype cj,
            const realtype * dx,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJDiag

Parameters

JDiag	array to which the Jacobian diagonal will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
dx	Vector with the derivative states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 199 of file model_dae.h.

10.12.3.28 fJv() [3/3]

```
virtual void fJv (
            realtype * Jv,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype cj,
            const realtype * dx,
            const realtype * v,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJv

Parameters

Jv	Matrix vector product of J with a vector v
t	timepoint

Parameters

x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
dx	Vector with the derivative states
v	Vector with which the Jacobian is multiplied
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 217 of file model_dae.h.

10.12.3.29 fJvB() [2/2]

```
virtual void fJvB (
            realtype * JvB,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype cj,
            const realtype * xB,
            const realtype * dx,
            const realtype * dxB,
            const realtype * vB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJvB

Parameters

JvB	Matrix vector product of JB with a vector v
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
cj	scaling factor, inverse of the step size
xB	Vector with the adjoint states
dx	Vector with the derivative states
dxB	Vector with the adjoint derivative states
vB	Vector with which the Jacobian is multiplied
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 238 of file model_dae.h.

10.12.3.30 froot() [3/3]

```
virtual void froot (
            realtype * root,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype * dx )  [protected], [virtual]
```

model specific implementation for froot

Parameters

root	values of the trigger function
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
dx	Vector with the derivative states

Definition at line 253 of file model_dae.h.

10.12.3.31 fxdot() [3/3]

```
virtual void fxdot (
            realtype * xdot,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype * dx,
            const realtype * w )  [protected], [pure virtual]
```

model specific implementation for fxdot

Parameters

xdot	residual function
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables
dx	Vector with the derivative states

10.12.3.32 fxBdot() [2/2]

```
virtual void fxBdot (
            realtype * xBdot,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype * xB,
            const realtype * dx,
            const realtype * dxB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fxBdot

Parameters

xBdot	adjoint residual function
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
dx	Vector with the derivative states
dxB	Vector with the adjoint derivative states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 284 of file model_dae.h.

10.12.3.33 fqBdot() [2/2]

```
virtual void fqBdot (
            realtype * qBdot,
            const int ip,
            const realtype t,
            const realtype * x,
            const double * p,
            const double * k,
            const realtype * h,
            const realtype * xB,
            const realtype * dx,
            const realtype * dxB,
            const realtype * w,
            const realtype * dwdp )  [protected], [virtual]
```

model specific implementation for fqBdot

Parameters

qBdot	adjoint quadrature equation
ip	sensitivity index
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
dx	Vector with the derivative states
dxB	Vector with the adjoint derivative states
w	vector with helper variables
dwdp	derivative of w wrt p

Definition at line 304 of file model_dae.h.

10.12.3.34 fdxdotdp() [3/3]

```
virtual void fdxdotdp (
            realtype * dxdotdp,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip,
            const realtype * dx,
            const realtype * w,
            const realtype * dwdp )  [protected], [virtual]
```

model specific implementation of fdxdotdp

Parameters

dxdotdp	partial derivative xdot wrt p
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
ip	parameter index
dx	Vector with the derivative states
w	vector with helper variables
dwdp	derivative of w wrt p

Definition at line 322 of file model_dae.h.

10.12.3.35 fsxdot() [3/3]

```
virtual void fsxdot (
            realtype * sxdot,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip,
            const realtype * dx,
            const realtype * sx,
            const realtype * sdx,
            const realtype * w,
            const realtype * dwdx,
            const realtype * M,
            const realtype * J,
            const realtype * dxdotdp )  [protected], [virtual]
```

model specific implementation of fsxdot

Parameters

sxdot	sensitivity rhs
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
ip	parameter index
dx	Vector with the derivative states
sx	Vector with the state sensitivities
sdx	Vector with the derivative state sensitivities
w	vector with helper variables
dwdx	derivative of w wrt x
M	mass matrix
J	jacobian
dxdotdp	parameter derivative of residual function

Definition at line 344 of file model_dae.h.

10.12.3.36 fM() [2/2]

```
virtual void fM (
            realtype * M,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k )  [protected], [virtual]
```

model specific implementation of fM

Parameters

M	mass matrix
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector

Definition at line 358 of file model_dae.h.

10.13 Model_ODE Class Reference

The Model class represents an AMICI ODE model. The model does not contain any data, but represents the state of the model at a specific time t. The states must not always be in sync, but may be updated asynchroneously.

```
#include <model_ode.h>
```

Inheritance diagram for Model_ODE:

Public Member Functions

- Model_ODE ()
- Model_ODE (const int nx_rdata, const int nxtrue_rdata, const int nx_solver, const int nxtrue_solver, const int ny, const int nytrue, const int nz, const int nztrue, const int ne, const int nJ, const int nw, const int ndwdx, const int ndwdp, const int nnz, const int ubw, const int lbw, const SecondOrderMode o2mode, std::vector< realtype > const &p, std::vector< realtype > const &k, std::vector< int > const &plist, std::vector< realtype > const &idlist, std::vector< int > const &z2event)
- virtual void fJ (realtype t, realtype cj, AmiVector *x, AmiVector *dx, AmiVector *xdot, DlsMat J) override
- void fJ (realtype t, N_Vector x, N_Vector xdot, DlsMat J)
- void fJB (realtype t, N_Vector x, N_Vector xB, N_Vector xBdot, DlsMat JB)
- virtual void fJSparse (realtype t, realtype cj, AmiVector *x, AmiVector *dx, AmiVector *xdot, SlsMat J) override
- void fJSparse (realtype t, N_Vector x, SlsMat J)
- void fJSparseB (realtype t, N_Vector x, N_Vector xB, N_Vector xBdot, SlsMat JB)
- void fJDiag (realtype t, N_Vector JDiag, N_Vector x)
- virtual void fJDiag (realtype t, AmiVector *Jdiag, realtype cj, AmiVector *x, AmiVector *dx) override
- virtual void fJv (realtype t, AmiVector *x, AmiVector *dx, AmiVector *xdot, AmiVector *v, AmiVector *nJv, realtype cj) override
- void fJv (N_Vector v, N_Vector Jv, realtype t, N_Vector x)

- void fJvB (N_Vector vB, N_Vector JvB, realtype t, N_Vector x, N_Vector xB)
- virtual void froot (realtype t, AmiVector *x, AmiVector *dx, realtype *root) override
- void froot (realtype t, N_Vector x, realtype *root)
- virtual void fxdot (realtype t, AmiVector *x, AmiVector *dx, AmiVector *xdot) override
- void fxdot (realtype t, N_Vector x, N_Vector xdot)
- void fxBdot (realtype t, N_Vector x, N_Vector xB, N_Vector xBdot)
- void fqBdot (realtype t, N_Vector x, N_Vector xB, N_Vector qBdot)
- void fdxdotdp (const realtype t, const N_Vector x)
- virtual void fdxdotdp (realtype t, AmiVector *x, AmiVector *dx) override
- void fsxdot (realtype t, AmiVector *x, AmiVector *dx, int ip, AmiVector *sx, AmiVector *sdx, AmiVector *sxdot) override
- void fsxdot (realtype t, N_Vector x, int ip, N_Vector sx, N_Vector sxdot)
- virtual std::unique_ptr< Solver > getSolver () override

Protected Member Functions

- virtual void fJ (realtype *J, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const realtype *dwdx)=0
- virtual void fJB (realtype *JB, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *xB, const realtype *w, const realtype *dwdx)
- virtual void fJSparse (SlsMat JSparse, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const realtype *dwdx)=0
- virtual void fJSparseB (SlsMat JSparseB, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *xB, const realtype *w, const realtype *dwdx)
- virtual void fJDiag (realtype *JDiag, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w, const realtype *dwdx)
- virtual void fJv (realtype *Jv, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *v, const realtype *w, const realtype *dwdx)
- virtual void fJvB (realtype *JvB, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *xB, const realtype *vB, const realtype *w, const realtype *dwdx)
- virtual void froot (realtype *root, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h)
- virtual void fxdot (realtype *xdot, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *w)=0
- virtual void fxBdot (realtype *xBdot, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *xB, const realtype *w, const realtype *dwdx)
- virtual void fqBdot (realtype *qBdot, const int ip, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const realtype *xB, const realtype *w, const realtype *dwdp)
- virtual void fdxdotdp (realtype *dxdotdp, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ip, const realtype *w, const realtype *dwdp)
- virtual void fsxdot (realtype *sxdot, const realtype t, const realtype *x, const realtype *p, const realtype *k, const realtype *h, const int ip, const realtype *sx, const realtype *w, const realtype *dwdx, const realtype *J, const realtype *dxdotdp)

Additional Inherited Members

10.13.1 Detailed Description

Definition at line 23 of file model_ode.h.

10.13.2 Constructor & Destructor Documentation

10.13.2.1 Model_ODE() [1/2]

```
Model_ODE ( )
```

default constructor

Definition at line 26 of file model_ode.h.

10.13.2.2 Model_ODE() [2/2]

```
Model_ODE (
            const int nx_rdata,
            const int nxtrue_rdata,
            const int nx_solver,
            const int nxtrue_solver,
            const int ny,
            const int nytrue,
            const int nz,
            const int nztrue,
            const int ne,
            const int nJ,
            const int nw,
            const int ndwdx,
            const int ndwdp,
            const int nnz,
            const int ubw,
            const int lbw,
            const SecondOrderMode o2mode,
            std::vector< realtype > const & p,
            std::vector< realtype > const & k,
            std::vector< int > const & plist,
            std::vector< realtype > const & idlist,
            std::vector< int > const & z2event )
```

constructor with model dimensions

Parameters

nx_rdata	number of state variables
nxtrue_rdata	number of state variables of the non-augmented model
nx_solver	number of state variables with conservation laws applied
nxtrue_solver	number of state variables of the non-augmented model with conservation laws applied
ny	number of observables
nytrue	number of observables of the non-augmented model
nz	number of event observables
nztrue	number of event observables of the non-augmented model
ne	number of events
nJ	number of objective functions
nw	number of repeating elements
ndwdx	number of nonzero elements in the x derivative of the repeating elements
ndwdp	number of nonzero elements in the p derivative of the repeating elements
nnz	number of nonzero elements in Jacobian
ubw	upper matrix bandwidth in the Jacobian

Parameters

lbw	lower matrix bandwidth in the Jacobian
o2mode	second order sensitivity mode
p	parameters
k	constants
plist	indexes wrt to which sensitivities are to be computed
idlist	indexes indicating algebraic components (DAE only)
z2event	mapping of event outputs to events

Definition at line 55 of file model_ode.h.

10.13.3 Member Function Documentation

10.13.3.1 fJ() [1/3]

```
void fJ (
            realtype t,
            realtype cj,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            DlsMat J )  [override], [virtual]
```

Dense Jacobian function

Parameters

t	time
cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
J	dense matrix to which values of the jacobian will be written

Implements Model.

Definition at line 6 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.2 fJ() [2/3]

```
void fJ (
            realtype t,
            N_Vector x,
            N_Vector xdot,
            DlsMat J )
```

implementation of fJ at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation aswell as the AmiVector level implementation

Parameters

t	timepoint
x	Vector with the states
xdot	Vector with the right hand side
J	Matrix to which the Jacobian will be written

Definition at line 20 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.3 fJB() [1/2]

```
void fJB (
            realtype t,
            N_Vector x,
            N_Vector xB,
            N_Vector xBdot,
            DlsMat JB )
```

implementation of fJB at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
x	Vector with the states
xB	Vector with the adjoint states
xBdot	Vector with the adjoint right hand side
JB	Matrix to which the Jacobian will be written

Definition at line 147 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.4 fJSparse() [1/3]

```
void fJSparse (
            realtype t,
            realtype cj,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            SlsMat J )  [override], [virtual]
```

Sparse Jacobian function

Parameters

t	time
cj	scaling factor (inverse of timestep, DAE only)
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
J	sparse matrix to which values of the Jacobian will be written

Implements Model.

Definition at line 28 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.5 fJSparse() [2/3]

```
void fJSparse (
            realtype t,
            N_Vector x,
            SlsMat J )
```

implementation of fJSparse at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation aswell as the AmiVector level implementation

Parameters

t	timepoint
x	Vector with the states
J	Matrix to which the Jacobian will be written

Definition at line 40 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.6 fJSparseB() [1/2]

```
void fJSparseB (
            realtype t,
            N_Vector x,
            N_Vector xB,
            N_Vector xBdot,
            SlsMat JB )
```

implementation of fJSparseB at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
x	Vector with the states
xB	Vector with the adjoint states
xBdot	Vector with the adjoint right hand side
JB	Matrix to which the Jacobian will be written

Definition at line 164 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.7 fJDiag() [1/3]

```
void fJDiag (
            realtype t,
            N_Vector JDiag,
            N_Vector x )
```

implementation of fJDiag at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
JDiag	Vector to which the Jacobian diagonal will be written
x	Vector with the states

Definition at line 178 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.8 fJDiag() [2/3]

```
void fJDiag (
            realtype t,
            AmiVector * JDiag,
            realtype cj,
            AmiVector * x,
            AmiVector * dx )  [override], [virtual]
```

diagonalized Jacobian (for preconditioning)

Parameters

t	timepoint
JDiag	Vector to which the Jacobian diagonal will be written
cj	scaling factor, inverse of the step size
x	Vector with the states
dx	Vector with the derivative states

Returns

status flag indicating successful execution

Implements Model.

Definition at line 114 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.9 fJv() [1/3]

```
void fJv (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot,
            AmiVector * v,
            AmiVector * nJv,
            realtype cj )  [override], [virtual]
```

Jacobian multiply function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
xdot	values of residual function (unused)
v	multiplication vector (unused)
nJv	array to which result of multiplication will be written
cj	scaling factor (inverse of timestep, DAE only)

Implements Model.

Definition at line 48 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.10 fJv() [2/3]

```
void fJv (
            N_Vector v,
            N_Vector Jv,
            realtype t,
            N_Vector x )
```

implementation of fJv at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation aswell as the AmiVector level implementation

Parameters

t	timepoint
x	Vector with the states
v	Vector with which the Jacobian is multiplied
Jv	Vector to which the Jacobian vector product will be written

Definition at line 62 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.11 fJvB() [1/2]

```
void fJvB (
            N_Vector vB,
            N_Vector JvB,
            realtype t,
            N_Vector x,
            N_Vector xB )
```

implementation of fJvB at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
x	Vector with the states
xB	Vector with the adjoint states
vB	Vector with which the Jacobian is multiplied
JvB	Vector to which the Jacobian vector product will be written

Definition at line 195 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.12 froot() [1/3]

```
void froot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            realtype * root )  [override], [virtual]
```

Root function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
root	array to which values of the root function will be written

Implements Model.

Definition at line 70 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.13 froot() [2/3]

```
void froot (
            realtype t,
            N_Vector x,
            realtype * root )
```

implementation of froot at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation aswell as the AmiVector level implementation

Parameters

t	timepoint
x	Vector with the states
root	array with root function values

Definition at line 81 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.14 fxdot() [1/3]

```
void fxdot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            AmiVector * xdot )  [override], [virtual]
```

Residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
xdot	array to which values of the residual function will be written

Implements Model.

Definition at line 87 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.15 fxdot() [2/3]

```
void fxdot (
            realtype t,
            N_Vector x,
            N_Vector xdot )
```

implementation of fxdot at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation aswell as the AmiVector level implementation

Parameters

t	timepoint
x	Vector with the states
xdot	Vector with the right hand side

Definition at line 98 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.16 fxBdot() [1/2]

```
void fxBdot (
            realtype t,
            N_Vector x,
            N_Vector xB,
            N_Vector xBdot )
```

implementation of fxBdot at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
x	Vector with the states
xB	Vector with the adjoint states
xBdot	Vector with the adjoint right hand side

Definition at line 210 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.17 fqBdot() [1/2]

```
void fqBdot (
            realtype t,
            N_Vector x,
            N_Vector xB,
            N_Vector qBdot )
```

implementation of fqBdot at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
x	Vector with the states
xB	Vector with the adjoint states
qBdot	Vector with the adjoint quadrature right hand side

Definition at line 225 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.18 fdxdotdp() [1/3]

```
void fdxdotdp (
            const realtype t,
            const N_Vector x )
```

Sensitivity of dx/dt wrt model parameters p

Parameters

t	timepoint
x	Vector with the states

Returns

status flag indicating successful execution

Definition at line 126 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.19 fdxdotdp() [2/3]

```
virtual void fdxdotdp (
            realtype t,
            AmiVector * x,
            AmiVector * dx )  [override], [virtual]
```

parameter derivative of residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)

Returns

flag indicating successful evaluation

Implements Model.

Definition at line 103 of file model_ode.h.

Here is the call graph for this function:

10.13.3.20 fsxdot() [1/3]

```
void fsxdot (
            realtype t,
            AmiVector * x,
            AmiVector * dx,
            int ip,
            AmiVector * sx,
            AmiVector * sdx,
            AmiVector * sxdot )  [override], [virtual]
```

Sensitivity Residual function

Parameters

t	time
x	state
dx	time derivative of state (DAE only)
ip	parameter index
sx	sensitivity state
sdx	time derivative of sensitivity state (DAE only)
sxdot	array to which values of the sensitivity residual function will be written

Implements Model.

Definition at line 235 of file model_ode.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.13.3.21 fsxdot() [2/3]

```
void fsxdot (
            realtype t,
            N_Vector x,
            int ip,
            N_Vector sx,
            N_Vector sxdot )
```

implementation of fsxdot at the N_Vector level, this function provides an interface to the model specific routines for the solver implementation

Parameters

t	timepoint
x	Vector with the states
ip	parameter index
sx	Vector with the state sensitivities
sxdot	Vector with the sensitivity right hand side

Definition at line 248 of file model_ode.cpp.

Here is the call graph for this function:

10.13.3.22 getSolver()

```
std::unique_ptr< Solver > getSolver ( ) [override], [virtual]
```

Retrieves the solver object

Returns

The Solver instance

Implements Model.

Definition at line 135 of file model_ode.cpp.

10.13.3.23 fJ() [3/3]

```
virtual void fJ (
            realtype * J,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w,
            const realtype * dwdx ) [protected], [pure virtual]
```

model specific implementation for fJ

Parameters

J	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables
dwdx	derivative of w wrt x

10.13.3.24 fJB() [2/2]

```
virtual void fJB (
            realtype * JB,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * xB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJB

Parameters

JB	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 138 of file model_ode.h.

10.13.3.25 fJSparse() [3/3]

```
virtual void fJSparse (
            SlsMat JSparse,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
```

```
            const realtype * h,
            const realtype * w,
            const realtype * dwdx )  [protected], [pure virtual]
```

model specific implementation for fJSparse

Parameters

JSparse	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables
dwdx	derivative of w wrt x

10.13.3.26 fJSparseB() [2/2]

```
virtual void fJSparseB (
            SlsMat JSparseB,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * xB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJSparseB

Parameters

JSparseB	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 166 of file model_ode.h.

10.13.3.27 fJDiag() [3/3]

```
virtual void fJDiag (
            realtype * JDiag,
```

```
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJDiag

Parameters

JDiag	Matrix to which the Jacobian will be written
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 181 of file model_ode.h.

10.13.3.28 fJv() [3/3]

```
virtual void fJv (
            realtype * Jv,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * v,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJv

Parameters

Jv	Matrix vector product of J with a vector v
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
v	Vector with which the Jacobian is multiplied
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 197 of file model_ode.h.

10.13.3.29 fJvB() [2/2]

```
virtual void fJvB (
            realtype * JvB,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * xB,
            const realtype * vB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fJvB

Parameters

JvB	Matrix vector product of JB with a vector v
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
vB	Vector with which the Jacobian is multiplied
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 214 of file model_ode.h.

10.13.3.30 froot() [3/3]

```
virtual void froot (
            realtype * root,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h )  [protected], [virtual]
```

model specific implementation for froot

Parameters

root	values of the trigger function
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector

Definition at line 227 of file model_ode.h.

10.13.3.31 fxdot() [3/3]

```
virtual void fxdot (
            realtype * xdot,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * w )  [protected], [pure virtual]
```

model specific implementation for fxdot

Parameters

xdot	residual function
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
w	vector with helper variables

10.13.3.32 fxBdot() [2/2]

```
virtual void fxBdot (
            realtype * xBdot,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * xB,
            const realtype * w,
            const realtype * dwdx )  [protected], [virtual]
```

model specific implementation for fxBdot

Parameters

xBdot	adjoint residual function
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
w	vector with helper variables
dwdx	derivative of w wrt x

Definition at line 253 of file model_ode.h.

10.13.3.33 fqBdot() [2/2]

```
virtual void fqBdot (
            realtype * qBdot,
            const int ip,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const realtype * xB,
            const realtype * w,
            const realtype * dwdp )  [protected], [virtual]
```

model specific implementation for fqBdot

Parameters

qBdot	adjoint quadrature equation
ip	sensitivity index
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
xB	Vector with the adjoint states
w	vector with helper variables
dwdp	derivative of w wrt p

Definition at line 270 of file model_ode.h.

10.13.3.34 fdxdotdp() [3/3]

```
virtual void fdxdotdp (
            realtype * dxdotdp,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip,
            const realtype * w,
            const realtype * dwdp )  [protected], [virtual]
```

model specific implementation of fdxdotdp

Parameters

dxdotdp	partial derivative xdot wrt p
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
ip	parameter index
w	vector with helper variables
dwdp	derivative of w wrt p

Definition at line 286 of file model_ode.h.

10.13.3.35 fsxdot() [3/3]

```
virtual void fsxdot (
            realtype * sxdot,
            const realtype t,
            const realtype * x,
            const realtype * p,
            const realtype * k,
            const realtype * h,
            const int ip,
            const realtype * sx,
            const realtype * w,
            const realtype * dwdx,
            const realtype * J,
            const realtype * dxdotdp )  [protected], [virtual]
```

model specific implementation of fsxdot

Parameters

sxdot	sensitivity rhs
t	timepoint
x	Vector with the states
p	parameter vector
k	constants vector
h	heavyside vector
ip	parameter index
sx	Vector with the state sensitivities
w	vector with helper variables
dwdx	derivative of w wrt x
J	jacobian
dxdotdp	parameter derivative of residual function

Definition at line 305 of file model_ode.h.

10.14 NewtonFailure Class Reference

newton failure exception this exception should be thrown when the steady state computation failed to converge for this exception we can assume that we can recover from the exception and return a solution struct to the user

```
#include <exception.h>
```

Inheritance diagram for NewtonFailure:

Public Member Functions

- NewtonFailure (int code, const char *function)

Public Attributes

- int error_code

10.14.1 Detailed Description

Definition at line 203 of file exception.h.

10.14.2 Constructor & Destructor Documentation

10.14.2.1 NewtonFailure()

```
NewtonFailure (
            int code,
            const char * function )
```

constructor, simply calls AmiException constructor

Parameters

function	name of the function in which the error occured
code	error code

Definition at line 211 of file exception.h.

10.14.3 Member Data Documentation

10.14.3.1 error_code

```
int error_code
```

error code returned by solver

Definition at line 206 of file exception.h.

10.15 NewtonSolver Class Reference

The NewtonSolver class sets up the linear solver for the Newton method.

```
#include <newton_solver.h>
```

Inheritance diagram for NewtonSolver:

Public Member Functions

- NewtonSolver (realtype ∗t, AmiVector ∗x, Model ∗model, ReturnData ∗rdata)
- void getStep (int ntry, int nnewt, AmiVector ∗delta)
- void computeNewtonSensis (AmiVectorArray ∗sx)
- virtual void prepareLinearSystem (int ntry, int nnewt)=0
- virtual void solveLinearSystem (AmiVector ∗rhs)=0

Static Public Member Functions

- static std::unique_ptr< NewtonSolver > getSolver (realtype ∗t, AmiVector ∗x, LinearSolver linsolType, Model ∗model, ReturnData ∗rdata, int maxlinsteps, int maxsteps, double atol, double rtol)

Public Attributes

- int maxlinsteps = 0
- int maxsteps = 0
- double atol = 1e-16
- double rtol = 1e-8

Protected Attributes

- realtype * t
- Model * model
- ReturnData * rdata
- AmiVector xdot
- AmiVector * x
- AmiVector dx

10.15.1 Detailed Description

Definition at line 25 of file newton_solver.h.

10.15.2 Constructor & Destructor Documentation

10.15.2.1 NewtonSolver()

```
NewtonSolver (
            realtype * t,
            AmiVector * x,
            Model * model,
            ReturnData * rdata )
```

default constructor, initializes all members with the provided objects

Parameters

t	pointer to time variable
x	pointer to state variables
model	pointer to the AMICI model object
rdata	pointer to the return data object

Definition at line 20 of file newton_solver.cpp.

10.15.3 Member Function Documentation

10.15.3.1 getSolver()

```
std::unique_ptr< NewtonSolver > getSolver (
            realtype * t,
            AmiVector * x,
            LinearSolver linsolType,
            Model * model,
            ReturnData * rdata,
            int maxlinsteps,
            int maxsteps,
            double atol,
            double rtol )  [static]
```

Tries to determine the steady state of the ODE system by a Newton solver, uses forward intergration, if the Newton solver fails, restarts Newton solver, if integration fails. Computes steady state sensitivities

Parameters

t	pointer to time variable
x	pointer to state variables
linsolType	integer indicating which linear solver to use
model	pointer to the AMICI model object
rdata	pointer to the return data object
maxlinsteps	maximum number of allowed linear steps per Newton step for steady state computation
maxsteps	maximum number of allowed Newton steps for steady state computation
atol	absolute tolerance
rtol	relative tolerance

Returns

solver NewtonSolver according to the specified linsolType

Definition at line 38 of file newton_solver.cpp.

Here is the caller graph for this function:

10.15.3.2 getStep()

```
void getStep (
            int ntry,
            int nnewt,
            AmiVector * delta )
```

Computes the solution of one Newton iteration

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step
delta	containing the RHS of the linear system, will be overwritten by solution to the linear system

Definition at line 109 of file newton_solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.15.3.3 computeNewtonSensis()

```
void computeNewtonSensis (
            AmiVectorArray * sx )
```

Computes steady state sensitivities

Parameters

sx	pointer to state variable sensitivities

Definition at line 129 of file newton_solver.cpp.

Here is the call graph for this function:

10.15.3.4 prepareLinearSystem()

```
virtual void prepareLinearSystem (
            int ntry,
            int nnewt )  [pure virtual]
```

Writes the Jacobian for the Newton iteration and passes it to the linear solver

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Implemented in NewtonSolverIterative, NewtonSolverSparse, and NewtonSolverDense.

Here is the caller graph for this function:

10.15.3.5 solveLinearSystem()

```
virtual void solveLinearSystem (
            AmiVector * rhs )  [pure virtual]
```

Solves the linear system for the Newton step

Parameters

rhs	containing the RHS of the linear system, will be overwritten by solution to the linear system

Implemented in NewtonSolverIterative, NewtonSolverSparse, and NewtonSolverDense.

Here is the caller graph for this function:

10.15.4 Member Data Documentation

10.15.4.1 maxlinsteps

```
int maxlinsteps = 0
```

maximum number of allowed linear steps per Newton step for steady state computation

Definition at line 59 of file newton_solver.h.

10.15.4.2 maxsteps

```
int maxsteps = 0
```

maximum number of allowed Newton steps for steady state computation

Definition at line 61 of file newton_solver.h.

10.15.4.3 atol

```
double atol = 1e-16
```

absolute tolerance

Definition at line 63 of file newton_solver.h.

10.15.4.4 rtol

```
double rtol = 1e-8
```

relative tolerance

Definition at line 65 of file newton_solver.h.

10.15.4.5 t

```
realtype* t  [protected]
```

time variable

Definition at line 69 of file newton_solver.h.

10.15.4.6 model

```
Model* model  [protected]
```

pointer to the AMICI model object

Definition at line 71 of file newton_solver.h.

10.15.4.7 rdata

```
ReturnData* rdata  [protected]
```

pointer to the return data object

Definition at line 73 of file newton_solver.h.

10.15.4.8 xdot

```
AmiVector xdot [protected]
```

right hand side AmiVector

Definition at line 75 of file newton_solver.h.

10.15.4.9 x

```
AmiVector* x [protected]
```

current state

Definition at line 77 of file newton_solver.h.

10.15.4.10 dx

```
AmiVector dx [protected]
```

current state time derivative (DAE)

Definition at line 79 of file newton_solver.h.

10.16 NewtonSolverDense Class Reference

The NewtonSolverDense provides access to the dense linear solver for the Newton method.

```
#include <newton_solver.h>
```

Inheritance diagram for NewtonSolverDense:

Public Member Functions

- NewtonSolverDense (realtype *t, AmiVector *x, Model *model, ReturnData *rdata)
- void solveLinearSystem (AmiVector *rhs) override
- void prepareLinearSystem (int ntry, int nnewt) override

Additional Inherited Members

10.16.1 Detailed Description

Definition at line 88 of file newton_solver.h.

10.16.2 Constructor & Destructor Documentation

10.16.2.1 NewtonSolverDense()

```
NewtonSolverDense (
            realtype * t,
            AmiVector * x,
            Model * model,
            ReturnData * rdata )
```

default constructor, initializes all members with the provided objects and initializes temporary storage objects

Parameters

t	pointer to time variable
x	pointer to state variables
model	pointer to the AMICI model object
rdata	pointer to the return data object

Definition at line 154 of file newton_solver.cpp.

10.16.3 Member Function Documentation

10.16.3.1 solveLinearSystem()

```
void solveLinearSystem (
            AmiVector * rhs )  [override], [virtual]
```

Solves the linear system for the Newton step

Parameters

rhs	containing the RHS of the linear system, will be overwritten by solution to the linear system

Solves the linear system for the Newton step

Parameters

rhs	containing the RHS of the linear system, will be overwritten by solution to the linear system

Implements NewtonSolver.

Definition at line 193 of file newton_solver.cpp.

Here is the call graph for this function:

10.16.3.2 prepareLinearSystem()

```
void prepareLinearSystem (
            int ntry,
            int nnewt )  [override], [virtual]
```

Writes the Jacobian for the Newton iteration and passes it to the linear solver

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Writes the Jacobian for the Newton iteration and passes it to the linear solver

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Implements NewtonSolver.

Definition at line 173 of file newton_solver.cpp.

Here is the call graph for this function:

10.17 NewtonSolverIterative Class Reference

The NewtonSolverIterative provides access to the iterative linear solver for the Newton method.

```
#include <newton_solver.h>
```

Inheritance diagram for NewtonSolverIterative:

Public Member Functions

- NewtonSolverIterative (realtype ∗t, AmiVector ∗x, Model ∗model, ReturnData ∗rdata)
- void solveLinearSystem (AmiVector ∗rhs) override
- void prepareLinearSystem (int ntry, int nnewt) override
- void linsolveSPBCG (int ntry, int nnewt, AmiVector ∗ns_delta)

Additional Inherited Members

10.17.1 Detailed Description

Definition at line 136 of file newton_solver.h.

10.17.2 Constructor & Destructor Documentation

10.17.2.1 NewtonSolverIterative()

```
NewtonSolverIterative (
            realtype * t,
            AmiVector * x,
            Model * model,
            ReturnData * rdata )
```

default constructor, initializes all members with the provided objects

Parameters

t	pointer to time variable
x	pointer to state variables
model	pointer to the AMICI model object
rdata	pointer to the return data object

Definition at line 337 of file newton_solver.cpp.

10.17.3 Member Function Documentation

10.17.3.1 solveLinearSystem()

```
void solveLinearSystem (
            AmiVector * rhs )  [override], [virtual]
```

Solves the linear system for the Newton step

Parameters

rhs	containing the RHS of the linear system, will be overwritten by solution to the linear system

Solves the linear system for the Newton step by passing it to linsolveSPBCG

Parameters

rhs	containing the RHS of the linear system, will be overwritten by solution to the linear system

Implements NewtonSolver.

Definition at line 375 of file newton_solver.cpp.

Here is the call graph for this function:

10.17.3.2 prepareLinearSystem()

```
void prepareLinearSystem (
            int ntry,
            int nnewt )  [override], [virtual]
```

Writes the Jacobian for the Newton iteration and passes it to the linear solver

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Writes the Jacobian for the Newton iteration and passes it to the linear solver. Also wraps around getSensis for iterative linear solver.

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Implements NewtonSolver.

Definition at line 354 of file newton_solver.cpp.

10.17.3.3 linsolveSPBCG()

```
void linsolveSPBCG (
            int ntry,
            int nnewt,
            AmiVector * ns_delta )
```

Iterative linear solver created from SPILS BiCG-Stab. Solves the linear system within each Newton step if iterative solver is chosen.

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step
ns_delta	Newton step

Definition at line 388 of file newton_solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.18 NewtonSolverSparse Class Reference

The NewtonSolverSparse provides access to the sparse linear solver for the Newton method.

```
#include <newton_solver.h>
```

Inheritance diagram for NewtonSolverSparse:

Public Member Functions

- NewtonSolverSparse (realtype ∗t, AmiVector ∗x, Model ∗model, ReturnData ∗rdata)
- void solveLinearSystem (AmiVector ∗rhs) override
- void prepareLinearSystem (int ntry, int nnewt) override

Additional Inherited Members

10.18.1 Detailed Description

Definition at line 109 of file newton_solver.h.

10.18.2 Constructor & Destructor Documentation

10.18.2.1 NewtonSolverSparse()

```
NewtonSolverSparse (
            realtype * t,
            AmiVector * x,
            Model * model,
            ReturnData * rdata )
```

default constructor, initializes all members with the provided objects, initializes temporary storage objects and the klu solver

Parameters

t	pointer to time variable
x	pointer to state variables
model	pointer to the AMICI model object
rdata	pointer to the return data object

Definition at line 223 of file newton_solver.cpp.

10.18.3 Member Function Documentation

10.18.3.1 solveLinearSystem()

```
void solveLinearSystem (
            AmiVector * rhs )  [override], [virtual]
```

Solves the linear system for the Newton step

Parameters

rhs	containing the RHS of the linear system, will be overwritten by solution to the linear system

Solves the linear system for the Newton step

Parameters

rhs	containing the RHS of the linear system,will be overwritten by solution to the linear system

Implements NewtonSolver.

Definition at line 303 of file newton_solver.cpp.

Here is the call graph for this function:

10.18.3.2 prepareLinearSystem()

```
void prepareLinearSystem (
            int ntry,
            int nnewt )  [override], [virtual]
```

Writes the Jacobian for the Newton iteration and passes it to the linear solver

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Writes the Jacobian for the Newton iteration and passes it to the linear solver

Parameters

ntry	integer newton_try integer start number of Newton solver (1 or 2)
nnewt	integer number of current Newton step

Implements NewtonSolver.

Definition at line 245 of file newton_solver.cpp.

Here is the call graph for this function:

10.19 ConservationLaw Class Reference

A conservation law defines the absolute the total amount of a (weighted) sum of states.

Inheritance diagram for ConservationLaw:

Public Member Functions

- def __init__ (self, identifier, name, value)

  Create a new ConservationLaw instance.

10.19.1 Detailed Description

Definition at line 500 of file ode_export.py.

10.19.2 Constructor & Destructor Documentation

10.19.2.1 __init__()

```
def __init__ (
              self,
              identifier,
              name,
              value )
```

Parameters

identifier	unique identifier of the ConservationLaw **Type**: sympy.Symbol
name	individual name of the ConservationLaw (does not need to be unique) **Type**: str
value	formula (sum of states) **Type**: symengine.Basic

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 519 of file ode_export.py.

10.20 Constant Class Reference

A Constant is a fixed variable in the model with respect to which sensitivites cannot be computed, abbreviated by `k`

Inheritance diagram for Constant:

Public Member Functions

- def __init__ (self, identifier, name, value)

  Create a new Expression instance.

10.20.1 Detailed Description

Definition at line 635 of file ode_export.py.

10.20.2 Constructor & Destructor Documentation

10.20.2.1 __init__()

```
def __init__ (
            self,
            identifier,
            name,
            value )
```

Parameters

identifier	unique identifier of the Constant **Type**: sympy.Symbol
name	individual name of the Constant (does not need to be unique) **Type**: str
value	numeric value **Type**: float

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 654 of file ode_export.py.

10.21 Expression Class Reference

An Expressions is a recurring elements in symbolic formulas.

Inheritance diagram for Expression:

Public Member Functions

- def __init__ (self, identifier, name, value)

  Create a new Expression instance.

10.21.1 Detailed Description

Specifying this may yield more compact expression which may lead to substantially shorter model compilation times, but may also reduce model simulation time, abbreviated by `w`

Definition at line 582 of file ode_export.py.

10.21.2 Constructor & Destructor Documentation

10.21.2.1 __init__()

```
def __init__ (
            self,
            identifier,
            name,
            value )
```

Parameters

identifier	unique identifier of the Expression **Type**: sympy.Symbol
name	individual name of the Expression (does not need to be unique) **Type**: str
value	formula **Type**: symengine.Basic

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 600 of file ode_export.py.

10.22 LogLikelihood Class Reference

A LogLikelihood defines the distance between measurements and experiments for a particular observable.

Inheritance diagram for LogLikelihood:

Public Member Functions

- def __init__ (self, identifier, name, value)
  Create a new Expression instance.

10.22.1 Detailed Description

The final LogLikelihood value in the simulation will be the sum of all specified LogLikelihood instances evaluated at all timepoints, abbreviated by `Jy`

Definition at line 664 of file ode_export.py.

10.22.2 Constructor & Destructor Documentation

10.22.2.1 __init__()

```
def __init__ (
              self,
              identifier,
              name,
              value )
```

Parameters

identifier	unique identifier of the LogLikelihood **Type**: sympy.Symbol
name	individual name of the LogLikelihood (does not need to be unique) **Type**: str
value	formula **Type**: symengine.Basic

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 684 of file ode_export.py.

10.23 ModelQuantity Class Reference

Base class for model components.

Inheritance diagram for ModelQuantity:

Public Member Functions

- def __init__ (self, identifier, name, value)

  Create a new ModelQuantity instance.
- def __repr__ (self)

  Representation of the ModelQuantity object.
- def get_id (self)

  ModelQuantity identifier.
- def get_name (self)

  ModelQuantity name.
- def get_val (self)

  ModelQuantity value.

10.23.1 Detailed Description

Definition at line 302 of file ode_export.py.

10.23.2 Constructor & Destructor Documentation

10.23.2.1 __init__()

```
def __init__ (
            self,
            identifier,
            name,
            value )
```

This function sanitizes input from pysb to make sure we are operating on flat symby.Symbol and sympy.Basic and not respective derived pysb classes

Parameters

identifier	unique identifier of the quantity **Type**: sympy.Symbol
name	individual name of the quantity (does not need to be unique) **Type**: str
value	either formula, numeric value or initial value

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented in LogLikelihood, Constant, Parameter, Expression, SigmaY, Observable, and ConservationLaw.

Definition at line 322 of file ode_export.py.

Here is the call graph for this function:

10.23.3 Member Function Documentation

10.23.3.1 __repr__()

```
def __repr__ (
              self )
```

Returns

string representation of the ModelQuantity

Definition at line 360 of file ode_export.py.

10.23.3.2 get_id()

```
def get_id (
              self )
```

Returns

identifier of the ModelQuantity

Definition at line 373 of file ode_export.py.

10.23.3.3 get_name()

```
def get_name (
              self )
```

Returns

name of the ModelQuantity

Definition at line 386 of file ode_export.py.

10.23.3.4 get_val()

```
def get_val (
              self )
```

Returns

value of the ModelQuantity

Definition at line 399 of file ode_export.py.

10.24 Observable Class Reference

An Observable links model simulations to experimental measurements, abbreviated by `y`

Inheritance diagram for Observable:

Public Member Functions

- def __init__ (self, identifier, name, value)
  Create a new Observable instance.

10.24.1 Detailed Description

Definition at line 527 of file ode_export.py.

10.24.2 Constructor & Destructor Documentation

10.24.2.1 __init__()

```
def __init__ (
              self,
              identifier,
              name,
              value )
```

Parameters

identifier	unique identifier of the Observable **Type**: sympy.Symbol
name	individual name of the Observable (does not need to be unique) **Type**: str
value	formula **Type**: symengine.Basic

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 545 of file ode_export.py.

10.25 ODEExporter Class Reference

The ODEExporter class generates AMICI C++ files for ODE model as defined in symbolic expressions.

Public Member Functions

- def __init__ (self, ode_model, outdir=None, verbose=False, assume_pow_positivity=False, compiler=None, allow_reinit_fixpar_initcond=True)

  Generate AMICI C++ files for the ODE provided to the constructor.
- def generateModelCode (self)

  Generates the native C++ code for the loaded model.
- def compileModel (self)

  Compiles the generated code it into a simulatable module.
- def setPaths (self, output_dir)

  Set output paths for the model and create if necessary.
- def setName (self, modelName)

  Sets the model name.

Public Attributes

- outdir

  see sbml_import.setPaths()
  ***Type**: str*
- verbose

  more verbose output if True
  ***Type**: bool*
- assume_pow_positivity

  if set to true, a special pow function is
- compiler

  distutils/setuptools compiler selection to build the
- modelName

  name of the model that will be used for compilation
- modelPath

  path to the generated model specific files
  ***Type**: str*
- modelSwigPath

  path to the generated swig files
  ***Type**: str*
- model

  ODE definition
  ***Type**: ODEModel.*
- functions

  carries C++ function signatures and other specifications
- allow_reinit_fixpar_initcond

  indicates whether reinitialization of

10.25.1 Detailed Description

```
initial states depending on fixedParmeters is allowed for this model
<br><b>Type</b>: bool
```

Definition at line 1862 of file ode_export.py.

10.25.2 Constructor & Destructor Documentation

10.25.2.1 __init__()

```
def __init__ (
              self,
              ode_model,
              outdir = None,
              verbose = False,
              assume_pow_positivity = False,
              compiler = None,
              allow_reinit_fixpar_initcond = True )
```

Parameters

ode_model	ODE definition **Type**: ODEModel
outdir	see sbml_import.setPaths() **Type**: str
verbose	more verbose output if True **Type**: bool
assume_pow_positivity	if set to true, a special pow function is used to avoid problems with state variables that may become negative due to numerical errors **Type**: bool
compiler	distutils/setuptools compiler selection to build the python extension **Type**: str
allow_reinit_fixpar_initcond	see ODEExporter

Returns

Definition at line 1944 of file ode_export.py.

10.25.3 Member Function Documentation

10.25.3.1 generateModelCode()

```
def generateModelCode (
              self )
```

Returns

Definition at line 1984 of file ode_export.py.

Here is the call graph for this function:

10.25.3.2 compileModel()

```
def compileModel (
            self )
```

Returns

Definition at line 1997 of file ode_export.py.

Here is the call graph for this function:

10.25.3.3 setPaths()

```
def setPaths (
            self,
            output_dir )
```

Parameters

output_dir	relative or absolute path where the generated model code is to be placed. will be created if does not exists. **Type**: str

Returns

Definition at line 2605 of file ode_export.py.

10.25.3.4 setName()

```
def setName (
            self,
            modelName )
```

Parameters

modelName	name of the model (must only contain valid filename characters) **Type**: str

Returns

Definition at line 2624 of file ode_export.py.

10.26 ODEModel Class Reference

An ODEModel defines an Ordinay Differential Equation as set of ModelQuantities.

Public Member Functions

- def __init__ (self)

  Create a new ODEModel instance.
- def import_from_sbml_importer (self, si)

  Imports a model specification from a amici.SBMLImporter instance.
- def add_component (self, component)

  Adds a new ModelQuantity to the model.
- def add_conservation_law (self, state, law)

  Adds a new conservation law to the model.
- def nx_rdata (self)

  Number of states.
- def nx_solver (self)

Number of states after applying conservation laws.

- def ncl (self)

  Number of conservation laws.
- def ny (self)

  Number of Observables.
- def nk (self)

  Number of Constants.
- def np (self)

  Number of Parameters.
- def sym (self, name)

  Returns (and constructs if necessary) the identifiers for a symbolic entity.
- def sparsesym (self, name)

  Returns (and constructs if necessary) the sparsified identifiers for a sparsified symbolic variable.
- def eq (self, name)

  Returns (and constructs if necessary) the formulas for a symbolic entity.
- def sparseeq (self, name)

  Returns (and constructs if necessary) the sparsified formulas for a sparsified symbolic variable.
- def colptr (self, name)

  Returns (and constructs if necessary) the column pointers for a sparsified symbolic variable.
- def rowval (self, name)

  Returns (and constructs if necessary) the row values for a sparsified symbolic variable.
- def val (self, name)

  Returns (and constructs if necessary) the numeric values of a symbolic entity.
- def name (self, name)

  Returns (and constructs if necessary) the names of a symbolic variable.
- def generateBasicVariables (self)

  Generates the symbolic identifiers for all variables in ODEModel.variable_prototype.
- def symNames (self)

  Returns a list of names of generated symbolic variables.
- def sym_or_eq (self, name, varname)

  Returns symbols or equations depending on whether a given variable appears in the function signature or not.
- def get_conservation_laws (self)

  Returns a list of states with conservation law set.
- def state_has_fixed_parameter_initial_condition (self, ix)

  Checks whether the state at specified index has a fixed parameter initial condition.
- def state_has_conservation_law (self, ix)

  Checks whether the state at specified index has a conservation law set.

10.26.1 Detailed Description

This class provides general purpose interfaces to compute arbitrary symbolic derivatives that are necessary for model simulation or sensitivity computation

```
derivative from a partial derivative call to enforce a partial
derivative in the next recursion. prevents infinite recursion
```

Definition at line 710 of file ode_export.py.

10.26.2 Constructor & Destructor Documentation

10.26.2.1 __init__()

```
def __init__ (
              self )
```

Returns

New ODEModel instance

Definition at line 870 of file ode_export.py.

Here is the call graph for this function:

10.26.3 Member Function Documentation

10.26.3.1 import_from_sbml_importer()

```
def import_from_sbml_importer (
              self,
              si )
```

Parameters

si	imported SBML model **Type**: amici.SbmlImporter

Returns

Definition at line 972 of file ode_export.py.

Here is the call graph for this function:

10.26.3.2 add_component()

```
def add_component (
            self,
            component )
```

Parameters

component	model quantity to be added **Type**: ModelQuantity

Returns

Exceptions

Exception	invalid component type

Definition at line 1006 of file ode_export.py.

Here is the caller graph for this function:

10.26.3.3 add_conservation_law()

```
def add_conservation_law (
              self,
              state,
              law )
```

Parameters

state	symbolic identifier of the state that should be replaced by the conservation law
law	symbolic formula that together with the state defines the conservation law, i.e., d/dt (state + law) = 0

Returns

```
        Exception if the specified state does not correspond to a valid
        state in the model
```

Definition at line 1031 of file ode_export.py.

Here is the call graph for this function:

10.26.3.4 nx_rdata()

```
def nx_rdata (
              self )
```

Returns

number of state variable symbols

Definition at line 1075 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.5 nx_solver()

```
def nx_solver (
              self )
```

Returns

number of state variable symbols

Definition at line 1088 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.6 ncl()

```
def ncl (
            self )
```

Returns

number of conservation laws

Definition at line 1101 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.7 ny()

```
def ny (
            self )
```

Returns

number of observable symbols

Definition at line 1114 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.8 nk()

```
def nk (
            self )
```

Returns

number of constant symbols

Definition at line 1127 of file ode_export.py.

Here is the call graph for this function:

10.26.3.9 np()

```
def np (
            self )
```

Returns

number of parameter symbols

Definition at line 1140 of file ode_export.py.

Here is the call graph for this function:

10.26.3.10 sym()

```
def sym (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

containing the symbolic identifiers
Type: symengine.DenseMatrix

Definition at line 1155 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.11 sparsesym()

```
def sparsesym (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

linearized symengine.DenseMatrix containing the symbolic identifiers

Definition at line 1172 of file ode_export.py.

Here is the call graph for this function:

10.26.3.12 eq()

```
def eq (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

symengine.DenseMatrix containing the symbolic identifiers

Definition at line 1191 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.13 sparseeq()

```
def sparseeq (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

linearized symengine.DenseMatrix containing the symbolic formulas

Definition at line 1209 of file ode_export.py.

Here is the call graph for this function:

10.26.3.14 colptr()

```
def colptr (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

symengine.DenseMatrix containing the column pointers

Definition at line 1228 of file ode_export.py.

Here is the call graph for this function:

10.26.3.15 rowval()

```
def rowval (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

symengine.DenseMatrix containing the row values

Definition at line 1247 of file ode_export.py.

Here is the call graph for this function:

10.26.3.16 val()

```
def val (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

list containing the numeric values

Definition at line 1266 of file ode_export.py.

Here is the call graph for this function:

10.26.3.17 name()

```
def name (
            self,
            name )
```

Parameters

name	name of the symbolic variable **Type**: str

Returns

list of names

Definition at line 1283 of file ode_export.py.

Here is the call graph for this function:

10.26.3.18 generateBasicVariables()

```
def generateBasicVariables (
            self )
```

Returns

Definition at line 1353 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.19 symNames()

```
def symNames (
            self )
```

Returns

list of names

Definition at line 1547 of file ode_export.py.

Here is the call graph for this function:

10.26.3.20 sym_or_eq()

```
def sym_or_eq (
              self,
              name,
              varname )
```

Parameters

name	name of function for which the signature should be checked
varname	name of the variable which should be contained in the function signature

Returns

the variable symbols if the variable is part of the signature and the variable equations otherwise.

Definition at line 1676 of file ode_export.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.26.3.21 get_conservation_laws()

```
def get_conservation_laws (
                self )
```

Returns

list of state identifiers

Definition at line 1760 of file ode_export.py.

Here is the caller graph for this function:

10.26.3.22 state_has_fixed_parameter_initial_condition()

```
def state_has_fixed_parameter_initial_condition (
              self,
              ix )
```

Parameters

ix	state index

Returns

boolean indicating if any of the initial condition free variables is contained in the model constants

Definition at line 1829 of file ode_export.py.

10.26.3.23 state_has_conservation_law()

```
def state_has_conservation_law (
              self,
              ix )
```

Parameters

ix	state index

Returns

boolean indicating if conservation_law is not None

Definition at line 1850 of file ode_export.py.

10.27 Parameter Class Reference

A Parameter is a free variable in the model with respect to which sensitivites may be computed, abbreviated by `p`

Inheritance diagram for Parameter:

Public Member Functions

- def __init__ (self, identifier, name, value)

  Create a new Expression instance.

10.27.1 Detailed Description

Definition at line 608 of file ode_export.py.

10.27.2 Constructor & Destructor Documentation

10.27.2.1 __init__()

```
def __init__ (
            self,
            identifier,
            name,
            value )
```

Parameters

identifier	unique identifier of the Parameter **Type**: sympy.Symbol
name	individual name of the Parameter (does not need to be unique) **Type**: str
value	numeric value **Type**: float

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 627 of file ode_export.py.

10.28 SigmaY Class Reference

A Standard Deviation SigmaY rescales the distance between simulations and measurements when computing residuals, abbreviated by `sigmay`

Inheritance diagram for SigmaY:

Public Member Functions

- def __init__ (self, identifier, name, value)
  Create a new Standard Deviation instance.

10.28.1 Detailed Description

Definition at line 553 of file ode_export.py.

10.28.2 Constructor & Destructor Documentation

10.28.2.1 __init__()

```
def __init__ (
            self,
            identifier,
            name,
            value )
```

Parameters

identifier	unique identifier of the Standard Deviation **Type**: sympy.Symbol
name	individual name of the Standard Deviation (does not need to be unique) **Type**: str
value	formula **Type**: symengine.Basic

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Reimplemented from ModelQuantity.

Definition at line 572 of file ode_export.py.

10.29 State Class Reference

A State variable defines an entity that evolves with time according to the provided time derivative, abbreviated by `x`

Inheritance diagram for State:

Public Member Functions

- def __init__ (self, identifier, name, value, dt)

  Create a new State instance.
- def set_conservation_law (self, law)

  Sets the conservation law of a state.
- def set_dt (self, dt)

  Sets the time derivative.
- def get_dt (self)

  Sets the time derivative.

Static Public Attributes

- conservation_law = None

  algebraic formula that allows computation of this

10.29.1 Detailed Description

```
species according to a conservation law
```

Definition at line 410 of file ode_export.py.

10.29.2 Constructor & Destructor Documentation

10.29.2.1 __init__()

```
def __init__ (
              self,
              identifier,
              name,
              value,
              dt )
```

Extends ModelQuantity.__init__ by dt

Parameters

identifier	unique identifier of the state **Type**: sympy.Symbol
name	individual name of the state (does not need to be unique) **Type**: str
value	initial value **Type**: symengine.Basic
dt	time derivative **Type**: symengine.Basic

Returns

ModelQuantity instance

TypeError

is thrown if input types do not match documented types

Definition at line 436 of file ode_export.py.

Here is the call graph for this function:

10.29.3 Member Function Documentation

10.29.3.1 set_conservation_law()

```
def set_conservation_law (
              self,
              law )
```

If the a conservation law is set, the respective state will be replaced by an algebraic formula according to the respective conservation law.

Parameters

law	linear sum of states that if added to this state remain constant over time

Returns

TypeError

is thrown if law type does not match documented type

Definition at line 459 of file ode_export.py.

10.29.3.2 set_dt()

```
def set_dt (
              self,
              dt )
```

Parameters

dt	time derivative **Type**: symengine.Basic

Returns

TypeError

is thrown if dt type does not match documented type

Definition at line 477 of file ode_export.py.

10.29.3.3 get_dt()

```
def get_dt (
            self )
```

Returns

time derivative
Type: symengine.Basic

Definition at line 492 of file ode_export.py.

10.30 TemplateAmici Class Reference

Template format used in AMICI (see string.template for more details).

Inheritance diagram for TemplateAmici:

Static Public Attributes

- string delimiter = 'TPL_'

  delimiter that identifies template variables
  ***Type**: str*

10.30.1 Detailed Description

Definition at line 2652 of file ode_export.py.

10.31 ReturnData Class Reference

class that stores all data which is later returned by the mex function

```
#include <rdata.h>
```

Public Member Functions

- ReturnData ()

  default constructor
- ReturnData (std::vector< realtype > ts, int np, int nk, int nx, int nx_solver, int nxtrue, int ny, int nytrue, int nz, int nztrue, int ne, int nJ, int nplist, int nmaxevent, int nt, int newton_maxsteps, std::vector< ParameterScaling > pscale, SecondOrderMode o2mode, SensitivityOrder sensi, SensitivityMethod sensi_meth)

  ReturnData.
- ReturnData (Solver const &solver, const Model *model)
- void initializeObjectiveFunction ()

  initializeObjectiveFunction
- void invalidate (const realtype t)
- void invalidateLLH ()
- void applyChainRuleFactorToSimulationResults (const Model *model)

Public Attributes

- const std::vector< realtype > ts
- std::vector< realtype > xdot
- std::vector< realtype > J
- std::vector< realtype > z
- std::vector< realtype > sigmaz
- std::vector< realtype > sz
- std::vector< realtype > ssigmaz
- std::vector< realtype > rz
- std::vector< realtype > srz
- std::vector< realtype > s2rz
- std::vector< realtype > x
- std::vector< realtype > sx
- std::vector< realtype > y
- std::vector< realtype > sigmay
- std::vector< realtype > sy
- std::vector< realtype > ssigmay
- std::vector< realtype > res
- std::vector< realtype > sres
- std::vector< realtype > FIM
- std::vector< int > numsteps
- std::vector< int > numstepsB
- std::vector< int > numrhsevals
- std::vector< int > numrhsevalsB
- std::vector< int > numerrtestfails

- std::vector< int > numerrtestfailsB
- std::vector< int > numnonlinsolvconvfails
- std::vector< int > numnonlinsolvconvfailsB
- std::vector< int > order
- int newton_status = 0
- double newton_cpu_time = 0.0
- std::vector< int > newton_numsteps
- std::vector< int > newton_numlinsteps
- realtype t_steadystate = NAN
- realtype wrms_steadystate = NAN
- realtype wrms_sensi_steadystate = NAN
- std::vector< realtype > x0
- std::vector< realtype > sx0
- realtype llh = 0.0
- realtype chi2 = 0.0
- std::vector< realtype > sllh
- std::vector< realtype > s2llh
- int status = 0
- const int np
- const int nk
- const int nx
- const int nx_solver
- const int nxtrue
- const int ny
- const int nytrue
- const int nz
- const int nztrue
- const int ne
- const int nJ
- const int nplist
- const int nmaxevent
- const int nt
- const int newton_maxsteps
- std::vector< ParameterScaling > pscale
- const SecondOrderMode o2mode
- const SensitivityOrder sensi
- const SensitivityMethod sensi_meth

Friends

- template<class Archive >
  void boost::serialization::serialize (Archive &ar, ReturnData &r, const unsigned int version)

  Serialize ReturnData (see boost::serialization::serialize)

10.31.1 Detailed Description

NOTE: multidimensional arrays are stored in row-major order (FORTRAN-style)

Definition at line 28 of file rdata.h.

10.31.2 Constructor & Destructor Documentation

10.31.2.1 ReturnData() [1/2]

```
ReturnData (
            std::vector< realtype > ts,
            int np,
            int nk,
            int nx,
            int nx_solver,
            int nxtrue,
            int ny,
            int nytrue,
            int nz,
            int nztrue,
            int ne,
            int nJ,
            int nplist,
            int nmaxevent,
            int nt,
            int newton_maxsteps,
            std::vector< ParameterScaling > pscale,
            SecondOrderMode o2mode,
            SensitivityOrder sensi,
            SensitivityMethod sensi_meth )
```

Parameters

ts	see amici::Model::ts
np	see amici::Model::np
nk	see amici::Model::nk
nx	see amici::Model::nx_rdata
nx_solver	see amici::Model::nx_solver
nxtrue	see amici::Model::nxtrue_rdata
ny	see amici::Model::ny
nytrue	see amici::Model::nytrue
nz	see amici::Model::nz
nztrue	see amici::Model::nztrue
ne	see amici::Model::ne
nJ	see amici::Model::nJ
nplist	see amici::Model::nplist
nmaxevent	see amici::Model::nmaxevent
nt	see amici::Model::nt
newton_maxsteps	see amici::Solver::newton_maxsteps
pscale	see amici::Model::pscale
o2mode	see amici::Model::o2mode
sensi	see amici::Solver::sensi
sensi_meth	see amici::Solver::sensi_meth

Definition at line 40 of file rdata.cpp.

Here is the call graph for this function:

10.31.2.2 ReturnData() [2/2]

```
ReturnData (
            Solver const & solver,
            const Model * model )
```

constructor that uses information from model and solver to appropriately initialize fields

Parameters

solver	solver
model	pointer to model specification object bool

Definition at line 22 of file rdata.cpp.

10.31.3 Member Function Documentation

10.31.3.1 invalidate()

```
void invalidate (
            const realtype t )
```

routine to set likelihood, state variables, outputs and respective sensitivities to NaN (typically after integration failure)

Parameters

t	time of integration failure

Definition at line 117 of file rdata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.31.3.2 invalidateLLH()

```
void invalidateLLH ( )
```

routine to set likelihood and respective sensitivities to NaN (typically after integration failure)

Definition at line 156 of file rdata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.31.3.3 applyChainRuleFactorToSimulationResults()

```
void applyChainRuleFactorToSimulationResults (
            const Model * model )
```

applies the chain rule to account for parameter transformation in the sensitivities of simulation results

Parameters

model	Model from which the ReturnData was obtained

Definition at line 168 of file rdata.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.31.4 Friends And Related Function Documentation

10.31.4.1 boost::serialization::serialize

```
void boost::serialization::serialize (
            Archive & ar,
            ReturnData & r,
            const unsigned int version )  [friend]
```

Parameters

ar	Archive to serialize to
r	Data to serialize
version	Version number

10.31.5 Member Data Documentation

10.31.5.1 ts

```
const std::vector<realtype> ts
```

timepoints (dimension: nt)

Definition at line 78 of file rdata.h.

10.31.5.2 xdot

```
std::vector<realtype> xdot
```

time derivative (dimension: nx)

Definition at line 81 of file rdata.h.

10.31.5.3 J

```
std::vector<realtype> J
```

Jacobian of differential equation right hand side (dimension: nx x nx, row-major)

Definition at line 85 of file rdata.h.

10.31.5.4 z

```
std::vector<realtype> z
```

event output (dimension: nmaxevent x nz, row-major)

Definition at line 88 of file rdata.h.

10.31.5.5 sigmaz

```
std::vector<realtype> sigmaz
```

event output sigma standard deviation (dimension: nmaxevent x nz, row-major)

Definition at line 92 of file rdata.h.

10.31.5.6 sz

```
std::vector<realtype> sz
```

parameter derivative of event output (dimension: nmaxevent x nz, row-major)

Definition at line 96 of file rdata.h.

10.31.5.7 ssigmaz

```
std::vector<realtype> ssigmaz
```

parameter derivative of event output standard deviation (dimension: nmaxevent x nz, row-major)

Definition at line 100 of file rdata.h.

10.31.5.8 rz

```
std::vector<realtype> rz
```

event trigger output (dimension: nmaxevent x nz, row-major)

Definition at line 103 of file rdata.h.

10.31.5.9 srz

```
std::vector<realtype> srz
```

parameter derivative of event trigger output (dimension: nmaxevent x nz x nplist, row-major)

Definition at line 107 of file rdata.h.

10.31.5.10 s2rz

```
std::vector<realtype> s2rz
```

second order parameter derivative of event trigger output (dimension: nmaxevent x nztrue x nplist x nplist, row-major)

Definition at line 111 of file rdata.h.

10.31.5.11 x

```
std::vector<realtype> x
```

state (dimension: nt x nx, row-major)

Definition at line 114 of file rdata.h.

10.31.5.12 sx

```
std::vector<realtype> sx
```

parameter derivative of state (dimension: nt x nplist x nx, row-major)

Definition at line 118 of file rdata.h.

10.31.5.13 y

```
std::vector<realtype> y
```

observable (dimension: nt x ny, row-major)

Definition at line 121 of file rdata.h.

10.31.5.14 sigmay

```
std::vector<realtype> sigmay
```

observable standard deviation (dimension: nt x ny, row-major)

Definition at line 124 of file rdata.h.

10.31.5.15 sy

```
std::vector<realtype> sy
```

parameter derivative of observable (dimension: nt x nplist x ny, row-major)

Definition at line 128 of file rdata.h.

10.31.5.16 ssigmay

```
std::vector<realtype> ssigmay
```

parameter derivative of observable standard deviation (dimension: nt x nplist x ny, row-major)

Definition at line 132 of file rdata.h.

10.31.5.17 res

```
std::vector<realtype> res
```

observable (dimension: nt∗ny, row-major)

Definition at line 135 of file rdata.h.

10.31.5.18 sres

```
std::vector<realtype> sres
```

parameter derivative of residual (dimension: nt∗ny x nplist, row-major)

Definition at line 139 of file rdata.h.

10.31.5.19 FIM

```
std::vector<realtype> FIM
```

fisher information matrix (dimension: nplist x nplist, row-major)

Definition at line 143 of file rdata.h.

10.31.5.20 numsteps

```
std::vector<int> numsteps
```

number of integration steps forward problem (dimension: nt)

Definition at line 146 of file rdata.h.

10.31.5.21 numstepsB

```
std::vector<int> numstepsB
```

number of integration steps backward problem (dimension: nt)

Definition at line 149 of file rdata.h.

10.31.5.22 numrhsevals

```
std::vector<int> numrhsevals
```

number of right hand side evaluations forward problem (dimension: nt)

Definition at line 152 of file rdata.h.

10.31.5.23 numrhsevalsB

```
std::vector<int> numrhsevalsB
```

number of right hand side evaluations backwad problem (dimension: nt)

Definition at line 155 of file rdata.h.

10.31.5.24 numerrtestfails

```
std::vector<int> numerrtestfails
```

number of error test failures forward problem (dimension: nt)

Definition at line 158 of file rdata.h.

10.31.5.25 numerrtestfailsB

```
std::vector<int> numerrtestfailsB
```

number of error test failures backwad problem (dimension: nt)

Definition at line 161 of file rdata.h.

10.31.5.26 numnonlinsolvconvfails

```
std::vector<int> numnonlinsolvconvfails
```

number of linear solver convergence failures forward problem (dimension: nt)

Definition at line 165 of file rdata.h.

10.31.5.27 numnonlinsolvconvfailsB

```
std::vector<int> numnonlinsolvconvfailsB
```

number of linear solver convergence failures backwad problem (dimension: nt)

Definition at line 169 of file rdata.h.

10.31.5.28 order

```
std::vector<int> order
```

employed order forward problem (dimension: nt)

Definition at line 172 of file rdata.h.

10.31.5.29 newton_status

```
int newton_status = 0
```

flag indicating success of Newton solver

Definition at line 175 of file rdata.h.

10.31.5.30 newton_cpu_time

```
double newton_cpu_time = 0.0
```

computation time of the Newton solver [s]

Definition at line 178 of file rdata.h.

10.31.5.31 newton_numsteps

```
std::vector<int> newton_numsteps
```

number of Newton steps for steady state problem (length = 2)

Definition at line 181 of file rdata.h.

10.31.5.32 newton_numlinsteps

```
std::vector<int> newton_numlinsteps
```

number of linear steps by Newton step for steady state problem (length = newton_maxsteps $*$ 2)

Definition at line 184 of file rdata.h.

10.31.5.33 t_steadystate

```
realtype t_steadystate = NAN
```

time at which steadystate was reached in the simulation based approach

Definition at line 187 of file rdata.h.

10.31.5.34 wrms_steadystate

```
realtype wrms_steadystate = NAN
```

weighted root-mean-square of the rhs when steadystate was reached

Definition at line 191 of file rdata.h.

10.31.5.35 wrms_sensi_steadystate

```
realtype wrms_sensi_steadystate = NAN
```

weighted root-mean-square of the rhs when steadystate was reached

Definition at line 195 of file rdata.h.

10.31.5.36 x0

```
std::vector<realtype> x0
```

preequilibration steady state found be Newton solver (dimension: nx)

Definition at line 198 of file rdata.h.

10.31.5.37 sx0

```
std::vector<realtype> sx0
```

preequilibration sensitivities found be Newton solver (dimension: nplist x nx, row-major)

Definition at line 201 of file rdata.h.

10.31.5.38 llh

```
realtype llh = 0.0
```

loglikelihood value

Definition at line 204 of file rdata.h.

10.31.5.39 chi2

```
realtype chi2 = 0.0
```

chi2 value

Definition at line 207 of file rdata.h.

10.31.5.40 sllh

```
std::vector<realtype> sllh
```

parameter derivative of loglikelihood (dimension: nplist)

Definition at line 210 of file rdata.h.

10.31.5.41 s2llh

```
std::vector<realtype> s2llh
```

second order parameter derivative of loglikelihood (dimension: (nJ-1) x nplist, row-major)

Definition at line 214 of file rdata.h.

10.31.5.42 status

```
int status = 0
```

status code

Definition at line 217 of file rdata.h.

10.31.5.43 np

```
const int np
```

total number of model parameters

Definition at line 220 of file rdata.h.

10.31.5.44 nk

```
const int nk
```

number of fixed parameters

Definition at line 222 of file rdata.h.

10.31.5.45 nx

```
const int nx
```

number of states

Definition at line 224 of file rdata.h.

10.31.5.46 nx_solver

```
const int nx_solver
```

number of states with conservation laws applied

Definition at line 226 of file rdata.h.

10.31.5.47 nxtrue

```
const int nxtrue
```

number of states in the unaugmented system

Definition at line 228 of file rdata.h.

10.31.5.48 ny

```
const int ny
```

number of observables

Definition at line 230 of file rdata.h.

10.31.5.49 nytrue

```
const int nytrue
```

number of observables in the unaugmented system

Definition at line 232 of file rdata.h.

10.31.5.50 nz

```
const int nz
```

number of event outputs

Definition at line 234 of file rdata.h.

10.31.5.51 nztrue

```
const int nztrue
```

number of event outputs in the unaugmented system

Definition at line 236 of file rdata.h.

10.31.5.52 ne

```
const int ne
```

number of events

Definition at line 238 of file rdata.h.

10.31.5.53 nJ

```
const int nJ
```

dimension of the augmented objective function for 2nd order ASA

Definition at line 240 of file rdata.h.

10.31.5.54 nplist

```
const int nplist
```

number of parameter for which sensitivities were requested

Definition at line 243 of file rdata.h.

10.31.5.55 nmaxevent

```
const int nmaxevent
```

maximal number of occuring events (for every event type)

Definition at line 245 of file rdata.h.

10.31.5.56 nt

```
const int nt
```

number of considered timepoints

Definition at line 247 of file rdata.h.

10.31.5.57 newton_maxsteps

```
const int newton_maxsteps
```

maximal number of newton iterations for steady state calculation

Definition at line 249 of file rdata.h.

10.31.5.58 pscale

```
std::vector<ParameterScaling> pscale
```

scaling of parameterization (lin,log,log10)

Definition at line 251 of file rdata.h.

10.31.5.59 o2mode

```
const SecondOrderMode o2mode
```

flag indicating whether second order sensitivities were requested

Definition at line 253 of file rdata.h.

10.31.5.60 sensi

```
const SensitivityOrder sensi
```

sensitivity order

Definition at line 255 of file rdata.h.

10.31.5.61 sensi_meth

```
const SensitivityMethod sensi_meth
```

sensitivity method

Definition at line 257 of file rdata.h.

10.32 SBMLException Class Reference

Inheritance diagram for SBMLException:

10.32.1 Detailed Description

Definition at line 13 of file sbml_import.py.

10.33 SbmlImporter Class Reference

The SbmlImporter class generates AMICI C++ files for a model provided in the Systems Biology Markup Language (SBML).

Public Member Functions

- def __init__ (self, SBMLFile, show_sbml_warnings=False)

  Create a new Model instance.
- def reset_symbols (self)

  Reset the symbols attribute to default values.
- def loadSBMLFile (self, SBMLFile)

  Parse the provided SBML file.
- def sbml2amici (self, modelName, output_dir=None, observables=None, constantParameters=None, sigmas=None, verbose=False, assume_pow_positivity=False, compiler=None, allow_reinit_fixpar_↩initcond=True)

  Generate AMICI C++ files for the model provided to the constructor.
- def processSBML (self, constantParameters=None)

  Read parameters, species, reactions, and so on from SBML model.
- def checkSupport (self)

  Check whether all required SBML features are supported.
- def processSpecies (self)

  Get species information from SBML model.
- def processParameters (self, constantParameters=None)

  Get parameter information from SBML model.
- def processCompartments (self)

  Get compartment information, stoichiometric matrix and fluxes from SBML model.

- def processReactions (self)

  Get reactions from SBML model.
- def processRules (self)

  Process Rules defined in the SBML model.
- def processVolumeConversion (self)

  Convert equations from amount to volume.
- def processTime (self)

  Convert time_symbol into cpp variable.
- def processObservables (self, observables, sigmas)

  Perform symbolic computations required for objective function evaluation.
- def replaceInAllExpressions (self, old, new)

  Replace 'old' by 'new' in all symbolic expressions.
- def cleanReservedSymbols (self)

  Remove all reserved symbols from self.symbols.
- def replaceSpecialConstants (self)

  Replace all special constants by their respective SBML csymbol definition.

Public Attributes

- show_sbml_warnings

  indicates whether libSBML warnings should be
- symbols

  dict carrying symbolic definitions
  ***Type**: dict*
- SBMLreader

  the libSBML sbml reader [!not storing this will result
- sbml_doc

  document carrying the sbml definition [!not storing this
- sbml

  sbml definition [!not storing this will result in a segfault!]
- speciesIndex

  maps species names to indices
  ***Type**: dict*
- speciesCompartment

  compartment for each species
  ***Type**:*
- constantSpecies

  ids of species that are marked as constant
  ***Type**: list*
- boundaryConditionSpecies

  ids of species that are marked as boundary
- speciesHasOnlySubstanceUnits

  flags indicating whether a species has
- speciesConversionFactor

  conversion factors for every species
  ***Type**:*
- compartmentSymbols

  compartment ids
  ***Type**: sympy.Matrix*
- compartmentVolume

numeric/symbolic compartment volumes
Type:

- stoichiometricMatrix

  stoichiometric matrix of the model
  Type:

- fluxVector

  reaction kinetic laws
  Type: *sympy.Matrix*

10.33.1 Detailed Description

Definition at line 35 of file sbml_import.py.

10.33.2 Constructor & Destructor Documentation

10.33.2.1 __init__()

```
def __init__ (
              self,
              SBMLFile,
              show_sbml_warnings = False )
```

Parameters

SBMLFile	Path to SBML file where the model is specified **Type**: string
show_sbml_warnings	indicates whether libSBML warnings should be displayed **Type**: bool

Returns

SbmlImporter instance with attached SBML document

Definition at line 143 of file sbml_import.py.

10.33.3 Member Function Documentation

10.33.3.1 reset_symbols()

```
def reset_symbols (
              self )
```

Returns

Definition at line 162 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.2 loadSBMLFile()

```
def loadSBMLFile (
              self,
              SBMLFile )
```

Parameters

SBMLFile	path to SBML file **Type**: str

Returns

Definition at line 175 of file sbml_import.py.

10.33.3.3 sbml2amici()

```
def sbml2amici (
              self,
              modelName,
              output_dir = None,
              observables = None,
              constantParameters = None,
              sigmas = None,
              verbose = False,
              assume_pow_positivity = False,
              compiler = None,
              allow_reinit_fixpar_initcond = True )
```

Parameters

modelName	name of the model/model directory **Type**: str
output_dir	see sbml_import.setPaths() **Type**: str
observables	dictionary(observableId:{'name':observableName (optional), 'formula':formulaString)}) to be added to the model **Type**: dict
sigmas	dictionary(observableId: sigma value or (existing) parameter name) **Type**: dict
constantParameters	list of SBML Ids identifying constant parameters **Type**: dict
verbose	more verbose output if True **Type**: bool
assume_pow_positivity	if set to true, a special pow function is used to avoid problems with state variables that may become negative due to numerical errors **Type**: bool
compiler	distutils/setuptools compiler selection to build the python extension **Type**: str
allow_reinit_fixpar_initcond	see ode_export.ODEExporter

Returns

Definition at line 236 of file sbml_import.py.

Here is the call graph for this function:

10.33.3.4 processSBML()

```
def processSBML (
            self,
            constantParameters = None )
```

Parameters

constantParameters	SBML Ids identifying constant parameters **Type**: list

Returns

Definition at line 285 of file sbml_import.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.33.3.5 checkSupport()

```
def checkSupport (
              self )
```

Returns

Definition at line 310 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.6 processSpecies()

```
def processSpecies (
              self )
```

Returns

Definition at line 347 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.7 processParameters()

```
def processParameters (
              self,
              constantParameters = None )
```

Parameters

constantParameters	SBML Ids identifying constant parameters **Type**: list

Returns

Definition at line 440 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.8 processCompartments()

```
def processCompartments (
              self )
```

Returns

Definition at line 517 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.9 processReactions()

```
def processReactions (
              self )
```

Returns

Definition at line 552 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.10 processRules()

```
def processRules (
              self )
```

Returns

Definition at line 664 of file sbml_import.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.33.3.11 processVolumeConversion()

```
def processVolumeConversion (
              self )
```

Returns

Definition at line 742 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.12 processTime()

```
def processTime (
              self )
```

Returns

Definition at line 764 of file sbml_import.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.33.3.13 processObservables()

```
def processObservables (
            self,
            observables,
            sigmas )
```

Parameters

observables	dictionary(observableId:{'name':observableName (optional), 'formula':formulaString)}) to be added to the model **Type**: dict
sigmas	dictionary(observableId: sigma value or (existing) parameter name) **Type**: dict

Returns

Definition at line 786 of file sbml_import.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.33.3.14 replaceInAllExpressions()

```
def replaceInAllExpressions (
              self,
              old,
              new )
```

Parameters

old	symbolic variables to be replaced **Type**: symengine.Symbol
new	replacement symbolic variables **Type**: symengine.Symbol

Returns

Definition at line 900 of file sbml_import.py.

Here is the caller graph for this function:

10.33.3.15 cleanReservedSymbols()

```
def cleanReservedSymbols (
              self )
```

Returns

Definition at line 927 of file sbml_import.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.33.3.16 replaceSpecialConstants()

```
def replaceSpecialConstants (
              self )
```

Returns

Definition at line 948 of file sbml_import.py.

Here is the call graph for this function:

Here is the caller graph for this function:

10.34 SetupFailure Class Reference

setup failure exception this exception should be thrown when the solver setup failed for this exception we can assume that we cannot recover from the exception and an error will be thrown

```
#include <exception.h>
```

Inheritance diagram for SetupFailure:

Public Member Functions

- SetupFailure (const char *msg)

10.34.1 Detailed Description

Definition at line 190 of file exception.h.

10.34.2 Constructor & Destructor Documentation

10.34.2.1 SetupFailure()

```
SetupFailure (
            const char * msg )  [explicit]
```

constructor, simply calls AmiException constructor

Parameters

msg	

Definition at line 195 of file exception.h.

10.35 Solver Class Reference

```
#include <solver.h>
```

Public Member Functions

- Solver (const Solver &other)

  Solver copy constructor.
- virtual Solver * clone () const =0

  Clone this instance.
- void setup (AmiVector *x, AmiVector *dx, AmiVectorArray *sx, AmiVectorArray *sdx, Model *model)

  Initialises the ami memory object and applies specified options.
- void setupAMIB (BackwardProblem *bwd, Model *model)
- virtual void getSens (realtype *tret, AmiVectorArray *yySout) const =0
- void getDiagnosis (const int it, ReturnData *rdata) const
- void getDiagnosisB (const int it, ReturnData *rdata, int which) const
- virtual void getRootInfo (int *rootsfound) const =0
- virtual void reInit (realtype t0, AmiVector *yy0, AmiVector *yp0)=0
- virtual void sensReInit (AmiVectorArray *yS0, AmiVectorArray *ypS0)=0
- virtual void calcIC (realtype tout1, AmiVector *x, AmiVector *dx)=0
- virtual void calcICB (int which, realtype tout1, AmiVector *xB, AmiVector *dxB)=0
- virtual int solve (realtype tout, AmiVector *yret, AmiVector *ypret, realtype *tret, int itask)=0
- virtual int solveF (realtype tout, AmiVector *yret, AmiVector *ypret, realtype *tret, int itask, int *ncheckPtr)=0
- virtual void solveB (realtype tBout, int itaskB)=0
- virtual void setStopTime (realtype tstop)=0
- virtual void reInitB (int which, realtype tB0, AmiVector *yyB0, AmiVector *ypB0)=0
- virtual void getB (int which, realtype *tret, AmiVector *yy, AmiVector *yp) const =0
- virtual void getQuadB (int which, realtype *tret, AmiVector *qB) const =0
- virtual void quadReInitB (int which, AmiVector *yQB0)=0
- virtual void turnOffRootFinding ()=0
- SensitivityMethod getSensitivityMethod () const
- void setSensitivityMethod (SensitivityMethod sensi_meth)

  setSensitivityMethod
- int getNewtonMaxSteps () const

  getNewtonMaxSteps
- void setNewtonMaxSteps (int newton_maxsteps)

  setNewtonMaxSteps
- bool getNewtonPreequilibration () const

  getNewtonPreequilibration
- void setNewtonPreequilibration (bool newton_preeq)

  setNewtonPreequilibration
- int getNewtonMaxLinearSteps () const

  getNewtonMaxLinearSteps
- void setNewtonMaxLinearSteps (int newton_maxlinsteps)

  setNewtonMaxLinearSteps
- SensitivityOrder getSensitivityOrder () const

  returns the sensitvity order
- void setSensitivityOrder (SensitivityOrder sensi)

  sets the sensitvity order
- double getRelativeTolerance () const

  returns the relative tolerances for the forward & backward problem
- void setRelativeTolerance (double rtol)

  sets the relative tolerances for the forward & backward problem
- double getAbsoluteTolerance () const

  returns the absolute tolerances for the forward & backward problem
- void setAbsoluteTolerance (double atol)

sets the absolute tolerances for the forward & backward problem

- double getRelativeToleranceSensi () const

  returns the relative tolerances for the forward sensitivity problem
- void setRelativeToleranceSensi (double rtol)

  sets the relative tolerances for the forward sensitivity problem
- double getAbsoluteToleranceSensi () const

  returns the absolute tolerances for the forward sensitivity problem
- void setAbsoluteToleranceSensi (double atol)

  sets the absolute tolerances for the forward sensitivity problem
- double getRelativeToleranceQuadratures () const

  returns the relative tolerance for the quadrature problem
- void setRelativeToleranceQuadratures (double rtol)

  sets the relative tolerance for the quadrature problem
- double getAbsoluteToleranceQuadratures () const

  returns the absolute tolerance for the quadrature problem
- void setAbsoluteToleranceQuadratures (double atol)

  sets the absolute tolerance for the quadrature problem
- double getRelativeToleranceSteadyState () const

  returns the relative tolerance for the steady state problem
- void setRelativeToleranceSteadyState (double rtol)

  sets the relative tolerance for the steady state problem
- double getAbsoluteToleranceSteadyState () const

  returns the absolute tolerance for the steady state problem
- void setAbsoluteToleranceSteadyState (double atol)

  sets the absolute tolerance for the steady state problem
- double getRelativeToleranceSteadyStateSensi () const

  returns the relative tolerance for the sensitivities of the steady state problem
- void setRelativeToleranceSteadyStateSensi (double rtol)

  sets the relative tolerance for the sensitivities of the steady state problem
- double getAbsoluteToleranceSteadyStateSensi () const

  returns the absolute tolerance for the sensitivities of the steady state problem
- void setAbsoluteToleranceSteadyStateSensi (double atol)

  sets the absolute tolerance for the sensitivities of the steady state problem
- int getMaxSteps () const

  returns the maximum number of solver steps for the forward problem
- void setMaxSteps (int maxsteps)

  sets the maximum number of solver steps for the forward problem
- int getMaxStepsBackwardProblem () const

  returns the maximum number of solver steps for the backward problem
- void setMaxStepsBackwardProblem (int maxsteps)

  sets the maximum number of solver steps for the backward problem
- LinearMultistepMethod getLinearMultistepMethod () const

  returns the linear system multistep method
- void setLinearMultistepMethod (LinearMultistepMethod lmm)

  sets the linear system multistep method
- NonlinearSolverIteration getNonlinearSolverIteration () const

  returns the nonlinear system solution method
- void setNonlinearSolverIteration (NonlinearSolverIteration iter)

  sets the nonlinear system solution method
- InterpolationType getInterpolationType () const

  getInterpolationType

- void setInterpolationType (InterpolationType interpType)

  sets the interpolation of the forward solution that is used for the backwards problem
- StateOrdering getStateOrdering () const

  sets KLU state ordering mode
- void setStateOrdering (StateOrdering ordering)

  sets KLU state ordering mode (only applies when linsol is set to amici.AMICI_KLU)
- booleantype getStabilityLimitFlag () const

  returns stability limit detection mode
- void setStabilityLimitFlag (booleantype stldet)

  set stability limit detection mode
- LinearSolver getLinearSolver () const

  getLinearSolver
- void setLinearSolver (LinearSolver linsol)

  setLinearSolver
- InternalSensitivityMethod getInternalSensitivityMethod () const

  returns the internal sensitivity method
- void setInternalSensitivityMethod (InternalSensitivityMethod ism)

  sets the internal sensitivity method

Protected Member Functions

- virtual void init (AmiVector *x, AmiVector *dx, realtype t)=0
- virtual void binit (int which, AmiVector *xB, AmiVector *dxB, realtype t)=0
- virtual void qbinit (int which, AmiVector *qBdot)=0
- virtual void rootInit (int ne)=0
- virtual void sensInit1 (AmiVectorArray *sx, AmiVectorArray *sdx, int nplist)=0
- virtual void setDenseJacFn ()=0
- virtual void setSparseJacFn ()=0
- virtual void setBandJacFn ()=0
- virtual void setJacTimesVecFn ()=0
- virtual void setDenseJacFnB (int which)=0
- virtual void setSparseJacFnB (int which)=0
- virtual void setBandJacFnB (int which)=0
- virtual void setJacTimesVecFnB (int which)=0
- virtual void allocateSolver ()=0
- virtual void setSStolerances (double rtol, double atol)=0
- virtual void setSensSStolerances (double rtol, double *atol)=0
- virtual void setSensErrCon (bool error_corr)=0
- virtual void setQuadErrConB (int which, bool flag)=0
- virtual void setErrHandlerFn ()=0
- virtual void setUserData (Model *model)=0
- virtual void setUserDataB (int which, Model *model)=0
- virtual void setMaxNumSteps (long int mxsteps)=0
- virtual void setMaxNumStepsB (int which, long int mxstepsB)=0
- virtual void setStabLimDet (int stldet)=0
- virtual void setStabLimDetB (int which, int stldet)=0
- virtual void setId (Model *model)=0
- virtual void setSuppressAlg (bool flag)=0
- virtual void setSensParams (realtype *p, realtype *pbar, int *plist)=0
- virtual void getDky (realtype t, int k, AmiVector *dky) const =0
- virtual void adjInit ()=0
- virtual void allocateSolverB (int *which)=0

- virtual void setSStolerancesB (int which, realtype relTolB, realtype absTolB)=0
- virtual void quadSStolerancesB (int which, realtype reltolQB, realtype abstolQB)=0
- virtual void dense (int nx)=0
- virtual void denseB (int which, int nx)=0
- virtual void band (int nx, int ubw, int lbw)=0
- virtual void bandB (int which, int nx, int ubw, int lbw)=0
- virtual void diag ()=0
- virtual void diagB (int which)=0
- virtual void spgmr (int prectype, int maxl)=0
- virtual void spgmrB (int which, int prectype, int maxl)=0
- virtual void spbcg (int prectype, int maxl)=0
- virtual void spbcgB (int which, int prectype, int maxl)=0
- virtual void sptfqmr (int prectype, int maxl)=0
- virtual void sptfqmrB (int which, int prectype, int maxl)=0
- virtual void klu (int nx, int nnz, int sparsetype)=0
- virtual void kluSetOrdering (int ordering)=0
- virtual void kluSetOrderingB (int which, int ordering)=0
- virtual void kluB (int which, int nx, int nnz, int sparsetype)=0
- virtual void getNumSteps (void ∗ami_mem, long int ∗numsteps) const =0
- virtual void getNumRhsEvals (void ∗ami_mem, long int ∗numrhsevals) const =0
- virtual void getNumErrTestFails (void ∗ami_mem, long int ∗numerrtestfails) const =0
- virtual void getNumNonlinSolvConvFails (void ∗ami_mem, long int ∗numnonlinsolvconvfails) const =0
- virtual void getLastOrder (void ∗ami_mem, int ∗order) const =0
- void initializeLinearSolver (const Model ∗model)
- void initializeLinearSolverB (const Model ∗model, const int which)
- virtual int nplist () const =0
- virtual int nx () const =0
- virtual const Model ∗ getModel () const =0
- virtual bool getMallocDone () const =0
- virtual bool getAdjMallocDone () const =0
- virtual void ∗ getAdjBmem (void ∗ami_mem, int which)=0
- void applyTolerances ()
- void applyTolerancesFSA ()
- void applyTolerancesASA (int which)
- void applyQuadTolerancesASA (int which)
- void applySensitivityTolerances ()

Static Protected Member Functions

- static void wrapErrHandlerFn (int error_code, const char ∗module, const char ∗function, char ∗msg, void ∗eh_data)

Protected Attributes

- std::unique_ptr< void, std::function< void(void ∗)> > solverMemory
- std::vector< std::unique_ptr< void, std::function< void(void ∗)> > > solverMemoryB
- bool solverWasCalled = false
- InternalSensitivityMethod ism = InternalSensitivityMethod::simultaneous
- LinearMultistepMethod lmm = LinearMultistepMethod::BDF
- NonlinearSolverIteration iter = NonlinearSolverIteration::newton
- InterpolationType interpType = InterpolationType::hermite
- int maxsteps = 10000

Friends

- template<class Archive >
  void boost::serialization::serialize (Archive &ar, Solver &r, const unsigned int version)

  Serialize Solver (see boost::serialization::serialize)
- bool operator== (const Solver &a, const Solver &b)

  Check equality of data members.

10.35.1 Detailed Description

Solver class. provides a generic interface to CVode and IDA solvers, individual realizations are realized in the CVodeSolver and the IDASolver class.

Definition at line 38 of file solver.h.

10.35.2 Constructor & Destructor Documentation

10.35.2.1 Solver()

```
Solver (
            const Solver & other )
```

Parameters

other	

Definition at line 46 of file solver.h.

10.35.3 Member Function Documentation

10.35.3.1 clone()

```
virtual Solver* clone ( ) const  [pure virtual]
```

Returns

The clone

Here is the caller graph for this function:

10.35.3.2 setup()

```
void setup (
            AmiVector * x,
            AmiVector * dx,
            AmiVectorArray * sx,
            AmiVectorArray * sdx,
            Model * model )
```

Parameters

x	state vector
dx	state derivative vector (DAE only)
sx	state sensitivity vector
sdx	state derivative sensitivity vector (DAE only)
model	pointer to the model object

Definition at line 27 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.3 setupAMIB()

```
void setupAMIB (
            BackwardProblem * bwd,
            Model * model )
```

setupAMIB initialises the AMI memory object for the backwards problem

Parameters

bwd	pointer to backward problem
model	pointer to the model object

Definition at line 87 of file solver.cpp.

Here is the call graph for this function:

10.35.3.4 getSens()

```
virtual void getSens (
            realtype * tret,
            AmiVectorArray * yySout ) const  [pure virtual]
```

getSens extracts diagnosis information from solver memory block and writes them into the return data instance

Parameters

tret	time at which the sensitivities should be computed
yySout	vector with sensitivities

10.35.3.5 getDiagnosis()

```
void getDiagnosis (
            const int it,
            ReturnData * rdata ) const
```

getDiagnosis extracts diagnosis information from solver memory block and writes them into the return data object

Parameters

it	time-point index
rdata	pointer to the return data object

Definition at line 171 of file solver.cpp.

Here is the call graph for this function:

10.35.3.6 getDiagnosisB()

```
void getDiagnosisB (
            const int it,
```

```
            ReturnData * rdata,
            int which ) const
```

getDiagnosisB extracts diagnosis information from solver memory block and writes them into the return data object for the backward problem

Parameters

it	time-point index
rdata	pointer to the return data object
which	identifier of the backwards problem

Definition at line 191 of file solver.cpp.

Here is the call graph for this function:

10.35.3.7 getRootInfo()

```
virtual void getRootInfo (
            int * rootsfound ) const  [pure virtual]
```

getRootInfo extracts information which event occured

Parameters

rootsfound	array with flags indicating whether the respective event occured

10.35.3.8 reInit()

```
virtual void reInit (
```

```
            realtype t0,
            AmiVector * yy0,
            AmiVector * yp0 )  [pure virtual]
```

ReInit reinitializes the states in the solver after an event occurence

Parameters

t0	new timepoint
yy0	new state variables
yp0	new derivative state variables (DAE only)

10.35.3.9 sensReInit()

```
virtual void sensReInit (
            AmiVectorArray * yS0,
            AmiVectorArray * ypS0 )  [pure virtual]
```

SensReInit reinitializes the state sensitivites in the solver after an event occurence

Parameters

yS0	new state sensitivity
ypS0	new derivative state sensitivities (DAE only)

10.35.3.10 calcIC()

```
virtual void calcIC (
            realtype tout1,
            AmiVector * x,
            AmiVector * dx )  [pure virtual]
```

CalcIC calculates consistent initial conditions, assumes initial states to be correct (DAE only)

Parameters

tout1	next timepoint to be computed (sets timescale)
x	initial state variables
dx	initial derivative state variables (DAE only)

10.35.3.11 calcICB()

```
virtual void calcICB (
            int which,
            realtype tout1,
```

```
            AmiVector * xB,
            AmiVector * dxB )  [pure virtual]
```

CalcIBC calculates consistent initial conditions for the backwards problem, assumes initial states to be correct (DAE only)

Parameters

which	identifier of the backwards problem
tout1	next timepoint to be computed (sets timescale)
xB	states of final solution of the forward problem
dxB	derivative states of final solution of the forward problem (DAE only)

10.35.3.12 solve()

```
virtual int solve (
            realtype tout,
            AmiVector * yret,
            AmiVector * ypret,
            realtype * tret,
            int itask )  [pure virtual]
```

Solve solves the forward problem until a predefined timepoint

Parameters

tout	timepoint until which simulation should be performed
yret	states
ypret	derivative states (DAE only)
tret	pointer to the time variable
itask	task identifier, can be CV_NORMAL or CV_ONE_STEP

Returns

status flag indicating success of execution

Here is the caller graph for this function:

10.35.3.13 solveF()

```
virtual int solveF (
            realtype tout,
            AmiVector * yret,
            AmiVector * ypret,
            realtype * tret,
            int itask,
            int * ncheckPtr )  [pure virtual]
```

SolveF solves the forward problem until a predefined timepoint (adjoint only)

Parameters

tout	timepoint until which simulation should be performed
yret	states
ypret	derivative states (DAE only)
tret	pointer to the time variable
itask	task identifier, can be CV_NORMAL or CV_ONE_STEP
ncheckPtr	pointer to a number that counts the internal checkpoints

Returns

status flag indicating success of execution

10.35.3.14 solveB()

```
virtual void solveB (
            realtype tBout,
            int itaskB )  [pure virtual]
```

SolveB solves the backward problem until a predefined timepoint (adjoint only)

Parameters

tBout	timepoint until which simulation should be performed
itaskB	task identifier, can be CV_NORMAL or CV_ONE_STEP

10.35.3.15 setStopTime()

```
virtual void setStopTime (
            realtype tstop )  [pure virtual]
```

SetStopTime sets a timepoint at which the simulation will be stopped

Parameters

tstop	timepoint until which simulation should be performed

10.35.3.16 reInitB()

```
virtual void reInitB (
            int which,
            realtype tB0,
            AmiVector * yyB0,
            AmiVector * ypB0 )  [pure virtual]
```

ReInitB reinitializes the adjoint states after an event occurence

Parameters

which	identifier of the backwards problem
tB0	new timepoint
yyB0	new adjoint state variables
ypB0	new adjoint derivative state variables (DAE only)

10.35.3.17 getB()

```
virtual void getB (
            int which,
            realtype * tret,
            AmiVector * yy,
            AmiVector * yp ) const  [pure virtual]
```

getB returns the current adjoint states

Parameters

which	identifier of the backwards problem
tret	time at which the adjoint states should be computed
yy	adjoint state variables
yp	adjoint derivative state variables (DAE only)

10.35.3.18 getQuadB()

```
virtual void getQuadB (
            int which,
            realtype * tret,
            AmiVector * qB ) const  [pure virtual]
```

getQuadB returns the current adjoint states

Parameters

which	identifier of the backwards problem
tret	time at which the adjoint states should be computed
qB	adjoint quadrature state variables

10.35.3.19 quadReInitB()

```
virtual void quadReInitB (
            int which,
            AmiVector * yQB0 )  [pure virtual]
```

ReInitB reinitializes the adjoint states after an event occurence

Parameters

which	identifier of the backwards problem
yQB0	new adjoint quadrature state variables

10.35.3.20 turnOffRootFinding()

```
virtual void turnOffRootFinding ( )  [pure virtual]
```

turnOffRootFinding disables rootfinding

10.35.3.21 getSensitivityMethod()

```
SensitivityMethod getSensitivityMethod ( ) const
```

sensitivity method

Returns

method enum

Definition at line 461 of file solver.cpp.

10.35.3.22 setSensitivityMethod()

```
void setSensitivityMethod (
            SensitivityMethod sensi_meth )
```

Parameters

sensi_meth	

Definition at line 465 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.23 getNewtonMaxSteps()

```
int getNewtonMaxSteps ( ) const
```

Returns

Definition at line 469 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.24 setNewtonMaxSteps()

```
void setNewtonMaxSteps (
            int newton_maxsteps )
```

Parameters

newton_maxsteps	

Definition at line 473 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.25 getNewtonPreequilibration()

```
bool getNewtonPreequilibration ( ) const
```

Returns

Definition at line 479 of file solver.cpp.

10.35.3.26 setNewtonPreequilibration()

```
void setNewtonPreequilibration (
            bool newton_preeq )
```

Parameters

newton_preeq	

Definition at line 483 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.27 getNewtonMaxLinearSteps()

```
int getNewtonMaxLinearSteps ( ) const
```

Returns

Definition at line 487 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.28 setNewtonMaxLinearSteps()

```
void setNewtonMaxLinearSteps (
            int newton_maxlinsteps )
```

Parameters

newton_maxlinsteps	

Definition at line 491 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.29 getSensitivityOrder()

```
SensitivityOrder getSensitivityOrder ( ) const
```

Returns

sensitivity order

Definition at line 497 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.30 setSensitivityOrder()

```
void setSensitivityOrder (
            SensitivityOrder sensi )
```

Parameters

sensi	sensitivity order

Definition at line 501 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.31 getRelativeTolerance()

```
double getRelativeTolerance ( ) const
```

Returns

relative tolerances

Definition at line 508 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.32 setRelativeTolerance()

```
void setRelativeTolerance (
            double rtol )
```

Parameters

rtol	relative tolerance (non-negative number)

Definition at line 512 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.33 getAbsoluteTolerance()

```
double getAbsoluteTolerance ( ) const
```

Returns

absolute tolerances

Definition at line 524 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.34 setAbsoluteTolerance()

```
void setAbsoluteTolerance (
            double atol )
```

Parameters

atol	absolute tolerance (non-negative number)

Definition at line 528 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.35 getRelativeToleranceSensi()

```
double getRelativeToleranceSensi ( ) const
```

Returns

relative tolerances

Definition at line 540 of file solver.cpp.

Here is the call graph for this function:

10.35.3.36 setRelativeToleranceSensi()

```
void setRelativeToleranceSensi (
            double rtol )
```

Parameters

rtol	relative tolerance (non-negative number)

Definition at line 544 of file solver.cpp.

Here is the call graph for this function:

10.35.3.37 getAbsoluteToleranceSensi()

```
double getAbsoluteToleranceSensi ( ) const
```

Returns

absolute tolerances

Definition at line 555 of file solver.cpp.

Here is the call graph for this function:

10.35.3.38 setAbsoluteToleranceSensi()

```
void setAbsoluteToleranceSensi (
            double atol )
```

Parameters

atol	absolute tolerance (non-negative number)

Definition at line 559 of file solver.cpp.

Here is the call graph for this function:

10.35.3.39 getRelativeToleranceQuadratures()

```
double getRelativeToleranceQuadratures ( ) const
```

Returns

relative tolerance

Definition at line 570 of file solver.cpp.

10.35.3.40 setRelativeToleranceQuadratures()

```
void setRelativeToleranceQuadratures (
            double rtol )
```

Parameters

rtol	relative tolerance (non-negative number)

Definition at line 574 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.41 getAbsoluteToleranceQuadratures()

```
double getAbsoluteToleranceQuadratures ( ) const
```

Returns

absolute tolerance

Definition at line 588 of file solver.cpp.

10.35.3.42 setAbsoluteToleranceQuadratures()

```
void setAbsoluteToleranceQuadratures (
            double atol )
```

Parameters

atol	absolute tolerance (non-negative number)

Definition at line 592 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.43 getRelativeToleranceSteadyState()

```
double getRelativeToleranceSteadyState ( ) const
```

Returns

relative tolerance

Definition at line 606 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.44 setRelativeToleranceSteadyState()

```
void setRelativeToleranceSteadyState (
            double rtol )
```

Parameters

rtol	relative tolerance (non-negative number)

Definition at line 610 of file solver.cpp.

10.35.3.45 getAbsoluteToleranceSteadyState()

```
double getAbsoluteToleranceSteadyState ( ) const
```

Returns

absolute tolerance

Definition at line 617 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.46 setAbsoluteToleranceSteadyState()

```
void setAbsoluteToleranceSteadyState (
            double atol )
```

Parameters

atol	absolute tolerance (non-negative number)

Definition at line 621 of file solver.cpp.

10.35.3.47 getRelativeToleranceSteadyStateSensi()

```
double getRelativeToleranceSteadyStateSensi ( ) const
```

Returns

relative tolerance

Definition at line 628 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.48 setRelativeToleranceSteadyStateSensi()

```
void setRelativeToleranceSteadyStateSensi (
            double rtol )
```

Parameters

rtol	relative tolerance (non-negative number)

Definition at line 632 of file solver.cpp.

10.35.3.49 getAbsoluteToleranceSteadyStateSensi()

```
double getAbsoluteToleranceSteadyStateSensi ( ) const
```

Returns

absolute tolerance

Definition at line 639 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.50 setAbsoluteToleranceSteadyStateSensi()

```
void setAbsoluteToleranceSteadyStateSensi (
            double atol )
```

Parameters

atol	absolute tolerance (non-negative number)

Definition at line 643 of file solver.cpp.

10.35.3.51 getMaxSteps()

```
int getMaxSteps ( ) const
```

Returns

maximum number of solver steps

Definition at line 650 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.52 setMaxSteps()

```
void setMaxSteps (
            int maxsteps )
```

Parameters

maxsteps	maximum number of solver steps (non-negative number)

Definition at line 654 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.53 getMaxStepsBackwardProblem()

```
int getMaxStepsBackwardProblem ( ) const
```

Returns

maximum number of solver steps

Definition at line 663 of file solver.cpp.

10.35.3.54 setMaxStepsBackwardProblem()

```
void setMaxStepsBackwardProblem (
            int maxsteps )
```

Parameters

maxsteps	maximum number of solver steps (non-negative number)

Definition at line 667 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.55 getLinearMultistepMethod()

```
LinearMultistepMethod getLinearMultistepMethod ( ) const
```

Returns

linear system multistep method

Definition at line 677 of file solver.cpp.

10.35.3.56 setLinearMultistepMethod()

```
void setLinearMultistepMethod (
            LinearMultistepMethod lmm )
```

Parameters

lmm	linear system multistep method

Definition at line 681 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.57 getNonlinearSolverIteration()

```
NonlinearSolverIteration getNonlinearSolverIteration ( ) const
```

Returns

Definition at line 687 of file solver.cpp.

10.35.3.58 setNonlinearSolverIteration()

```
void setNonlinearSolverIteration (
            NonlinearSolverIteration iter )
```

Parameters

iter	nonlinear system solution method

Definition at line 691 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.59 getInterpolationType()

```
InterpolationType getInterpolationType ( ) const
```

Returns

Definition at line 697 of file solver.cpp.

10.35.3.60 setInterpolationType()

```
void setInterpolationType (
            InterpolationType interpType )
```

Parameters

interpType	interpolation type

Definition at line 701 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.61 getStateOrdering()

```
StateOrdering getStateOrdering ( ) const
```

Returns

Definition at line 707 of file solver.cpp.

10.35.3.62 setStateOrdering()

```
void setStateOrdering (
            StateOrdering ordering )
```

Parameters

ordering	state ordering

Definition at line 711 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.63 getStabilityLimitFlag()

```
int getStabilityLimitFlag ( ) const
```

Returns

stldet can be amici.FALSE (deactivated) or amici.TRUE (activated)

Definition at line 721 of file solver.cpp.

10.35.3.64 setStabilityLimitFlag()

```
void setStabilityLimitFlag (
            booleantype stldet )
```

Parameters

stldet	can be amici.FALSE (deactivated) or amici.TRUE (activated)

Definition at line 725 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.65 getLinearSolver()

```
LinearSolver getLinearSolver ( ) const
```

Returns

Definition at line 738 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.66 setLinearSolver()

```
void setLinearSolver (
            LinearSolver linsol )
```

Parameters

linsol	

Definition at line 742 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.67 getInternalSensitivityMethod()

```
InternalSensitivityMethod getInternalSensitivityMethod ( ) const
```

Returns

internal sensitivity method

Definition at line 750 of file solver.cpp.

10.35.3.68 setInternalSensitivityMethod()

```
void setInternalSensitivityMethod (
            InternalSensitivityMethod ism )
```

Parameters

ism	internal sensitivity method

Definition at line 754 of file solver.cpp.

Here is the caller graph for this function:

10.35.3.69 init()

```
virtual void init (
            AmiVector * x,
            AmiVector * dx,
            realtype t )  [protected], [pure virtual]
```

init initialises the states at the specified initial timepoint

Parameters

x	initial state variables
dx	initial derivative state variables (DAE only)
t	initial timepoint

10.35.3.70 binit()

```
virtual void binit (
            int which,
            AmiVector * xB,
            AmiVector * dxB,
            realtype t )  [protected], [pure virtual]
```

binit initialises the adjoint states at the specified final timepoint

Parameters

which	identifier of the backwards problem
xB	initial adjoint state variables
dxB	initial adjoint derivative state variables (DAE only)
t	final timepoint

Here is the caller graph for this function:

10.35.3.71 qbinit()

```
virtual void qbinit (
            int which,
            AmiVector * qBdot )  [protected], [pure virtual]
```

qbinit initialises the quadrature states at the specified final timepoint

Parameters

which	identifier of the backwards problem
qBdot	initial adjoint quadrature state variables

Here is the caller graph for this function:

10.35.3.72 rootInit()

```
virtual void rootInit (
            int ne )  [protected], [pure virtual]
```

RootInit initialises the rootfinding for events

Parameters

ne	number of different events

10.35.3.73 sensInit1()

```
virtual void sensInit1 (
            AmiVectorArray * sx,
            AmiVectorArray * sdx,
            int nplist )  [protected], [pure virtual]
```

SensInit1 initialises the sensitivities at the specified initial timepoint

Parameters

sx	initial state sensitivities
sdx	initial derivative state sensitivities (DAE only)
nplist	number parameter wrt which sensitivities are to be computed

10.35.3.74 setDenseJacFn()

```
virtual void setDenseJacFn ( )  [protected], [pure virtual]
```

SetDenseJacFn sets the dense Jacobian function Here is the caller graph for this function:

10.35.3.75 setSparseJacFn()

```
virtual void setSparseJacFn ( )  [protected], [pure virtual]
```

SetSparseJacFn sets the sparse Jacobian function

10.35.3.76 setBandJacFn()

```
virtual void setBandJacFn ( )  [protected], [pure virtual]
```

SetBandJacFn sets the banded Jacobian function Here is the caller graph for this function:

10.35.3.77 setJacTimesVecFn()

```
virtual void setJacTimesVecFn ( ) [protected], [pure virtual]
```

SetJacTimesVecFn sets the Jacobian vector multiplication function

10.35.3.78 setDenseJacFnB()

```
virtual void setDenseJacFnB (
            int which ) [protected], [pure virtual]
```

SetDenseJacFn sets the dense Jacobian function

Parameters

which	identifier of the backwards problem

Here is the caller graph for this function:

10.35.3.79 setSparseJacFnB()

```
virtual void setSparseJacFnB (
            int which ) [protected], [pure virtual]
```

SetSparseJacFn sets the sparse Jacobian function

Parameters

which	identifier of the backwards problem

10.35.3.80 setBandJacFnB()

```
virtual void setBandJacFnB (
            int which )  [protected], [pure virtual]
```

SetBandJacFn sets the banded Jacobian function

Parameters

which	identifier of the backwards problem

Here is the caller graph for this function:

10.35.3.81 setJacTimesVecFnB()

```
virtual void setJacTimesVecFnB (
            int which )  [protected], [pure virtual]
```

SetJacTimesVecFn sets the Jacobian vector multiplication function

Parameters

which	identifier of the backwards problem

10.35.3.82 wrapErrHandlerFn()

```
void wrapErrHandlerFn (
            int error_code,
            const char * module,
            const char * function,
            char * msg,
            void * eh_data )  [static], [protected]
```

ErrHandlerFn extracts diagnosis information from solver memory block and writes them into the return data object for the backward problem

Parameters

error_code	error identifier
module	name of the module in which the error occured
function	name of the function in which the error occured **Type**: char
msg	error message
eh_data	unused input

Definition at line 136 of file solver.cpp.

10.35.3.83 allocateSolver()

```
virtual void allocateSolver ( )  [protected], [pure virtual]
```

Create specifies solver method and initializes solver memory for the forward problem

10.35.3.84 setSStolerances()

```
virtual void setSStolerances (
            double rtol,
            double atol )  [protected], [pure virtual]
```

SStolerances sets scalar relative and absolute tolerances for the forward problem

Parameters

rtol	relative tolerances
atol	absolute tolerances

Here is the caller graph for this function:

10.35.3.85 setSensSStolerances()

```
virtual void setSensSStolerances (
            double rtol,
            double * atol )  [protected], [pure virtual]
```

SensSStolerances activates sets scalar relative and absolute tolerances for the sensitivity variables

Parameters

rtol	relative tolerances
atol	array of absolute tolerances for every sensitivy variable

10.35.3.86 setSensErrCon()

```
virtual void setSensErrCon (
            bool error_corr )  [protected], [pure virtual]
```

SetSensErrCon specifies whether error control is also enforced for sensitivities for the forward problem

Parameters

error_corr	activation flag

10.35.3.87 setQuadErrConB()

```
virtual void setQuadErrConB (
            int which,
            bool flag )  [protected], [pure virtual]
```

SetSensErrCon specifies whether error control is also enforced for the backward quadrature problem

Parameters

which	identifier of the backwards problem
flag	activation flag

10.35.3.88 setErrHandlerFn()

```
virtual void setErrHandlerFn ( )  [protected], [pure virtual]
```

SetErrHandlerFn attaches the error handler function (errMsgIdAndTxt) to the solver

10.35.3.89 setUserData()

```
virtual void setUserData (
            Model * model )  [protected], [pure virtual]
```

SetUserData attaches the user data instance (here this is a Model) to the forward problem

Parameters

model	Model instance,

10.35.3.90 setUserDataB()

```
virtual void setUserDataB (
            int which,
            Model * model )  [protected], [pure virtual]
```

SetUserDataB attaches the user data instance (here this is a Model) to the backward problem

Parameters

which	identifier of the backwards problem
model	Model instance,

Here is the caller graph for this function:

10.35.3.91 setMaxNumSteps()

```
virtual void setMaxNumSteps (
            long int mxsteps )  [protected], [pure virtual]
```

SetMaxNumSteps specifies the maximum number of steps for the forward problem

Parameters

mxsteps	number of steps

Here is the caller graph for this function:

10.35.3.92 setMaxNumStepsB()

```
virtual void setMaxNumStepsB (
            int which,
            long int mxstepsB )  [protected], [pure virtual]
```

SetMaxNumStepsB specifies the maximum number of steps for the forward problem

Parameters

which	identifier of the backwards problem
mxstepsB	number of steps

Here is the caller graph for this function:

10.35.3.93 setStabLimDet()

```
virtual void setStabLimDet (
            int stldet )  [protected], [pure virtual]
```

SetStabLimDet activates stability limit detection for the forward problem

Parameters

stldet	flag for stability limit detection (TRUE or FALSE)

Here is the caller graph for this function:

10.35.3.94 setStabLimDetB()

```
virtual void setStabLimDetB (
            int which,
            int stldet )  [protected], [pure virtual]
```

SetStabLimDetB activates stability limit detection for the backward problem

Parameters

which	identifier of the backwards problem
stldet	flag for stability limit detection (TRUE or FALSE)

Here is the caller graph for this function:

10.35.3.95 setId()

```
virtual void setId (
            Model * model )  [protected], [pure virtual]
```

SetId specify algebraic/differential components (DAE only)

Parameters

model	model specification

10.35.3.96 setSuppressAlg()

```
virtual void setSuppressAlg (
            bool flag )  [protected], [pure virtual]
```

SetId deactivates error control for algebraic components (DAE only)

Parameters

flag	deactivation flag

10.35.3.97 setSensParams()

```
virtual void setSensParams (
            realtype * p,
            realtype * pbar,
            int * plist )  [protected], [pure virtual]
```

SetSensParams specifies the scaling and indexes for sensitivity computation

Parameters

p	paramaters
pbar	parameter scaling constants
plist	parameter index list

10.35.3.98 getDky()

```
virtual void getDky (
            realtype t,
            int k,
            AmiVector * dky ) const  [protected], [pure virtual]
```

getDky interpolates the (derivative of the) solution at the requested timepoint

Parameters

t	timepoint
k	derivative order
dky	interpolated solution

10.35.3.99 adjInit()

```
virtual void adjInit ( )  [protected], [pure virtual]
```

AdjInit initializes the adjoint problem

10.35.3.100 allocateSolverB()

```
virtual void allocateSolverB (
            int * which )  [protected], [pure virtual]
```

specifies solver method and initializes solver memory for the backward problem

Parameters

which	identifier of the backwards problem

Here is the caller graph for this function:

10.35.3.101 setSStolerancesB()

```
virtual void setSStolerancesB (
            int which,
            realtype relTolB,
            realtype absTolB )  [protected], [pure virtual]
```

SStolerancesB sets relative and absolute tolerances for the backward problem

Parameters

which	identifier of the backwards problem
relTolB	relative tolerances
absTolB	absolute tolerances

10.35.3.102 quadSStolerancesB()

```
virtual void quadSStolerancesB (
            int which,
            realtype reltolQB,
            realtype abstolQB )  [protected], [pure virtual]
```

SStolerancesB sets relative and absolute tolerances for the quadrature backward problem

Parameters

which	identifier of the backwards problem
reltolQB	relative tolerances
abstolQB	absolute tolerances

10.35.3.103 dense()

```
virtual void dense (
            int nx )  [protected], [pure virtual]
```

Dense attaches a dense linear solver to the forward problem

Parameters

nx	number of state variables

Here is the caller graph for this function:

10.35.3.104 denseB()

```
virtual void denseB (
            int which,
            int nx )  [protected], [pure virtual]
```

DenseB attaches a dense linear solver to the backward problem

Parameters

which	identifier of the backwards problem
nx	number of state variables

Here is the caller graph for this function:

10.35.3.105 band()

```
virtual void band (
            int nx,
            int ubw,
            int lbw )  [protected], [pure virtual]
```

Band attaches a banded linear solver to the forward problem

Parameters

nx	number of state variables
ubw	upper matrix bandwidth
lbw	lower matrix bandwidth

Here is the caller graph for this function:

10.35.3.106 bandB()

```
virtual void bandB (
            int which,
            int nx,
            int ubw,
            int lbw )  [protected], [pure virtual]
```

BandB attaches a banded linear solver to the backward problem

Parameters

which	identifier of the backwards problem
nx	number of state variables
ubw	upper matrix bandwidth
lbw	lower matrix bandwidth

Here is the caller graph for this function:

10.35.3.107 diag()

```
virtual void diag ( )  [protected], [pure virtual]
```

Diag attaches a diagonal linear solver to the forward problem

10.35.3.108 diagB()

```
virtual void diagB (
            int which )  [protected], [pure virtual]
```

DiagB attaches a diagonal linear solver to the backward problem

Parameters

which	identifier of the backwards problem

10.35.3.109 spgmr()

```
virtual void spgmr (
            int prectype,
            int maxl )  [protected], [pure virtual]
```

DAMISpgmr attaches a scaled predonditioned GMRES linear solver to the forward problem

Parameters

prectype	preconditioner type PREC_NONE, PREC_LEFT, PREC_RIGHT or PREC_BOTH
maxl	maximum Kryloc subspace dimension

10.35.3.110 spgmrB()

```
virtual void spgmrB (
            int which,
            int prectype,
            int maxl )  [protected], [pure virtual]
```

DAMISpgmrB attaches a scaled predonditioned GMRES linear solver to the backward problem

Parameters

which	identifier of the backwards problem
prectype	preconditioner type PREC_NONE, PREC_LEFT, PREC_RIGHT or PREC_BOTH
maxl	maximum Kryloc subspace dimension

10.35.3.111 spbcg()

```
virtual void spbcg (
            int prectype,
            int maxl )  [protected], [pure virtual]
```

Spbcg attaches a scaled predonditioned Bi-CGStab linear solver to the forward problem

Parameters

prectype	preconditioner type PREC_NONE, PREC_LEFT, PREC_RIGHT or PREC_BOTH
maxl	maximum Kryloc subspace dimension

10.35.3.112 spbcgB()

```
virtual void spbcgB (
            int which,
            int prectype,
            int maxl )  [protected], [pure virtual]
```

SpbcgB attaches a scaled predonditioned Bi-CGStab linear solver to the backward problem

Parameters

which	identifier of the backwards problem
prectype	preconditioner type PREC_NONE, PREC_LEFT, PREC_RIGHT or PREC_BOTH
maxl	maximum Kryloc subspace dimension

10.35.3.113 sptfqmr()

```
virtual void sptfqmr (
            int prectype,
            int maxl )  [protected], [pure virtual]
```

Sptfqmr attaches a scaled predonditioned TFQMR linear solver to the forward problem

Parameters

prectype	preconditioner type PREC_NONE, PREC_LEFT, PREC_RIGHT or PREC_BOTH
maxl	maximum Kryloc subspace dimension

10.35.3.114 sptfqmrB()

```
virtual void sptfqmrB (
            int which,
```

```
            int prectype,
            int maxl )  [protected], [pure virtual]
```

SptfqmrB attaches a scaled predonditioned TFQMR linear solver to the backward problem

Parameters

which	identifier of the backwards problem
prectype	preconditioner type PREC_NONE, PREC_LEFT, PREC_RIGHT or PREC_BOTH
maxl	maximum Kryloc subspace dimension

10.35.3.115 klu()

```
virtual void klu (
            int nx,
            int nnz,
            int sparsetype )  [protected], [pure virtual]
```

KLU attaches a sparse linear solver to the forward problem

Parameters

nx	number of state variables
nnz	number of nonzero entries in the jacobian
sparsetype	sparse storage type, CSC_MAT for column matrix, CSR_MAT for row matrix

10.35.3.116 kluSetOrdering()

```
virtual void kluSetOrdering (
            int ordering )  [protected], [pure virtual]
```

KLUSetOrdering sets the ordering for the sparse linear solver of the forward problem

Parameters

ordering	ordering algorithm to reduce fill 0:AMD 1:COLAMD 2: natural ordering

10.35.3.117 kluSetOrderingB()

```
virtual void kluSetOrderingB (
            int which,
            int ordering )  [protected], [pure virtual]
```

KLUSetOrderingB sets the ordering for the sparse linear solver of the backward problem

Parameters

which	identifier of the backwards problem
ordering	ordering algorithm to reduce fill 0:AMD 1:COLAMD 2: natural ordering

10.35.3.118 kluB()

```
virtual void kluB (
            int which,
            int nx,
            int nnz,
            int sparsetype )  [protected], [pure virtual]
```

KLUB attaches a sparse linear solver to the forward problem

Parameters

which	identifier of the backwards problem
nx	number of state variables
nnz	number of nonzero entries in the jacobian
sparsetype	sparse storage type, CSC_MAT for column matrix, CSR_MAT for row matrix

10.35.3.119 getNumSteps()

```
virtual void getNumSteps (
            void * ami_mem,
            long int * numsteps ) const  [protected], [pure virtual]
```

getNumSteps reports the number of solver steps

Parameters

ami_mem	pointer to the solver memory instance (can be from forward or backward problem)
numsteps	output array

Here is the caller graph for this function:

10.35.3.120 getNumRhsEvals()

```
virtual void getNumRhsEvals (
            void * ami_mem,
            long int * numrhsevals ) const  [protected], [pure virtual]
```

getNumRhsEvals reports the number of right hand evaluations

Parameters

ami_mem	pointer to the solver memory instance (can be from forward or backward problem)
numrhsevals	output array

Here is the caller graph for this function:

10.35.3.121 getNumErrTestFails()

```
virtual void getNumErrTestFails (
            void * ami_mem,
            long int * numerrtestfails ) const  [protected], [pure virtual]
```

getNumErrTestFails reports the number of local error test failures

Parameters

ami_mem	pointer to the solver memory instance (can be from forward or backward problem)
numerrtestfails	output array

Here is the caller graph for this function:

10.35.3.122 getNumNonlinSolvConvFails()

```
virtual void getNumNonlinSolvConvFails (
            void * ami_mem,
            long int * numnonlinsolvconvfails ) const  [protected], [pure virtual]
```

getNumNonlinSolvConvFails reports the number of nonlinear convergence failures

Parameters

ami_mem	pointer to the solver memory instance (can be from forward or backward problem)
numnonlinsolvconvfails	output array

Here is the caller graph for this function:

10.35.3.123 getLastOrder()

```
virtual void getLastOrder (
            void * ami_mem,
            int * order ) const  [protected], [pure virtual]
```

Reports the order of the integration method during the last internal step

Parameters

ami_mem	pointer to the solver memory instance (can be from forward or backward problem)
order	output array

Here is the caller graph for this function:

10.35.3.124 initializeLinearSolver()

```
void initializeLinearSolver (
            const Model * model )  [protected]
```

initializeLinearSolver sets the linear solver for the forward problem

Parameters

model	pointer to the model object

Definition at line 214 of file solver.cpp.

Here is the call graph for this function:

10.35.3.125 initializeLinearSolverB()

```
void initializeLinearSolverB (
            const Model * model,
            const int which )  [protected]
```

Sets the linear solver for the backward problem

Parameters

model	pointer to the model object
which	index of the backward problem

Definition at line 291 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.126 nplist()

```
virtual int nplist ( ) const  [protected], [pure virtual]
```

Accessor function to the number of sensitivity parameters in the model stored in the user data

Returns

number of sensitivity parameters

10.35.3.127 nx()

```
virtual int nx ( ) const  [protected], [pure virtual]
```

Accessor function to the number of state variables in the model stored in the user data

Returns

number of state variables

10.35.3.128 getModel()

```
virtual const Model* getModel ( ) const  [protected], [pure virtual]
```

Accessor function to the model stored in the user data

Returns

user data model

10.35.3.129 getMallocDone()

```
virtual bool getMallocDone ( ) const  [protected], [pure virtual]
```

checks whether memory for the forward problem has been allocated

Returns

solverMemory->(cv|ida)__MallocDone

Here is the caller graph for this function:

10.35.3.130 getAdjMallocDone()

```
virtual bool getAdjMallocDone ( ) const  [protected], [pure virtual]
```

checks whether memory for the backward problem has been allocated

Returns

solverMemory->(cv|ida)__adjMallocDone

Here is the caller graph for this function:

10.35.3.131 getAdjBmem()

```
virtual void* getAdjBmem (
            void * ami_mem,
            int which )  [protected], [pure virtual]
```

getAdjBmem retrieves the solver memory instance for the backward problem

Parameters

which	identifier of the backwards problem
ami_mem	pointer to the forward solver memory instance

Returns

ami_memB pointer to the backward solver memory instance

10.35.3.132 applyTolerances()

```
void applyTolerances ( )  [protected]
```

updates solver tolerances according to the currently specified member variables

Definition at line 398 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.133 applyTolerancesFSA()

```
void applyTolerancesFSA ( ) [protected]
```

updates FSA solver tolerances according to the currently specified member variables

Definition at line 405 of file solver.cpp.

Here is the call graph for this function:

10.35.3.134 applyTolerancesASA()

```
void applyTolerancesASA (
            int which ) [protected]
```

updates ASA solver tolerances according to the currently specified member variables

Parameters

which	identifier of the backwards problem

Definition at line 419 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.135 applyQuadTolerancesASA()

```
void applyQuadTolerancesASA (
            int which )  [protected]
```

updates ASA quadrature solver tolerances according to the currently specified member variables

Parameters

which	identifier of the backwards problem

Definition at line 430 of file solver.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.35.3.136 applySensitivityTolerances()

```
void applySensitivityTolerances ( ) [protected]
```

updates all senstivivity solver tolerances according to the currently specified member variables

Definition at line 449 of file solver.cpp.

Here is the caller graph for this function:

10.35.4 Friends And Related Function Documentation

10.35.4.1 boost::serialization::serialize

```
void boost::serialization::serialize (
            Archive & ar,
            Solver & r,
            const unsigned int version ) [friend]
```

Parameters

ar	Archive to serialize to
r	Data to serialize
version	Version number

10.35.4.2 operator==

```
bool operator== (
            const Solver & a,
            const Solver & b ) [friend]
```

Parameters

a	
b	

Returns

Definition at line 365 of file solver.cpp.

10.35.5 Member Data Documentation

10.35.5.1 solverMemory

```
std::unique_ptr<void, std::function<void(void *)> > solverMemory  [protected]
```

pointer to solver memory block

Definition at line 1107 of file solver.h.

10.35.5.2 solverMemoryB

```
std::vector<std::unique_ptr<void, std::function<void(void *)> > > solverMemoryB  [protected]
```

pointer to solver memory block

Definition at line 1110 of file solver.h.

10.35.5.3 solverWasCalled

```
bool solverWasCalled = false  [protected]
```

flag indicating whether the solver was called

Definition at line 1113 of file solver.h.

10.35.5.4 ism

```
InternalSensitivityMethod ism = InternalSensitivityMethod::simultaneous  [protected]
```

internal sensitivity method flag used to select the sensitivity solution method. Only applies for Forward Sensitivities.

Definition at line 1117 of file solver.h.

10.35.5.5 lmm

```
LinearMultistepMethod lmm = LinearMultistepMethod::BDF  [protected]
```

specifies the linear multistep method.

Definition at line 1121 of file solver.h.

10.35.5.6 iter

```
NonlinearSolverIteration iter = NonlinearSolverIteration::newton  [protected]
```

specifies the type of nonlinear solver iteration

Definition at line 1126 of file solver.h.

10.35.5.7 interpType

```
InterpolationType interpType = InterpolationType::hermite  [protected]
```

interpolation type for the forward problem solution which is then used for the backwards problem.

Definition at line 1131 of file solver.h.

10.35.5.8 maxsteps

```
int maxsteps = 10000  [protected]
```

maximum number of allowed integration steps

Definition at line 1134 of file solver.h.

10.36 SteadystateProblem Class Reference

The SteadystateProblem class solves a steady-state problem using Newton's method and falls back to integration on failure.

```
#include <steadystateproblem.h>
```

Public Member Functions

- void workSteadyStateProblem (ReturnData *rdata, Solver *solver, Model *model, int it)
- realtype getWrmsNorm (AmiVector const &x, AmiVector const &xdot, realtype atol, realtype rtol)
- bool checkConvergence (const Solver *solver, Model *model)
- void applyNewtonsMethod (ReturnData *rdata, Model *model, NewtonSolver *newtonSolver, int newton_try)
- void writeNewtonOutput (ReturnData *rdata, const Model *model, NewtonStatus newton_status, double run_time, int it)
- void getSteadystateSimulation (ReturnData *rdata, Solver *solver, Model *model, int it)
- std::unique_ptr< Solver > createSteadystateSimSolver (Solver *solver, Model *model, realtype tstart)
- SteadystateProblem (realtype *t, AmiVector *x, AmiVectorArray *sx)

10.36.1 Detailed Description

Definition at line 25 of file steadystateproblem.h.

10.36.2 Constructor & Destructor Documentation

10.36.2.1 SteadystateProblem()

```
SteadystateProblem (
            realtype * t,
            AmiVector * x,
            AmiVectorArray * sx )
```

default constructor

Parameters

t	pointer to time variable
x	pointer to state variables
sx	pointer to state sensitivity variables

Definition at line 108 of file steadystateproblem.h.

10.36.3 Member Function Documentation

10.36.3.1 workSteadyStateProblem()

```
void workSteadyStateProblem (
            ReturnData * rdata,
            Solver * solver,
            Model * model,
            int it )
```

Tries to determine the steady state of the ODE system by a Newton solver, uses forward intergration, if the Newton solver fails, restarts Newton solver, if integration fails. Computes steady state sensitivities

Parameters

solver	pointer to the AMICI solver object
model	pointer to the AMICI model object
it	integer with the index of the current time step
rdata	pointer to the return data object

Definition at line 21 of file steadystateproblem.cpp.

Here is the call graph for this function:

10.36.3.2 getWrmsNorm()

```
realtype getWrmsNorm (
            AmiVector const & x,
            AmiVector const & xdot,
            realtype atol,
            realtype rtol )
```

Computes the weighted root mean square of xdot the weights are computed according to x: w_i = 1 / (rtol ∗ x_i + atol)

Parameters

x	current state
xdot	current rhs
atol	absolute tolerance
rtol	relative tolerance

Returns

root-mean-square norm

Definition at line 94 of file steadystateproblem.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.36.3.3 checkConvergence()

```
bool checkConvergence (
            const Solver * solver,
            Model * model )
```

Checks convergence for state and respective sensitivities

Parameters

solver	Solver instance
model	instance

Returns

boolean indicating convergence

Definition at line 106 of file steadystateproblem.cpp.

Here is the call graph for this function:

Here is the caller graph for this function:

10.36.3.4 applyNewtonsMethod()

```
void applyNewtonsMethod (
            ReturnData * rdata,
            Model * model,
            NewtonSolver * newtonSolver,
            int newton_try )
```

Runs the Newton solver iterations and checks for convergence to steady state

Parameters

rdata	pointer to the return data object
model	pointer to the AMICI model object
newtonSolver	pointer to the NewtonSolver object **Type**: NewtonSolver
newton_try	integer start number of Newton solver (1 or 2)

Definition at line 131 of file steadystateproblem.cpp.

Here is the call graph for this function:

10.36.3.5 writeNewtonOutput()

```
void writeNewtonOutput (
            ReturnData * rdata,
            const Model * model,
            NewtonStatus newton_status,
            double run_time,
            int it )
```

Stores output of workSteadyStateProblem in return data

Parameters

newton_status	integer flag indicating when a steady state was found
run_time	double coputation time of the solver in milliseconds
rdata	pointer to the return data instance
model	pointer to the model instance
it	current timepoint index, <0 indicates preequilibration

Definition at line 220 of file steadystateproblem.cpp.

10.36.3.6 getSteadystateSimulation()

```
void getSteadystateSimulation (
            ReturnData * rdata,
            Solver * solver,
            Model * model,
            int it )
```

Forward simulation is launched, if Newton solver fails in first try

Parameters

solver	pointer to the AMICI solver object
model	pointer to the AMICI model object
rdata	pointer to the return data object
it	current timepoint index, <0 indicates preequilibration

Definition at line 245 of file steadystateproblem.cpp.

Here is the call graph for this function:

10.36.3.7 createSteadystateSimSolver()

```
std::unique_ptr< Solver > createSteadystateSimSolver (
            Solver * solver,
            Model * model,
            realtype tstart )
```

initialize CVodeSolver instance for preequilibration simulation

Parameters

solver	pointer to the AMICI solver object
model	pointer to the AMICI model object
tstart	time point for starting Newton simulation

Returns

solver instance

Definition at line 273 of file steadystateproblem.cpp.

Here is the call graph for this function:

10.37 amidata Class Reference

AMIDATA provides a data container to pass experimental data to the simulation routine for likelihood computation. when any of the properties are updated, the class automatically checks consistency of dimension and updates related properties and initialises them with NaNs.

Inheritance diagram for amidata:

Public Member Functions

- amidata (matlabtypesubstitute varargin)

  amidata creates an amidata container for experimental data with specified dimensions amidata.

Public Attributes

- matlabtypesubstitute nt = 0

  number of timepoints
- matlabtypesubstitute ny = 0

  number of observables
- matlabtypesubstitute nz = 0

  number of event observables
- matlabtypesubstitute ne = 0

number of events

- matlabtypesubstitute nk = 0

  number of conditions/constants

- matlabtypesubstitute t = double.empty("")

  timepoints of observations

- matlabtypesubstitute Y = double.empty("")

  observations

- matlabtypesubstitute Sigma_Y = double.empty("")

  standard deviation of observations

- matlabtypesubstitute Z = double.empty("")

  event observations

- matlabtypesubstitute Sigma_Z = double.empty("")

  standard deviation of event observations

- matlabtypesubstitute condition = double.empty("")

  experimental condition

- matlabtypesubstitute conditionPreequilibration = double.empty("")

  experimental condition for preequilibration

10.37.1 Detailed Description

Definition at line 17 of file amidata.m.

10.37.2 Constructor & Destructor Documentation

10.37.2.1 amidata()

```
amidata (
            matlabtypesubstitute varargin )
```

AMIDATA(amidata) creates a copy of the input container

AMIDATA(struct) tries to creates an amidata container from the input struct. the struct should have the following

fields

t [nt,1] Y [nt,ny] Sigma_Y [nt,ny] Z [ne,nz] Sigma_Z [ne,nz] condition [nk,1] conditionPreequilibration [nk,1] if some fields are missing the function will try to initialise them with NaNs with consistent dimensions

AMIDATA(nt,ny,nz,ne,nk) constructs an empty data container with in the provided dimensions intialised with NaNs

Parameters

varargin	

Definition at line 130 of file amidata.m.

10.37.3 Member Data Documentation

10.37.3.1 nt

```
nt = 0
```

Default: 0

Note

This property has custom functionality when its value is changed.

Definition at line 31 of file amidata.m.

10.37.3.2 ny

```
ny = 0
```

Default: 0

Note

This property has custom functionality when its value is changed.

Definition at line 39 of file amidata.m.

10.37.3.3 nz

```
nz = 0
```

Default: 0

Note

This property has custom functionality when its value is changed.

Definition at line 47 of file amidata.m.

10.37.3.4 ne

```
ne = 0
```

Default: 0

Note

This property has custom functionality when its value is changed.

Definition at line 55 of file amidata.m.

10.37.3.5 nk

```
nk = 0
```

Default: 0

Note

This property has custom functionality when its value is changed.

Definition at line 63 of file amidata.m.

10.37.3.6 t

```
t = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 71 of file amidata.m.

10.37.3.7 Y

```
Y = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 79 of file amidata.m.

10.37.3.8 Sigma_Y

```
Sigma_Y = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 87 of file amidata.m.

10.37.3.9 Z

```
Z = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 95 of file amidata.m.

10.37.3.10 Sigma_Z

```
Sigma_Z = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 103 of file amidata.m.

10.37.3.11 condition

```
condition = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 111 of file amidata.m.

10.37.3.12 conditionPreequilibration

```
conditionPreequilibration = double.empty("")
```

Default: double.empty("")

Note

This property has custom functionality when its value is changed.

Definition at line 119 of file amidata.m.

10.38 amievent Class Reference

AMIEVENT defines events which later on will be transformed into appropriate C code.

Public Member Functions

- amievent (matlabtypesubstitute trigger, matlabtypesubstitute bolus, matlabtypesubstitute z)

  amievent constructs an amievent object from the provided input.
- mlhsInnerSubst< matlabtypesubstitute > setHflag (::double hflag)

  gethflag sets the hflag property.

Public Attributes

- ::symbolic trigger = sym.empty("")

  the trigger function activates the event on every zero crossing
- ::symbolic bolus = sym.empty("")

  the bolus function defines the change in states that is applied on every event occurence
- ::symbolic z = sym.empty("")

  output function for the event
- matlabtypesubstitute hflag = logical.empty("")

  flag indicating that a heaviside function is present, this helps to speed up symbolic computations

10.38.1 Detailed Description

Definition at line 17 of file amievent.m.

10.38.2 Constructor & Destructor Documentation

10.38.2.1 amievent()

```
amievent (
            matlabtypesubstitute trigger,
            matlabtypesubstitute bolus,
            matlabtypesubstitute z )
```

Parameters

trigger	trigger function, the event will be triggered on at all roots of this function
bolus	the bolus that will be added to all states on every occurence of the event
z	the event output that will be reported on every occurence of the event

Definition at line 75 of file amievent.m.

10.38.3 Member Function Documentation

10.38.3.1 setHflag()

```
mlhsInnerSubst<::amievent > setHflag (
            ::double hflag )
```

Parameters

hflag	value for the hflag property

Return values

this	updated event definition object

Definition at line 18 of file setHflag.m.

Here is the caller graph for this function:

10.38.4 Member Data Documentation

10.38.4.1 trigger

```
trigger = sym.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: sym.empty("")

Definition at line 27 of file amievent.m.

10.38.4.2 bolus

```
bolus = sym.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: sym.empty("")

Definition at line 38 of file amievent.m.

10.38.4.3 z

```
z = sym.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: sym.empty("")

Definition at line 49 of file amievent.m.

10.38.4.4 hflag

```
hflag = logical.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: logical.empty("")

Definition at line 60 of file amievent.m.

10.39 amifun Class Reference

AMIFUN defines functions which later on will be transformed into appropriate C code.

Public Member Functions

- amifun (matlabtypesubstitute funstr, matlabtypesubstitute model)

  amievent constructs an amifun object from the provided input.
- noret::substitute writeCcode_sensi (::amimodel model,::fileid fid)

  writeCcode_sensi is a wrapper for writeCcode which loops over parameters and reduces overhead by check nonzero values
- noret::substitute writeCcode (::amimodel model,::fileid fid)

  writeCcode is a wrapper for gccode which initialises data and reduces overhead by check nonzero values
- noret::substitute writeMcode (::amimodel model)

  writeMcode generates matlab evaluable code for specific model functions
- noret::substitute gccode (::amimodel model,::fileid fid)

  gccode transforms symbolic expressions into c code and writes the respective expression into a specified file
- mlhsInnerSubst< matlabtypesubstitute > getDeps (::amimodel model)

  getDeps populates the sensiflag for the requested function
- mlhsInnerSubst< matlabtypesubstitute > getArgs (::amimodel model)

  getFArgs populates the fargstr property with the argument string of the respective model function (if applicable). model functions are not wrapped versions of functions which have a model specific name and for which the call is solver specific.
- mlhsInnerSubst< matlabtypesubstitute > getNVecs ()

  getfunargs populates the nvecs property with the names of the N_Vector elements which are required in the execution of the function (if applicable). the information is directly extracted from the argument string
- mlhsInnerSubst< matlabtypesubstitute > getCVar ()

  getCVar populates the cvar property
- mlhsInnerSubst< matlabtypesubstitute > getSensiFlag ()

  getSensiFlag populates the sensiflag property
- mlhsSubst< mlhsInnerSubst< matlabtypesubstitute >,mlhsInnerSubst<::amimodel > > getSyms (↩ ::amimodel model)

  getSyms computes the symbolic expression for the requested function

Public Attributes

- ::symbolic sym = sym("[ ]")

  symbolic definition struct
- ::symbolic sym_noopt = sym("[ ]")

  symbolic definition which was not optimized (no dependencies on w)
- ::symbolic strsym = sym("[ ]")

  short symbolic string which can be used for the reuse of precomputed values
- ::symbolic strsym_old = sym("[ ]")

  short symbolic string which can be used for the reuse of old values
- ::char funstr = char.empty("")

  name of the model
- ::char cvar = char.empty("")

  name of the c variable
- ::char argstr = char.empty("")

  argument string (solver specific)

- ::cell deps = cell.empty("")

  dependencies on other functions
- matlabtypesubstitute nvecs = cell.empty("")

  nvec dependencies
- matlabtypesubstitute sensiflag = logical.empty("")

  indicates whether the function is a sensitivity or derivative with respect to parameters

10.39.1 Detailed Description

Definition at line 17 of file amifun.m.

10.39.2 Constructor & Destructor Documentation

10.39.2.1 amifun()

```
amifun (
            matlabtypesubstitute funstr,
            matlabtypesubstitute model )
```

Parameters

funstr	name of the requested function
model	amimodel object which carries all symbolic definitions to construct the function

Definition at line 111 of file amifun.m.

10.39.3 Member Function Documentation

10.39.3.1 writeCcode_sensi()

```
noret::substitute writeCcode_sensi (
            ::amimodel model,
            ::fileid fid )
```

Parameters

model	model defintion object
fid	file id in which the final expression is written

Return values

fid	void

Definition at line 18 of file writeCcode_sensi.m.

10.39.3.2 writeCcode()

```
noret::substitute writeCcode (
            ::amimodel model,
            ::fileid fid )
```

Parameters

model	model defintion object
fid	file id in which the final expression is written

Return values

fid	void

Definition at line 18 of file writeCcode.m.

Here is the call graph for this function:

10.39.3.3 writeMcode()

```
noret::substitute writeMcode (
            ::amimodel model )
```

Parameters

model	model defintion object

Return values

model	void

Definition at line 18 of file writeMcode.m.

10.39.3.4 gccode()

```
mlhsInnerSubst<::amifun > gccode (
            ::amimodel model,
            ::fileid fid )
```

Parameters

model	model definition object
fid	file id in which the expression should be written

Return values

this	function definition object

Definition at line 18 of file gccode.m.

Here is the caller graph for this function:

10.39.3.5 getDeps()

```
mlhsInnerSubst<::amifun > getDeps (
            ::amimodel model )
```

Parameters

model	model definition object

Return values

this	updated function definition object

Definition at line 18 of file getDeps.m.

10.39.3.6 getArgs()

```
mlhsInnerSubst<::amifun > getArgs (
            ::amimodel model )
```

Parameters

model	model definition object

Return values

this	updated function definition object

Definition at line 18 of file getArgs.m.

10.39.3.7 getNVecs()

```
mlhsInnerSubst<::amifun > getNVecs ( )
```

Return values

this	updated function definition object

Definition at line 18 of file getNVecs.m.

10.39.3.8 getCVar()

```
mlhsInnerSubst<::amifun > getCVar ( )
```

Return values

this	updated function definition object

Definition at line 18 of file getCVar.m.

10.39.3.9 getSensiFlag()

```
mlhsInnerSubst<::amifun > getSensiFlag ( )
```

Return values

this	updated function definition object

Definition at line 18 of file getSensiFlag.m.

10.39.3.10 getSyms()

```
mlhsSubst< mlhsInnerSubst<::amifun >,mlhsInnerSubst<::amimodel > > getSyms (
            ::amimodel model )
```

Parameters

model	model definition object

Return values

this	updated function definition object
model	updated model definition object

Definition at line 18 of file getSyms.m.

10.39.4 Member Data Documentation

10.39.4.1 sym

```
sym = sym("[]")
```

Default: sym("[]")

Definition at line 27 of file amifun.m.

10.39.4.2 sym_noopt

```
sym_noopt = sym("[]")
```

Default: sym("[]")

Definition at line 35 of file amifun.m.

10.39.4.3 strsym

```
strsym = sym("[]")
```

Default: sym("[]")

Definition at line 43 of file amifun.m.

10.39.4.4 strsym_old

```
strsym_old = sym("[]")
```

Default: sym("[]")

Definition at line 51 of file amifun.m.

10.39.4.5 funstr

```
funstr = char.empty("")
```

Default: char.empty("")

Definition at line 59 of file amifun.m.

10.39.4.6 cvar

```
cvar = char.empty("")
```

Default: char.empty("")

Definition at line 67 of file amifun.m.

10.39.4.7 argstr

```
argstr = char.empty("")
```

Default: char.empty("")

Definition at line 75 of file amifun.m.

10.39.4.8 deps

```
deps = cell.empty("")
```

Default: cell.empty("")

Definition at line 83 of file amifun.m.

10.39.4.9 nvecs

```
nvecs = cell.empty("")
```

Default: cell.empty("")

Definition at line 91 of file amifun.m.

10.39.4.10 sensiflag

```
sensiflag = logical.empty("")
```

Default: logical.empty("")

Definition at line 99 of file amifun.m.

10.40 amimodel Class Reference

AMIMODEL carries all model definitions including functions and events.

Inheritance diagram for amimodel:

Public Member Functions

- amimodel (::string symfun,::string modelname)

  amimodel initializes the model object based on the provided symfun and modelname
- noret::substitute updateRHS (matlabtypesubstitute xdot)

  updateRHS updates the private fun property .fun.xdot.sym (right hand side of the differential equation)
- noret::substitute updateModelName (matlabtypesubstitute modelname)

  updateModelName updates the modelname
- noret::substitute updateWrapPath (matlabtypesubstitute wrap_path)

  updateModelName updates the modelname
- noret::substitute parseModel ()

  parseModel parses the model definition and computes all necessary symbolic expressions.

- noret::substitute generateC ()

  generateC generates the c files which will be used in the compilation.
- noret::substitute compileC ()

  compileC compiles the mex simulation file
- noret::substitute generateM (::amimodel amimodelo2)

  generateM generates the matlab wrapper for the compiled C files.
- noret::substitute getFun (::struct HTable,::string funstr)

  getFun generates symbolic expressions for the requested function.
- noret::substitute makeEvents ()

  makeEvents extracts discontiniuties from the model right hand side and converts them into events
- noret::substitute makeSyms ()

  makeSyms extracts symbolic definition from the user provided model and checks them for consistency
- mlhsInnerSubst< matlabtypesubstitute > checkDeps (::struct HTable,::cell deps)

  checkDeps checks the dependencies of functions and populates sym fields if necessary
- mlhsInnerSubst< matlabtypesubstitute > loadOldHashes ()

  loadOldHashes loads information from a previous compilation of the model.
- mlhsInnerSubst< matlabtypesubstitute > augmento2 ()

  augmento2 augments the system equation to also include equations for sensitivity equation. This will enable us to compute second order sensitivities in a forward-adjoint or forward-forward apporach later on.
- mlhsInnerSubst< matlabtypesubstitute > augmento2vec ()

  augmento2 augments the system equation to also include equations for sensitivity equation. This will enable us to compute second order sensitivities in a forward-adjoint or forward-forward apporach later on.

Static Public Member Functions

- static noret::substitute compileAndLinkModel (matlabtypesubstitute modelname, matlabtypesubstitute modelSourceFolder, matlabtypesubstitute coptim, matlabtypesubstitute debug, matlabtypesubstitute funs, matlabtypesubstitute cfun)

  compileAndLinkModel compiles the mex simulation file. It does not check if the model files have changed since generating C++ code or whether all files are still present. Use only if you know what you are doing. The safer alternative is rerunning amiwrap().
- static noret::substitute generateMatlabWrapper (matlabtypesubstitute nx, matlabtypesubstitute ny, matlabtypesubstitute np, matlabtypesubstitute nk, matlabtypesubstitute nz, matlabtypesubstitute o2flag,::amimodel amimodelo2, matlabtypesubstitute wrapperFilename, matlabtypesubstitute modelname, matlabtypesubstitute pscale, matlabtypesubstitute forward, matlabtypesubstitute adjoint)

  generateMatlabWrapper generates the matlab wrapper for the compiled C files.

Public Attributes

- ::struct sym = struct.empty("")

  symbolic definition struct
- ::struct fun = struct.empty("")

  struct which stores information for which functions c code needs to be generated
- ::amievent event = amievent.empty("")

  struct which stores information for which functions c code needs to be generated
- ::string modelname = char.empty("")

  name of the model
- ::struct HTable = struct.empty("")

  struct that contains hash values for the symbolic model definitions
- ::bool debug = false

  flag indicating whether debugging symbols should be compiled

- ::bool adjoint = true

  flag indicating whether adjoint sensitivities should be enabled
- ::bool forward = true

  flag indicating whether forward sensitivities should be enabled
- ::double t0 = 0

  default initial time
- ::string wtype = char.empty("")

  type of wrapper (cvodes/idas)
- ::int nx = double.empty("")

  number of states
- ::int nxtrue = double.empty("")

  number of original states for second order sensitivities
- ::int ny = double.empty("")

  number of observables
- ::int nytrue = double.empty("")

  number of original observables for second order sensitivities
- ::int np = double.empty("")

  number of parameters
- ::int nk = double.empty("")

  number of constants
- ::int ng = double.empty("")

  number of objective functions
- ::int nevent = double.empty("")

  number of events
- ::int nz = double.empty("")

  number of event outputs
- ::int nztrue = double.empty("")

  number of original event outputs for second order sensitivities
- ::∗int id = double.empty("")

  flag for DAEs
- ::int ubw = double.empty("")

  upper Jacobian bandwidth
- ::int lbw = double.empty("")

  lower Jacobian bandwidth
- ::int nnz = double.empty("")

  number of nonzero entries in Jacobian
- ::∗int sparseidx = double.empty("")

  dataindexes of sparse Jacobian
- ::∗int rowvals = double.empty("")

  rowindexes of sparse Jacobian
- ::∗int colptrs = double.empty("")

  columnindexes of sparse Jacobian
- ::∗int sparseidxB = double.empty("")

  dataindexes of sparse Jacobian
- ::∗int rowvalsB = double.empty("")

  rowindexes of sparse Jacobian
- ::∗int colptrsB = double.empty("")

  columnindexes of sparse Jacobian
- ::∗cell funs = cell.empty("")

  cell array of functions to be compiled
- ::∗cell mfuns = cell.empty("")

cell array of matlab functions to be compiled

- ::string coptim = "-O3"

  optimisation flag for compilation
- ::string param = "lin"

  default parametrisation
- matlabtypesubstitute wrap_path = char.empty("")

  path to wrapper
- matlabtypesubstitute recompile = false

  flag to enforce recompilation of the model
- matlabtypesubstitute cfun = struct.empty("")

  storage for flags determining recompilation of individual functions
- matlabtypesubstitute o2flag = 0

  flag which identifies augmented models 0 indicates no augmentation 1 indicates augmentation by first order sensitivities (yields second order sensitivities) 2 indicates augmentation by one linear combination of first order sensitivities (yields hessian-vector product)
- matlabtypesubstitute z2event = double.empty("")

  vector that maps outputs to events
- matlabtypesubstitute splineflag = false

  flag indicating whether the model contains spline functions
- matlabtypesubstitute minflag = false

  flag indicating whether the model contains min functions
- matlabtypesubstitute maxflag = false

  flag indicating whether the model contains max functions
- ::int nw = 0

  number of derived variables w, w is used for code optimization to reduce the number of frequently occuring expressions
- ::int ndwdx = 0

  number of derivatives of derived variables w, dwdx
- ::int ndwdp = 0

  number of derivatives of derived variables w, dwdp

10.40.1 Detailed Description

Definition at line 17 of file amimodel.m.

10.40.2 Constructor & Destructor Documentation

10.40.2.1 amimodel()

```
amimodel (
            ::string symfun,
            ::string modelname )
```

Parameters

symfun	this is the string to the function which generates the modelstruct. You can also directly pass the struct here
modelname	name of the model

Definition at line 515 of file amimodel.m.

Here is the caller graph for this function:

10.40.3 Member Function Documentation

10.40.3.1 updateRHS()

```
noret::substitute updateRHS (
            matlabtypesubstitute xdot )
```

Parameters

xdot	new right hand side of the differential equation

Return values

xdot	void

Definition at line 612 of file amimodel.m.

10.40.3.2 updateModelName()

```
noret::substitute updateModelName (
            matlabtypesubstitute modelname )
```

Parameters

modelname	new modelname

Return values

modelname	void

Definition at line 627 of file amimodel.m.

10.40.3.3 updateWrapPath()

```
noret::substitute updateWrapPath (
            matlabtypesubstitute wrap_path )
```

Parameters

wrap_path	new wrap_path

Return values

wrap_path	void

Definition at line 640 of file amimodel.m.

10.40.3.4 parseModel()

```
noret::substitute parseModel ( )
```

Return values

void	

Definition at line 18 of file parseModel.m.

Here is the call graph for this function:

10.40.3.5 generateC()

```
noret::substitute generateC ( )
```

Return values

void	

Definition at line 18 of file generateC.m.

10.40.3.6 compileC()

```
noret::substitute compileC ( )
```

Return values

void	

Definition at line 18 of file compileC.m.

Here is the call graph for this function:

10.40.3.7 generateM()

```
noret::substitute generateM (
            ::amimodel amimodelo2 )
```

Parameters

amimodelo2	this struct must contain all necessary symbolic definitions for second order sensivities

Return values

amimodelo2	void

Definition at line 18 of file generateM.m.

Here is the call graph for this function:

10.40.3.8 getFun()

```
noret::substitute getFun (
            ::struct HTable,
            ::string funstr )
```

Parameters

HTable	struct with hashes of symbolic definition from the previous compilation
funstr	function for which symbolic expressions should be computed

Return values

funstr	void

Definition at line 18 of file getFun.m.

Here is the call graph for this function:

Here is the caller graph for this function:

10.40.3.9 makeEvents()

```
noret::substitute makeEvents ( )
```

Return values

void	

Definition at line 18 of file makeEvents.m.

Here is the call graph for this function:

10.40.3.10 makeSyms()

```
noret::substitute makeSyms ( )
```

Return values

void	

Definition at line 18 of file makeSyms.m.

10.40.3.11 checkDeps()

```
mlhsInnerSubst<::bool > checkDeps (
            ::struct HTable,
            ::cell deps )
```

Parameters

HTable	struct with reference hashes of functions in its fields
deps	cell array with containing a list of dependencies

Return values

cflag	boolean indicating whether any of the dependencies have changed with respect to the hashes stored in HTable

Definition at line 18 of file checkDeps.m.

Here is the call graph for this function:

Here is the caller graph for this function:

10.40.3.12 loadOldHashes()

```
mlhsInnerSubst<::struct > loadOldHashes ( )
```

Return values

HTable	struct with hashes of symbolic definition from the previous compilation

Definition at line 18 of file loadOldHashes.m.

Here is the caller graph for this function:

10.40.3.13 augmento2()

```
mlhsInnerSubst< matlabtypesubstitute > augmento2 ( )
```

Return values

this	augmented system which contains symbolic definition of the original system and its sensitivities

Definition at line 18 of file augmento2.m.

Here is the call graph for this function:

10.40.3.14 augmento2vec()

```
mlhsInnerSubst<::amimodel > augmento2vec ( )
```

Return values

modelo2vec	augmented system which contains symbolic definition of the original system and its sensitivities

Definition at line 18 of file augmento2vec.m.

Here is the call graph for this function:

10.40.3.15 compileAndLinkModel()

```
noret::substitute compileAndLinkModel (
            matlabtypesubstitute modelname,
            matlabtypesubstitute modelSourceFolder,
            matlabtypesubstitute coptim,
            matlabtypesubstitute debug,
            matlabtypesubstitute funs,
            matlabtypesubstitute cfun )  [static]
```

Parameters

modelname	name of the model as specified for amiwrap()
modelSourceFolder	path to model source directory
coptim	optimization flags
debug	enable debugging
funs	array with names of the model functions, will be guessed from source files if left empty
cfun	struct indicating which files should be recompiled

Return values

cfun	void

Definition at line 18 of file compileAndLinkModel.m.

Here is the caller graph for this function:

10.40.3.16 generateMatlabWrapper()

```
noret::substitute generateMatlabWrapper (
            matlabtypesubstitute nx,
            matlabtypesubstitute ny,
            matlabtypesubstitute np,
            matlabtypesubstitute nk,
            matlabtypesubstitute nz,
            matlabtypesubstitute o2flag,
            ::amimodel amimodelo2,
            matlabtypesubstitute wrapperFilename,
            matlabtypesubstitute modelname,
            matlabtypesubstitute pscale,
            matlabtypesubstitute forward,
            matlabtypesubstitute adjoint )  [static]
```

Parameters

nx	number of states
ny	number of observables
np	number of parameters
nk	number of fixed parameters
nz	number of events

Parameters

o2flag	o2flag
amimodelo2	this struct must contain all necessary symbolic definitions for second order sensivities
wrapperFilename	output filename
modelname	name of the model
pscale	default parameter scaling
forward	has forward sensitivity equations
adjoint	has adjoint sensitivity equations

Return values

adjoint	void

Definition at line 18 of file generateMatlabWrapper.m.

Here is the caller graph for this function:

10.40.4 Member Data Documentation

10.40.4.1 sym

```
sym = struct.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: struct.empty("")

Definition at line 27 of file amimodel.m.

10.40.4.2 fun

```
fun = struct.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: struct.empty("")

Definition at line 38 of file amimodel.m.

10.40.4.3 event

```
event = amievent.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: amievent.empty("")

Definition at line 49 of file amimodel.m.

10.40.4.4 modelname

```
modelname = char.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: char.empty("")

Definition at line 61 of file amimodel.m.

10.40.4.5 HTable

```
HTable = struct.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: struct.empty("")

Definition at line 72 of file amimodel.m.

10.40.4.6 debug

```
debug = false
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: false

Definition at line 83 of file amimodel.m.

10.40.4.7 adjoint

```
adjoint = true
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: true

Definition at line 94 of file amimodel.m.

10.40.4.8 forward

```
forward = true
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: true

Definition at line 105 of file amimodel.m.

10.40.4.9 t0

```
t0 = 0
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: 0

Definition at line 116 of file amimodel.m.

10.40.4.10 wtype

```
wtype = char.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: char.empty("")

Definition at line 127 of file amimodel.m.

10.40.4.11 nx

```
nx = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 138 of file amimodel.m.

10.40.4.12 nxtrue

```
nxtrue = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 149 of file amimodel.m.

10.40.4.13 ny

```
ny = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 160 of file amimodel.m.

10.40.4.14 nytrue

```
nytrue = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 171 of file amimodel.m.

10.40.4.15 np

```
np = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 182 of file amimodel.m.

10.40.4.16 nk

```
nk = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 193 of file amimodel.m.

10.40.4.17 ng

```
ng = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 204 of file amimodel.m.

10.40.4.18 nevent

```
nevent = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 215 of file amimodel.m.

10.40.4.19 nz

```
nz = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 226 of file amimodel.m.

10.40.4.20 nztrue

```
nztrue = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 237 of file amimodel.m.

10.40.4.21 id

```
id = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 248 of file amimodel.m.

10.40.4.22 ubw

```
ubw = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 259 of file amimodel.m.

10.40.4.23 lbw

```
lbw = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 270 of file amimodel.m.

10.40.4.24 nnz

```
nnz = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 281 of file amimodel.m.

10.40.4.25 sparseidx

```
sparseidx = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 292 of file amimodel.m.

10.40.4.26 rowvals

```
rowvals = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 303 of file amimodel.m.

10.40.4.27 colptrs

```
colptrs = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 314 of file amimodel.m.

10.40.4.28 sparseidxB

```
sparseidxB = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 325 of file amimodel.m.

10.40.4.29 rowvalsB

```
rowvalsB = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 336 of file amimodel.m.

10.40.4.30 colptrsB

```
colptrsB = double.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: double.empty("")

Definition at line 347 of file amimodel.m.

10.40.4.31 funs

```
funs = cell.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: cell.empty("")

Definition at line 358 of file amimodel.m.

10.40.4.32 mfuns

```
mfuns = cell.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: cell.empty("")

Definition at line 369 of file amimodel.m.

10.40.4.33 coptim

```
coptim = "-O3"
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: "-O3"

Definition at line 380 of file amimodel.m.

10.40.4.34 param

```
param = "lin"
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: "lin"

Definition at line 391 of file amimodel.m.

10.40.4.35 wrap_path

```
wrap_path = char.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: char.empty("")

Definition at line 402 of file amimodel.m.

10.40.4.36 recompile

```
recompile = false
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: false

Definition at line 413 of file amimodel.m.

10.40.4.37 cfun

```
cfun = struct.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: struct.empty("")

Definition at line 424 of file amimodel.m.

10.40.4.38 o2flag

```
o2flag = 0
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: 0

Definition at line 436 of file amimodel.m.

10.40.4.39 z2event

```
z2event = double.empty("")
```

Default: double.empty("")

Definition at line 455 of file amimodel.m.

10.40.4.40 splineflag

```
splineflag = false
```

Default: false

Definition at line 463 of file amimodel.m.

10.40.4.41 minflag

```
minflag = false
```

Default: false

Definition at line 471 of file amimodel.m.

10.40.4.42 maxflag

```
maxflag = false
```

Default: false

Definition at line 479 of file amimodel.m.

10.40.4.43 nw

```
nw = 0
```

Default: 0

Definition at line 487 of file amimodel.m.

10.40.4.44 ndwdx

```
ndwdx = 0
```

Default: 0

Definition at line 496 of file amimodel.m.

10.40.4.45 ndwdp

```
ndwdp = 0
```

Default: 0

Definition at line 504 of file amimodel.m.

10.41 amioption Class Reference

AMIOPTION provides an option container to pass simulation parameters to the simulation routine.

Inheritance diagram for amioption:

Public Member Functions

- amioption (matlabtypesubstitute varargin)

  amioptions Construct a new amioptions object OPTS = amioption() creates a set of options with each option set to its default value.

Public Attributes

- matlabtypesubstitute atol = 1e-16

  absolute integration tolerace
- matlabtypesubstitute rtol = 1e-8

  relative integration tolerace
- matlabtypesubstitute maxsteps = 1e4

  maximum number of integration steps
- matlabtypesubstitute quad_atol = 1e-12

  absolute quadrature tolerace
- matlabtypesubstitute quad_rtol = 1e-8

  relative quadrature tolerace
- matlabtypesubstitute maxstepsB = 0

  maximum number of integration steps
- matlabtypesubstitute ss_atol = 1e-16

  absolute steady state tolerace
- matlabtypesubstitute ss_rtol = 1e-8

  relative steady state tolerace
- matlabtypesubstitute sens_ind = double.empty("")

  index of parameters for which the sensitivities are computed
- matlabtypesubstitute tstart = 0

  starting time of the simulation
- matlabtypesubstitute lmm = 2

  linear multistep method.
- matlabtypesubstitute iter = 2

  iteration method for linear multistep.
- matlabtypesubstitute linsol = 9

  linear solver
- matlabtypesubstitute stldet = true

  stability detection flag
- matlabtypesubstitute interpType = 1

  interpolation type
- matlabtypesubstitute ism = 1

  forward sensitivity mode
- matlabtypesubstitute sensi_meth = 1

  sensitivity method
- matlabtypesubstitute sensi = 0

  sensitivity order
- matlabtypesubstitute nmaxevent = 10

  number of reported events
- matlabtypesubstitute ordering = 0

  reordering of states
- matlabtypesubstitute ss = 0

  steady state sensitivity flag
- matlabtypesubstitute x0 = double.empty("")

custom initial state

- matlabtypesubstitute sx0 = double.empty("")

  custom initial sensitivity

- matlabtypesubstitute newton_maxsteps = 40

  newton solver: maximum newton steps

- matlabtypesubstitute newton_maxlinsteps = 100

  newton solver: maximum linear steps

- matlabtypesubstitute newton_preeq = false

  preequilibration of system via newton solver

- matlabtypesubstitute z2event = double.empty("")

  mapping of event ouputs to events

- matlabtypesubstitute pscale = "[ ]"

  parameter scaling Single value or vector matching sens_ind. Valid options are "log","log10" and "lin" for log, log10 or unscaled parameters p. Use [] for default as specified in the model (fallback: `lin`).

10.41.1 Detailed Description

Definition at line 17 of file amioption.m.

10.41.2 Constructor & Destructor Documentation

10.41.2.1 amioption()

```
amioption (
            matlabtypesubstitute varargin )
```

OPTS = amioption(PARAM, VAL, ...) creates a set of options with the named parameters altered with the specified values.

OPTS = amioption(OLDOPTS, PARAM, VAL, ...) creates a copy of OLDOPTS with the named parameters altered with the specified value

Note: to see the parameters, check the documentation page for amioption

Parameters

varargin	input to construct amioption object, see function function description

Definition at line 259 of file amioption.m.

10.41.3 Member Data Documentation

10.41.3.1 atol

```
atol = 1e-16
```

Default: 1e-16

Definition at line 28 of file amioption.m.

10.41.3.2 rtol

```
rtol = 1e-8
```

Default: 1e-8

Definition at line 36 of file amioption.m.

10.41.3.3 maxsteps

```
maxsteps = 1e4
```

Default: 1e4

Definition at line 44 of file amioption.m.

10.41.3.4 quad_atol

```
quad_atol = 1e-12
```

Default: 1e-12

Definition at line 52 of file amioption.m.

10.41.3.5 quad_rtol

```
quad_rtol = 1e-8
```

Default: 1e-8

Definition at line 60 of file amioption.m.

10.41.3.6 maxstepsB

```
maxstepsB = 0
```

Default: 0

Definition at line 68 of file amioption.m.

10.41.3.7 ss_atol

```
ss_atol = 1e-16
```

Default: 1e-16

Definition at line 76 of file amioption.m.

10.41.3.8 ss_rtol

```
ss_rtol = 1e-8
```

Default: 1e-8

Definition at line 84 of file amioption.m.

10.41.3.9 sens_ind

```
sens_ind = double.empty("")
```

Default: double.empty("")

Definition at line 92 of file amioption.m.

10.41.3.10 tstart

```
tstart = 0
```

Default: 0

Definition at line 100 of file amioption.m.

10.41.3.11 lmm

```
lmm = 2
```

Default: 2

Definition at line 108 of file amioption.m.

10.41.3.12 iter

```
iter = 2
```

Default: 2

Definition at line 116 of file amioption.m.

10.41.3.13 linsol

```
linsol = 9
```

Default: 9

Definition at line 124 of file amioption.m.

10.41.3.14 stldet

```
stldet = true
```

Default: true

Definition at line 132 of file amioption.m.

10.41.3.15 interpType

```
interpType = 1
```

Default: 1

Definition at line 140 of file amioption.m.

10.41.3.16 ism

```
ism = 1
```

Default: 1

Definition at line 148 of file amioption.m.

10.41.3.17 sensi_meth

```
sensi_meth = 1
```

Default: 1

Note

This property has custom functionality when its value is changed.

Definition at line 156 of file amioption.m.

10.41.3.18 sensi

```
sensi = 0
```

Default: 0

Note

This property has custom functionality when its value is changed.

Definition at line 164 of file amioption.m.

10.41.3.19 nmaxevent

```
nmaxevent = 10
```

Default: 10

Definition at line 172 of file amioption.m.

10.41.3.20 ordering

```
ordering = 0
```

Default: 0

Definition at line 180 of file amioption.m.

10.41.3.21 ss

```
ss = 0
```

Default: 0

Definition at line 188 of file amioption.m.

10.41.3.22 x0

```
x0 = double.empty("")
```

Default: double.empty("")

Definition at line 196 of file amioption.m.

10.41.3.23 sx0

```
sx0 = double.empty("")
```

Default: double.empty("")

Definition at line 204 of file amioption.m.

10.41.3.24 newton_maxsteps

```
newton_maxsteps = 40
```

Default: 40

Note

This property has custom functionality when its value is changed.

Definition at line 212 of file amioption.m.

10.41.3.25 newton_maxlinsteps

```
newton_maxlinsteps = 100
```

Default: 100

Note

This property has custom functionality when its value is changed.

Definition at line 220 of file amioption.m.

10.41.3.26 newton_preeq

```
newton_preeq = false
```

Default: false

Note

This property has custom functionality when its value is changed.

Definition at line 228 of file amioption.m.

10.41.3.27 z2event

```
z2event = double.empty("")
```

Default: double.empty("")

Definition at line 236 of file amioption.m.

10.41.3.28 pscale

```
pscale = "[]"
```

Default: "[]"

Note

This property has custom functionality when its value is changed.

Definition at line 244 of file amioption.m.

10.42 amised Class Reference

AMISED is a container for SED-ML objects.

Inheritance diagram for amised:

Public Member Functions

- amised (matlabtypesubstitute sedname)

  amised reads in an SEDML document using the JAVA binding of of libSEDML

Public Attributes

- matlabtypesubstitute model = struct("'event',[ ],'sym',[ ]")

  amimodel from the specified model
- matlabtypesubstitute modelname = {""}

  cell array of model identifiers
- matlabtypesubstitute sedml = struct.empty("")

  stores the struct tree from the xml definition
- matlabtypesubstitute outputcount = "[ ]"

  count the number of outputs per model
- matlabtypesubstitute varidx = "[ ]"

  indexes for dataGenerators
- matlabtypesubstitute varsym = sym("[ ]")

  symbolic expressions for variables
- matlabtypesubstitute datasym = sym("[ ]")

  symbolic expressions for data

10.42.1 Detailed Description

Definition at line 17 of file amised.m.

10.42.2 Constructor & Destructor Documentation

10.42.2.1 amised()

```
amised (
            matlabtypesubstitute sedname )
```

Parameters

sedname	name/path of the SEDML document

Definition at line 112 of file amised.m.

Here is the call graph for this function:

10.42.3 Member Data Documentation

10.42.3.1 model

```
model = struct("'event',[],'sym',[]")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: struct("'event',[],'sym',[]")

Definition at line 27 of file amised.m.

10.42.3.2 modelname

```
modelname = {""}
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: {""}

Definition at line 38 of file amised.m.

10.42.3.3 sedml

```
sedml = struct.empty("")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: struct.empty("")

Definition at line 49 of file amised.m.

10.42.3.4 outputcount

```
outputcount = "[]"
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: "[]"

Definition at line 60 of file amised.m.

10.42.3.5 varidx

```
varidx = "[]"
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: "[]"

Definition at line 71 of file amised.m.

10.42.3.6 varsym

```
varsym = sym("[]")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: sym("[]")

Definition at line 82 of file amised.m.

10.42.3.7 datasym

```
datasym = sym("[]")
```

Note

This property has non-standard access specifiers: `SetAccess = Private, GetAccess = Public`
`Matlab documentation of property attributes.`
Default: sym("[]")

Definition at line 93 of file amised.m.

10.43 optsym Class Reference

OPTSYM is an auxiliary class to gain access to the private symbolic property `s` which is necessary to be able to call symobj::optimize on it.

Inheritance diagram for optsym:

Public Member Functions

- optsym (::sym symbol)
  optsym converts the symbolic object into a optsym object
- mlhsInnerSubst<::sym > getoptimized ()
  getoptimized calls symobj::optimize on the optsym object

10.43.1 Detailed Description

Definition at line 17 of file optsym.m.

10.43.2 Constructor & Destructor Documentation

10.43.2.1 optsym()

```
optsym (
            ::sym symbol )
```

Parameters

symbol	symbolic object

Definition at line 32 of file optsym.m.

10.43.3 Member Function Documentation

10.43.3.1 getoptimized()

```
mlhsInnerSubst<::sym > getoptimized ( )
```

Return values

out	optimized symbolic object

Definition at line 42 of file optsym.m.

11 File Documentation

11.1 am_and.m File Reference

am_and is the amici implementation of the symbolic and function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_and (::sym a,::sym b)
  am_and is the amici implementation of the symbolic and function

11.1.1 Function Documentation

11.1.1.1 am_and()

```
mlhsInnerSubst< matlabtypesubstitute > am_and (
            ::sym a,
            ::sym b )
```

Parameters

a	first input parameter
b	second input parameter

Return values

fun	logical value, negative for false, positive for true

Definition at line 17 of file am_and.m.

Here is the call graph for this function:

Here is the caller graph for this function:

11.2 am_eq.m File Reference

am_eq is currently a placeholder that simply produces an error message

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_eq (matlabtypesubstitute varargin)

  am_eq is currently a placeholder that simply produces an error message

11.2.1 Function Documentation

11.2.1.1 am_eq()

```
mlhsInnerSubst< matlabtypesubstitute > am_eq (
            matlabtypesubstitute varargin )
```

Parameters

varargin	elements for chain of equalities

Return values

fun	logical value, negative for false, positive for true

Definition at line 17 of file am_eq.m.

11.3 am_ge.m File Reference

am_ge is the amici implementation of the n-ary mathml greaterorequal function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} >= varargin{2},varargin{2} >= varargin{3},...)

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_ge (::sym varargin)

  am_ge is the amici implementation of the n-ary mathml greaterorequal function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} >= varargin{2},varargin{2} >= varargin{3},...)

11.3.1 Function Documentation

11.3.1.1 am_ge()

```
mlhsInnerSubst< matlabtypesubstitute > am_ge (
            ::sym varargin )
```

Parameters

varargin	chain of input parameters

Return values

fun	a >= b logical value, negative for false, positive for true

Definition at line 17 of file am_ge.m.

Here is the call graph for this function:

11.4 am_gt.m File Reference

am_gt is the amici implementation of the n-ary mathml greaterthan function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} > varargin{2},varargin{2} > varargin{3},...)

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_gt (::sym varargin)

  am_gt is the amici implementation of the n-ary mathml greaterthan function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} > varargin{2},varargin{2} > varargin{3},...)

11.4.1 Function Documentation

11.4.1.1 am_gt()

```
mlhsInnerSubst< matlabtypesubstitute > am_gt (
            ::sym varargin )
```

Parameters

varargin	chain of input parameters

Return values

fun	a > b logical value, negative for false, positive for true

Definition at line 17 of file am_gt.m.

Here is the call graph for this function:

11.5 am_if.m File Reference

am_if is the amici implementation of the symbolic if function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_if (::sym condition,::sym truepart,::sym falsepart)

  am_if is the amici implementation of the symbolic if function

11.5.1 Function Documentation

11.5.1.1 am_if()

```
mlhsInnerSubst< matlabtypesubstitute > am_if (
            ::sym condition,
            ::sym truepart,
            ::sym falsepart )
```

Parameters

condition	logical value
truepart	value if condition is true
falsepart	value if condition is false

Return values

fun	if condition is true truepart, else falsepart

Definition at line 17 of file am_if.m.

Here is the caller graph for this function:

11.6 am_le.m File Reference

am_le is the amici implementation of the n-ary mathml lessorequal function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} <= varargin{2},varargin{2} <= varargin{3},...)

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_le (::sym varargin)

  am_le is the amici implementation of the n-ary mathml lessorequal function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} <= varargin{2},varargin{2} <= varargin{3},...)

11.6.1 Function Documentation

11.6.1.1 am_le()

```
mlhsInnerSubst< matlabtypesubstitute > am_le (
            ::sym varargin )
```

Parameters

varargin	chain of input parameters

Return values

fun	a <= b logical value, negative for false, positive for true

Definition at line 17 of file am_le.m.

Here is the call graph for this function:

11.7 am_lt.m File Reference

am_lt is the amici implementation of the n-ary mathml lessthan function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} < varargin{2},varargin{2} < varargin{3},...)

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_lt (::sym varargin)

  am_lt is the amici implementation of the n-ary mathml lessthan function this is an n-ary function, for more than 2 input parameters it will check whether and(varargin{1} < varargin{2},varargin{2} < varargin{3},...)

11.7.1 Function Documentation

11.7.1.1 am_lt()

```
mlhsInnerSubst< matlabtypesubstitute > am_lt (
            ::sym varargin )
```

Parameters

varargin	chain of input parameters

Return values

fun	a < b logical value, negative for false, positive for true

Definition at line 17 of file am_lt.m.

Here is the call graph for this function:

11.8 am_max.m File Reference

am_max is the amici implementation of the symbolic max function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_max (::sym a,::sym b)

  am_max is the amici implementation of the symbolic max function

11.8.1 Function Documentation

11.8.1.1 am_max()

```
mlhsInnerSubst< matlabtypesubstitute > am_max (
            ::sym a,
            ::sym b )
```

Parameters

a	first input parameter
b	second input parameter

Return values

fun	maximum of a and b

Definition at line 17 of file am_max.m.

Here is the caller graph for this function:

11.9 am_min.m File Reference

am_min is the amici implementation of the symbolic min function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_min (::sym a,::sym b)

  am_min is the amici implementation of the symbolic min function

11.9.1 Function Documentation

11.9.1.1 am_min()

```
mlhsInnerSubst< matlabtypesubstitute > am_min (
            ::sym a,
            ::sym b )
```

Parameters

a	first input parameter
b	second input parameter

Return values

fun	minimum of a and b

Definition at line 17 of file am_min.m.

Here is the call graph for this function:

Here is the caller graph for this function:

11.10 am_or.m File Reference

am_or is the amici implementation of the symbolic or function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_or (::sym a,::sym b)

  am_or is the amici implementation of the symbolic or function

11.10.1 Function Documentation

11.10.1.1 am_or()

```
mlhsInnerSubst< matlabtypesubstitute > am_or (
            ::sym a,
            ::sym b )
```

Parameters

a	first input parameter
b	second input parameter

Return values

fun	logical value, negative for false, positive for true

Definition at line 17 of file am_or.m.

Here is the call graph for this function:

Here is the caller graph for this function:

11.11 am_piecewise.m File Reference

am_piecewise is the amici implementation of the mathml piecewise function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_piecewise (matlabtypesubstitute piece, matlabtypesubstitute condition, matlabtypesubstitute default)

  am_piecewise is the amici implementation of the mathml piecewise function

11.11.1 Function Documentation

11.11.1.1 am_piecewise()

```
mlhsInnerSubst< matlabtypesubstitute > am_piecewise (
            matlabtypesubstitute piece,
            matlabtypesubstitute condition,
            matlabtypesubstitute default )
```

Parameters

piece	value if condition is true
condition	logical value
default	value if condition is false

Return values

fun	return value, piece if condition is true, default if not

Definition at line 17 of file am_piecewise.m.

Here is the call graph for this function:

11.12 am_stepfun.m File Reference

am_stepfun is the amici implementation of the step function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_stepfun (::sym t, matlabtypesubstitute tstart, matlabtypesubstitute vstart, matlabtypesubstitute tend, matlabtypesubstitute vend)

  am_stepfun is the amici implementation of the step function

11.12.1 Function Documentation

11.12.1.1 am_stepfun()

```
mlhsInnerSubst< matlabtypesubstitute > am_stepfun (
            ::sym t,
            matlabtypesubstitute tstart,
            matlabtypesubstitute vstart,
            matlabtypesubstitute tend,
            matlabtypesubstitute vend )
```

Parameters

t	input variable
tstart	input variable value at which the step starts
vstart	value during the step
tend	input variable value at which the step end
vend	value after the step

Return values

fun	0 before tstart, vstart between tstart and tend and vend after tend

Definition at line 17 of file am_stepfun.m.

11.13 am_xor.m File Reference

am_xor is the amici implementation of the symbolic exclusive or function

Functions

- mlhsInnerSubst< matlabtypesubstitute > am_xor (::sym a,::sym b)

  am_xor is the amici implementation of the symbolic exclusive or function

11.13.1 Function Documentation

11.13.1.1 am_xor()

```
mlhsInnerSubst< matlabtypesubstitute > am_xor (
            ::sym a,
            ::sym b )
```

Parameters

a	first input parameter
b	second input parameter

Return values

fun	logical value, negative for false, positive for true

Definition at line 17 of file am_xor.m.

Here is the call graph for this function:

11.14 amici.cpp File Reference

core routines for integration

```
#include "amici/amici.h"
#include "amici/backwardproblem.h"
#include "amici/forwardproblem.h"
#include "amici/misc.h"
#include <sundials/sundials_types.h>
#include <cvodes/cvodes.h>
#include <type_traits>
#include <cassert>
#include <cstdlib>
#include <cstring>
#include <cstdarg>
#include <memory>
```

Include dependency graph for amici.cpp:

Namespaces

- amici

  The AMICI Python module (in doxygen this will also contain documentation about the C++ library)

Functions

- std::unique_ptr< ReturnData > runAmiciSimulation (Solver &solver, const ExpData *edata, Model &model)
- void printErrMsgIdAndTxt (const char *identifier, const char *format,...)
- void printWarnMsgIdAndTxt (const char *identifier, const char *format,...)
- std::vector< std::unique_ptr< ReturnData > > runAmiciSimulations (Solver const &solver, const std::vector< ExpData * > &edatas, Model const &model, int num_threads)

11.15 amiwrap.m File Reference

AMIWRAP generates c++ mex files for the simulation of systems of differential equations via CVODES and IDAS.

Functions

- noret::substitute amiwrap (matlabtypesubstitute varargin)

  AMIWRAP generates c++ mex files for the simulation of systems of differential equations via CVODES and IDAS.

11.15.1 Function Documentation

11.15.1.1 amiwrap()

```
noret::substitute amiwrap (
            matlabtypesubstitute varargin )
```

Parameters

varargin	`amiwrap ( modelname, symfun, tdir, o2flag )` *Required Parameters for varargin:* • modelname specifies the name of the model which will be later used for the naming of the simulation file • symfun specifies a function which executes model definition see MATLAB Interface for details • tdir target directory where the simulation file should be placed **Default:** $AMICIDIR/models/modelname • o2flag boolean whether second order sensitivities should be enabled **Default:** false

Return values

o2flag	void

Definition at line 17 of file amiwrap.m.

11.16 cblas.cpp File Reference

BLAS routines required by AMICI.

```
#include "amici/cblas.h"
```

Include dependency graph for cblas.cpp:

Namespaces

- amici

  The AMICI Python module (in doxygen this will also contain documentation about the C++ library)

Functions

- void amici_dgemm (BLASLayout layout, BLASTranspose TransA, BLASTranspose TransB, const int M, const int N, const int K, const double alpha, const double ∗A, const int lda, const double ∗B, const int ldb, const double beta, double ∗C, const int ldc)
- void amici_dgemv (BLASLayout layout, BLASTranspose TransA, const int M, const int N, const double alpha, const double ∗A, const int lda, const double ∗X, const int incX, const double beta, double ∗Y, const int incY)
- void amici_daxpy (int n, double alpha, const double ∗x, const int incx, double ∗y, int incy)

  Compute y = a∗x + y.

11.17 interface_matlab.cpp File Reference

core routines for mex interface

```
#include "amici/interface_matlab.h"
#include "amici/model.h"
#include "amici/exception.h"
#include "amici/edata.h"
#include "amici/returndata_matlab.h"
#include <assert.h>
#include <blas.h>
```

```
#include <cstring>
#include <memory>
```

Include dependency graph for interface_matlab.cpp:

Namespaces

- amici

  The AMICI Python module (in doxygen this will also contain documentation about the C++ library)

Enumerations

- enum mexRhsArguments {
  RHS_TIMEPOINTS, **RHS_PARAMETERS**, **RHS_CONSTANTS**, **RHS_OPTIONS**, **RHS_PLIST**, **RHS_XSCALE_UNUSED**, **RHS_INITIALIZATION**, **RHS_DATA**, **RHS_NUMARGS_REQUIRED** = RHS_DATA, **RHS_NUMARGS** }

  The mexFunctionArguments enum takes care of the ordering of mex file arguments (indexing in prhs)

Functions

- int dbl2int (const double x)
- char amici_blasCBlasTransToBlasTrans (BLASTranspose trans)
- void amici_dgemm (BLASLayout layout, BLASTranspose TransA, BLASTranspose TransB, const int M, const int N, const int K, const double alpha, const double ∗A, const int lda, const double ∗B, const int ldb, const double beta, double ∗C, const int ldc)
- void amici_dgemv (BLASLayout layout, BLASTranspose TransA, const int M, const int N, const double alpha, const double ∗A, const int lda, const double ∗X, const int incX, const double beta, double ∗Y, const int incY)
- void amici_daxpy (int n, double alpha, const double ∗x, const int incx, double ∗y, int incy)

  Compute y = a∗x + y.
- std::vector< realtype > mxArrayToVector (const mxArray ∗array, int length)
- std::unique_ptr< ExpData > expDataFromMatlabCall (const mxArray ∗prhs[ ], const Model &model)
- void setSolverOptions (const mxArray ∗prhs[ ], int nrhs, Solver &solver)

  setSolverOptions solver options from the matlab call to a solver object
- void setModelData (const mxArray ∗prhs[ ], int nrhs, Model &model)

  setModelData sets data from the matlab call to the model object
- void mexFunction (int nlhs, mxArray ∗plhs[ ], int nrhs, const mxArray ∗prhs[ ])

11.17.1 Detailed Description

This file defines the fuction mexFunction which is executed upon calling the mex file from matlab

11.17.2 Function Documentation

11.17.2.1 mexFunction()

```
void mexFunction (
            int nlhs,
            mxArray * plhs[],
            int nrhs,
            const mxArray * prhs[] )
```

mexFunction is the main interface function for the MATLAB interface. It reads in input data (udata and edata) and creates output data compound (rdata) and then calls the AMICI simulation routine to carry out numerical integration.

Parameters

nlhs	number of output arguments of the matlab call
plhs	pointer to the array of output arguments
nrhs	number of input arguments of the matlab call
prhs	pointer to the array of input arguments

Returns

void

Definition at line 525 of file interface_matlab.cpp.

Here is the call graph for this function:

11.18 SBML2AMICI.m File Reference

SBML2AMICI generates AMICI model definition files from SBML.

Functions

- noret::substitute SBML2AMICI (matlabtypesubstitute filename, matlabtypesubstitute modelname)

  SBML2AMICI generates AMICI model definition files from SBML.

11.18.1 Function Documentation

11.18.1.1 SBML2AMICI()

```
noret::substitute SBML2AMICI (
            matlabtypesubstitute filename,
            matlabtypesubstitute modelname )
```

Parameters

filename	name of the SBML file (withouth extension)
modelname	name of the model, this will define the name of the output file (default: input filename)

Return values

modelname	void

Definition at line 17 of file SBML2AMICI.m.

Here is the caller graph for this function:

11.19 spline.cpp File Reference

definition of spline functions

Namespaces

- amici

  The AMICI Python module (in doxygen this will also contain documentation about the C++ library)

Functions

- int spline (int n, int end1, int end2, double slope1, double slope2, double x[ ], double y[ ], double b[ ], double c[ ], double d[ ])
- double seval (int n, double u, double x[ ], double y[ ], double b[ ], double c[ ], double d[ ])

  Evaluate the cubic spline function.
- double sinteg (int n, double u, double x[ ], double y[ ], double b[ ], double c[ ], double d[ ])

11.19.1 Detailed Description

Author

Peter & Nigel, Design Software, 42 Gubberley St, Kenmore, 4069, Australia.

11.20 symbolic_functions.cpp File Reference

definition of symbolic functions

```
#include "amici/symbolic_functions.h"
#include "amici/spline.h"
#include <algorithm>
#include <cfloat>
#include <cmath>
#include <cstdarg>
#include <cstdlib>
#include <alloca.h>
```

Include dependency graph for symbolic_functions.cpp:

Namespaces

- amici

  The AMICI Python module (in doxygen this will also contain documentation about the C++ library)

Functions

- int isNaN (double what)
- int isInf (double what)
- double getNaN ()
- double log (double x)
- double dirac (double x)
- double heaviside (double x)
- double sign (double x)
- double max (double a, double b, double c)
- double min (double a, double b, double c)
- double Dmax (int id, double a, double b, double c)
- double Dmin (int id, double a, double b, double c)
- double pos_pow (double base, double exponent)
- double spline (double t, int num,...)
- double spline_pos (double t, int num,...)
- double Dspline (int id, double t, int num,...)
- double Dspline_pos (int id, double t, int num,...)
- double DDspline (int id1, int id2, double t, int num,...)
- double DDspline_pos (int id1, int id2, double t, int num,...)

11.20.1 Detailed Description

This file contains definitions of various symbolic functions which

Index

__init__
    ConservationLaw, 380
    Constant, 381
    Expression, 382
    LogLikelihood, 384
    ModelQuantity, 385
    Observable, 387
    ODEExporter, 389
    ODEModel, 394
    Parameter, 410
    SbmlImporter, 436
    SigmaY, 411
    State, 413
__repr__
    ModelQuantity, 386
~Model
    Model, 169

add_component
    ODEModel, 395
add_conservation_law
    ODEModel, 396
adjInit
    Solver, 497
adjoint
    amimodel, 554
allocateSolver
    Solver, 491
allocateSolverB
    Solver, 497
am_and
    am_and.m, 576
am_and.m, 576
    am_and, 576
am_eq
    am_eq.m, 578
am_eq.m, 577
    am_eq, 578
am_ge
    am_ge.m, 578
am_ge.m, 578
    am_ge, 578
am_gt
    am_gt.m, 579
am_gt.m, 579
    am_gt, 579
am_if
    am_if.m, 580
am_if.m, 580
    am_if, 580
am_le
    am_le.m, 581
am_le.m, 581
    am_le, 581
am_lt
    am_lt.m, 582
am_lt.m, 582
    am_lt, 582
am_max
    am_max.m, 583
am_max.m, 583
    am_max, 583
am_min
    am_min.m, 584
am_min.m, 584
    am_min, 584
am_or
    am_or.m, 585
am_or.m, 585
    am_or, 585
am_piecewise
    am_piecewise.m, 586
am_piecewise.m, 586
    am_piecewise, 586
am_stepfun
    am_stepfun.m, 587
am_stepfun.m, 587
    am_stepfun, 587
am_xor
    am_xor.m, 588
am_xor.m, 588
    am_xor, 588
amici, 14
    amici_blasCBlasTransToBlasTrans, 72
    amici_daxpy, 28
    amici_dgemm, 26
    amici_dgemv, 25
    amici_path, 76
    BLASLayout, 20
    BLASTranspose, 20
    checkFieldNames, 47
    checkFinite, 33
    checkSigmaPositivity, 29
    dbl2int, 72
    DDspline, 68
    DDspline_pos, 68
    deserializeFromChar, 49
    deserializeFromString, 50
    dirac, 56
    Dmax, 59
    Dmin, 58
    Dspline, 66
    Dspline_pos, 67
    errMsgIdAndTxt, 76
    ExpData, 70
    expDataFromMatlabCall, 32
    getNaN, 63
    getReturnDataMatlabFromAmiciCall, 38
    getScaledParameter, 36
    getUnscaledParameter, 35

getValueById, 73
heaviside, 56
initAndAttachArray, 46
initMatlabDiagnosisFields, 40
initMatlabReturnFields, 39
InternalSensitivityMethod, 21
InterpolationType, 21
isInf, 62
isNaN, 61
LinearMultistepMethod, 21
LinearSolver, 21
log, 55
max, 58
min, 57
msgIdAndTxtFp, 19
mxArrayToVector, 73
NewtonStatus, 22
NonlinearSolverIteration, 21
operator==, 38, 51
ParameterScaling, 20
pi, 76
pos_pow, 60
printErrMsgIdAndTxt, 22
printWarnMsgIdAndTxt, 23
realtype, 19
reorder, 48
runAmiciSimulation, 23, 69
runAmiciSimulations, 24, 71
scaleParameters, 37
SecondOrderMode, 20
SensitivityMethod, 20
SensitivityOrder, 20
serializeToChar, 49
serializeToStdVec, 50
serializeToString, 50
setModelData, 30
setSolverOptions, 30
setupReturnData, 31
setValueById, 74
setValueByIdRegex, 75
seval, 53
sign, 64
sinteg, 54
spline, 51, 64
spline_pos, 65
StateOrdering, 22
SteadyStateSensitivityMode, 22
unscaleParameters, 34, 35
warnMsgIdAndTxt, 76
writeMatlabField0, 41
writeMatlabField1, 42
writeMatlabField2, 43
writeMatlabField3, 44
writeMatlabField4, 45
amici.cpp, 589
amici.ode_export, 77
applyTemplate, 80
functions, 83
get_function_definition, 81
get_function_implementation, 82
getSymbolicDiagonal, 79
multiobs_functions, 84
remove_typedefs, 82
sanitize_basic_sympy, 80
sensi_functions, 84
sparse_functions, 83
symbol_to_type, 84
var_in_function_signature, 78
amici.plotting, 85
plotObservableTrajectories, 85
plotStateTrajectories, 85
amici.sbml_import, 86
assignmentRules2observables, 87
checkLibSBMLErrors, 89
constantSpeciesToParameters, 87
default_symbols, 89
getRuleVars, 86
l2s, 88
replaceLogAB, 88
amici_blasCBlasTransToBlasTrans
amici, 72
amici_daxpy
amici, 28
amici_dgemm
amici, 26
amici_dgemv
amici, 25
amici_path
amici, 76
amidata, 524
amidata, 525
condition, 528
conditionPreequilibration, 528
ne, 526
nk, 527
nt, 526
ny, 526
nz, 526
Sigma_Y, 527
Sigma_Z, 528
t, 527
Y, 527
Z, 528
amievent, 529
amievent, 529
bolus, 531
hflag, 531
setHflag, 530
trigger, 530
z, 531
AmiException, 90
AmiException, 91
getBacktrace, 92
storeBacktrace, 92
what, 91
amifun, 532

amifun, 533
argstr, 538
cvar, 538
deps, 538
funstr, 538
gccode, 534
getArgs, 535
getCVar, 536
getDeps, 535
getNVecs, 536
getSensiFlag, 536
getSyms, 536
nvecs, 538
sensiflag, 539
strsym, 537
strsym_old, 537
sym, 537
sym_noopt, 537
writeCcode, 534
writeCcode_sensi, 533
writeMcode, 534
amimodel, 539
adjoint, 554
amimodel, 542
augmento2, 549
augmento2vec, 550
cfun, 561
checkDeps, 548
colptrs, 559
colptrsB, 559
compileAndLinkModel, 550
compileC, 545
coptim, 560
debug, 553
event, 553
forward, 554
fun, 552
funs, 560
generateC, 544
generateM, 545
generateMatlabWrapper, 551
getFun, 546
HTable, 553
id, 557
lbw, 558
loadOldHashes, 549
makeEvents, 547
makeSyms, 547
maxflag, 562
mfuns, 560
minflag, 562
modelname, 553
ndwdp, 563
ndwdx, 563
nevent, 556
ng, 556
nk, 556
nnz, 558
np, 556
nw, 562
nx, 555
nxtrue, 555
ny, 555
nytrue, 555
nz, 557
nztrue, 557
o2flag, 561
param, 560
parseModel, 544
recompile, 561
rowvals, 558
rowvalsB, 559
sparseidx, 558
sparseidxB, 559
splineflag, 562
sym, 552
t0, 554
ubw, 557
updateModelName, 543
updateRHS, 543
updateWrapPath, 544
wrap_path, 561
wtype, 554
z2event, 562
amioption, 563
amioption, 565
atol, 565
interpType, 568
ism, 568
iter, 568
linsol, 568
lmm, 567
maxsteps, 566
maxstepsB, 566
newton_maxlinsteps, 570
newton_maxsteps, 570
newton_preeq, 571
nmaxevent, 569
ordering, 569
pscale, 571
quad_atol, 566
quad_rtol, 566
rtol, 566
sens_ind, 567
sensi, 569
sensi_meth, 569
ss, 570
ss_atol, 567
ss_rtol, 567
stldet, 568
sx0, 570
tstart, 567
x0, 570
z2event, 571
amised, 572
amised, 572

datasym, 574
model, 573
modelname, 573
outputcount, 574
sedml, 573
varidx, 574
varsym, 574
AmiVector, 93
AmiVector, 93, 94
at, 102, 104
data, 95, 96
getLength, 99
getNVector, 97
getVector, 98
minus, 101
operator=, 94
operator[], 102
reset, 100
set, 101
AmiVectorArray, 104
AmiVectorArray, 104, 106
at, 107, 108
data, 106, 107
flatten_to_vector, 110
getLength, 110
getNVector, 109
getNVectorArray, 108
operator[], 109
reset, 110
amiwrap
amiwrap.m, 590
amiwrap.m, 590
amiwrap, 590
anyStateNonNegative
Model, 299
applyChainRuleFactorToSimulationResults
ReturnData, 420
applyDataDimension
ExpData, 142
applyDimensions
ExpData, 142
applyEventDimension
ExpData, 143
applyNewtonsMethod
SteadystateProblem, 521
applyQuadTolerancesASA
Solver, 514
applySensitivityTolerances
Solver, 514
applyTemplate
amici.ode_export, 80
applyTolerances
Solver, 512
applyTolerancesASA
Solver, 513
applyTolerancesFSA
Solver, 512
argstr
amifun, 538
assignmentRules2observables
amici.sbml_import, 87
at
AmiVector, 102, 104
AmiVectorArray, 107, 108
atol
amioption, 565
NewtonSolver, 368
augmento2
amimodel, 549
augmento2vec
amimodel, 550

BackwardProblem, 111
BackwardProblem, 111
getdJydx, 115
getdxBptr, 115
gett, 112
getwhich, 113
getwhichptr, 113
getxBptr, 114
getxQBptr, 114
workBackwardProblem, 112
band
Solver, 500
bandB
Solver, 501
binit
Solver, 486
BLASLayout
amici, 20
BLASTranspose
amici, 20
bolus
amievent, 531
boost::serialization::serialize
Model, 285
ReturnData, 421
Solver, 515

calcIC
Solver, 459
calcICB
Solver, 459
cblas.cpp, 590
cfun
amimodel, 561
checkConvergence
SteadystateProblem, 520
checkDataDimension
ExpData, 144
checkDeps
amimodel, 548
checkEventsDimension
ExpData, 144
checkFieldNames
amici, 47
checkFinite

amici, 33
Model, 237
checkLibSBMLErrors
amici.sbml_import, 89
checkSigmaPositivity
amici, 29
checkSupport
SbmlImporter, 440
chi2
ReturnData, 429
cleanReservedSymbols
SbmlImporter, 446
clone
Model, 169
Solver, 453
colptr
ODEModel, 403
colptrs
amimodel, 559
colptrsB
amimodel, 559
compileAndLinkModel
amimodel, 550
compileC
amimodel, 545
compileModel
ODEExporter, 390
computeNewtonSensis
NewtonSolver, 366
computeX_pos
Model, 283
condition
amidata, 528
conditionPreequilibration
amidata, 528
ConservationLaw, 379
__init__, 380
Constant, 380
__init__, 381
constantSpeciesToParameters
amici.sbml_import, 87
coptim
amimodel, 560
createSteadystateSimSolver
SteadystateProblem, 523
cvar
amifun, 538
CvodeException, 116
CvodeException, 117

data
AmiVector, 95, 96
AmiVectorArray, 106, 107
datasym
amised, 574
dbl2int
amici, 72
DDspline
amici, 68
DDspline_pos
amici, 68
debug
amimodel, 553
default_symbols
amici.sbml_import, 89
deltaqB
Model, 292
deltasx
Model, 291
deltax
Model, 291
deltaxB
Model, 291
dense
Solver, 498
denseB
Solver, 500
deps
amifun, 538
deserializeFromChar
amici, 49
deserializeFromString
amici, 50
diag
Solver, 501
diagB
Solver, 502
dirac
amici, 56
dJrzdsigma
Model, 294
dJrzdz
Model, 293
dJydp
Model, 291
dJydsigma
Model, 293
dJydy
Model, 293
dJzdp
Model, 291
dJzdsigma
Model, 293
dJzdz
Model, 293
Dmax
amici, 59
Dmin
amici, 58
drzdp
Model, 294
drzdx
Model, 294
dsigmaydp
Model, 290
dsigmazdp
Model, 290

Dspline
amici, 66
Dspline_pos
amici, 67
dwdp
Model, 295
dwdx
Model, 295
dx
NewtonSolver, 370
dxdotdp
Model, 292
dydp
Model, 295
dydx
Model, 295
dzdp
Model, 294
dzdx
Model, 294

edata
ForwardProblem, 154
eq
ODEModel, 401
errMsgIdAndTxt
amici, 76
error_code
IntegrationFailure, 157
IntegrationFailureB, 158
NewtonFailure, 363
event
amimodel, 553
ExpData, 117
amici, 70
applyDataDimension, 142
applyDimensions, 142
applyEventDimension, 143
checkDataDimension, 144
checkEventsDimension, 144
ExpData, 119–123
fixedParameters, 145
fixedParametersPreequilibration, 145
fixedParametersPresimulation, 145
getObservedData, 129
getObservedDataPtr, 129
getObservedDataStdDev, 134
getObservedDataStdDevPtr, 134
getObservedEvents, 137
getObservedEventsPtr, 137
getObservedEventsStdDev, 141
getObservedEventsStdDevPtr, 141
getTimepoint, 126
getTimepoints, 126
isSetObservedData, 128
isSetObservedDataStdDev, 132
isSetObservedEvents, 136
isSetObservedEventsStdDev, 140
nmaxevent, 124
nmaxevent_, 146
nt, 124
nytrue, 123
nytrue_, 146
nztrue, 124
nztrue_, 146
observedData, 146
observedDataStdDev, 147
observedEvents, 147
observedEventsStdDev, 147
setObservedData, 127
setObservedDataStdDev, 130–132
setObservedEvents, 135, 136
setObservedEventsStdDev, 138–140
setTimepoints, 125
ts, 146
expDataFromMatlabCall
amici, 32
Expression, 382
__init__, 382

fchi2
Model, 235
fdeltaqB
Model, 193, 268
fdeltasx
Model, 192, 267
fdeltax
Model, 191, 266
fdeltaxB
Model, 192, 268
fdJrzdsigma
Model, 202, 275
fdJrzdz
Model, 202, 274
fdJydp
Model, 205
fdJydsigma
Model, 200, 273
fdJydx
Model, 206
fdJydy
Model, 199, 272
fdJzdp
Model, 207
fdJzdsigma
Model, 201, 274
fdJzdx
Model, 208
fdJzdz
Model, 200, 273
fdrzdp
Model, 190, 265
fdrzdx
Model, 190, 266
fdsigmaydp
Model, 195, 269
fdsigmazdp
Model, 196, 270

fdwdp
Model, 231, 276
fdwdx
Model, 232, 276
fdx0
Model, 179
fdxdotdp
Model, 173
Model_DAE, 318, 319, 330
Model_ODE, 351, 360
fdydp
Model, 183, 261
fdydx
Model, 184, 262
fdzdp
Model, 188, 264
fdzdx
Model, 189, 265
fFIM
Model, 236
FIM
ReturnData, 425
fixedParameters
ExpData, 145
Model, 297
fixedParametersPreequilibration
ExpData, 145
fixedParametersPresimulation
ExpData, 145
fJ
Model, 171
Model_DAE, 303, 304, 323
Model_ODE, 335, 336, 354
fJB
Model_DAE, 305, 324
Model_ODE, 337, 355
fJDiag
Model, 173
Model_DAE, 309, 325
Model_ODE, 341, 342, 356
fJrz
Model, 199, 272
fJSparse
Model, 172
Model_DAE, 306, 307, 324
Model_ODE, 338, 339, 355
fJSparseB
Model_DAE, 308, 325
Model_ODE, 340, 356
fJv
Model, 174
Model_DAE, 310, 311, 326
Model_ODE, 343, 344, 357
fJvB
Model_DAE, 312, 327
Model_ODE, 345, 358
fJy
Model, 197, 271
fJz
Model, 198, 271
flatten_to_vector
AmiVectorArray, 110
fM
Model_DAE, 322, 331
forward
amimodel, 554
ForwardProblem, 147
edata, 154
ForwardProblem, 148
getDiscontinuities, 151
getDJydx, 151
getDJzdx, 151
getNumberOfRoots, 150
getRHSAtDiscontinuities, 150
getRHSBeforeDiscontinuities, 150
getRootCounter, 152
getRootIndexes, 151
getStateDerivativePointer, 152
getStateDerivativeSensitivityPointer, 153
getStatePointer, 152
getStatesAtDiscontinuities, 150
getStateSensitivity, 149
getStateSensitivityPointer, 153
getTime, 149
model, 153
rdata, 153
solver, 154
workForwardProblem, 149
fqBdot
Model_DAE, 317, 329
Model_ODE, 350, 360
fres
Model, 234
froot
Model, 170
Model_DAE, 313, 314, 328
Model_ODE, 346, 347, 358
frz
Model, 186, 263
fsdx0
Model, 181
fsigmay
Model, 194, 269
fsigmaz
Model, 195, 270
fsJy
Model, 204
fsJz
Model, 207
fsres
Model, 235
fsrz
Model, 187, 264
fstau
Model, 181, 260
fstotal_cl

Model, 257
fsx0
Model, 179, 259
fsx0_fixedParameters
Model, 180, 259
fsx_rdata
Model, 176, 255
fsx_solver
Model, 256
fsxdot
Model, 171
Model_DAE, 320, 321, 330
Model_ODE, 352, 353, 361
fsy
Model, 203
fsz
Model, 185, 263
fsz_tf
Model, 204
ftotal_cl
Model, 257
fun
amimodel, 552
functions
amici.ode_export, 83
funs
amimodel, 560
funstr
amifun, 538
fw
Model, 230, 275
fx0
Model, 177, 258
fx0_fixedParameters
Model, 178, 259
fx_rdata
Model, 175, 254
fx_solver
Model, 255
fxBdot
Model_DAE, 316, 329
Model_ODE, 349, 359
fxdot
Model, 170
Model_DAE, 314, 315, 328
Model_ODE, 347, 348, 359
fy
Model, 182, 260
fz
Model, 185, 262

gccode
amifun, 534
generateBasicVariables
ODEModel, 405
generateC
amimodel, 544
generateM
amimodel, 545
generateMatlabWrapper
amimodel, 551
generateModelCode
ODEExporter, 390
get_conservation_laws
ODEModel, 408
get_dt
State, 415
get_function_definition
amici.ode_export, 81
get_function_implementation
amici.ode_export, 82
get_id
ModelQuantity, 386
get_name
ModelQuantity, 386
get_val
ModelQuantity, 386
getAbsoluteTolerance
Solver, 469
getAbsoluteToleranceQuadratures
Solver, 473
getAbsoluteToleranceSensi
Solver, 471
getAbsoluteToleranceSteadyState
Solver, 475
getAbsoluteToleranceSteadyStateSensi
Solver, 477
getAdjBmem
Solver, 511
getAdjMallocDone
Solver, 511
getAmiciCommit
Model, 239
getAmiciVersion
Model, 238
getArgs
amifun, 535
getB
Solver, 462
getBacktrace
AmiException, 92
getCVar
amifun, 536
getDeps
amifun, 535
getDiagnosis
Solver, 457
getDiagnosisB
Solver, 457
getDiscontinuities
ForwardProblem, 151
getDJydx
ForwardProblem, 151
getdJydx
BackwardProblem, 115
getDJzdx
ForwardProblem, 151

getDky
Solver, 497
getdxBptr
BackwardProblem, 115
getFixedParameterById
Model, 219
getFixedParameterByName
Model, 220
getFixedParameterIds
Model, 251
getFixedParameterNames
Model, 242
getFixedParameters
Model, 219
getFun
amimodel, 546
getInitialStates
Model, 226
getInitialStateSensitivities
Model, 227
getInternalSensitivityMethod
Solver, 485
getInterpolationType
Solver, 481
getLastOrder
Solver, 507
getLength
AmiVector, 99
AmiVectorArray, 110
getLinearMultistepMethod
Solver, 480
getLinearSolver
Solver, 484
getMallocDone
Solver, 511
getMaxSteps
Solver, 478
getMaxStepsBackwardProblem
Solver, 479
getModel
Solver, 510
getmy
Model, 277
getmz
Model, 278
getNaN
amici, 63
getNewtonMaxLinearSteps
Solver, 465
getNewtonMaxSteps
Solver, 464
getNewtonPreequilibration
Solver, 465
getNonlinearSolverIteration
Solver, 481
getNumberOfRoots
ForwardProblem, 150
getNumErrTestFails
Solver, 506
getNumNonlinSolvConvFails
Solver, 507
getNumRhsEvals
Solver, 506
getNumSteps
Solver, 505
getNVecs
amifun, 536
getNVector
AmiVector, 97
AmiVectorArray, 109
getNVectorArray
AmiVectorArray, 108
getObservableIds
Model, 252
getObservableNames
Model, 243
getObservedData
ExpData, 129
getObservedDataPtr
ExpData, 129
getObservedDataStdDev
ExpData, 134
getObservedDataStdDevPtr
ExpData, 134
getObservedEvents
ExpData, 137
getObservedEventsPtr
ExpData, 137
getObservedEventsStdDev
ExpData, 141
getObservedEventsStdDevPtr
ExpData, 141
getoptimized
optsym, 576
getParameterById
Model, 245
getParameterByName
Model, 246
getParameterIds
Model, 245
getParameterList
Model, 225
getParameterNames
Model, 240
getParameters
Model, 218
getParameterScale
Model, 217
getQuadB
Solver, 462
getReinitializeFixedParameterInitialStates
Model, 254
getRelativeTolerance
Solver, 468
getRelativeToleranceQuadratures
Solver, 472

getRelativeToleranceSensi
Solver, 470
getRelativeToleranceSteadyState
Solver, 474
getRelativeToleranceSteadyStateSensi
Solver, 476
getReturnDataMatlabFromAmiciCall
amici, 38
getRHSAtDiscontinuities
ForwardProblem, 150
getRHSBeforeDiscontinuities
ForwardProblem, 150
getRootCounter
ForwardProblem, 152
getRootIndexes
ForwardProblem, 151
getRootInfo
Solver, 458
getRuleVars
amici.sbml_import, 86
getrz
Model, 281
getScaledParameter
amici, 36
getSens
Solver, 456
getSensiFlag
amifun, 536
getSensitivityMethod
Solver, 463
getSensitivityOrder
Solver, 466
getSolver
Model, 169
Model_DAE, 323
Model_ODE, 354
NewtonSolver, 364
getsrz
Model, 282
getStabilityLimitFlag
Solver, 483
getStateDerivativePointer
ForwardProblem, 152
getStateDerivativeSensitivityPointer
ForwardProblem, 153
getStateIds
Model, 250
getStateIsNonNegative
Model, 224
getStateNames
Model, 241
getStateOrdering
Solver, 482
getStatePointer
ForwardProblem, 152
getStatesAtDiscontinuities
ForwardProblem, 150
getStateSensitivity
ForwardProblem, 149
getStateSensitivityPointer
ForwardProblem, 153
getSteadyStateSensitivityMode
Model, 253
getSteadystateSimulation
SteadystateProblem, 522
getStep
NewtonSolver, 365
getSymbolicDiagonal
amici.ode_export, 79
getSyms
amifun, 536
getsz
Model, 282
gett
BackwardProblem, 112
Model, 237
getTime
ForwardProblem, 149
getTimepoint
ExpData, 126
getTimepoints
ExpData, 126
Model, 223
getUnscaledParameter
amici, 35
getUnscaledParameters
Model, 218
getValueById
amici, 73
getVector
AmiVector, 98
getwhich
BackwardProblem, 113
getwhichptr
BackwardProblem, 113
getWrmsNorm
SteadystateProblem, 519
getxBptr
BackwardProblem, 114
getxQBptr
BackwardProblem, 114
gety
Model, 279
getz
Model, 280

h
Model, 297
hasFixedParameterIds
Model, 250
hasFixedParameterNames
Model, 241
hasObservableIds
Model, 252
hasObservableNames
Model, 243
hasParameterIds

Model, 244
hasParameterNames
Model, 239
hasStateIds
Model, 249
hasStateNames
Model, 240
heaviside
amici, 56
hflag
amievent, 531
HTable
amimodel, 553

id
amimodel, 557
IDAException, 154
IDAException, 155
idlist
Model, 290
import_from_sbml_importer
ODEModel, 394
init
Solver, 486
initAndAttachArray
amici, 46
initHeaviside
Model, 212
initialize
Model, 209
initializeLinearSolver
Solver, 508
initializeLinearSolverB
Solver, 509
initializeStates
Model, 210
initializeStateSensitivities
Model, 211
initMatlabDiagnosisFields
amici, 40
initMatlabReturnFields
amici, 39
IntegrationFailure, 155
error_code, 157
IntegrationFailure, 156
time, 157
IntegrationFailureB, 157
error_code, 158
IntegrationFailureB, 158
time, 158
interface_matlab.cpp, 591
mexFunction, 593
InternalSensitivityMethod
amici, 21
InterpolationType
amici, 21
interpType
amioption, 568
Solver, 517
invalidate
ReturnData, 419
invalidateLLH
ReturnData, 420
isFixedParameterStateReinitializationAllowed
Model, 283
isInf
amici, 62
ism
amioption, 568
Solver, 516
isNaN
amici, 61
isSetObservedData
ExpData, 128
isSetObservedDataStdDev
ExpData, 132
isSetObservedEvents
ExpData, 136
isSetObservedEventsStdDev
ExpData, 140
iter
amioption, 568
Solver, 517

J
Model, 292
ReturnData, 422

k
Model, 215
klu
Solver, 504
kluB
Solver, 505
kluSetOrdering
Solver, 504
kluSetOrderingB
Solver, 504

l2s
amici.sbml_import, 88
lbw
amimodel, 558
Model, 289
LinearMultistepMethod
amici, 21
LinearSolver
amici, 21
linsol
amioption, 568
linsolveSPBCG
NewtonSolverIterative, 375
llh
ReturnData, 429
lmm
amioption, 567
Solver, 516
loadOldHashes

amimodel, 549
loadSBMLFile
SbmlImporter, 437
log
amici, 55
LogLikelihood, 383
__init__, 384

M
Model, 296
makeEvents
amimodel, 547
makeSyms
amimodel, 547
max
amici, 58
maxflag
amimodel, 562
maxlinsteps
NewtonSolver, 368
maxsteps
amioption, 566
NewtonSolver, 368
Solver, 517
maxstepsB
amioption, 566
mexFunction
interface_matlab.cpp, 593
mfuns
amimodel, 560
min
amici, 57
minflag
amimodel, 562
minus
AmiVector, 101
Model, 159
~Model, 169
anyStateNonNegative, 299
boost::serialization::serialize, 285
checkFinite, 237
clone, 169
computeX_pos, 283
deltaqB, 292
deltasx, 291
deltax, 291
deltaxB, 291
dJrzdsigma, 294
dJrzdz, 293
dJydp, 291
dJydsigma, 293
dJydy, 293
dJzdp, 291
dJzdsigma, 293
dJzdz, 293
drzdp, 294
drzdx, 294
dsigmaydp, 290
dsigmazdp, 290
dwdp, 295
dwdx, 295
dxdotdp, 292
dydp, 295
dydx, 295
dzdp, 294
dzdx, 294
fchi2, 235
fdeltaqB, 193, 268
fdeltasx, 192, 267
fdeltax, 191, 266
fdeltaxB, 192, 268
fdJrzdsigma, 202, 275
fdJrzdz, 202, 274
fdJydp, 205
fdJydsigma, 200, 273
fdJydx, 206
fdJydy, 199, 272
fdJzdp, 207
fdJzdsigma, 201, 274
fdJzdx, 208
fdJzdz, 200, 273
fdrzdp, 190, 265
fdrzdx, 190, 266
fdsigmaydp, 195, 269
fdsigmazdp, 196, 270
fdwdp, 231, 276
fdwdx, 232, 276
fdx0, 179
fdxdotdp, 173
fdydp, 183, 261
fdydx, 184, 262
fdzdp, 188, 264
fdzdx, 189, 265
fFIM, 236
fixedParameters, 297
fJ, 171
fJDiag, 173
fJrz, 199, 272
fJSparse, 172
fJv, 174
fJy, 197, 271
fJz, 198, 271
fres, 234
froot, 170
frz, 186, 263
fsdx0, 181
fsigmay, 194, 269
fsigmaz, 195, 270
fsJy, 204
fsJz, 207
fsres, 235
fsrz, 187, 264
fstau, 181, 260
fstotal_cl, 257
fsx0, 179, 259
fsx0_fixedParameters, 180, 259
fsx_rdata, 176, 255

fsx_solver, 256
fsxdot, 171
fsy, 203
fsz, 185, 263
fsz_tf, 204
ftotal_cl, 257
fw, 230, 275
fx0, 177, 258
fx0_fixedParameters, 178, 259
fx_rdata, 175, 254
fx_solver, 255
fxdot, 170
fy, 182, 260
fz, 185, 262
getAmiciCommit, 239
getAmiciVersion, 238
getFixedParameterById, 219
getFixedParameterByName, 220
getFixedParameterIds, 251
getFixedParameterNames, 242
getFixedParameters, 219
getInitialStates, 226
getInitialStateSensitivities, 227
getmy, 277
getmz, 278
getObservableIds, 252
getObservableNames, 243
getParameterById, 245
getParameterByName, 246
getParameterIds, 245
getParameterList, 225
getParameterNames, 240
getParameters, 218
getParameterScale, 217
getReinitializeFixedParameterInitialStates, 254
getrz, 281
getSolver, 169
getsrz, 282
getStateIds, 250
getStateIsNonNegative, 224
getStateNames, 241
getSteadyStateSensitivityMode, 253
getsz, 282
gett, 237
getTimepoints, 223
getUnscaledParameters, 218
gety, 279
getz, 280
h, 297
hasFixedParameterIds, 250
hasFixedParameterNames, 241
hasObservableIds, 252
hasObservableNames, 243
hasParameterIds, 244
hasParameterNames, 239
hasStateIds, 249
hasStateNames, 240
idlist, 290
initHeaviside, 212
initialize, 209
initializeStates, 210
initializeStateSensitivities, 211
isFixedParameterStateReinitializationAllowed, 283
J, 292
k, 215
lbw, 289
M, 296
Model, 167, 168
my, 292
mz, 292
ncl, 215
ndwdp, 288
ndwdx, 288
ne, 288
nJ, 289
nk, 214
nMaxEvent, 216
nmaxevent, 299
nnz, 288
np, 214
nplist, 212
nt, 216
nw, 288
nx_rdata, 286
nx_solver, 286
nxtrue_rdata, 286
nxtrue_solver, 287
ny, 287
nytrue, 287
nz, 287
nztrue, 287
o2mode, 289
operator=, 169
operator==, 286
originalParameters, 297
plist, 229
plist_, 298
pscale, 299
reinitializeFixedParameterInitialStates, 300
setFixedParameterById, 221
setFixedParameterByName, 222
setFixedParameters, 219
setFixedParametersByIdRegex, 221
setFixedParametersByNameRegex, 222
setInitialStates, 226
setInitialStateSensitivities, 227
setNMaxEvent, 216
setParameterById, 247
setParameterByName, 248
setParameterList, 226
setParameters, 218
setParametersByIdRegex, 247
setParametersByNameRegex, 249
setParameterScale, 217
setReinitializeFixedParameterInitialStates, 253
setStateIsNonNegative, 224

setSteadyStateSensitivityMode, 253
setT0, 228
setTimepoints, 223
setUnscaledInitialStateSensitivities, 227
sigmay, 290
sigmaz, 290
stateIsNonNegative, 299
stau, 296
steadyStateSensitivityMode, 300
stotal_cl, 298
sx, 296
sx0data, 298
sx_rdata, 296
t, 224
t0, 228
total_cl, 297
ts, 298
tstart, 300
ubw, 289
unscaledParameters, 297
updateHeaviside, 236
updateHeavisideB, 237
w, 295
x0data, 298
x_pos_tmp, 299
x_rdata, 296
z2event, 289
model
amised, 573
ForwardProblem, 153
NewtonSolver, 369
Model_DAE, 300
fdxdotdp, 318, 319, 330
fJ, 303, 304, 323
fJB, 305, 324
fJDiag, 309, 325
fJSparse, 306, 307, 324
fJSparseB, 308, 325
fJv, 310, 311, 326
fJvB, 312, 327
fM, 322, 331
fqBdot, 317, 329
froot, 313, 314, 328
fsxdot, 320, 321, 330
fxBdot, 316, 329
fxdot, 314, 315, 328
getSolver, 323
Model_DAE, 302
Model_ODE, 332
fdxdotdp, 351, 360
fJ, 335, 336, 354
fJB, 337, 355
fJDiag, 341, 342, 356
fJSparse, 338, 339, 355
fJSparseB, 340, 356
fJv, 343, 344, 357
fJvB, 345, 358
fqBdot, 350, 360
froot, 346, 347, 358
fsxdot, 352, 353, 361
fxBdot, 349, 359
fxdot, 347, 348, 359
getSolver, 354
Model_ODE, 333, 334
modelname
amimodel, 553
amised, 573
ModelQuantity, 384
__init__, 385
__repr__, 386
get_id, 386
get_name, 386
get_val, 386
msgIdAndTxtFp
amici, 19
multiobs_functions
amici.ode_export, 84
mxArrayToVector
amici, 73
my
Model, 292
mz
Model, 292

name
ODEModel, 405
ncl
Model, 215
ODEModel, 398
ndwdp
amimodel, 563
Model, 288
ndwdx
amimodel, 563
Model, 288
ne
amidata, 526
Model, 288
ReturnData, 432
nevent
amimodel, 556
newton_cpu_time
ReturnData, 427
newton_maxlinsteps
amioption, 570
newton_maxsteps
amioption, 570
ReturnData, 433
newton_numlinsteps
ReturnData, 428
newton_numsteps
ReturnData, 427
newton_preeq
amioption, 571
newton_status
ReturnData, 427
NewtonFailure, 362

error_code, 363
NewtonFailure, 362
NewtonSolver, 363
atol, 368
computeNewtonSensis, 366
dx, 370
getSolver, 364
getStep, 365
maxlinsteps, 368
maxsteps, 368
model, 369
NewtonSolver, 364
prepareLinearSystem, 367
rdata, 369
rtol, 369
solveLinearSystem, 367
t, 369
x, 370
xdot, 369
NewtonSolverDense, 370
NewtonSolverDense, 371
prepareLinearSystem, 372
solveLinearSystem, 371
NewtonSolverIterative, 373
linsolveSPBCG, 375
NewtonSolverIterative, 373
prepareLinearSystem, 375
solveLinearSystem, 374
NewtonSolverSparse, 376
NewtonSolverSparse, 377
prepareLinearSystem, 378
solveLinearSystem, 378
NewtonStatus
amici, 22
ng
amimodel, 556
nJ
Model, 289
ReturnData, 432
nk
amidata, 527
amimodel, 556
Model, 214
ODEModel, 399
ReturnData, 430
nMaxEvent
Model, 216
nmaxevent
amioption, 569
ExpData, 124
Model, 299
ReturnData, 432
nmaxevent_
ExpData, 146
nnz
amimodel, 558
Model, 288
NonlinearSolverIteration
amici, 21
np
amimodel, 556
Model, 214
ODEModel, 399
ReturnData, 430
nplist
Model, 212
ReturnData, 432
Solver, 510
nt
amidata, 526
ExpData, 124
Model, 216
ReturnData, 432
numerrtestfails
ReturnData, 426
numerrtestfailsB
ReturnData, 426
numnonlinsolvconvfails
ReturnData, 426
numnonlinsolvconvfailsB
ReturnData, 427
numrhsevals
ReturnData, 426
numrhsevalsB
ReturnData, 426
numsteps
ReturnData, 425
numstepsB
ReturnData, 425
nvecs
amifun, 538
nw
amimodel, 562
Model, 288
nx
amimodel, 555
ReturnData, 430
Solver, 510
nx_rdata
Model, 286
ODEModel, 396
nx_solver
Model, 286
ODEModel, 397
ReturnData, 430
nxtrue
amimodel, 555
ReturnData, 431
nxtrue_rdata
Model, 286
nxtrue_solver
Model, 287
ny
amidata, 526
amimodel, 555
Model, 287

ODEModel, 398
ReturnData, 431
nytrue
amimodel, 555
ExpData, 123
Model, 287
ReturnData, 431
nytrue_
ExpData, 146
nz
amidata, 526
amimodel, 557
Model, 287
ReturnData, 431
nztrue
amimodel, 557
ExpData, 124
Model, 287
ReturnData, 431
nztrue_
ExpData, 146

o2flag
amimodel, 561
o2mode
Model, 289
ReturnData, 433
Observable, 387
__init__, 387
observedData
ExpData, 146
observedDataStdDev
ExpData, 147
observedEvents
ExpData, 147
observedEventsStdDev
ExpData, 147
ODEExporter, 388
__init__, 389
compileModel, 390
generateModelCode, 390
setName, 392
setPaths, 391
ODEModel, 392
__init__, 394
add_component, 395
add_conservation_law, 396
colptr, 403
eq, 401
generateBasicVariables, 405
get_conservation_laws, 408
import_from_sbml_importer, 394
name, 405
ncl, 398
nk, 399
np, 399
nx_rdata, 396
nx_solver, 397
ny, 398
rowval, 404
sparseeq, 402
sparsesym, 401
state_has_conservation_law, 409
state_has_fixed_parameter_initial_condition, 409
sym, 400
sym_or_eq, 407
symNames, 406
val, 404
operator=
AmiVector, 94
Model, 169
operator==
amici, 38, 51
Model, 286
Solver, 515
operator[]
AmiVector, 102
AmiVectorArray, 109
optsym, 575
getoptimized, 576
optsym, 575
order
ReturnData, 427
ordering
amioption, 569
originalParameters
Model, 297
outputcount
amised, 574

param
amimodel, 560
Parameter, 409
__init__, 410
ParameterScaling
amici, 20
parseModel
amimodel, 544
pi
amici, 76
plist
Model, 229
plist_
Model, 298
plotObservableTrajectories
amici.plotting, 85
plotStateTrajectories
amici.plotting, 85
pos_pow
amici, 60
prepareLinearSystem
NewtonSolver, 367
NewtonSolverDense, 372
NewtonSolverIterative, 375
NewtonSolverSparse, 378
printErrMsgIdAndTxt
amici, 22
printWarnMsgIdAndTxt

amici, 23
processCompartments
SbmlImporter, 441
processObservables
SbmlImporter, 444
processParameters
SbmlImporter, 440
processReactions
SbmlImporter, 441
processRules
SbmlImporter, 442
processSBML
SbmlImporter, 438
processSpecies
SbmlImporter, 440
processTime
SbmlImporter, 443
processVolumeConversion
SbmlImporter, 443
pscale
amioption, 571
Model, 299
ReturnData, 433

qbinit
Solver, 487
quad_atol
amioption, 566
quad_rtol
amioption, 566
quadReInitB
Solver, 463
quadSStolerancesB
Solver, 498

rdata
ForwardProblem, 153
NewtonSolver, 369
realtype
amici, 19
recompile
amimodel, 561
reInit
Solver, 458
reInitB
Solver, 462
reinitializeFixedParameterInitialStates
Model, 300
remove_typedefs
amici.ode_export, 82
reorder
amici, 48
replaceInAllExpressions
SbmlImporter, 445
replaceLogAB
amici.sbml_import, 88
replaceSpecialConstants
SbmlImporter, 446
res
ReturnData, 425
reset
AmiVector, 100
AmiVectorArray, 110
reset_symbols
SbmlImporter, 436
ReturnData, 416
applyChainRuleFactorToSimulationResults, 420
boost::serialization::serialize, 421
chi2, 429
FIM, 425
invalidate, 419
invalidateLLH, 420
J, 422
llh, 429
ne, 432
newton_cpu_time, 427
newton_maxsteps, 433
newton_numlinsteps, 428
newton_numsteps, 427
newton_status, 427
nJ, 432
nk, 430
nmaxevent, 432
np, 430
nplist, 432
nt, 432
numerrtestfails, 426
numerrtestfailsB, 426
numnonlinsolvconvfails, 426
numnonlinsolvconvfailsB, 427
numrhsevals, 426
numrhsevalsB, 426
numsteps, 425
numstepsB, 425
nx, 430
nx_solver, 430
nxtrue, 431
ny, 431
nytrue, 431
nz, 431
nztrue, 431
o2mode, 433
order, 427
pscale, 433
res, 425
ReturnData, 418, 419
rz, 423
s2llh, 429
s2rz, 423
sensi, 433
sensi_meth, 433
sigmay, 424
sigmaz, 422
sllh, 429
sres, 425
srz, 423
ssigmay, 424

ssigmaz, 423
status, 430
sx, 424
sx0, 429
sy, 424
sz, 422
t_steadystate, 428
ts, 422
wrms_sensi_steadystate, 428
wrms_steadystate, 428
x, 423
x0, 428
xdot, 422
y, 424
z, 422
rootInit
Solver, 487
rowval
ODEModel, 404
rowvals
amimodel, 558
rowvalsB
amimodel, 559
rtol
amioption, 566
NewtonSolver, 369
runAmiciSimulation
amici, 23, 69
runAmiciSimulations
amici, 24, 71
rz
ReturnData, 423

s2llh
ReturnData, 429
s2rz
ReturnData, 423
sanitize_basic_sympy
amici.ode_export, 80
SBML2AMICI
SBML2AMICI.m, 594
sbml2amici
SbmlImporter, 437
SBML2AMICI.m, 593
SBML2AMICI, 594
SBMLException, 434
SbmlImporter, 434
__init__, 436
checkSupport, 440
cleanReservedSymbols, 446
loadSBMLFile, 437
processCompartments, 441
processObservables, 444
processParameters, 440
processReactions, 441
processRules, 442
processSBML, 438
processSpecies, 440
processTime, 443
processVolumeConversion, 443
replaceInAllExpressions, 445
replaceSpecialConstants, 446
reset_symbols, 436
sbml2amici, 437
scaleParameters
amici, 37
SecondOrderMode
amici, 20
sedml
amised, 573
sens_ind
amioption, 567
sensi
amioption, 569
ReturnData, 433
sensi_functions
amici.ode_export, 84
sensi_meth
amioption, 569
ReturnData, 433
sensiflag
amifun, 539
sensInit1
Solver, 488
SensitivityMethod
amici, 20
SensitivityOrder
amici, 20
sensReInit
Solver, 459
serializeToChar
amici, 49
serializeToStdVec
amici, 50
serializeToString
amici, 50
set
AmiVector, 101
set_conservation_law
State, 414
set_dt
State, 414
setAbsoluteTolerance
Solver, 469
setAbsoluteToleranceQuadratures
Solver, 473
setAbsoluteToleranceSensi
Solver, 471
setAbsoluteToleranceSteadyState
Solver, 475
setAbsoluteToleranceSteadyStateSensi
Solver, 477
setBandJacFn
Solver, 488
setBandJacFnB
Solver, 490
setDenseJacFn

Solver, 488
setDenseJacFnB
Solver, 489
setErrHandlerFn
Solver, 493
setFixedParameterById
Model, 221
setFixedParameterByName
Model, 222
setFixedParameters
Model, 219
setFixedParametersByIdRegex
Model, 221
setFixedParametersByNameRegex
Model, 222
setHflag
amievent, 530
setId
Solver, 496
setInitialStates
Model, 226
setInitialStateSensitivities
Model, 227
setInternalSensitivityMethod
Solver, 485
setInterpolationType
Solver, 482
setJacTimesVecFn
Solver, 489
setJacTimesVecFnB
Solver, 490
setLinearMultistepMethod
Solver, 480
setLinearSolver
Solver, 484
setMaxNumSteps
Solver, 494
setMaxNumStepsB
Solver, 494
setMaxSteps
Solver, 478
setMaxStepsBackwardProblem
Solver, 479
setModelData
amici, 30
setName
ODEExporter, 392
setNewtonMaxLinearSteps
Solver, 466
setNewtonMaxSteps
Solver, 464
setNewtonPreequilibration
Solver, 465
setNMaxEvent
Model, 216
setNonlinearSolverIteration
Solver, 481
setObservedData
ExpData, 127
setObservedDataStdDev
ExpData, 130–132
setObservedEvents
ExpData, 135, 136
setObservedEventsStdDev
ExpData, 138–140
setParameterById
Model, 247
setParameterByName
Model, 248
setParameterList
Model, 226
setParameters
Model, 218
setParametersByIdRegex
Model, 247
setParametersByNameRegex
Model, 249
setParameterScale
Model, 217
setPaths
ODEExporter, 391
setQuadErrConB
Solver, 493
setReinitializeFixedParameterInitialStates
Model, 253
setRelativeTolerance
Solver, 468
setRelativeToleranceQuadratures
Solver, 472
setRelativeToleranceSensi
Solver, 470
setRelativeToleranceSteadyState
Solver, 474
setRelativeToleranceSteadyStateSensi
Solver, 476
setSensErrCon
Solver, 493
setSensitivityMethod
Solver, 463
setSensitivityOrder
Solver, 467
setSensParams
Solver, 497
setSensSStolerances
Solver, 491
setSolverOptions
amici, 30
setSparseJacFn
Solver, 488
setSparseJacFnB
Solver, 489
setSStolerances
Solver, 491
setSStolerancesB
Solver, 498
setStabilityLimitFlag

Solver, 483
setStabLimDet
Solver, 495
setStabLimDetB
Solver, 495
setStateIsNonNegative
Model, 224
setStateOrdering
Solver, 482
setSteadyStateSensitivityMode
Model, 253
setStopTime
Solver, 461
setSuppressAlg
Solver, 496
setT0
Model, 228
setTimepoints
ExpData, 125
Model, 223
setUnscaledInitialStateSensitivities
Model, 227
setup
Solver, 454
setupAMIB
Solver, 454
SetupFailure, 447
SetupFailure, 448
setupReturnData
amici, 31
setUserData
Solver, 493
setUserDataB
Solver, 494
setValueById
amici, 74
setValueByIdRegex
amici, 75
seval
amici, 53
Sigma_Y
amidata, 527
Sigma_Z
amidata, 528
SigmaY, 411
__init__, 411
sigmay
Model, 290
ReturnData, 424
sigmaz
Model, 290
ReturnData, 422
sign
amici, 64
sinteg
amici, 54
sllh
ReturnData, 429
solve
Solver, 460
solveB
Solver, 461
solveF
Solver, 460
solveLinearSystem
NewtonSolver, 367
NewtonSolverDense, 371
NewtonSolverIterative, 374
NewtonSolverSparse, 378
Solver, 448
adjInit, 497
allocateSolver, 491
allocateSolverB, 497
applyQuadTolerancesASA, 514
applySensitivityTolerances, 514
applyTolerances, 512
applyTolerancesASA, 513
applyTolerancesFSA, 512
band, 500
bandB, 501
binit, 486
boost::serialization::serialize, 515
calcIC, 459
calcICB, 459
clone, 453
dense, 498
denseB, 500
diag, 501
diagB, 502
getAbsoluteTolerance, 469
getAbsoluteToleranceQuadratures, 473
getAbsoluteToleranceSensi, 471
getAbsoluteToleranceSteadyState, 475
getAbsoluteToleranceSteadyStateSensi, 477
getAdjBmem, 511
getAdjMallocDone, 511
getB, 462
getDiagnosis, 457
getDiagnosisB, 457
getDky, 497
getInternalSensitivityMethod, 485
getInterpolationType, 481
getLastOrder, 507
getLinearMultistepMethod, 480
getLinearSolver, 484
getMallocDone, 511
getMaxSteps, 478
getMaxStepsBackwardProblem, 479
getModel, 510
getNewtonMaxLinearSteps, 465
getNewtonMaxSteps, 464
getNewtonPreequilibration, 465
getNonlinearSolverIteration, 481
getNumErrTestFails, 506
getNumNonlinSolvConvFails, 507
getNumRhsEvals, 506

getNumSteps, 505
getQuadB, 462
getRelativeTolerance, 468
getRelativeToleranceQuadratures, 472
getRelativeToleranceSensi, 470
getRelativeToleranceSteadyState, 474
getRelativeToleranceSteadyStateSensi, 476
getRootInfo, 458
getSens, 456
getSensitivityMethod, 463
getSensitivityOrder, 466
getStabilityLimitFlag, 483
getStateOrdering, 482
init, 486
initializeLinearSolver, 508
initializeLinearSolverB, 509
interpType, 517
ism, 516
iter, 517
klu, 504
kluB, 505
kluSetOrdering, 504
kluSetOrderingB, 504
lmm, 516
maxsteps, 517
nplist, 510
nx, 510
operator==, 515
qbinit, 487
quadReInitB, 463
quadSStolerancesB, 498
reInit, 458
reInitB, 462
rootInit, 487
sensInit1, 488
sensReInit, 459
setAbsoluteTolerance, 469
setAbsoluteToleranceQuadratures, 473
setAbsoluteToleranceSensi, 471
setAbsoluteToleranceSteadyState, 475
setAbsoluteToleranceSteadyStateSensi, 477
setBandJacFn, 488
setBandJacFnB, 490
setDenseJacFn, 488
setDenseJacFnB, 489
setErrHandlerFn, 493
setId, 496
setInternalSensitivityMethod, 485
setInterpolationType, 482
setJacTimesVecFn, 489
setJacTimesVecFnB, 490
setLinearMultistepMethod, 480
setLinearSolver, 484
setMaxNumSteps, 494
setMaxNumStepsB, 494
setMaxSteps, 478
setMaxStepsBackwardProblem, 479
setNewtonMaxLinearSteps, 466
setNewtonMaxSteps, 464
setNewtonPreequilibration, 465
setNonlinearSolverIteration, 481
setQuadErrConB, 493
setRelativeTolerance, 468
setRelativeToleranceQuadratures, 472
setRelativeToleranceSensi, 470
setRelativeToleranceSteadyState, 474
setRelativeToleranceSteadyStateSensi, 476
setSensErrCon, 493
setSensitivityMethod, 463
setSensitivityOrder, 467
setSensParams, 497
setSensSStolerances, 491
setSparseJacFn, 488
setSparseJacFnB, 489
setSStolerances, 491
setSStolerancesB, 498
setStabilityLimitFlag, 483
setStabLimDet, 495
setStabLimDetB, 495
setStateOrdering, 482
setStopTime, 461
setSuppressAlg, 496
setup, 454
setupAMIB, 454
setUserData, 493
setUserDataB, 494
solve, 460
solveB, 461
solveF, 460
Solver, 453
solverMemory, 516
solverMemoryB, 516
solverWasCalled, 516
spbcg, 502
spbcgB, 503
spgmr, 502
spgmrB, 502
sptfqmr, 503
sptfqmrB, 503
turnOffRootFinding, 463
wrapErrHandlerFn, 490
solver
ForwardProblem, 154
solverMemory
Solver, 516
solverMemoryB
Solver, 516
solverWasCalled
Solver, 516
sparse_functions
amici.ode_export, 83
sparseeq
ODEModel, 402
sparseidx
amimodel, 558
sparseidxB

amimodel, 559
sparsesym
ODEModel, 401
spbcg
Solver, 502
spbcgB
Solver, 503
spgmr
Solver, 502
spgmrB
Solver, 502
spline
amici, 51, 64
spline.cpp, 594
spline_pos
amici, 65
splineflag
amimodel, 562
sptfqmr
Solver, 503
sptfqmrB
Solver, 503
sres
ReturnData, 425
srz
ReturnData, 423
ss
amioption, 570
ss_atol
amioption, 567
ss_rtol
amioption, 567
ssigmay
ReturnData, 424
ssigmaz
ReturnData, 423
State, 412
__init__, 413
get_dt, 415
set_conservation_law, 414
set_dt, 414
state_has_conservation_law
ODEModel, 409
state_has_fixed_parameter_initial_condition
ODEModel, 409
stateIsNonNegative
Model, 299
StateOrdering
amici, 22
status
ReturnData, 430
stau
Model, 296
SteadystateProblem, 517
applyNewtonsMethod, 521
checkConvergence, 520
createSteadystateSimSolver, 523
getSteadystateSimulation, 522
getWrmsNorm, 519
SteadystateProblem, 518
workSteadyStateProblem, 518
writeNewtonOutput, 522
SteadyStateSensitivityMode
amici, 22
steadyStateSensitivityMode
Model, 300
stldet
amioption, 568
storeBacktrace
AmiException, 92
stotal_cl
Model, 298
strsym
amifun, 537
strsym_old
amifun, 537
sx
Model, 296
ReturnData, 424
sx0
amioption, 570
ReturnData, 429
sx0data
Model, 298
sx_rdata
Model, 296
sy
ReturnData, 424
sym
amifun, 537
amimodel, 552
ODEModel, 400
sym_noopt
amifun, 537
sym_or_eq
ODEModel, 407
symbol_to_type
amici.ode_export, 84
symbolic_functions.cpp, 595
symNames
ODEModel, 406
sz
ReturnData, 422

t
amidata, 527
Model, 224
NewtonSolver, 369
t0
amimodel, 554
Model, 228
t_steadystate
ReturnData, 428
TemplateAmici, 415
time
IntegrationFailure, 157
IntegrationFailureB, 158

total_cl
Model, 297
trigger
amievent, 530
ts
ExpData, 146
Model, 298
ReturnData, 422
tstart
amioption, 567
Model, 300
turnOffRootFinding
Solver, 463

ubw
amimodel, 557
Model, 289
unscaledParameters
Model, 297
unscaleParameters
amici, 34, 35
updateHeaviside
Model, 236
updateHeavisideB
Model, 237
updateModelName
amimodel, 543
updateRHS
amimodel, 543
updateWrapPath
amimodel, 544

val
ODEModel, 404
var_in_function_signature
amici.ode_export, 78
varidx
amised, 574
varsym
amised, 574

w
Model, 295
warnMsgIdAndTxt
amici, 76
what
AmiException, 91
workBackwardProblem
BackwardProblem, 112
workForwardProblem
ForwardProblem, 149
workSteadyStateProblem
SteadystateProblem, 518
wrap_path
amimodel, 561
wrapErrHandlerFn
Solver, 490
writeCcode
amifun, 534
writeCcode_sensi
amifun, 533
writeMatlabField0
amici, 41
writeMatlabField1
amici, 42
writeMatlabField2
amici, 43
writeMatlabField3
amici, 44
writeMatlabField4
amici, 45
writeMcode
amifun, 534
writeNewtonOutput
SteadystateProblem, 522
wrms_sensi_steadystate
ReturnData, 428
wrms_steadystate
ReturnData, 428
wtype
amimodel, 554

x
NewtonSolver, 370
ReturnData, 423
x0
amioption, 570
ReturnData, 428
x0data
Model, 298
x_pos_tmp
Model, 299
x_rdata
Model, 296
xdot
NewtonSolver, 369
ReturnData, 422

Y
amidata, 527
y
ReturnData, 424

Z
amidata, 528
z
amievent, 531
ReturnData, 422
z2event
amimodel, 562
amioption, 571
Model, 289