
Same jobs, same order (J2 → J3 → J1): buffered flow shop vs no-wait flow shop
Processing times [M1, M2]: J1 = [7, 1] J2 = [5, 2] J3 = [4, 9]
1 Standard flow shop: buffers allowed
Utilisation M1 84% · M2 63% · overall 74%
C_{max} = 19
M1
M2
Buffer 1→2
J2
J3
J1
J1 waits 2
2 No-wait flow shop: a started job never stops
Utilisation M1 84% · M2 63% · overall 74%
C_{max} = 19
J1 held 2 units
empty: buffers not allowed
0 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22
Time (units)
J1
J2
J3
Waiting in buffer
Held before M1
Machine idle
Job moves to next machine