

ALLME

Product User Manual

Platform: Microsoft Windows (x64) | **Version:** AllmeD_v36 | **Document Ref:** ALLME-UM-V36

1. Introduction & Overview

Welcome to **Allme**! Allme is a smart, friendly desktop widget that floats as a smooth circular orb on your Windows desktop. It is designed to sit gently on top of your open applications, providing instant 1-click access to window switching, browser tab control, screenshot capture, high-definition screen video recording, audio spectrum music visualizers, and live computer hardware telemetry.

What Allme Does For You (Summary):

- **Instant Window Switcher:** Switch active open application windows with a single click.
- **Web Browser Tab Control:** Step through browser tabs forward and backward directly from the orb.
- **One-Click Screenshots & Screen Recording:** Capture snapshot images or record MP4 screen video clips.
- **Audio Spectrum Visualizations:** Watch the orb dance to music played through your speakers.

2. The Allme Widget Interface & Visual Components

The Allme widget consists of a 3-zone interactive circular orb surrounded by a customizable ambient glow halo:




Figure 2.1: The Allme Desktop Widget (showing central core, ring sectors, icon preview, dark backdrop card, and ambient glow halo).

Orb Area	Visual Description	Core Functionality
Center Core	Small circle in the middle displaying active app/	Performs Quick Switch (between windows), Tab

Orb Area	Visual Description	Core Functionality
	browser icon.	Switch (in browser), or toggles Screen Video Recording (turns red).
Left Sector	Outer left arc sector separated by subtle dashed dividers.	Cycles windows left, steps browser tabs left, or takes screen capture.
Right Sector	Outer right arc sector separated by subtle dashed dividers.	Cycles windows right, steps browser tabs right, or takes screen capture.
Ambient Glow Halo	Soft glowing light ring shining around the orb.	Pulses with breathing effects, moves with sound volume, or shifts color based on PC hardware load.

3. How to Operate Allme (Mouse Clicks & Keyboard Controls)

Direct Mouse Button Controls

Mouse Button	Where You Click	Executed Action
Left Click	Center Core	Quick Switch: Jumps instantly back to your previous active window.
Left Click	Left Sector	Previous Window: Cycles backward through open desktop application windows.
Left Click	Right Sector	Next Window: Cycles forward through open desktop application windows.
Right Click	Center Core	Switch Browser Tab: Focuses web browser and switches active tab.
Right Click	Left Sector	Previous Browser Tab: Steps to the browser tab on the left (Ctrl+PageUp).
Right Click	Right Sector	Next Browser Tab: Steps to the browser tab on the right (Ctrl+PageDown).
Middle Click	Center Core	Record Screen Video: Starts or stops MP4 video recording (orb border turns red).
Middle Click	Left or Right Sector	Take Screenshot: Captures a full-screen snapshot picture (orb flashes white).

Keyboard Modifier Combinations

- **Shift + Left Click:** Toggle **Lock Position** (locks widget to prevent accidental movement).
- **Ctrl + Left Click:** Toggle **Fly Mode** (makes the widget follow mouse cursor).
- **Alt + Left Click:** Safely terminates and **Exits Allme**.

Widget Dragging & Positioning

Left-click and hold anywhere on the widget body to drag it to any screen location. Allme automatically saves your chosen coordinates and restores them when you reboot your PC.

4. Complete Menu & Settings Reference

Right-clicking the System Tray icon or widget opens the **Persistent Settings Menu**:




Figure 4.1: The Allme Persistent Context Menu (showing toggles, submenus, audio visualizers, telemetry links, and sliders).

Part A: General Display & Control Toggles

Menu Setting Name	Description & Purpose
Always on Top	Keeps Allme visible above all open windows so it never gets hidden under application windows.
Lock Position	Freezes Allme in its current spot so you cannot accidentally drag or nudge it while clicking.
Clickthrough (Pass Mouse)	Makes Allme transparent to mouse clicks, letting clicks pass through to background apps.
 Clickthrough Mode	Submenu options: 1. Pass All (Hardware Pass-Through), 2. Pass Left Click Only, 3. Pass Right Click Only, 4. Pass Middle Click Only.
Fly Mode (Follow Cursor)	Makes Allme float and follow your mouse cursor coordinates across the screen.
 Futuristic Dashboard	Opens the full system diagnostic and hardware performance monitoring window.
Start with Windows	Configures Allme to start automatically whenever you log into Windows.

Part B: Visual Animations, Breathing & Colors

Menu Setting Name	Description & Purpose
Enable Ambient Glow	Turns the outer glowing light halo around the orb on or off.
Enable Breathing Animation	Adds a slow, calm pulsing rhythm to the widget so it feels alive.
 Breathing Target	Submenu choices: 1. Both (App & Glow), 2. App Only, 3. Glow Only.
Enable Mouse Movement Activity	Makes the orb and glow expand and brighten dynamically based on mouse movement speed.
 Mouse Movement Target	Submenu choices: 1. Both, 2. App Only, 3. Glow Only.
 Color Hue Target	Submenu choices: Both, App Only, Glow Only.
Link System Accent	Automatically matches Allme's color theme to your Windows DWM system accent color.

Part C: Audio Spectrum Music Visualizers

Menu Setting Name	Description & Purpose
Enable Audio Overlay Visualizations	Turns on live music visualizer effects so Allme dances when speaker audio plays.
 Audio Driver Mode	Submenu: 1. Both (Volume & Frequency), 2. Volume Only, 3. Frequency Only.
 Audio Visualizations (Profiles)	Select music visualization style: • Pulsing Aura: Classic smooth glowing halo pulsing to volume beat. • Chroma Pulse: Rainbow spectrum color rotation synchronized with audio peaks. • Equalizer Ring: 24 radial spectrum equalizer bars dancing around the orb. • Waveform Orbit: Oscillating circular sound wave spinning around the outer edge. • Frequency Ripple: Shockwave light rings expanding outward on heavy drum/bass beats. • Particle Spark: 12 glowing beat dots orbiting and bouncing to rhythm.

Part D: System Data Binding (Link Source & Link Sink)

Connect live PC hardware metrics (Link Source) to visual attributes of Allme (Link Sink):

- **Link Source Options (0-9):** None, Breathing Sine, CPU Frequency, CPU Usage, HDD Activity (with drive & IO mode options), Memory Usage, Ethernet & Ping Latency, GPU Usage (GPU 0/1/Max), System Power Usage, Keyboard Typing WPM.
- **Link Sink Options (0-9):** Modulates App Size, App Color, Glow Size, Glow Color, App Opacity, Glow Opacity, or

combined Size/Color/Opacity attributes.

Part E: Customization Sliders

- **App Opacity (0-100%):** Adjusts widget transparency (solid to transparent).
- **Glow Opacity (0-100%):** Adjusts outer glow halo brightness.
- **Glow Size (0-100%):** Adjusts diameter of the outer glowing halo.
- **Color Hue (0°-360°):** Smooth spectrum slider to pick any custom color.
- **Breathing Speed (1-100%):** Adjusts breathing animation frequency.
- **App Size (0-100%):** Resizes the Allme orb on screen.

5. The Futuristic Diagnostic Dashboard

Selecting  **Futuristic Dashboard** launches a dedicated diagnostic panel:




Figure 5.1: The AllMeD Futuristic Control Dashboard (showing Core Modules, Telemetry Links, Visual Targets, and Adjustments).

- **Core Modules Box:** Toggle ambient glow, audio visualizations, breathing, mouse activity, and Windows auto-startup.
- **Telemetry Links Box:** Select live Link Source and Link Sink hardware data bindings.
- **Visual Targets Box:** Configure Audio Driver Modes, Audio Visualizer Effects, Breathing Targets, and Mouse Targets.
- **Adjustments Box:** Direct slider adjustments for App Size, App Opacity, Glow Size, Glow Opacity, App Hue, and Breath Speed.

6. Media Capture & System Paths

Item / File Type	Default Storage Location on Windows
Screenshots	C:/Users/[YourName]/Pictures/Allme/Screenshots/
Video Recordings	C:/Users/[YourName]/Pictures/Allme/Recordings/
Configuration File	C:/Users/[YourName]/AppData/Roaming/Allme/config.json
Crash Diagnostic Logs	C:/Users/[YourName]/AppData/Local/Allme/Logs/allme_crash_report.txt

Allme Product User Manual — Version 36 | Created & Developed by ATK (Amit Kumar Singh) © 2026